
Part E

CHAPTER 3

Architecture and Organization



Alan Clements

1

These slides are being provided with permission from the copyright for CS2208 use only. The slides must not be reproduced or provided to anyone outside of the class.

All download copies of the slides are for personal use only.
Students must destroy these copies within 30 days after receipt of final course evaluations.



Subroutine Call and Return

- A subroutine (a.k.a. function, procedure, and subprogram) is a set of instructions that may be repeatedly called by a program to do a given function.
- □ A *subroutine* gives the simplest form of program abstraction.
- ☐ There are two main characteristics in any subroutine.
 - 1. A subroutine can be called from anywhere in the program.
 - 2. Once the subroutine is completed, it should return to the instruction directly after the subroutine calling location.


goes back to the main Inne

ded and copyrighted by © Mahmoud R. El-Sakka.

Subroutine Call and Return

- \square A hypothetical instruction BSR Proc_A calls subroutine Proc_A.
 - The processor saves the address of the next instruction to be executed in a safe place, and
 - loads the program counter with the address of the first instruction in the subroutine.
- \square At the end of the subroutine a return from subroutine instruction, RTS,

o causes the processor to return to the point immediately following the



RTS

This

ARM Support for Subroutines

- □ RISC processors (including ARM) do not provide a fully automatic subroutine call/return mechanism like CISC processors.
- So you have we mannedly add the reason □ ARM's branch with link instruction, BL,

branch with link instruction.

o automatically saves the return address in register r14.


This is the main difference between B and BL

☐ The branch instruction (Figure 3.41) has a 24-bit *signed* program counter relative offset (word address offset).

> You may want to review slides 89 to 91 to remember how to encode and decode this 24-bit offset.

FIGURE 3.41

Encoding ARM's branch and branch-with-link instructions



to create a 26-bit byte offset.

191

d R. El-Sakka

ARM Support for Subroutines

- ☐ The branch with link instruction behaves like the branch instruction but the processor also copies the return address (i.e., the address of the next instruction to be executed following a return) into the link register **r14**.
- ☐ If you execute:

```
Sub A ; save return address in r14
BL
                ;branch to "Sub A"
```

Store the addlerss of the next instr

2~ LR To wrine the program, ARM will take care of (reverse) the effect of the pipelining

☐ At the end of the subroutine, you return by

o copying the return address in r14 to the program counter by executing:

MOV pc, lr

or

MOV **r15**, r14

Should it be LT

or LE?

ARM Support for Subroutines

□ Suppose that you want to evaluate the following expression several times in a program.

```
if x > 0 then x = 16*x + 1 else x = 32*x

spline Thys.
```

 \square Assuming that **x** is loaded into **r0**, we can write:

```
Funcl CMP r0, #0 ; test for x > 0

MOVGT r0, r0, LSL #4 ; if x > 0 x = 16*x

ADDGT r0, r0, #1 ; if x > 0 then x = 16*x + 1

MOVLT r0, r0, LSL #5 ; ELSE if x < 0 THEN x = 32*x

MOV pc, lr ; return by restoring saved PC
```

□ Consider the following invocation of the above subroutine.


```
LDR r0,[r4] ;get P
BL Func1 ;First call
    ;P = (if P > 0 then 16*P + 1 else 32*P)
STR r0,[r4] ;save P
```

Later on ...

```
LDR r0,[r5] ;get Q
BL Func1 ;Second call
    ;Q = (if Q > 0 then 16*Q + 1 else 32*Q)
STR r0,[r5] ; save Q
```

0x00000054: 00 00 00 00 00 00 00 00

ARM Support for Subroutines



RIS: Stack pointer RIY: link register when uszy 13/13RL, return add will he swore in RIY.
when using 13/13RL, redurn add will he shore
in 214.
B-> branch to the target add, and not apolite Ruy
BL-> (vore the rext instruction.
BLS-> sweet so sum.
BX > sump to the target add.
LDR: memory -> register
STR: regisser -> memory
MOV: rejister -> register
The state of the s

Conditional Subroutine Calls

- ☐ **BL** instruction can be conditionally executed.
- ☐ For example

```
CMP r9, r4; if r9 < r4
```

BLLT ABC ; then call subroutine ABC

- 🗖 **BLLT** means
 - o Branch
 - o with Link
 - o execute on condition Less Than

Subroutine Call and Return

- ☐ An important application of the stack is to save the address to return to after executing the subroutine.

 This is another method to
 - A subroutine call can be implemented by • implement a subroutine call, other than using R14.
 - o Branching to the target address.
 - Once the execution of the subroutine code is completed, a *return from* subroutine instruction is executed
 - o Popping the return address from the stake
 - O Copy the return address to the PC register

197



Subroutine Call and Return

Grows up

□ Example

```
This is B. It is NOT BL
```

```
...
STR r15, [r13,#-4]!
B Target
...
The proper return address
```

; assume that the stack grows towards
; low addresses and the SP points at
; the top item on the stack.
; pre-decrement the stack pointer AND
; push the return address on the stack
; jump to the target address (B not BL)

Due to the pipeline effect, the PC value will not be the address of the current instruction. Instead, it will be current address +12. Yes, it is +12, not +8, as it is STR instruction

The address pushed onto the stake.

□ Because ARM does not support a stack-based subroutine return mechanism, you would have to write:

; to return here

```
LDR r12, [r13], #+4

SUB r15, r12, #4
```

;get saved PC and post-increment
;stack pointer
;fix PC and load into r15 to return


The 4 is subtracted to make the popped address pointing to the proper return address.


Why did not we copy the stack content directory to r15?

Elements and used with permission. New content added and copyrighted by © **Mahmoud R. El-Sakka**.

Nested subroutines

FIGURE 3.48 An example of nested subroutines






198

Occupied memory

Example of nested subroutine

Grows up





199


- Subroutine Fun_1 is a leaf subroutine that <u>does not call any other</u> subroutine and, therefore, we don't have to worry about saving the link register, **r14**, and we can return by executing MOV **pc**, lr.
- Subroutine Fun_2 contains a call to another subroutine (i.e., nested subroutine) and we have to save the link register in order to return from Fun_2.


 STR Ir Lipl, AY.
- \Box The simplest way of *saving* the link register is to *push* it onto the stack.
- □ To return from Fun_2, we restore the pushed r14 into the program counter.

 □ Q PC Lsp, #-47.











205








207

Clements












210




211



212





Subroutines and Block Move Instructions

- ☐ All subroutines commonly use the same set of registers to save values, and this might cause problems.
 - Assume that a program used **R1** to store a temporary value.
 - Later, this program called a function.
 - o The function also used **R1** to store a different value.
 - After returning from the function, the program will not have access to the original **R1** value that was there before calling the function.
- ☐ To solve this issue, the followings need to be done:
 - At the beginning of the function, the values of all registers that will be used in the function <u>must</u> be pushed onto a stack.
 - O Just before returning from the function, all pushed values must be popped and loaded to the same registers.

Subroutines and Block Move Instructions

- ☐ The *ARM*'s block move instructions can be used to
 - save register values once entering a subroutine and
 - restore registers just before returning from a subroutine.
- ☐ Consider the following ARM code:

```
; call test, save return
    BL
        test
                                  ; address in r14
test STMFD r13!, {r0-r4, r10}
                                  ; subroutine test, save working
                                  ; registers
     . body of code
     LDMFD r13!, {r0-r4,r10}
                                  ; subroutine completes,
                                  ; restore the registers
    VOM
         pc, r14
                                  ; copy the return address in
                                  ;r14 to the PC
   moltyple full designding
```

216

STMPD SP! {RO-RI, LRZ
F 20-27
start-add = Sp-9.4 gregisters are push mostle stack.
end-add = SP-4 + rop of the stack: 1 position.
LDMFD SP!, (20-27, LZ3
Stort-add = SP
end-add = sp + 9.4.

Subroutines and Block Move Instructions

☐ If you are using a block move to restore registers from the stack, you can also include the program counter.

```
We can write:

test STMFD r13!, {r0-r4, r10, r14} ; save working registers

; and return address in r14

:

LDMFD r13!, {r0-r4, r10, r15} ; restore working registers

; and put r14 in the PC
```

- \square At the beginning of the subroutine, we push the *link register r14* containing the return address onto the stack, and then at the end we pull the saved registers, including the value of the return address which is placed in the *PC*, to make the return.
 - By doing so, we reduced the size of this code by one instruction