
The trachea and the bronchial 'tree' conduct air down to the respiratory surfaces.



# What is "Respiratory" Air?

See B&L[6+], pages 444-446

#### Composition

- $\approx 21\% \ 0_2$
- $\approx 79\% N_2$
- trace amounts of other gases
- Partial pressure (of a gas in a mixture)
  - $-P_X = \%X \times P_{baro}$ 
    - $P_{oxygen} = 0.21 \times 760 \text{ mmHg} = 160 \text{ mmHg}$
- Humidification
  - Inhaled air is humidified; saturated with water vapor
    - P<sub>water vapor</sub> = 47 mmHg (@ body temperature)
    - $P_{\text{oxygen, saturated}} = 0.21 \times (760 47) \text{ mmHg} = 150 \text{ mmHg}$

### What is Alveolar Gas?

- $P_{alv oxy} = P_{inhaled (wet) oxy} (P_{alv CO2}/RQ)$ 
  - $-RQ = CO_2$  excreted by lung/ $O_2$  uptake in lung

$$-RQ = \dot{V}_{CO2}/\dot{V}_{O2}$$

- 0.7 ≤ RQ ≤ 1
  - "normal" RQ ≈ 0.8
- $P_{alv CO2} = \dot{V}_{CO2} \times ((P_{baro} P_{water vapor})/\dot{V}_{alv})$ 
  - $-V_{alv}$  = alveolar ventilation
    - =  $\dot{V}_{tidal} \dot{V}_{dead space}$

See B&L[6+], pages 444-446





Figure 22-1 Alveolar  $PCO_2$  as a function of alveolar ventilation in the lung. Each line corresponds to a given metabolic rate associated with a constant production of  $CO_2$  ( $Vco_2$  isometabolic line). Normally, alveolar ventilation is controlled to maintain an alveolar  $Pco_2$  of about 40 torr. Thus, at rest, when  $Vco_2$  is approximately 250 mL/min, alveolar ventilation of 5 L/min will result in an alveolar  $Pco_2$  of 40 mm Hg. A 50% decrease in ventilation at rest (i.e., from 5 to 2.5 L/min) results in doubling of alveolar  $Pco_2$ . During exercise,  $CO_2$  production is increased ( $Vco_2$  = 750 mL/min), and to maintain a normal  $Pco_2$ , ventilation must increase (in this case to 15 L/min). Again, however, a 50% reduction in ventilation (15 to 7.5 L/min) will

result in doubling of Pco<sub>2</sub>.


### Distribution of Ventilation

- When upright ...
  - Not uniform throughout lung
    - More to base than to apex
      - Less evident at higher lung volumes
- At terminal respiratory units ...
  - Local regulation
    - Airway resistance
    - Alveolar compliance
  - Affect fill/empty time
    - $\tau = RC$



Koeppen & Stanton: Berne and Levy Physiology, 6th Edition.
Copyright © 2008 by Mosby, an imprint of Elsevier, Inc. All rights reserved

Figure 22-2 Regional distribution of lung volume, including alveolar size and location on the pressure-volume curve of the lung at different lung volumes. Because of suspension of the lung in the upright position, the pleural pressure (Ppl) and translung pressure (PL) of units at the apex will be greater than those at the base. These lung units will be larger at any lung volume than units at the base. The effect is greatest at residual volume (RV), is less at functional residual capacity (FRC), and disappears at total lung capacity (TLC). Note also that because of their location on the pressure-volume curve, inspired air will be differentially distributed to these lung units; the lung units at the apex are less compliant and will receive a smaller proportion of the inspired air than the lung units at the base, which are more compliant (i.e., reside at a steeper part of the pressure-volume curve).



Koeppen & Stanton: Berne and Levy Physiology, 6th Edition. Copyright © 2008 by Mosby, an imprint of Elsevier, Inc. All rights reserved

Figure 22-3 Examples of local regulation of ventilation as a result of variation in the resistance (R) or compliance (C) of individual lung units. In the upper schema are shown the individual resistance and compliance of three different lung units. In the lower graph are shown the volume of these three lung units as a function of time. In the upper schema, the normal lung has a time constant ( $\tau$ ) of 0.56 second. This unit reaches 97% of final equilibrium in 2 seconds, the normal inspiratory time, as shown in the lower graph. The unit at the right has a twofold increase in resistance; hence its time constant is doubled. That unit fills more slowly and reaches only 80% equilibrium during a normal breath (graph). The unit is underventilated. The unit on the left has reduced compliance (stiff), which acts to reduce its time constant. This unit fills faster than the normal unit but receives only half the ventilation of a normal unit.

## **Dead Space Ventilation**

- Ventilation to airways without gas exchange
- Two kinds of dead space
  - Anatomic
    - Conducting airways
      - See Module 11, Video 2, Slide 4
  - Physiological
    - TOTAL volume of gas per breath with no gas exchange
      - Some alveoli are are ventilated but not perfused
    - Physiological = anatomic + "bad" alveoli

### **END**

Video 1, Module 12