Prometheus监控方案

Prometheus是一套开源的系统监控报警框架。它启发于 Google 的 borgmon 监控系统,被称为运维界的"火种"基于时间序列的数值数据的容器的监控解决方案,适合监控容器,扩展性强可做集群和读写分离

最初是在SoundCloud建立的。自2012年成立以来,许多公司和组织都采用了普罗米修斯,该项目拥有一个非常活跃的开发者和用户社区。它现在是一个独立的开放源码项目,并且独立于任何公司。为了强调这一点,为了澄清项目的治理结构,普罗米修斯在2016年加入了云计算基金会,成为继Kubernetes之后的第二个托管项目。

特征:

多维度数据模型

灵活的查询语言

不依赖分布式存储,单个服务器节点是自主的

以HTTP方式,通过pull模型拉去时间序列数据

也通过中间网关支持push模型

通过服务发现或者静态配置,来发现目标服务对象

支持多种多样的图表和界面展示,grafana也支持它

高效: 平均每个采样点仅占 3.5 bytes, 且一个 Prometheus server 可以处理数百万的 metrics。


Prometheus组件

Prometheus负责收集数据, Grafana负责展示数据。其中采用Prometheus 中的 Exporter含:

- ② Node Exporter,负责收集 host 硬件和操作系统数据。它将以容器方式运行在所有 host 上。
- ② cadvisor,负责收集容器数据。它将以容器方式运行在所有 host 上。
- ③ Alertmanager,负责告警。它将以容器方式运行在所有 host 上。

架构

下面这张图说明了Prometheus的整体架构,以及生态中的一些组件作用:



计划监控标准

- 1. 统一监控内容:将基础监控进行统一,默认每个机器都包含CPU,内存,磁盘空间等基础信息监控;
- 2. 覆盖式监控:将所有机器均纳入监控,除去基础监控以外,最重要的当属业务监控,尽可能的覆盖业务流程,通过自定义监控减少和去除重复的问题,保障业务稳定运行。
- **3.** 及时通知,确保无漏报:将所有监控分类,根据重要程度、紧急程度等,分别用邮件,微信,短信,电话等不同级别的方式通知,确保每个监控都有人处理。

部署流程

docker安装prometheus+grafana

1. 修改时区

```
调整时区

先查看当前系统时间

root@ubuntu:/# date -R

1.运行tzselect

root@ubuntu:/# tzselect

在这里我们选择亚洲 Asia,确认之后选择中国 (China),最后选择北京(Beijing)

2.复制文件到/etc目录下

root@ubuntu:/# cp /usr/share/zoneinfo/Asia/Shanghai /etc/localtime

3.再次查看时间date -R,已经修改为北京时间
```

2.时间同步

```
安装chrony:
apt -y install chrony ntpdate
修改配置: nano /etc/chrony.conf
# Use public servers from the pool.ntp.org project.
# Please consider joining the pool (http://www.pool.ntp.org/join.html).
#server 0.centos.pool.ntp.org iburst
#server 1.centos.pool.ntp.org iburst
#server 2.centos.pool.ntp.org iburst
#server 3.centos.pool.ntp.org iburst
server ntp1.aliyun.com iburst minpoll 4 maxpoll 10
server ntp2.aliyun.com iburst minpoll 4 maxpoll 10
server ntp3.aliyun.com iburst minpoll 4 maxpoll 10
server ntp4.aliyun.com iburst minpoll 4 maxpoll 10
server ntp5.aliyun.com iburst minpoll 4 maxpoll 10
server ntp6.aliyun.com iburst minpoll 4 maxpoll 10
server ntp7.aliyun.com iburst minpoll 4 maxpoll 10
# Record the rate at which the system clock gains/losses time.
driftfile /var/lib/chrony/drift
# Allow the system clock to be stepped in the first three updates
```

```
# if its offset is larger than 1 second.
makestep 1.0 3
# Enable kernel synchronization of the real-time clock (RTC).
# Enable hardware timestamping on all interfaces that support it.
#hwtimestamp
# Increase the minimum number of selectable sources required to adjust
# the system clock.
#minsources 2
# Allow NTP client access from local network. allow 192.168.0.0/24
# Serve time even if not synchronized to a time source.
#local stratum 10
# Specify file containing keys for NTP authentication.
#keyfile /etc/chrony.keys
# Specify directory for log files. logdir /var/log/chrony
# Select which information is logged.
#log measurements statistics tracking
```

3、安装docker

```
1. 卸载旧版本: sudo apt remove docker docker-engine docker.io containerd runc
2. 更新apt包: sudo apt update
3. 安装 repository
sudo apt install apt-transport-https ca-certificates curl gnupg-agent
software-properties-common
4.添加Docker官方的GPG密钥
sudo curl -fssL http://mirrors.aliyun.com/docker-ce/linux/ubuntu/gpg | sudo apt-
key add -
5. 安装稳定存储库 sudo add-apt-repository \
"deb [arch=amd64] http://mirrors.aliyun.com/docker-ce/linux/ubuntu ∖
$(lsb_release -cs) \
 stable"
6. 更新并安装
dockers sudo apt update sudo apt install docker-ce docker-ce-cli
containerd.io
7. 查看dockers 信息
sudo docker info
8. 为了永久性保留更改,您可以修改 /etc/docker/daemon.json 文件并添加上 registry-
mirrors 键值
cat << EOF >> /etc/docker/daemon.json
"registry-mirrors": ["http://hub-mirror.c.163.com"]
}
EOF
9. 重启docker
systemctl daemon-reload && systemctl restart docker
```

4.服务器端安装

```
1. 启动prometheus
mkdir /opt/prometheus && cd /opt/prometheus
cat <<EOF> prometheus.yml
global:
 scrape_interval:
  evaluation_interval: 60s
scrape_configs:
 - job_name: prometheus
    static_configs:
      - targets: ['192.168.0.35:9090']
       labels:
         instance: prometheus
  - job_name: linux
    static_configs:
      - targets: ['192.168.0.35:9100']
       labels:
         instance: localhost
EOF
docker run -d \
  -p 9090:9090 \
  --restart=always \
  --name=prometheus \
  -v /opt/prometheus/:/etc/prometheus/ \
  prom/prometheus
测试 curl http://192.168.0.35:9090/graph
2. 启动grafana
mkdir /opt/grafana-storage && chmod 777 -R /opt/grafana-storage
docker run -d \
  -p 3000:3000 \
  --restart=always \
  --name=grafana ∖
  -v /opt/grafana-storage:/var/lib/grafana \
  grafana/grafana
 测试 curl http://192.168.0.35:3000
3. 启动node-exporter
  docker run -d -p 9100:9100 \
  --name=node-exporter \
  --restart=always \
  -v "/proc:/host/proc:ro" \
   -v "/sys:/host/sys:ro" \
  -v "/:/rootfs:ro" \
   --network=host \
  prom/node-exporter
4. 测试 curl http://192.168.0.35:9100/metrics
```

5、客户端安装配置

```
1. 启动node-exporter
docker run -d -p 9100:9100 \
--name=node-exporter \
--restart=always \
-v "/proc:/host/proc:ro"\
-v "/sys:/host/sys:ro" \
-v "/:/rootfs:ro" \
--network=host \
prom/node-exporter
测试 curl http://192.168.0.35:9100/metrics
2. 修改服务器端配置
cat <<EOF>> prometheus.yml
-- job_name: node-01
   static_configs:
    - targets: ['192.168.0.23:9100']
     labels:
       instance: zabbix-agent
EOF
```

```
- targets: ['192.168.0.23:9100']
labels:
instance: zabbix-agent
```

EOF

6、浏览器登录

```
http://192.168.0.35:3000
默认账号密码: admin / admin
Admin / 123123
```

7、常用模板 - https://grafana.com/grafana/dashboards

```
https://grafana.com/grafana/dashboards
https://grafana.com/grafana/dashboards/8919
https://grafana.com/grafana/dashboards/11074
https://grafana.com/grafana/dashboards/12227
https://grafana.com/grafana/dashboards/12377
```

8、注意事项

- job_name: node-01 ##节点名称 可看做一个组

static_configs: ##静态配置

- targets: ['192.168.0.23:9100'] ##配置被监控的主机+端口

labels: ##标签可省略

instance: zabbix-agent ##选择数据源,被监控主机不写

- job_name: node-01

static_configs:


-targets: ['192.168.0.23:9100']

##一般只需配置这三行即可

设置Granfana图形化表示流程


登陆http://localhost:9090,即可看到监控的主机

Targets





访问http://localhost:3000即可登陆Grafana

如下图点击Config



点击Add data source 选择数据源






填写 名称 URL 这里选择http请求方式为GET


添加数据源格式为 http://本机地址:9090

点击 Save & Test 即可测试保存

添加模块




点击import后点击Add new panel添加模板 在Import via grafana.com下面输出ID点击Load即可添加模块(本案例ID为8919) ## ID号举例 8919 11074 12227 12377 在可以连接互联网才可以



选择

名称、唯一标识符(uid)、默认放在Genearl的夹子里 选择数据源 Prometheus

最后点击 Import (导入)





Prometheus GPU监控

注:本实验是通过显卡驱动来获取显卡信息最后编辑Metrics的值,通过Grafana来显示出GPU的信息

1.安装 datacenter-gpu-manager_1.7.2_amd64.deb

```
拉取datacenter-gpu-manager_1.7.2_amd64.deb的软件包到本地
root@HBD907:~# dpkg -i datacenter-gpu-manager_1.7.2_amd64.deb
root@HBD907:~# nvidia-smi -L ##查看当前显卡驱动
```

```
##如果没有驱动则下载驱动root@HBD907:~# apt install -y ubuntu-drivers-common ubuntu-drivers devices#获取推荐显卡驱动
root@HBD907:~# apt-get install -y nvidia-driver-440 --fix-missing ##安装驱动
root@HBD907:~# nvidia-smi -L ##再次查看当前显卡驱动
GPU 0: GeForce RTX 2080 Ti (UUID: GPU-518560ea-0b35-5dec-0ffa-5d77816dcc82)
##看到GPU型号即可成功
```

2.为gpu-monitoring-tools安装依赖软件 golang

```
cat <<EOF>>~/.bashrc

export GOPROXY=https://goproxy.io

EOF

root@HBD907:~# source .bashrc

root@HBD907:~# add-apt-repository ppa:longsleep/golang-backports

root@HBD907:~# apt update

root@HBD907:~# apt install -y golang-go
```

3.安装gpu-monitoring-tools

```
root@HBD907:~# git clone https://github.com/NVIDIA/gpu-monitoring-tools.git
root@HBD907:~# cd gpu-monitoring-tools
root@HBD907:~# make binary

###返回信息:
go build -o dcgm-exporter github.com/NVIDIA/gpu-monitoring-tools/pkg
root@HBD907:~# make install

###返回信息:
go build -o dcgm-exporter github.com/NVIDIA/gpu-monitoring-tools/pkg
install -m 557 dcgm-exporter /usr/bin/dcgm-exporter
install -m 557 -D ./etc/dcgm-exporter/default-counters.csv /etc/dcgm-exporter/default-counters.csv
install -m 557 -D ./etc/dcgm-exporter/dcp-metrics-included.csv /etc/dcgm-exporter/dcp-metrics-included.csv
```

4.运行dcgm-exporter

```
root@HBD907:~# which dcgm-exporter
/usr/bin/dcgm-exporter ##查看dcgm-exporter命令路径
##进入gpu-monitoring-tools目录
root@HBD907:~/gpu-monitoring-tools# dcgm-expor
返回值如下:
INFO[0000] Starting dcgm-exporter
INFO[0000] DCGM successfully initialized!
INFO[0000] Pipeline starting
```

```
INFO[0000] Starting webserver
测试,可以看到监控的数据
root@HBD907:~# curl 192.168.6.21:9400/metrics
##ip地址为"客户端"dcgm-exporter的地址
```

5.设置dcgm-exporter开机启动

```
cat <<EOF>> /lib/systemd/system/dcgm-exporter.service
[Unit]
Description=dcgm-exporter service
[Service]
User=root
ExecStart=/usr/bin/dcgm-exporter
TimeoutStopSec=10
Restart=on-failure
RestartSec=5
[Install]
WantedBy=multi-user.target
EOF
systemctl daemon-reload
systemctl enable dcgm-exporter.service
systemctl start dcgm-exporter.service
systemctl status dcgm-exporter.service
```

6. 修改Prometheus 配置

```
在添加配置/opt/prometheus/prometheus.yml ##注意格式

- job_name: 'gpu' ##定义一个GPU的组
    static_configs:
    - targets:
    -"192.168.6.21:9400"

重启prometheus

systemctl restart 容器ID
```

使用12027模板

All dashboards » GPU-Nodes-Metrics



手动设置监控

导入ID为12027的模板默认无法识别节点

```
- job_name: gpu
static_configs:
    - targets:
    - "120.92.132.156:9400"
    - "192.168.0.49:9400"
```

因为我们的job_name为gpu所以要与主机名的语法对应



点击设置



点击hostname字段

+	← GPU监控 / Settings																
_	General	Variables >	Edit														
	Annotations																
	Variables	General															
	Links Versions	Name	me hostname				Query										
	Pernissions	Label	gpu_hos	t	Hide			١.									
_	JSON Model	Query Options															
_		Dalla source		Prometheus		iefresh	•	┢	On Dashboard Load								
8	ave dashboard	Query		label_values(DCGM_FLDEV_GPU_UTIL(job=100)), instance)													
	Save As	Begax ○ /A(4)-17															
		Sort		Alphabetical (case													

因为我们的job_name为gpu所以这里要对应否则无法显示节点

点击保存,应用。

手动插入指标

比如说为GPU使用率插入值 则点击Edit





将内容插入到Metrics这一行

查看抓取的数据

curl http://127.0.0.1:9400/metrics

指标如下

```
DCGM_FI_DEV_GPU_UTIL{instance=~"$hostname"}
                                              ##GPU使用率
DCGM_FI_DEV_FB_USED{instance=~"$hostname"} ## GPU 已用内存
DCGM_FI_DEV_FB_USED{instance=~"$hostname"}+DCGM_FI_DEV_FB_FREE{instance=~"$hostn
ame"}
# GPU 总内存`
DCGM_FI_DEV_GPU_TEMP{instance=~"$hostname"}
                                               ## GPU运行温度
平均值
GPU温度平均值 GPU Avg. Temperature
avg(DCGM_FI_DEV_GPU_TEMP{instance=~"$hostname"})
GPU 功率 GPU Total Power
sum(DCGM_FI_DEV_POWER_USAGE{instance=~"$hostname"})
GPU 内存使用率 GPU Total Mem Cpy Utilization
avg(DCGM_FI_DEV_MEM_COPY_UTIL{instance=~"$hostname"})
GPU 使用率 GPU Total Utilization
avg(DCGM_FI_DEV_GPU_UTIL{instance=~"$hostname"})
详细可看连接 https://blog.csdn.net/u010953692/article/details/107143338
```

```
项目实际部署

头机: 已部署Promrtheus
ip.txt ##监控主机IP地址
prometheus.sh 自动写Prometheus的配置文件

## node_export.sh docker节点自动部署node_exporter监控

## dcgm_dcgm_exporter.sh 节点自动部署 dcgm_exporter.sh

头机执行 prometheus.sh

被监控主机执行
node_exporter.sh和dcgm_exporter.sh
```

Prometheus实现钉钉告警

在 prometheus 中定义你的监控规则,即配置一个触发器,某个值超过了设置的阈值就触发告警, prometheus 会推送当前的告警规则到 alertmanager,alertmanager 收到了会进行一系列的流程处理,然后发送到接收人手里。

Alertmanager 主要用于接收 Prometheus 发送的告警信息,它支持丰富的告警通知渠道,例如邮件、微信、钉钉、Slack 等常用沟通工具,而且很容易做到告警信息进行去重,降噪,分组等,是一款很好用的告警通知系统。本案例是Prometheus通过webhook推送告警至钉钉

注:本项目基于安装Docker+Prometheus+Grafana和node_exporter的基础上

项目架构

192.168.6.1 Docker+Prometheus+Grafana+node_exporter

192.168.6.2 Docker+node_exporter


踩坑点

- 1. yaml语法较为严格切记要严谨所以添加内容尽量用 cat <<EOF>> 文件名 内容 EOF的方式写入
- 2. 在 cat <<EOF>> 文件名 内容 EOF 这的方式写入时 "summary: "{{\$labels.instance}}"这样 的配置会把 \$labels给漏掉需要检查配置文件 {{\$value }} 遇到这样的双括号的配置要注意检查!!!


创建钉钉机器人获得token

1.1 webhook

打开钉钉群点击群设置



##然后点击智能群助手



##点击添加机器人,添加自定义机器人



##上面的划线的Webhook 里面有钉钉的token

##这里我们选择"自定义关键词"

https://oapi.dingtalk.com/robot/send?access_token=771dbdc604e83dc044c4411521ec1d3b8760 958cb6fd464f762e1170dfdaa32e

1.2 docker部署(192.168.6.1操作)

```
docker pull timonwong/prometheus-webhook-dingtalk

# 启动容器

docker run -d \
-p 8060:8060 \
--name webhook timonwong/prometheus-webhook --
ding.profile=https://oapi.dingtalk.com/robot/send?
access_token=771dbdc604e83dc044c4411521ec1d3b8760958cb6fd464f762e1170dfdaa32e

##上面是我的token切莫盲目重复
```

2. 配置alertmanager

2.1 docker安装alertmanger

```
docker run -d \
--name alertmanager \
-p 9093:9093 \
-v /opt/alertmanager/:/etc/alertmanager/ \
prom/alertmanager:latest
```

2.2 alertmanager配置文件

```
alertmanager.yml

global:

resolve_timeout: 5
```

```
route:
    receiver: webhook

group_wait: 30s

group_interval: 1m

repeat_interval: 1m

group_by: [alertname]

routes:
    receiver: webhook

group_wait: 10s

receivers:
    - name: webhook

webhook_configs:
    - url: http://192.168.6.1:8060/dingtalk/webhook1/send

send_resolved: true
```

3. prometheus配置告警文件文件

3.1 修改prometheus-config.yml


```
alerting:
   alertmanagers:
   - static_configs:
   - targets: ["192.168.6.1:9093"]
rule_files:
   - "/opt/prometheus/rules.yml"
```

3.2 配置rules.yml文件**

```
cat <<EOF>> rules.yml
groups:
```

```
- name: test-rule
rules:
- alert: 主机状态
expr: up == 0
for: 5s
labels:
status: warning
annotations:
summary: "{{$labels.instance}}:服务器类闭"
description: "{{$labels.instance}}:服务器类闭"
```

##配置完rules.yaml文件重启prometheus就可以看到告警规则



##此时停止node_export或关机就会收到报警

