NITRO-Composer Sound Programmer Guide

Version 1.2.3

The contents in this document are highly confidential and should be handled accordingly.

© 2005 Nintendo NTR-06-0079-001-A9

Confidential

These coded instructions, statements, and computer programs contain proprietary information of Nintendo of America Inc. and/or Nintendo Company Ltd. and are protected by Federal copyright law. They may not be disclosed to third parties or copied or duplicated in any form, in whole or in part, without the prior written consent of Nintendo.

Table of Contents

1	Introdu	ction	7			
2	Sound	Program Development Environment	8			
-						
		le Organization				
	2.2.1	Library File				
	2.2.1	Header File				
	2.2.2	Sound Data				
	2.2.3	ARM7 Component				
3		mplementation Example				
		evelopment Environment				
	3.1.1	Makefile				
	3.1.2	ROM storage file				
	3.1.3	Operational Procedure				
	3.2 TI	ne NitroMain Function	10			
	3.3 B	asic setup	12			
	3.3.1	Initializing the OS and Other Processes	12			
	3.3.2	Initializing the Sound Library	12			
	3.3.3	Creating the Sound Heap	12			
	3.3.4	Initializing the Sound Archive	12			
	3.3.5	Setting Up the Player	13			
	3.3.6	Stream library initialization	13			
	3.3.7	Sound Frame Processing	13			
	3.4 Lo	pading Sound Data	13			
	3.4.1	Loading Groups	14			
	3.5 S	equence Operation	14			
	3.5.1	Sound Handles	14			
	3.5.1.	1 Using Sound Handles	14			
	3.5.1.2	What is a Sound Handle?	14			
	3.5.1.	3 Disconnecting the Sequence	14			
	3.5.1.	4 Tips for Creating Sound Handles	15			
	3.5.2	Sequence Playback	15			
	3.5.3	Sequence Archive Playback	15			
	3.5.4	Stopping the Sequence	15			
	3.6 O	ther Demos	16			
	3.6.1	stream	16			
	3.6.2	stream-2	16			
	3.6.3	stream-3	16			
	3.6.4	moveVolume	16			

	3.6.5	onMemory	16
	3.6.6	reverb	16
	3.6.7	effect	16
	3.6.8	outputEffect	17
	3.6.9	sampling	17
	3.6.10	waveout	17
	3.6.11	micThrough	17
	3.6.12	driverInfo	17
4	Hean (Operations	18
_	•	Overview	
		Memory Management Basics	
	4.2.1	The Sound Heap and the Player Heap	
	4.2.2	Appropriate Usage of the Two Heaps	
		Sound Heap Operations	
	4.3.1	Clearing the Heap	
	4.3.2	Restoring the Heap to the Previous State	
	4.3.3	Multiple Sound Heaps	19
	4.4 P	Player Heap Operations	20
	4.4.1	Deleting the Player Heap	20
5	Stream	n Playback	21
		nitializing the stream library	
	5.1.1	Stream thread	
	5.1.2	Stream buffer	
	_	Stream operations	
	5.2.1	The stream handle	
	5.2.1	Stream playback	
	5.2.3	Stopping a Stream	
	5.2.4	Pausing a Stream	
		void Interrupting Streams	
	5.3.1	Stream Thread	
	5.3.1.		
	5.3.1.		
	5.3.1.	·	
	5.3.1.		
	5.3.2	Accessing the Card / Backup Media	
	5.3.3	Stream Buffer	
	5.3.4	Simultaneous Playback	24
6	Caution	ns	25
	6.1 S	Sound Processes in Sleep Mode	25
	6.1.1	Playback Status After Being Awakened	25

6.	1.2 Wa	it While Stabilizing Operations After Being Awakened	25
7 Lik	orary Org	anization	26
7.1	Librar	y Organization	26
7.2	Playe	r Library	26
7.3	Sound	d Archive Player Library	27
7.4	Sound	d Archive Stream Library	28
7.5		n Library	
7.6		d Archive Library	
7.7		d Heap library	
7.8		re Library	
7.9	-	form Playback Library	
0	.,,,,		
Cod	le		
Co	ode 3-1	Makefile	9
Co	ode 3-2	The NitroMain Function	10
Co	ode 3-3	Initializing the Sound Library	12
Co	ode 3-4	Sound Heap Creation	12
Tab	les		
Ta	ble 7-1	Player Library Functions	Error! Bookmark not defined.
Та	ble 7-2	Sound Archive Player Library Functions	Error! Bookmark not defined.
Та	ble 7-3	Sound Archive Stream Library Functions	28
Ta	ble 7-4	Stream Library Functions	Error! Bookmark not defined.
Ta	ble 7-5	Sound Archive Library Functions	Error! Bookmark not defined.
Ta	ble 7-6	Sound Heap Library Functions	Error! Bookmark not defined.
Ta	ble 7-7	Capture Library Functions	Error! Bookmark not defined.
Та	ble 7-8	Waveform Playback Library Functions	Error! Bookmark not defined.
Figu	ırae		
	gure 4-1	Restoring the Previous State	19

Figure 7-1 Library Organization Diagram26

5

Revision History

Version	Revision Date	Description
1.2.3	03/28/2005	Added a description of the driverInfo demo
1.2.2	01/31/2005	Added a description of the micThrough demo
		Supplement to the description of the waveform playback library
		Changed "NITRO" to "Nintendo DS"
1.2.1	12/06/2004	Added the description of stream-2 and stream-3 demos
1.2.0	10/12/2004	Added description of changing to sleep mode
		Added description to avoid interrupting streams
		Added description of sampling demo and outputEffect demo
1.1.2	09/16/2004	Unified the name of .sadl files as "sound label files"
1.1.1	09/02/2004	Revised due to the change in the sample source code
1.1.0	08/10/2004	Added a description of stream playback
		Added a description of stream library
1.0.0	07/20/2004	Revised text to reflect the addition of the Waveform Playback Library
		Revised text to reflect the addition of effect functionality
		Changed the file extension from .bin to .srl
		Revised the description of the ARM7 component
0.4.0	6/1/2004	Revised text to reflect file system support
		Revised text to reflect the ability for a player to play multiple sequences
		Added description of heap operations
		Changed the library organization
0.3.0	04-01-2004	A complete organizational change was done.
		Added a description of the library organization
		Added an overview of the sample demo
0.2.0	03-18-2004	Fixed the makefile of the SoundPlayer
		Added cautions for OS_EnableIrqMask()
		Added a tempo change function
0.1.0	03-01-2004	Initial version

1 Introduction

This document provides programmers with fundamental information about developing sound programs on the Nintendo DS (DS).

The setup for the NITRO-Composer environment is explained. This is followed by an example that shows how to implement a sound program. The last section explains the structure of the sound library, and lists the type of provided functions.

For a detailed explanation of each function, refer to the function reference.

2 Sound Program Development Environment

2.1 NITRO System Build Environment

NITRO-Composer is part of the NITRO-System. By setting up the NITRO-System build environment, you will be able to use NITRO-Composer.

Refer to the NITRO-System documentation for details.

2.2 File Organization

2.2.1 Library File

The NITRO-SDK and NITRO-System library files listed below must be linked...

```
libsnd.a
libnnssnd.a
```

2.2.2 Header File

Header files that include definitions for created functions must be placed in an include statement using the following statement format:

```
#include <nnsys/snd.h>
```

By listing an include statement for the sound label file (*.sadl) created by the sound designer as shown below, the sound data can be specified using the label defined by the sound designer instead of the number.

```
#include "../data/sound data.sadl"
```

2.2.3 Sound Data

All sound data sets are stored in a single sound archive file that has the *.sdat file extension. Set the configuration to ensure that this sound archive file is stored in ROM. An example of how to store this file in ROM is shown in Chapter 3..

2.2.4 ARM7 Component

The ARM7 component is stored in the NitroSDK. The sound functionality must be implemented in the ARM7 component. If the ARM7 component is not specified explicitly, the component that implements the sound functionality will be used.

Sound Programmer Guide NITRO-Composer

Basic Implementation Example

This chapter demonstrates a basic implementation using Nitro-Composer for a project called simple. The simple project can be found in \$NitroSystem/build/demos/snd/simple.

3.1 **Development Environment**

This section explains how to set up the development environment.

3.1.1 Makefile

The following is an example makefile. Some of the comments have been omitted.

Code 3-1 Makefile

```
#! make -f
#-----
SRCS
                    main.c
TARGET NEF =
             main.nef
TARGET BIN = main.srl
MAKEROM ROMROOT = ../data
MAKEROM ROMFILES = sound data.sdat
include $(NITROSYSTEM ROOT)/build/buildtools/commondefs
do-build: $(TARGETS)
         $(NITROSYSTEM ROOT)/build/buildtools/modulerules
include
#==== End of Makefile =====
```

The basic elements of a makefile are not discussed in this section. Refer to the NITRO-SDK and NITRO-System manuals for makefile information. Setting the two MAKEROM .* variables is crucial.

3.1.2 ROM storage file

MAKEROM_ROMROOT defines the root directory in ROM. MAKEROM_ROMFILES defines the files to be stored in the root directory. In other words, the files that have the path ../data/sound_data.sdat are stored in ROM using the path directory and filename.

3.1.3 Operational Procedure

If the makefile in 3.1.1 is used, the program builds in the following sequence.

- The main.c file registered in SRCS compiles.
- The compiled file is linked to the library, which creates the ARM9 component main.
- The ARM9 component main combines with the ARM7 component and sound archive which creates main.srl
- The main.srl file becomes the executable file.

3.2 The NitroMain Function

First, examine the NitroMain function in src/main.c. Some of the comments have been omitted.

Code 3-2 The NitroMain Function

```
void NitroMain()
   OS Init();
   GX Init();
   // VBlank settings
   OS_SetIrqFunction(OS_IE_V_BLANK, VBlankIntr);
   (void) OS EnableIrqMask ( OS IE V BLANK );
   (void)OS EnableIrq();
   (void)GX VBlankIntr(TRUE);
FS Init ( MI DMA MAX NUM );
   // Initialize sound
   NNS SndInit();
   heap = NNS SndHeapCreate( & sndHeap, sizeof( sndHeap ) );
   NNS SndArcInit( &arc, "/sound data.sdat", heap, FALSE );
   (void) NNS SndArcPlayerSetup( heap );
   NNS SndArcStrmInit( STREAM THREAD PRIO, heap );
   // Load sound data
   (void) NNS SndArcLoadSeq( SEQ MARIOKART64 TITLE, heap );
   (void)NNS_SndArcLoadSeqArc( SEQ_SE, heap );
```

NTR-06-0079-001-A9 10 © 2005 Nintendo

```
(void) NNS SndArcLoadBank ( BANK SE, heap );
// Initialize sound handles
NNS_SndHandleInit( &bgmHandle );
NNS SndHandleInit( &seHandle );
// dummy pad read
Cont = PAD Read();
//===== Main Loop
while(1)
{
   u16 ReadData;
   SVC_WaitVBlankIntr();
   ReadData = PAD_Read();
   Trg = (u16)(ReadData & (ReadData ^ Cont));
   Cont = ReadData;
   if ( Trg & PAD BUTTON A ) {
// start BGM
       (void) NNS SndArcPlayerStartSeq(&bgmHandle, SEQ MARIOKART64 TITLE );
   if ( Trg & PAD_BUTTON_B ) {
// stop BGM
       (void) NNS SndPlayerStopSeq( &bgmHandle, 1 );
   }
   if ( Trg & PAD_KEY_UP ) {
// start SE
       (void) NNS SndArcPlayerStartSeqArc( &seHandle, SEQ SE, SE COIN );
   }
   //--- framework
   NNS SndMain();
```

The key points are described in subsequent sections.

}

3.3 Basic setup

This section explains fundamental functions--for example, library initialization.

3.3.1 Initializing the OS and Other Processes

First initialize the OS and other basic processes.

```
OS_Init();
GX_Init();

// VBlank settings
OS_SetIrqFunction(OS_IE_V_BLANK, VBlankIntr);
(void)OS_EnableIrqMask( OS_IE_V_BLANK );
(void)OS_EnableIrq();
(void)GX_VBlankIntr(TRUE);

FS_Init( MI_DMA_MAX_NUM );
```

3.3.2 Initializing the Sound Library

The sound library must be initialized before any NNS Snd functions are called.

Code 3-3 Initializing the Sound Library

```
NNS SndInit();
```

3.3.3 Creating the Sound Heap

Create the heap that is used to store sound data.

Code 3-4 Sound Heap Creation

```
heap = NNS_SndHeapCreate( &sndHeap, sizeof( sndHeap ) );
```

The first argument is the starting address in memory that is used for the sound heap. The second argument is the size of the sound heap.

The return value is the heap handle. The heap handle is used to allocate memory from the sound heap.

3.3.4 Initializing the Sound Archive

Initialize the sound archive. The sound archive structure must be allocated statically.

```
NNS SndArcInit( &arc, "/sound data.sdat", heap, FALSE );
```

The first argument is the sound archive structure. The second argument is the path to the sound archive on the ROM file system.

NTR-06-0079-001-A9 12 © 2005 Nintendo

Sound Programmer Guide NITRO-Composer

The third argument is the heap needed to allocate memory for initialization of sound archives, and the sound heap handle that was just created is used. Note that if the allocated memory is released, the sound archive will no longer be usable.

The fourth argument is a flag that controls the loading of symbol data in the sound archive. If the argument is set to True, symbol data is used for debugging. Set the argument to FALSE for standard initialization.

3.3.5 Setting Up the Player

Set up the player.

```
NNS SndArcPlayerSetup( heap );
```

The player settings in the sound archive determine the setup.

Because the player setup requires memory, enter the heap handle as an argument.

3.3.6 Stream library initialization

To do stream playback, the stream library must be initialized.

```
NNS SndArcStrmInit( STREAM THREAD PRIO, heap );
```

For details on streams, see Chapter 5.

3.3.7 Sound Frame Processing

Perform sound library frame processing. This function should be called once for each frame. The location of the function call is not important.

```
NNS SndMain();
```

Loading Sound Data 3.4

Before playing a sound sequence, the sound data must be loaded.

```
(void) NNS SndArcLoadSeq( SEQ MARIOKART64 TITLE, heap );
(void) NNS SndArcLoadSeqArc( SEQ SE, heap );
(void) NNS SndArcLoadBank ( BANK SE, heap );
```

NNS SndArcLoadSeq loads the data that is required to play the sequence SEQ MARIOKART64 TITLE. This function concurrently loads the bank and waveform data in addition to the sequence data.

NNS SndArcLoadSeqArc loads the SE sequence archive. Because sequence archives are associated with multiple banks, bank and waveform data are not loaded automatically. The following

© 2005 Nintendo 13 NTR-06-0079-001-A9 function, NNS_SndArcLoadBank, loads the bank data for SE. With this function, both the bank and waveform data are loaded. Therefore, it is unnecessary to load waveform data separately.

3.4.1 Loading Groups

Sound data is not normally loaded alone, unlike the example. If the sound designer defines a group, the group can be loaded as shown in the following example.

```
(void) NNS SndArcLoadGroup( GROUP STATIC, heap );
```

The group defines which data sets to load. By calling NNS_SndArcLoadGroup, all the data sets are loaded at once. By loading groups, the data can be loaded without changing the code in the program.

3.5 Sequence Operation

3.5.1 Sound Handles

3.5.1.1 Using Sound Handles

A sound handle is required to work with a sequence:

```
NNSSndHandle bgmHandle;
NNSSndHandle seHandle;
```

Temporarily allocate a sound handle statically. Before using a sound handle, initialize it with the following function.

```
void NNS SndHandleInit( NNSSndHandle* handle );
```

3.5.1.2 What is a Sound Handle?

A sound handle is an object that controls the sequence after playback. A sound handle can control one sequence. If a sequence playback is successful, that sequence will be linked to a sound handle. From that point and until that link is disconnected, operations for that sound handle will operate the sequence.

3.5.1.3 Disconnecting the Sequence

Sometimes a sequence is manually or automatically disconnected. A sequence can be automatically disconnected if a second sequence attempts to start when a player can play only one sequence., The played back sequence is forcibly stopped. Under these circumstances, the sound handle is involuntarily disconnected from the sequence and disabled. Even if operations are performed on a disabled sound handle, no processing will occur.

This means that the programmer does not need to check if the sequence they played back is still playing. Even if the same process is executed while the sequence is being played or the sequence is stopped, there will be no problems, such as a separate sequence being operated by error.

NTR-06-0079-001-A9 14 © 2005 Nintendo

Sound Programmer Guide NITRO-Composer

3.5.1.4 **Tips for Creating Sound Handles**

When sound is played back without any pauses, as with one-shot sound effects, the same sound handle can be used to play repeated sounds. All sounds can be played simultaneously as long as the number does not exceed the maximum number of simultaneous sequences that are allowed. Each parameter can be changed separately immediately after the playback occurs.

Because continuous sounds such as background music or engine noises must be stopped, each of these sound effects requires a separate sound handle.

3.5.2 Sequence Playback

The following function plays back a sequence:

```
BOOL NNS SndArcPlayerStartSeq( NNSSndHandle* handle, int seqNo );
```

seqNo is the sequence number, and the sounds are ordered as they appear in the sound archive.

If the function executes, the sequence links to a sound handle that is passed in as an argument. From this point, this sound handle can be used to carry out processes (e.g., stopping the sequence).

If the sound handle is already linked to a sequence, the connection to the original sequence is disconnected and the sound handle connects to the new sequence. Because the sequence that disconnects from the sound handle can no longer be controlled directly, be careful; however, when there is no need to control the sequence in the future—for example, when a one-shot sound effect is played – no special requirements are needed.

```
if ( Trg & PAD BUTTON A ) {
(void) NNS SndArcPlayerStartSeq(&bgmHandle, SEQ MARIOKART64 TITLE );
}
```

3.5.3 Sequence Archive Playback

The following function plays back the sequence from the sequence archive:

```
BOOL NNS SndArcPlayerStartSegArc(
NNSSndHandle* handle, int segArcNo, int index );
```

segArcNo is the sequence archive number, which is the order of the sequences in the sound archive. index is the index number of the sequence in the sequence archive. The rest is the same as the playback of the sequence.

```
if ( Trg & PAD KEY UP ) {
(void) NNS SndArcPlayerStartSeqArc( &seHandle, SEQ SE, SE COIN );
```

3.5.4 Stopping the Sequence

The following function stops the sequence:

```
void NNS SndPlayerStopSeq( NNSSndHandle* handle, int fadeFrame );
```

© 2005 Nintendo 15 NTR-06-0079-001-A9 Enter the sound handle passed into NNSSndHandle when played back to handle. fadeFrame is the fadeout frame. The volume level gradually decreases over the specified number of frames.

```
if ( Trg & PAD_BUTTON_B ) {
  (void) NNS_SndPlayerStopSeq( &bgmHandle, 1 );
}
```

3.6 Other Demos

No descriptions for the functions that are used with the simple demo are described. This section contains an overview of other demos. The demo programs for NITRO-Composer are all stored under \$NitroSystem/build/demos/snd.

3.6.1 stream

Plays back streams. Stream playback is explained in Chapter 5.

3.6.2 stream-2

Combines multiple stream data in real time and plays back. It registers the callback function that performs the combining process by using the NNS SndArcStrmStartEx2 function.

3.6.3 stream-3

Applies effects to the stream and plays back. It registers the callback function that processes effects by using the NNS SndArcStrmStartEx2 function.

3.6.4 moveVolume

Changes the volume of a sequence over a period of time.. This demo uses the NNS_SndPlayerMoveVolume () function to change the volume. It includes code for a fade-in playback.

3.6.5 onMemory

The entire sound archives that are loaded into memory. For that purpose, the sound archives are initialized with NNS SndArcInitOnMemory() function.

3.6.6 reverb

A reverb demo that uses the capture feature. This demo uses $\mbox{NNS_SndCaptureStartReverb}$ and $\mbox{NNS_SndCaptureStopReverb}$.

3.6.7 effect

An effects demo that uses the sound capture feature. It passes the output through a simple low-pass

NTR-06-0079-001-A9 16 © 2005 Nintendo

Sound Programmer Guide NITRO-Composer

filter (moving average).

This demo uses NNS SndCaptureStartEffect and NNS SndCaptureStopEffect.

3.6.8 outputEffect

Effects demo that uses the sound capture feature. Switches between the surround mode and the headphones mode for output.

It uses the NNS_SndCaptureStartOutputEffect and NNS_SndCaptureChangeOutputEffect functions.

3.6.9 sampling

Sampling demo that uses the sound capture feature. Calculates output levels using sampling data for the display.

It uses NNS_SndCaptureStartSampling and other functions.

3.6.10 waveout

Plays waveform data directly instead of using sequence playback. It plays back sounds recorded with a microphone. Uses NNS SndWaveOutStart for the playback of waveform data.

3.6.11 micThrough

Uses the low-level stream library NNS_SndStrm. Plays back real-time input from the microphone and applies effects to output sounds.

This demo uses NNS SndStrmSetup and NNS SndStrmStart.

3.6.12 driverInfo

Displays on-screen sound driver information.

The sound driver information is updated with NNS_SndUpdateDriverInfo, and the player information in the sound driver can be obtained with NNS_SndPlayerReadDriverPlayerInfo.

4 Heap Operations

4.1 Overview

In the simple demo, memory management functions are not used. In the simple demo, only the sound heap is created using NNS SndheapCreate during initialization, and data is loaded into the memory.

The heap operations are explained in subsequent sections.

4.2 Memory Management Basics

For information about the basics of memory management, see the Sound System Manual. The following is a brief explanation about memory management.

4.2.1 The Sound Heap and the Player Heap

There are two heaps: the sound and player heap.

The sound heap is a stack-based heap that programmers use for loading and deleting data.

The player heap is used for loading data automatically during the sequence playback. Programmers do not need to work directly with the player heap.

4.2.2 Appropriate Usage of the Two Heaps

The sound heap loads relatively large blocks of data at system startup and during scene changes. The player heap loads relatively small blocks of data (e.g., BGM data) during sequence playback.

Even though sound and player heap are generally used in this way everything can be managed in the sound heap to improve the load efficiency.

4.3 Sound Heap Operations

Because the sound heap is stack-based, memory is allocated from the top to the bottom and is released from the bottom to the top. Memory is allocated automatically from the heap when sound data loads. To delete unwanted sound data, the memory regions must be released. There are two ways to release memory regions:

- Clearing the heap.
- Restoring the heap to the previous state.

4.3.1 Clearing the Heap

All of the sound data can be cleared from the heap. This process is very simple, but when the used

Sound Programmer Guide NITRO-Composer

function is executed, all playing sounds will stop. If the memory region that is used for the initialization of the sound archive is released, the sound archive will no longer be available.

To clear all sound data from the heap, call the NNS SndHeapClear function.

4.3.2 Restoring the Heap to the Previous State

Restoring the heap to the previous state is used more frequently than clearing the heap..

NNS SndHeapSaveState saves the current state. After saving, the return value is the hierarchy level of the heap. The hierarchy level indicates the value for the state that was saved. The hierarchy level value can be used to restore the sound heap to the saved state.

After loading several blocks of sound data, calling NNS SndHeapLoadState by passing the hierarchy level value will return the heap to the state that it was in immediately after the call was made to NNS SndHeapSaveState. In other words, all data that was loaded after the call to NNS SndHeapSaveState is deleted.

NNS SndHeapSaveState Load Sound Data NNS SndHeapLoadState Loaded Loaded Loaded Loaded Sound Data Sound Data Sound Data Sound Data Newly Loaded Sound Data Level 0 Level 1 Level 1 Level 1

Figure 4-1 Restoring the Previous State

When the data is deleted, already loaded sounds will not be stopped.

Also, NNS SndHeapSaveState can be called repeatedly, and the value of the hierarchy level will increase each time the function is called.

4.3.3 **Multiple Sound Heaps**

Usually a single sound heap is used to restore the heap, but multiple sound heaps can be also used to restore different heap states. If there are several sound heaps, each sound heap can save and restore an individual state.

To use multiple sound heaps, you only need to create multiple heaps using NNS_SndHeapCreate. When allocating memory for a sound heap, the heap handle must always be specified. To allocate the memory, specify the sound heap by passing the heap handle return value as the argument of the function.

4.4 Player Heap Operations

Normally, the programmer does not have to manage the player heap. The player heap is created using the following function.

```
BOOL NNS SndArcPlayerSetup( NNSSndHeapHandle heap);
```

The sound designer sets the size of the heap needed by the player. The amount of memory is allocated from the sound heap and is passed as an argument in the function to create the player heap.

4.4.1 Deleting the Player Heap

The player heap allocates memory from the sound heap. When the memory region that is allocated to the player heap is released, the player heap is automatically deleted.

Sound Programmer Guide NITRO-Composer

5 Stream Playback

This chapter explains stream playback, which was not included in the simple demo.

5.1 Initializing the stream library

To play a stream, the stream library must be initialized.

```
NNS SndArcStrmInit( STREAM THREAD PRIO, heap );
```

The first argument is the stream thread priority. The second argument is the sound heap handle, which is used to allocate the stream buffer.

5.1.1 Stream thread

The stream thread is a thread that loads the data from ROM when necessary.

Data is loaded while stream playback is played; the sound stops if the data is not loaded in time. Therefore, the data must be loaded quickly. When a stream thread needs to load data, a stream thread can interrupt other processes running on the main loop of the game and load the data.

If you want the stream thread to interrupt the main processing loop and load data, the stream thread must be assigned a higher thread priority. The main loop (main thread) has a default value of 16 Therefore, specify a value that is less than 16.

5.1.2 Stream buffer

To play a stream, a buffer is required to load data. To play a single stream, the buffer needs approximately 2 to 4 KB of memory. This buffer uses part of the sound heap and is passed as the second argument in the function.

Note that once the stream buffer is released, the stream cannot be played.

5.2 Stream operations

5.2.1 The stream handle

Just as a sound handle is necessary to play a sequence, a stream handle is required to play a stream.

```
NNSSndStrmHandle strmHandle;
```

The stream handle should be allocated statically for now. Before using the stream handle, initialize a stream function with the following function.

```
void NNS SndStrmHandleInit( NNSSndStrmHandle* handle );
```

In other respects, a stream handle is identical to a sound handle.

5.2.2 Stream playback

To play back a stream, call the following function.

```
BOOL NNS_SndArcStrmStart( NNSSndStrmHandle* handle, int strmNo, u32 offset );
```

strmNo is the stream number that specifies which stream to play. offset specifies in milliseconds when to start playing back in the stream data. Playback generally starts at the beginning of the stream, so set this parameter to zero.

Similar to a when using a sequence, the stream handle is bound to the stream if playback is successful.

5.2.3 Stopping a Stream

To stop a stream, call the following function.

```
void NNS SndArcStrmStop( NNSSndStrmHandle* handle, int fadeFrames );
```

fadeFrames specifies the number of frames over which the volume should be gradually lowered before the stream stops. If fadeFrames is set to a value of zero, the stream stops immediately.

5.2.4 Pausing a Stream

There is no function to pause a stream. However, a process similar to pausing a stream is possible. The following procedure allows you to create the effect of pausing.

1. When you want to pause the stream, use the following function to obtain the current position of playback.

```
u32 NNS SndArcStrmGetCurrentPlayingPos( NNSSndStrmHandle* handle );
```

NTR-06-0079-001-A9 22 © 2005 Nintendo

Sound Programmer Guide NITRO-Composer

- 2. Use NNS SndArcStrmStop to stop the stream.
- 3. Restart the stream playback by passing the playback location as the offset argument of NNS_SndArcStrmStart and start the stream playback. The playback will start from where the stream stopped.

The stream will not restart at the precise position in the stream.

5.3 Avoid Interrupting Streams

With stream playback, data is loaded in real-time; therefore, if the sound is not loaded in time, the sound will be interrupted. Here are some tips to avoid interrupting streams.

5.3.1 Stream Thread

Stream data is loaded with the stream thread. The basic rule is to maintain stream thread processes without delay.

Here are some circumstances that cause delays in the stream thread processes.

5.3.1.1 Disabling Interrupts

Stream threads cannot run while interrupts are disabled. Interrupts should be disabled only for short periods of time.

5.3.1.2 DMA

Stream threads cannot run while DMA is running. By dividing a large DMA into chunks, the delay in stream thread processes can be reduced.

5.3.1.3 Interrupt Handler Process

Stream threads cannot run while an interrupt handler is being processed. Interrupt handler processes should last only for short periods of time.

5.3.1.4 Higher Priority Threads

Stream threads cannot run while higher priority threads are being processed. Higher priority thread processes need to last only for short periods of time or the priority of stream threads needs to be raised.

5.3.2 Accessing the Card / Backup Media

Stream data cannot be loaded while the card or backup media is accessed. Therefore, divide the bandwidth between the card and stream data.

5.3.3 Stream Buffer

If the buffer size for stream playback is large, the sound will not be interrupted even if the stream thread process speed is reduced. However, when the buffer size is larger, the process for one stream

thread requires more bandwidth, and a negative effect on the lower priority threads may occur.

5.3.4 Simultaneous Playback

When multiple streams are played simultaneously, the stream thread processes increase and require more bandwidth. The sound may be interrupted even with a short delay in the processes. Exercise caution when playing back multiple streams simultaneously.

Sound Programmer Guide NITRO-Composer

6 Cautions

6.1 Sound Processes in Sleep Mode

When changing into sleep mode, sound processes are executed automatically in the library. Programmers only need to call $PM_GosleepMode$, and the rest of the processes are performed by the library.

However, pay attention to the information in the following sections for Sleep Mode.

6.1.1 Playback Status After Being Awakened

The playback status after being awakened from sleep mode may not match the playback status before entering sleep mode. The sound may temporarily become distorted or skip.

When this problem becomes severe, the programmer needs to stop playback before entering sleep mode and restart playback after being awakened.

6.1.2 Wait While Stabilizing Operations After Being Awakened

After awakening from sleep mode, the sound circuitry becomes stable after 15 msecs. The wait time is processed inside the library function, PM_GosleepMode. Therefore, programmers do not need to pay attention to the wait time.

7 Library Organization

This chapter describes the organization of the NITRO-Composer library.

7.1 Library Organization

The NITRO-Composer library composes several libraries as shown below:

Sound Archive Sound Archive Plaver Stream NNS_SndArcPlayer NNS SndArcStrm Sound Archive NNS SndArc Player Stream Waveform Playback Capture NNS_SndPlayer NNS_SndStrm NNS_SndWaveOut NNS_SndCapture Sound Heap NNS_SndHeap Sound Driver Interface (ARM9) Sound Driver (ARM7)

Figure 7-1 Library Organization Diagram

The libraries with NNS_Snd prefixes are the sound libraries included in NitroSystem. Usually, the programmer uses these library functions. The libraries are described in the following sections.

7.2 Player Library

The Player Library is the most basic library for playing back sequences. The function prefix set is NNS_SndPlayer.

This library is used to change parameters for sequences and stopping sequences. However, the sound archive player functions from the upper library are used for only playback. The sequence playback functions in the player library are used to simply run sequences. For actual sequence playback, complex processing (e.g, data loading) is required. Therefore, sequence playback is processed with the sound archive player.

Sound Programmer Guide NITRO-Composer

The player library also includes some functions that operate the sound handles. The function set prefix is NNS SndHandle. The sound handle and player are closely related. Refer to section 3.5.1 Sound Handle for an overview of the sound handle.

The main functions of the Player Library are shown in Table 7-1.

Table 7-1 Player Library Functions

Function Name	Description
NNS_SndPlayerStopSeq	Stops the sequence.
NNS_SndPlayerPause	Pauses or restarts the sequence.
NNS_SndPlayerSetTempoRatio	Changes the tempo of the sequence.
NNS_SndPlayerSetVolume	Changes the volume of the sequence.
NNS_SndPlayerSetTrackVolume	Changes the volume of the sequence track.
NNS_SndPlayerSetTrackPitch	Changes the pitch of the sequence track.
NNS_SndPlayerSetTrackPan	Changes the pan (location) of the sequence track.

Sound Archive Player Library 7.3

The Sound Archive Player Library plays back the sequence using the sound archive. The function set prefix is NNS_SndArcPlayer.

The Sound Archive Player Library is located in the upper-level libraries of the player library and the sound archive library. Sequences can be easily played back using these functionalities.

The main functions of the Sound Archive Player Library are shown in Table 7-2.

Table 7-2 Sound Archive Player Library Functions

Function Name	Description
NNS_SndArcPlayerSetup	Sets up the player using the settings in the sound archive.
NNS_SndArcPlayerStartSeq	Plays back the sequence.
NNS_SndArcPlayerStartSeqArc	Plays back the sequence archive.

7.4 Sound Archive Stream Library

Sound Archive Stream Library is used to play stream data in a sound archive. The function names begin with NNS SndArcStrm.

This library is a upper-level library of the stream library and the sound archive library. The Sound Archive Stream Library uses the functionality of the stream library and the sound archive library to make playing streams simple.

The main functions of the Sound Archive Stream Library are shown in Table 7-3.

Table 7-3 Sound Archive Stream Library Functions

Function Name	Description
NNS_SndArcStrmInit	Initializes the sound archive stream library.
NNS_SndArcStrmStart	Plays a stream.
NNS_SndArcStrmStop	Stops a stream.

7.5 Stream Library

The Stream Library is a low-level library for the playback of streams. The function names begin with NNS SndStrm.

This library is used to play data that is received through communications in real time and for stream playback of waveform data in unique stream data format.

The main functions of the Stream Library are shown in Table 7-4.

Table 7-4 Stream Library Functions

Function Name	Description
NNS_SndStrmInit	Initializes a stream.
NNS_SndStrmAllocChannel	Allocates a channel for stream playback.
NNS_SndStrmFreeChannel	Frees a stream playback channel.
NNS_SndStrmSetup	Prepares for stream playback.
NNS_SndStrmStart	Plays a stream.
NNS_SndStrmStop	Stops a stream.

Sound Programmer Guide NITRO-Composer

7.6 **Sound Archive Library**

The Sound Archive Library loads sound data in the sound archives and retrieves parameters. The function set prefix is NNS SndArc.

The main functions of the Sound Archive Library are shown in Table 7-5.

Table 7-5 Sound Archive Library Functions

Function Name	Description
NNS_SndArcInit	Initializes a sound archive.
NNS_SndArcLoadGroup	Loads sound data in units of the group.

Sound Heap library 7.7

The Sound Heap Library manages the sound heap. The function set prefix is NNS SndHeap.

The main functions of the Sound Heap Library are shown in Table 7-6.

Table 7-6 Sound Heap Library Functions

Function Name	Description
NNS_SndHeapCreate	Creates the sound heap.
NNS_SndHeapClear	Clears all heap memory.
NNS_SndHeapSaveState	Saves the heap state.
NNS_SndHeapLoadState	Restores the heap state.

Capture Library 7.8

Nintendo DS has the sound capture feature. The Capture Library is used for generating effects using the capture feature (e.g., reverb). The function set prefix is NNS SndCapture.

The main functions of the Capture Library are shown in Table 7-7.

Table 7-7 Capture Library Functions

Function Names	Description
NNS_SndCaptureStartReverb	Starts the reverb.
NNS_SndCaptureStopReverb	Stops the reverb.
NNS_SndCaptureStartEffect	Starts the effect.
NNS_SndCaptureStopEffect	Stops the effect.

7.9 Waveform Playback Library

The Waveform Playback Library provides functionality to play waveform data without using sequence playback. The function set prefix is NNS SndWaveOut.

The Waveform Playback Library is used for playing sampled data captured with a microphone. Use this stream library to play back waveform data that is generated in real time.

The main functions of the Waveform Playback Library are shown in Table 7-8.

Table 7-8 Waveform Playback Library Functions

Function Names	Description
NNS_SndWaveOutAllocChannel	Allocates a channel for playing waveform.
NNS_SndWaveOutStart	Starts waveform playback.
NNS_SndWaveOutStop	Stops waveform playback.

© 2005 Nintendo

The contents of this document cannot be duplicated, copied, reprinted, transferred, distributed or loaned in whole or in part without the prior approval of Nintendo.