ranger配置从Idap获取用户和组&配置hive(导出)

1dap安装及配置:



slap.conf:

database definitions

database bdb

suffix "dc=asiainfo,dc=com"

checkpoint 1024 15

rootdn "cn=root, dc=asiainfo, dc=com"

Cleartext passwords, especially for the rootdn, should

be avoided. See slappasswd(8) and slapd.conf(5) for details.

Use of strong authentication encouraged.

rootpw secret

rootpw {crypt}ijFYNcSNctBYg

#rootpw {SSHA}KxwI67Nyx7DcIZ0CF2VZ8f1zehuxKi1k

Idapsearch -x -b 'dc=asiainfo,dc=com'

cd /usr/hdp/current/ranger-usersync/ldaptool/conf

配置: input.properties

ranger.usersync.ldap.url=ldap://ochadoop09:389

ranger.usersync.ldap.binddn=cn=root,dc=asiainfo,dc=com

 $ranger.\,usersync.\,1dap.\,1dapbindpassword=123456$

Mandatory only for openLdap

ranger.usersync.ldap.user.searchbase=ou=People,dc=asiainfo,dc=com

ranger.usersync.ldap.user.searchfilter=cn=*

 $\mbox{\tt\#}$ For verifying authentication please provide sample username and password

ranger.admin.auth.sampleuser=usertest ranger.admin.auth.samplepassword=usertest

Optional properties will be determined based on the above search

User attributes

ranger.usersync.ldap.user.nameattribute=uid

ranger.usersync.ldap.user.objectclass=posixAccount

ranger.usersync.ldap.user.groupnameattribute=memberof, ismemberof


Group attributes

```
ranger.\ usersync.\ group.\ searchenable d=true
ranger.\,usersync.\,group.\,member attribute name = member Uid
ranger.usersync.group.nameattribute=cn
ranger.usersync.group.objectclass=posixGroup
ranger.usersync.group.searchbase=ou=Group,dc=asiainfo,dc=com
ranger.usersync.group.searchfilter=cn=*
# Other UserSync related attributes
ranger.\,usersync.\,ldap.\,authentication.\,mechanism=simple
ranger.\,usersync.\,pagedresultsenabled \!\!=\! true
ranger.\,usersync.\,pagedresultssize = 500
ranger.usersync.ldap.username.caseconversion=lower
ranger.usersync.ldap.groupname.caseconversion=lower
ranger.usersync.ldap.user.searchscope=sub
ranger.\,usersync.\,group.\,search scope = sub
ranger.usersync.credstore.filename=
ranger.usersync.ldap.bindalias=
ranger.usersync.ldap.searchBase=
ranger.usersync.group.usermapsyncenabled=false
# Authentication properties
ranger.\,authentication.\,method =
ranger.ldap.ad.domain=
ranger.ldap.user.dnpattern=
ranger.ldap.group.roleattribute=
ranger.ldap.group.searchbase=
ranger.ldap.group.searchfilter=
```

测试ldap是否可用:


./run.sh -r all -i conf/input.properties

如果可以执行则ldap可用,可以在ambari界面进行相关配置。



sub		
Jser Group Name Attribute		
memberof, ismemberof		
Group User Map Sync Yes		
Common Configs User Configs	Group Configs	
Enable Group Sync		
Yes		
Group Member Attribute		
memberoid		
Group Name Attribute		
cn		
Group Object Class		
posixGroup		
Group Search Base		
ou=Group,dc=asiainfo,dc=com		
Group Object Class		_
posixGroup		
Group Search Base		
ou=Group,dc=asiainfo,dc=com		
Group Search Filter		

hive配置ldap认证:





ldap添加用户:

cat /etc/passwd |grep usertest > testpwd.in /usr/share/migrationtools/migrate_passwd.pl testpwd.in > testpwd.ldif

Idapadd -x -D "cn=root,dc=asiainfo,dc=com" -w 123456 -f testpwd.ldif

Idapsearch -x -b 'dc=asiainfo,dc=com'



这个参数没有作用。重启一下Ranger Usersync 新加的用户立刻就可以同步到ranger。