

User Manual (Implementation Guide)

UN/EDIFACT MESSAGE

COREOR

Import Container Release Message

Version 1.0

D95B

Message Version : ITIGG 1.4
Manual Version : 1.0 rev. 1
Date : May 2007
Source : EUREDIOPS

Introduction

This user manual (Message Implementation Guide) has been developed by Maersk Line to assist interested EDI partners in developing and implementing the UN/EDIFACT COREOR message with Maersk Line.

This user manual is based on the UN/EDIFACT D.95B directory and the International Transport Implementation Guidelines Group (ITIGG) document "International reference Guideline for the Implementation of Transport EDI Messages – COREOR Import Container Release message", version 1.4, dated March 1998, document reference JM4/ITIGG/107v14. This user manual and the actual COREOR messages send by Maersk Line are not fully compliant with ITIGG rules and recommendations.

General

The COREOR message is to be used as an order to release containers, and giving permission for them to be picked up by or on behalf of a specified party.

Document maintenance

Any remarks, questions, amendments or requested alterations to this document are to be addressed to :

Maersk Benelux B.V. Attn. Jacco Bruijnes P.O. Box 240 3000 DH Rotterdam The Netherlands

Phone : +31 10 712 7620 Fax : +31 10 712 7609

e-mail: eurediops@maersk.com

Message: COREOR 2 May 2007

Version : 1.0 rev. 1 / D.95B

Source : Maersk Line / EUREDIOPS

Status indicators and usage indicators

Status Indicators

Status Indicators (M and C) form part of the UN/EDIFACT standard and indicate a minimum requirement to fulfil the needs of the message structure.

The Status Indicators are:

Value	Description
М	Mandatory This entity must appear in all messages. Shown as Usage Indicator "M" in Implementation Guidelines.
С	Conditional This entity is used by agreement between the parties to the transaction.

A 'Conditional' Status Indicator may be represented by a supporting Usage Indicator which is either R, O, D or X (see below)

Usage Indicators

Throughout this document reference is made to indicators (M, R, D, O and X) which are shown adjacent to data items and which dictate for the particular message or set thereof the agreed usage of the data items or entities.

Set out below are the indicators and their respective uses:-

Value	Description
М	Mandatory Indicates that this item is mandatory in the message.
R	Required Indicates that this entity must be sent in this implementation.
D	Dependent Indicates that the use of the entity depends upon a well-defined condition or set of conditions. These conditions must be clearly specified in the relevant implementation guideline.
0	Optional Indicates that this entity is at the need or discretion of the sender of the message.
Χ	Not Used Indicates that the entity is not to be used is this message implementation.

Message : COREOR 3 May 2007


COREOR Container Release Order Message

Introduction:

Order to release containers, and giving permission for them to be picked up by or on behalf of a specified party. This message is part of a total set of container-related messages. These messages serve to facilitate the intermodal handling of containers by streamlining the information exchange. The business scenario for the container messages is clarified in a separate document, called: 'Guide to the scenario of EDIFACT container messages'.

М	Pos. No. 0010	Seg. <u>ID</u> UNH	<u>Name</u> Message Header	Req. <u>Des.</u> M	Max.Use	Group <u>Repeat</u>	Notes and Comments
М	0020	BGM	Beginning of Message	М	1		
R	0040	RFF	Reference	С	9		
M	0050		Segment Group 1: TDT-RFF	М		1	
M	0060	TDT	Details of Transport	М	1		
0	0070	RFF	Reference	С	9		
М	0100		Segment Group 2: NAD	М		9	
М	0110	NAD	Name and Address	М	1		
R	0320		Segment Group 7: EQD-RFF-DTM- SG8	С		999	
M	0330	EQD	Equipment Details	М	1		
0	0423	DTM	Date/Time/Period	С	1		
0	0425		Segment Group 8: TDT	С		9	
М	0440	TDT	Details of Transport	М	1		
М	0520	CNT	Control Total	М	1	•	
М	0530	UNT	Message Trailer	M	1		

Message : COREOR 4 May 2007



Message : COREOR
Version : 1.0 rev. 1 / D.95B
Source : Maersk Line / EUREDIOPS 5 May 2007

9 ω 41 S

Segment: **UNH Message Header**

Position: 0010

> Group: Level: 0

Usage: Mandatory

Max Use:

Purpose: A service segment starting and uniquely identifying a message. The

message type code for the Container release order message is

COREOR.

Note: Container release order messages conforming to this document must contain the following data in segment UNH, composite S009: Data element 0065 COREOR 0052 D 0054 95B

0051 UN

UNH+3000001+COREOR:D:95B:UN' **Comments:**

Data Element Summary

Data Component

	Element	Element	<u>Name</u>		<u>Att</u>	ributes
M	0062		MESSAGE REF	ERENCE NUMBER	M	an14
			Unique messa	ge reference assigned by the	sen	der. This
			reference mus	st also be transmitted in the U	JNT :	segment.
M	S009		MESSAGE IDE	NTIFIER	M	
M		0065	Message type	identifier	M	an6
			COREOR	Container release order messag	је	
M		0052	Message type	version number	M	an3
			D	Draft version/UN/EDIFACT Dire	ctory	/
M		0054	Message type	release number	M	an3
			95B	Release 1995 - B		
M		0051	Controlling ag	•	M	an2
			UN	UN/ECE/TRADE/WP.4, United N	latior	าร
				Standard Messages (UNSM)		
X		0057	Association as	_	C	an6
X	0068		COMMON ACC	ESS REFERENCE	C	an35
X	S010		STATUS OF TH	IE TRANSFER	C	
X		0070	<u>-</u>	ssage transfer number	M	n2
X		0073	First/last sequindication	uence message transfer	С	a1

Message : COREOR 6 May 2007

Segment: BGM Beginning of Message

Position: 0020

Group:

Level: 0

Usage: Mandatory

Max Use: 1

Purpose: A segment to indicate the beginning of a message and to transmit

identifying number and the further specification of the message type (in data element 1001: Document/message name, coded), such as

Container release order.

Comments: BGM+12+20070309104848+1'

Data Element Summary

Data Component Element Element Name Attributes R C002 **DOCUMENT/MESSAGE NAME** R 1001 Document/message name, coded C an..3 12 Transport cargo release order X 1131 Code list qualifier C an..3 X 3055 Code list responsible agency, coded C an..3 X **Document/message name** 1000 C an..35 R 1004 **DOCUMENT/MESSAGE NUMBER** C an..35 Sender's unique reference number R 1225 **MESSAGE FUNCTION, CODED** C an..3 1 Cancellation 5 Replace 9 Original **RESPONSE TYPE, CODED** X 4343 C an..3

Message: COREOR 7 May 2007

Version : 1.0 rev. 1 / D.95B

Source : Maersk Line / EUREDIOPS

Segment: **RFF Reference**

Position: 0040

Group: Level: 1

Usage: Conditional (Required)

Max Use:

Purpose: A segment to express a reference which applies to the entire message,

such as: - release order reference number - container

announcement reference number

RFF+REO:555144' **Comments:**

RFF+BM:500309378'

Data Element Summary

Data Component

	Element Element	<u>Name</u>		<u>Att</u>	ributes
M	C506	REFERENCE		M	
M	1153	Reference qua	alifier	M	an3
		ВМ	Bill of Lading number		
		REO	Release order reference		
R	1154	Reference nui		C	an35
			number (if C506.e1153 = `BM reference and/or PIN code (:'REO')		
X	1156	Line number	•	C	an6
X	4000	Reference ver	sion number	С	an35

Message : COREOR 8 May 2007

Segment: TDT Details of Transport Position: 0060 (Trigger Segment)

Group: Segment Group 1 (Details of Transport) Mandatory

Level: 1

Usage: Mandatory

Max Use: 1

Purpose: A segment to indicate the main carriage stage of the transport, such

as carrier/liner service; also inland transport details can be specified.

Comments: TDT+20+0610+1++MAE:172:20+++OXLD2:103::ADRIAN MAERSK'

Data Element Summary

Data Component

		ompone 			
	<u>Element</u>	<u> Element</u>			<u>ributes</u>
М	8051		TRANSPORT STAGE QUALIFIER	M	an3
			20 Main-carriage transport		
0	8028		CONVEYANCE REFERENCE NUMBER	С	an17
			Vessel operator's voyage number		
R	C220		MODE OF TRANSPORT	C	
R		8067	Mode of transport, coded	C	an3
			1 Maritime transport		
X		8066	Mode of transport	C	an17
X	C228		TRANSPORT MEANS	C	
X		8179	Type of means of transport identification	C	an8
X		8178	Type of means of transport	C	an17
R	C040		CARRIER	C	
R		3127	Carrier identification	C	an17
			Vessel operator's code		
0		1131	Code list qualifier	C	an3
			172 Carrier code		
0		3055	Code list responsible agency, coded	C	an3
			20 BIC (Bureau International des 0		
			166 US, National Motor Freight Clas		
			Association		
0		3128	Carrier name	С	an35
X	8101		TRANSIT DIRECTION, CODED	C	an3
X	C401		EXCESS TRANSPORTATION INFORMATION	С	
X		8457	Excess transportation reason, coded	М	an3
X		8459	Excess transportation responsibility,	М	an3
			coded		
X		7130	Customer authorization number	С	an17
R	C222		TRANSPORT IDENTIFICATION	Č	
R		8213	Id. of means of transport identification	Č	an9
			Call sign (if C222.e1131 = '103')		
			Lloyd's no (if C222.e1131 = '146')		
R		1131	Code list qualifier	С	an3
			103 Call sign directory		
			146 Means of transport identification	n	
0		3055	Code list responsible agency, coded	C	an3
•			11 Lloyd's register of shipping	_	35
R		8212	Id. of the means of transport	С	an35
			Vessel name	_	
X		8453	Nationality of means of transport, coded	С	an3
X	8281	U-133	TRANSPORT OWNERSHIP, CODED	Č	an3
^	5201		HARIOI OKI OMILKOHIF, CODED	-	a11113

Message: COREOR 9 May 2007

Segment: **RFF Reference**

Position: 0070

Group: Segment Group 1 (Details of Transport) Mandatory

Level:

Usage: Conditional (Optional)

Max Use:

Purpose: A segment to provide a reference for the liner service, such as: -

conference - marketing organization - syndicate - vessel sharing

agreement

Comments: RFF+VON:0610'

Data Element Summary

Data Component

	Element Element	ent <u>Name</u>		<u>Att</u>	<u>ributes</u>
M	C506	REFEREN	CE	M	
M	115	3 Reference	e qualifier	М	an3
		VON	Voyage number		
R	115	4 Reference	e number	С	an35
		Alternati	ve (non vessel operator's) voy	age nun	ıber
X	115	6 Line num	ber	С	an6
X	400	0 Reference	e version number	С	an35

Message : COREOR 10 May 2007

Segment: NAD Name and Address Position: 0110 (Trigger Segment)

Group: Segment Group 2 (Name and Address) Mandatory

Level: 1

Usage: Mandatory

Max Use: 1

Purpose: A segment to identify the party's name and address, and function,

such as: - message recipient - message sender - carrier or agent -

ordering customer - ordering customer agent

Comments: NAD+CA+MAE:172:20'

Data Element Summary

Data Component

		Flomoni		V ++	wib.utoc
М	Element 3035	Elemeni			<u>ributes</u> an3
IYI	3033		PARTY QUALIFIER CA Carrier	IAI	ans
			CB Customs broker		
R	C082		PARTY IDENTIFICATION DETAILS	С	
M	CUBZ	2020	Party id. identification	М	an35
IVI		3039			
			Carrier code 'MAE' or 'SCL' (as applicable) ('CA')	ıı e.	5035 =
			Maersk Sealand internal customer code (if	e30:	35 = 'CB'
0		1131	Code list qualifier	C	an3 ´
			Only used when e3035 = 'CA'		
			172 Carrier code		
0		3055	Code list responsible agency, coded	C	an3
			Only used when e3035 = 'CA'		
			20 BIC (Bureau International des 0	Conta	aineurs)
0	C058		NAME AND ADDRESS	C	
M		3124	Name and address line	M	an35
			Company name (if e3035 = 'CB')		
X		3124	Name and address line	C	an35
X		3124	Name and address line	C	an35
X		3124		C	an35
X		3124	Name and address line	C	an35
X	C080		PARTY NAME	C	
X		3036	Party name	М	an35
X		3036	Party name	C	an35
X		3036	Party name	C	an35
X		3036	Party name	C	an35
X		3036	Party name	C	an35
X		3045	Party name format, coded	C	an3
X	C059		STREET	C	
X		3042	, , , , , , , , , , , , , , , , , , ,	M	an35
X		3042	- •	С	an35
X		3042	* •	C	an35
X	3164		CITY NAME	C	an35
X	3229		COUNTRY SUB-ENTITY IDENTIFICATION	C	an9
X	3251		POSTCODE IDENTIFICATION	C	an9
X	3207		COUNTRY, CODED	С	an3

Message: COREOR 11 May 2007

EQD Equipment Details Segment: **Position:** 0330 (Trigger Segment)

Segment Group 7 (Equipment Details) Conditional (Required) Group:

Level: 1

Usage: Mandatory

Max Use:

Purpose: A segment to specify a container, container size and type, and

full/empty indication.

Comments: EQD+CN+MAEU1234567+22R1:102:5++11+5'

Data Element Summary

Data Component

	<u>Element</u>	Element	<u>Name</u>	<u>Att</u>	ributes
M	8053		EQUIPMENT QUALIFIER	M	an3
			CN Container		
R	C237		EQUIPMENT IDENTIFICATION	C	
R		8260	Equipment identification number	C	an17
			Container number		
X		1131	Code list qualifier	C	an3
X		3055	Code list responsible agency, coded	C	an3
X		3207	Country, coded	C	an3
R	C224		EQUIPMENT SIZE AND TYPE	C	
R		8155	Equipment size and type identification		an10
			Equipment size/type code as per ISO6346 (.1 c	or .2, .2
			preferred)		
0		1131	Code list qualifier	С	an3
			102 Size and type		
0		3055	Code list responsible agency, coded		an3
			5 ISO (International Organization	for	
			Standardization)	_	
X		8154	Equipment size and type	С	an35
X	8077		EQUIPMENT SUPPLIER, CODED	C	
0	8249		EQUIPMENT STATUS, CODED	С	an3
			3 Import	_	_
0	8169		FULL/EMPTY INDICATOR, CODED	С	an3
			4 Empty		
			5 Full		

Message : COREOR 12 May 2007

Segment: **RFF Reference**

Position: 0340

> Group: Level: 1

Conditional (Required) Usage:

Max Use:

Purpose: A segment to express a reference which applies to the entire message,

such as: - release order reference number - container

announcement reference number

Comments: RFF+SQ:1'

Data Element Summary

Data Component Element Element Name Attributes М C506 **REFERENCE** М 1153 Reference qualifier M an..3 Sequence number R 1154 Reference number C an..35 Dummy sequence number '1' 1156 Line number X C an..6 X 4000 Reference version number C an..35

Message : COREOR 13 May 2007

DTM Date/Time/Period Segment:

Position: 0423

Group: Segment Group 7 (Equipment Details) Conditional (Required)

Level:

Usage: Conditional (Optional)

Max Use:

Purpose: To specify date, and/or time, or period.

Comments:

Notes: SEGMENT ADDED - NOT IN D.95B COREOR MESSAGE

Data Element Summary

Data Component

	Element Element Name					Attributes		
M	C507		DATE/TIN	DATE/TIME/PERIOD				
M	2	2005	Date/time	Date/time/period qualifier				
			400	Ultimate release date/time				
0	2	2380	Date/time	Date/time/period				
			Release e	xpiry date/time				
O 2379 Date/time/period f			e/period format qualifier	С	an3			
			203	CCYYMMDDHHMM				

Message : COREOR 14 May 2007

Segment: TDT Details of Transport Position: 0440 (Trigger Segment)

Group: Segment Group 8 (Details of Transport) Conditional (Optional)

Level: 2

Usage: Mandatory

Max Use: 1

Purpose: A segment to specify details of the inland transport associated with the

collection of the container.

Comments: TDT+30++3'

Notes: Segment to be used to specify in-land/on-carriage mode

and/or means of transport

Data Element Summary

Data Component

	Element	-		۸++	ributes
М	8051	Licilieli	TRANSPORT STAGE QUALIFIER		an3
1*1	8031		30 On-carriage transport	1-1	alliis
0	8028		CONVEYANCE REFERENCE NUMBER	С	an17
Ö	C220		MODE OF TRANSPORT	Č	uiii.17
Ö	CLLO	8067	Mode of transport, coded		an3
•		0007	1 Maritime transport	·	aiiiis
			2 Rail		
			3 Road		
			8 Inland water		
			9 Mode unknown		
X		8066	Mode of transport	C	an17
X	C228		TRANSPORT MEANS	C	
X		8179	Type of means of transport identification	С	an8
X		8178	Type of means of transport	C	an17
0	C040		CARRIER	C	
0		3127	Carrier identification	C	an17
			Carrier code		
0		1131	Code list qualifier	C	an3
			172 Carrier code		
0		3055	Code list responsible agency, coded	_	an3
			20 BIC (Bureau International des 0		
			166 US, National Motor Freight Clas	sifica	ation
			Association		
0		3128	Carrier name	С	an35
			Carrier name (free text)	_	_
X	8101		TRANSIT DIRECTION, CODED	C	an3
X	C401		EXCESS TRANSPORTATION INFORMATION	С	_
X		8457	Excess transportation reason, coded	M	an3
X		8459	Excess transportation responsibility,	М	an3
v		7400	coded	_	
X	6222	7130	Customer authorization number	C	an17
0	C222	0040	TRANSPORT IDENTIFICATION	C	0
0		8213	Id. of means of transport identification	C	an9
			Call Sign (if e8067 = 1 and C222.e1131 = 1		_ 146\
			Lloyd's Number (if e8067 = 1 and C222.e11	151	= 140 <i>)</i>
0		1131	Code list qualifier	С	an3
•		1131	103 Call sign directory		anns
			146 Means of transport identification	n	
0		3055	Code list responsible agency, coded	" c	an3
			- court is the corporation against a court		

Message: COREOR 15 May 2007

11 Lloyd's register of shipping 8212 Id. of the means of transport Name of inland transport means (free text) C an..35 0 8453 Nationality of means of transport, coded TRANSPORT OWNERSHIP, CODED X C an..3 X 8281 C an..3

May 2007 Message : COREOR 16

Segment: **CNT Control Total**

Position: 0520

Group: Level: 0

Usage: Mandatory

Max Use:

A segment to specify the number of containers in the message, **Purpose:**

explicitly given by the sender.

CNT+16:1' **Comments:**

Data Element Summary

Data Component

	Element Element	<u>Name</u>		Attributes
M	C270	CONTROL		M
M	6069	Control qualifi	er	M an3
		1	Algebraic total of the quantity vitems in a message	values in line
		16	Total number of equipment	
M	6066	Control value		M n18
			of 1 (if e6069 = 1) D segments in the message (if e6069 =
X	6411	Measure unit	qualifier	C an3

May 2007 Message : COREOR 17

Segment: **UNT Message Trailer**

Position: 0530

Group: Level: 0

Usage: Mandatory

Max Use:

Purpose: A service segment ending a message, giving the total number of

segments in the message and the control reference number of the

message.

Comments: UNT+11+3000001'

Data Element Summary

Data Component

Element Element Name			Attributes	
M	0074	NUMBER OF SEGMENTS IN A MESSAGE	M	n6
		Total number of segments in the message		
M	0062	MESSAGE REFERENCE NUMBER	M	an14
		Message reference identical to e0062 in UN	IH se	egment

May 2007 Message : COREOR 18

Sample message

UNA:+,?'

UNB+UNOA:1+MAEU:ZZ+NLRTMAPMT+070425:0854+355091'

UNH+35509100001+COREOR:D:95B:UN'

BGM+12+20070425085422+9'

RFF+REO:143143' RFF+BM:557900953'

TDT+20+0702+1++MAE:172:20+++OZSK2:103::SVENDBORG MAERSK'

RFF+VON:0702'

NAD+CA+MAE:172:20'

EQD+CN+MSKU6368150+42G1:102:5++11+5'

RFF+SQ:1'

TDT+30++2++MAE:172:20'

CNT+16:1'

UNT+12+35509100001'

UNZ+1+355091'

Message : COREOR 19 May 2007