

Global Family Service

Foundation

Components

Case Studies

v 3.5

Buttons

Action Button

Floating Action Button

Icon Button

Contents

Avatar

Tag

Image Grid

Skeleton

Video Player

Indicators

Badge

Page Controller

Page Indicator

Progress Indicator

Inputs

Checkbox

Chip

Radio Button

Slider

Stepper

Switch

Text Area

Text Input

Pulldown

Navigations

Tab

Tab - Expanded Tab List

Side Drawer

Footer

Top Navigation

Segmented Control

Bottom Navigation

Bottom Sheet

Bottom Sheet is fixed at the bottom of the screen and used to provide content or additional description and icons related to the current page.

In addition, it can be used to provide significant feedback to a specific user action or get user confirmation. Users can focus on a description, option, or confirmation through the bottom sheet.

Anatomy

1

2

3

4

5

6

1. Dimmer

2. Header Area (Optional)

3. Handlebar (Optional)

4. Contents Area

5. Button Area (Optional)

Element Patterns and Types

Element Pattern	Text, Avatar & Image List (Default)	Avatar	Grid	List	Image	Full Image	Custom	Select from 7 types.
Dimmer	Modal (Default)	Interactive						Select modal type or interactive type.

Overlays
Popup
Snackbar
Toast Overlay
Tooltip
Bottom Sheet
Pulldown Menu

Systems
LIFF View

Handlebar	True	False (Default)				Choose to use Handlebar or not.
Header Area	Normal	Close Only (Default)	Tab Only	Search Only	None	Select a type.
Button Area	Vertical (Default)	Horizontal	Full Bleed	None		Select a type.

Element Pattern

Light

Title

Description Here

Confirm

Controls

Element Pattern

- Text
- Avatar
- Grid
- List
- Image
- Banner
- Custom

Seven types of the bottom sheet are available based on the element pattern.

Element Pattern	Description
Text	Basic bottom sheet for user confirmation.
Avatar	Bottom sheet with an avatar image, mainly used for adding the OA (official account).
Grid	Bottom sheet with icons for single selection.
List	Bottom sheet with a list of texts or icons for single or multiple selection.
Image	Bottom sheet in two ratios with an image, title, and text for feedback on user action or user confirmation.
Full Image	Bottom sheet with a full image except for the button area for ad images.
Custom	Bottom sheet customizable by users.

General

Dimmer & Handlebar

Light

Controls

List Item Title

List Item Title

List Item Title

Type

☒ Modal (With Dimmer)

☐ Interactive

Handle

☒ With Handle

☐ Without Handle

- Modal and interactive types are determined by the use of dimmer.
- Handlebar is used to adjust the layout of the screen in terms of the position.
Handlebar can be selected or unselected for all types of bottom sheets.

Option Name	Description
Modal	No other action can take place until the action in the bottom sheet is completed or cancelled. Dimmer should be used behind the bottom sheet.
Interactive	Unlike the modal type, there can be interaction with the current page. Dimmer is not used to view the current page without completing the action in the bottom sheet.

Header Area

Normal (Top Navigation)

Light

< Title Max 20 byte ☆ ♥ ✕

Controls

Additional Component

☒ None

☐ Tap

☐ Search

Title

☒ With Title

☐ Without Title


Title Position


☒ Left

☐ Center

Choose the position of the title and whether it has a title or not in the header.
Normal type includes Top Navigation by default.
Also, it is optional to include a search or tab option to control the contents area
Refer to [Top Navigation](#) for more details.


Close Only






When Close Only is selected, it is optional to include a search or tab option to control the contents area.
 Take caution when using the close button as it makes it difficult to close the bottom sheet.
 The color of the close button can be freely changed.

Tab Only



Choose Tab to control the contents area.

Search Only





Choose search to control the contents Area.

Button Area

Light

Confirm

Controls

Element Pattern

☒ Vertical

☐ Horizontal

Type

☒ Primary

☐ Primary + Outlined

☐ Primary + Ghost

☐ Primary + Secondary + Tertiary

Home Indicator

☒ With Home Indicator

☐ Without Home Indicator


- Button area can have horizontal or vertical buttons.
- Vertical buttons grab more attention, and they are recommended for a lot of contents.
- Horizontal buttons are recommended for simpler bottom sheet.
- Home indicator can be selectively added to the button area.

Option Name	Element Patterns	Description
Vertical	Primary	For a single action only such as simple confirmation.
	Primary + Outlined	Emphasizing the secondary action.
	Primary + Ghost	Emphasizing the primary button instead of the second button.
	Primary + Secondary + Tertiary	Using three buttons is not recommended. Use only when required.
Horizontal	Contained Primary + Secondary	For two options, especially emphasizing the primary action.
	Ghost Primary + Secondary	For two options without highlighting the primary action.


Options

Text, Avatar & Image List

Light





- Title and description are provided in two sizes. Default size is large and medium can be selected for a given situation.
- In addition to basic elements including an image, text, and button, you can use additional elements for the bottom sheet. It will perform as per respective additional elements.



Choose the position of the title and description.


Grid






Module and expanded types are available as grid.

List



List offers various options. Refer to the Basic List.

Full Image






Four aspect ratios are supported.
Vertical 4:3 and square 1:1 can be used in the full image bottom sheet only.
It is recommended to prepare an image pursuant to the guideline in the library file.

Pattern	Horizontal 16:9	Horizontal 4:3	1:1	Vertical 4:3
Image Bottom Sheet	O	O	X	X
Full Image Bottom Sheet	O	O	O	O


Custom




You can customize the slot for a given situation.

Behavior

Appear / Disappear






When you tap the close button or the dimmer, the modal disappears soon.

Expandable / Not Expandable

Expandable




Handlebar is used to expand the screen.

- You can drag the handlebar to expand the screen.
It can be expanded up to the full-height, depending on contents.

- If you scroll or drag beyond the top of the bottom sheet, you can expand the screen. (Optional)
- You can dismiss the bottom sheet by dragging the handlebar down when the scroll bar is at the top.

Not Expandable




If the screen cannot expand, there are cases when the modal is closed by dragging the handlebar down or not. It can apply appropriately depending on the content.

- You can dismiss the bottom sheet by dragging the handlebar down when the scroll bar is at the top.
- The bottom sheet can fix if it is not valid to close the modal by dragging the handlebar down depending on the content.

With Keyboard


Non-Scrollable





When there is an action to call the keyboard in the bottom sheet, the modal moves up by the height of the keyboard.


Scrollable



If the bottom sheet cannot be fully viewed after calling the keyboard, the scroll bar should appear in the contents area to allow users to view the contents in the modal.


Expanded View






As for an expandable bottom sheet, the modal should be expanded up to the full height with the keyboard fixed on the screen. It should be the same for bringing down the expanded the modal back to the original height.


Scroll Area



If the height of the content exceeds the maximum height or preset height, the top section is fixed as a scroll area.




Usage




Do

Bottom sheet is fixed at the bottom of the screen and appears over other UI elements.
Header area can be skipped, and it can be arranged from the contents area.



Don't

Fixed position at the bottom and left/right gap cannot be changed.
If you need to align differently with side margins, it is recommended to use a popup.




Don't

Bottom sheet cannot be used in devices such as tablets or PCs.
It is recommended to use a drawer or pulldown.

Design Specs


Resizing




Element	Description
1 Flexible Width	The width is adjustable based on the width of the screen (100% of the screen width).
2 Auto Height	- Height is automatically set according to the ratio of the content and image. It cannot be arbitrarily changed. - It can be set between 0% and 100% excluding the safe area such as status bar. - When the bottom sheet is taller than the maximum height of a device, the scroll bar should appear without exceeding the maximum height.

Styles


General






Element	Properties
1 Container	• Width: Flexible Width, 100% • Height: Auto • Background Color: Changeable ◦ Default: Idsg-color-white
2 Title	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Changeable ◦ Default: Idsg-color-black
3 Icon	• Iconography: Changeable ◦ Contained: Unchangeable ◦ Outlined: Unchangeable • Size: Unchangeable • Color: Changeable ◦ Default: Idsg-color-black
4 Tab	• Follows tab rules.
5 Search	• Follows search rules. (Link, TBD)
6 Button Area	• Follows button rules.

Options







Element	Properties
1 Image Area	- Background Fill: Changeable - Default: None - Provided Size 16:9 - W 375px, H 210px 4:3 - W 375px, H 281px 1:1 - W 375px, H 375px 3:4 - W 375px, H 500px
2 Avatar	Follows avatar rules.
3 Title	Medium - Typhography: Changeable - Size: Unchangeable - Color: Changeable - Default: Idsg-color-black Large (Default) - Typhography: Changeable - Size: Unchangeable - Color: Changeable - Default: Idsg-color-black
4 Description	Medium (Default) - Typhography: Changeable - Size: Unchangeable - Color: Changeable - Default: Idsg-gray-500 Large (Default) - Typhography: Changeable - Size: Unchangeable - Color: Changeable - Default: Idsg-gray-500 Medium (Emphasized) - Typhography: Changeable - Size: Unchangeable - Color: Changeable

		◦ Default: Idsg-gray-800
		Large (Emphasized)
		• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Changeable ◦ Default: Idsg-gray-800
5	Link	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Idsg-color-role-link
6	Page Indicator	• Follows page indicator rules. (Link, TBD)
7	List	• Follows list rules.
8	Gird Background	• Background Color: Changeable ◦ Default: Idsg-gray-150
9	Grid Icon	• Iconography: Changeable ◦ Contained: Unchangeable ◦ Outlined: Unchangeable • Size: Unchangeable • Color: Changeable ◦ Default: Idsg-color-black
10	Grid Text	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Changeable ◦ Default: Idsg-color-black

Landscape Mode





- The height of the bottom sheet is determined by the height of its content.
It is same for the landscape mode.
- The height of the bottom sheet may be changed if the height of its content is changed due to device width (if the device does not support standard resolution).
- When the height of the bottom sheet exceeds the maximum height of the screen in the landscape mode, the scroll bar appears in the landscape mode.
It should show the top of the content with the scroll bar at '0'.