


Bottom Navigation

Overlays

- Popup
- Snackbar
- Toast Overlay
- Tooltip
- Bottom Sheet
- Pulldown Menu

Systems

- LIFF View




- We recommend you use Size S on mobile. You can display up to seven pages.
- We recommend you use Size L on desktop. Do not use Size L on mobile. You can display up to 14 pages.
- In both sizes, if it exceeds the maximum number of pages that can be displayed, replace the number of the second page or the page before the last page with a truncation symbol.

Behavior

Interaction States

Selected Item



Normal


Hover

Background Color: Opacity 70%

Pressed

Background Color: Opacity 50%

Unselected Item, Previous/Next Button



Normal

Hover


Background Color: Gray 150 (Idsg-color-gray-150)

Pressed

Background Color: Gray 200 (Idsg-color-gray-200)


Interaction

Selecting Page Number



- When you select a page, the content area shows the selected page.
- When a truncation symbol is provided, if you select the last page, you'll be moved to the selected page and the second page number will be replaced with a truncation symbol.
- If you select a number in the middle, the number of the second page and the page before the last page will be replaced with a truncation symbol.

Selecting Previous / Next Button



- By selecting the Previous/Next button, you can navigate one page at a time.
- A truncation symbol is used in the same way as in the Selection Page Number section, depending on the number of pages.

Usage

Page controllers are mostly used on desktop web pages.


Avoid using them on mobile pages unless you have a specific purpose.


On mobile, we recommend you use infinite scroll instead of the page controller.

Using a page controller on mobile is allowed in the following cases:

1. If the page needs to be branched for business purposes.
2. When a user needs to navigate pages for a specific purpose.
3. If the user needs to be able to estimate the total amount of content.
4. When there is other content at the bottom of the scroll area and it is difficult to access the bottom if you use infinite scroll.

Examples of Cases Where Page Needs to be Branched for Business Purposes






You can branch the page to make the top banner or featured products more visible.

Design Specs

Resizing

If the number of pages is reduced to the minimum, two page numbers are displayed and the horizontal size is also reduced. The maximum size is different for mobile and desktop.


Mobile



The maximum number of page numbers on mobile is 7, including the truncation symbol. The width of the component cannot be increased to provide more than 7 page numbers.


Desktop





The maximum number of page numbers on desktop is 14, including the truncation symbol.
The width of the component cannot be increased to provide more than 14 page numbers.

Styles



Element	Properties
1 Previous/Next Button	• Enabled ◦ Color: Changeable ◦ Default: Gray 700 (Idsg-color-gray-700) • Disabled ◦ Color: Unchangeable ◦ Default: Disabled Gray (Idsg-color-disabled)
	• Container ◦ Border Radius: Changeable ◦ Default: 5px (Idsg-radius-200) ◦ Background Color ◦ Selected: Changeable ◦ Default: Gray 900 (Idsg-color-gray-900) ◦ Unselected: Changeable ◦ Default: Transparent ◦ Hover: Changeable ◦ Default: Idsg-color-gray-150 ◦ Pressed: Changeable ◦ Default: Idsg-color-gray-200
2 Page Number	• Text

- Selected
 - Font: Changeable
 - Default: Text M Bold (ldsg-typography-text-m-200)
 - Color: Changeable
 - Default : White (ldsg-color-white)
- Unselected
 - Font: Changeable
 - Default: Text M Regular (ldsg-typography-text-m-100)
 - Color: Changeable
 - Default: Gray 700 (ldsg-color-gray-700)

3 Truncation

- Same as ② Page Number > Unselected properties
-