

Buttons

- Action Button
- Floating Action Button
- Icon Button

Contents

- Avatar
- Tag
- Image Grid
- Skeleton
- Video Player

Indicators

- Badge
- Page Controller
- Page Indicator
- Progress Indicator

Inputs

- Checkbox
- Chip
- Radio Button
- Slider
- Stepper
- Switch
- Text Area
- Text Input
- Pulldown

Navigations

- Tab
- Tab - Expanded Tab List


Side Drawer

- Footer
- Top Navigation
- Segmented Control
- Bottom Navigation

Side Drawer

Side Drawer provides users with an access to their desired destination within the entire page.

Anatomy



1. Header (Optional)
2. Container
3. Dimmer
4. Divider (Optional)
5. Active Area (Optional)
6. Inactive Area
7. Footer (Optional)


Element Patterns and Types

Avatar

True

False

Avatar




Overlays

- Popup
- Snackbar
- Toast Overlay
- Tooltip
- Bottom Sheet
- Pulldown Menu

Systems

- LIFF View







Two types of Side Drawers are available: Side Drawer with Avatar and Side Drawer without Avatar. In order to increase the visibility of menu items, they must be provided in the "Icon + Text" form, and in some cases, the footer and dividers for each menu item can be omitted.

Child Elements

Basic List


Use a Basic List for the side drawer's menus. For more information, refer to Element Patterns and Types in the Basic List page.






Footer

Use a Basic List for the side drawer's menus.
For more information, refer to [Element Patterns and Types in the Footer](#).




Behavior

Opening




You can open a side drawer using a burger menu icon.


Closing



Tap the dimmer or swipe the side drawer to close the open side drawer.

Scrolling






If you can't see all of the items in the Above the Fold because there are many items in the side drawer, you scroll vertically and display menus.


Usage

Icon + Text or Text Only



Do



Select from "Icon + Text" and "Text" for the list.




Don't

Do not use "Icon + Text" and "Text" types together on the same level of list.

Nasted Menus





Do

In some cases, you can create menus with multiple levels.




Caution

Do not create menus with three or more levels.

Design Specs

Styles



Element	Properties
1 Header (Optional)	- Width: Changeable (Max 80%) - You can increase the width by up to 80%. - Default Screen Width: 280px (Max 300px) - Height: Fixed - Avatar - Element Pattern: Changeable - Size: Changeable - Badge: Changeable - Outline: Changeable - Title Text - Font: Changeable - Default: Idsg-typography-en-title-m-200 - Sub Text - Font: Changeable - Default: Idsg-typography-en-text-xs-100 - Color: Changeable - Default: Idsg-typography-en-text-xs-100

2	Container	- Width: Changeable - You can increase the width by up to 80%. - Default Screen Width: 280px (Max 300px) - Height: Auto - Color: Changeable - Default: \$ldsg-color-white
3	Dimmer	- Width: Fixed - Default: 240px - Height: Fixed - Color: Changeable - Default: ldsg-opacity-black-40
4	Divider (Optional)	- Width: Changeable - Default: 280px - Height: Fixed - Color: Changeable - Default: ldsg-color-gray-150
5	Active Area (Optional)	- Icon: Changeable - Type: Solid - Color: Changeable - Default: ldsg-color-black - Font: Changeable - Default: ldsg-typography-en-text-m-100 - Color: Changeable - Default: ldsg-color-gray-900 - Container - Color: Changeable - Default: ldsg-color-gray-150
6	Inactive Area	- Icon: Changeable - Type: Solid - Color: Changeable - Default: ldsg-color-black - Font: Changeable - Default: ldsg-typography-en-title-m-100 - Color: Changeable - Default: ldsg-color-gray-900
		- Width: Changeable - You can increase the width by up to 80%. - Default Screen Width: 280px (Max 300px) - Height: Fixed - Font: Changeable

7 Footer (Optional)

- Default: ldsg-typography-en-title-xs-100
- Color: ldsg-color-gray-500
- Social Icon: Changeable
 - Default
 - Type: Ghost
 - Size: Medium