



Buttons

Action Button

Floating Action Button

Icon Button

Contents

Avatar

Tag

Image Grid

Skeleton

Video Player

Indicators

Badge

Page Controller

Page Indicator

Progress Indicator

Inputs

Checkbox

Chip

Radio Button

Slider

Stepper

Switch

Text Area

Text Input

Pulldown

Navigations

Tab

Tab - Expanded Tab List

Side Drawer

Footer

Top Navigation

Segmented Control

Bottom Navigation


Top Navigation

Top navigation is a component which provides navigation at the top of the screen.

This document covers the full-flex, sub window top navigation in the LIFF (LINE Front-end Framework).

First read the document on [the LIFF browser view type](#), which is recommended for the family service.

Anatomy




1. Container
2. Left Icon Area
3. Title Area
4. Right Icon Area


Element Patterns and Types

iOS

Main Window (Full Flex)



Sub Window Header




Overlays

- Popup
- Snackbar
- Toast Overlay
- Tooltip
- Bottom Sheet
- Pulldown Menu

Systems

LIFF View




LIFF Browser top navigation is provided per view type and OS.
Options and how to use vary, depending on the type.

	Separate OS	Height	Position of the close button	Close button form
Full-flex	O	- iOS : 44 - Android : 56	Fixed on the right	Icon only
Sub Window	X	50	Either right or left	Icon or text

Refer to [LIFF](#) for more information.

Full-flex Top Navigation




Full-flex view is the LIFF view type recommended as main window in the family service.
Full-flex top navigation provides a design for both iOS and Android.

Left Items	Title Area	Right Items
1 Icon	Title Text	Close + 1 Icon
2 Icons (iOS Only)	Logo	Close + 2 Icons (Android Only)
Text Button (iOS Only)	None	Close Icon Only
None		

- Left Icons:** The first icon acts as the back button for pages with the page depth of 2 or deeper.
Other icons can be changed within the boundary of LUI icons.


- **Title Area:** Title is provided as text by default.
You can either add a logo image or delete the title area.
- **Right Icons:** Close button is always provided in the right icon area.
Other icons can be changed within the boundary of LUI icons.

Full-flex - Title Area




There are 3 options for the title area including text, logo, and none.
You can add any image as a logo.


Sub Window Top Navigation



Sub window header is provided regardless of OS.
Close button can be placed either on the right or left as text or icon.
There are 3 types based on the position of the close button.
Title area supports the same options in all patterns.


Sub Window - Title Area





There are 3 options for the title area including text, logo, and none.
You can add any image as a logo.


Sub Window - Right Close Button



Sub window top navigation pattern with the native close button on the top right with the following options.

Left Items	Title Area	Right Items
1 Icon	Title Text	Close + 1 Icon
2 Icons	Title Text + Sub Text	Close Icon Only
Text Button	Logo	Close Text Only
	None	

Sub Window - Left Close Button






Sub window top navigation pattern with the native close button on the top left with the following options.

Left Items	Title Area	Right Items
Close + 1 Icon	Title Text	1 Icon
Close Icon Only	Title Text + Sub Text	Close Text Only
Close Text Only	Close Icon Only	Text Button
	Close Text Only	

Sub Window - Left Title




Sub window top navigation pattern with the native close button on the top right and title on the left with the following options.

Left Items	Title Area	Right Items
1 Icon	Title Text	Close + 1 Icon
None	Title Text + Sub Text	Close + 2 Icons
	Logo	Close Icon Only
	None	Close Text Only

Design Specs

Container




Element	Properties
	- Changeable - Default
Background Color	- Light Mode: Idsg-color-white (#ffffff) - Dark Mode: Idsg-color-gray-900 (#111111)
Width	Flexible Width
Height	- Unchangeable - Full-flex iOS: 44 - Full-flex Android: 56 - Sub Window: 50


Margins & Gaps

Gaps within the top navigation are fixed and cannot be modified. Values are different per component pattern and type.


Full-flex




Android



Sub Window



Title Area



Title area is adjusted based on the width of the container with fixed gaps.

Take caution to keep text within 136 px in consideration of the minimum size (i. e. 320, iPhone SE).

When the text is longer than the given space, it is automatically displayed with an ellipsis.

Image logo should meet the following specifications.

- Width: 136 px
- Height: 24 px



Element	Properties
	- Token: Idsg-typography-title-m-200(EN/TH 17px, JP/TC 16px), Unchangeable - Color: Changeable
1 Title Text	- Default - Light Mode: Idsg-color-gray-900 (#111111) - Dark Mode: Idsg-color-white (#000000)

Button Area

Icons



It is recommended to use LUI icons in the top navigation.
If you want to use a non-LUI icon, you should align the style of such icons with LUI icons.
The thickness for LUI icons is 1.5.
You can develop icons in the library with LAICON.


[LUI Icons on LAICON >](#)
[Figma Library >](#)

Element	Properties
	Color: Unchangeable

	- Color: Unchangeable - Light Mode: Idsg-color-black (#000000) - Dark Mode: Idsg-color-white (ffffff)
Close Icon	- Width: 1.5, Unchangeable - Size: Unchangeable - Height: 24px - Width: 24px

	- Color: Changeable - Default - Light Mode: Idsg-color-black (#000000) - Dark Mode: Idsg-color-white (ffffff)
Other Icons	- Width: 1.5, Unchangeable - Size: Unchangeable - Height: 24px - Width: 24px

Text Buttons



The width of the text button container is fixed at the minimum of 40 px up to 75 px.
Text cannot exceed this width.

Element	Properties
Container	- Min-width: 40 - Max-width: 75
Typography	Idsg-typography-text-m-200, Changeable
Color	- Changeable - Default - Light Mode: Idsg-color-gray-900 (#111111) - Dark Mode: Idsg-color-white (#000000)

Customization


Be careful with the native close button during customization. Except for the close button, LIFF top navigation elements are implemented in the web.

It is recommended to comply with the guide, but you can still customize other elements except for the close button, if required.

In the full-flex type, the close button can be either black (ldsg-color-black, #000000) or white (ldsg-color-white, #FFFFFF).

The color set upon initially calling the service cannot be changed until the service is closed.


Background Color



Background color can be adjusted.


You can change the transparency ratio or use another solid color.


Different Icon, Text Color by Screen



If the white button is used upon initially calling the service, it cannot be changed to black on other pages.

Using Different Icons and Text Colors when Switching to Sub-windows





When calling a sub window from the main window, the color or position of the close button can be changed.