

SYSTEM SETUP FOR WINDOWS 10 or 11

This is a brief tutorial on how to setup your personal Windows 10 or 11 64bit Home or Professional system to be ready for the COMS20008 unit. The below steps represent one out of many ways of setting up your Windows 10 or 11 system for the unit. Before you start make sure Windows 10 or 11 is up-to-date with respect to updates and features. It is your responsibility to keep your personal system and passwords safe.

Step 1: CHECK SYSTEM COMPATIBILITY

- Windows search "about" (i.e. hold the Windows key down and simultaneously press "s" so the Windows search bar appears, then type "about" into the search bar).
- Click "About your PC" in the results and the system specifications window should open.
- Your system is compatible only if:
 - Your "System type" is "64-bit operating system, x64-based processor".
 - Your system is not in S-Mode and your "Edition" is either "Windows 10 Home" or
 "Windows 10 Professional" or "Windows 11 Home" or "Windows 11 Professional" without
 "S Mode". If you need to switch out of S-Mode, follow the instructions on the Microsoft
 Support Page.
 - If you use Windows 10 then "Version" must be at least 2004, including 20H2, 20H2, 21H1, 21H2. Version 1909 and before are unsupported. If you are running Version 1909 or earlier, you must update your system by going to "Settings -> Update & Security -> Windows Update", then checking for updates and installing any that are available.

ACTIVATE WSL2 (WINDOWS SUBSYSTEM FOR LINUX) IN WINDOWS 10 or 11

- Windows search "powershell".
- Right-click "Windows PowerShell" and click "Run as administrator".
- Click yes on the consent prompt and an elevated PowerShell will open.
- In PowerShell, run wsl --install -d Ubuntu (i.e. type "wsl --install -d Ubuntu" and press enter). If PowerShell can't find the wsl command, make sure your Windows is fully updated, then try again. If it still isn't there, make sure PowerShell is in 64-bit mode by running [Environment]::Is64BitProcess (Which will return "True" if it is and "False" if it isn't).
- Once the command finishes, restart your computer.
- Soon after your computer reboots, an Ubuntu window should open and complete the installation process. This may take a few minutes.
- Once the installation is complete, you will then be prompted to enter a UNIX username and password in the Ubuntu window. Make sure you remember them. You can use any username, but many people just use their name in lowercase (eg. "tilo").
- Update Ubuntu by running sudo apt update (this checks for upgrades), then sudo apt upgrade (this installs the upgrades). When asked "Do you want to continue? [Y/n]", press enter to select the default "Y"/"Yes" option, and wait for the upgrade to complete. [Side note: apt is a "package manager", which does what it says on the tin and manages packages/software on your system. sudo stands for "SuperUser DO" and you add it to the front of a command to run that command as the superuser (a.k.a. administrator or "root").]

- Your Ubuntu files are stored in a separate filesystem to your Windows files, which makes difficult to access from Windows (and you shouldn't try to). However, you can easily access your Windows C drive from Ubuntu by going to the "/mnt/c" directory in the Ubuntu terminal (if your Windows is on the D drive, it would be "/mnt/d" instead etc.). For convenience, you can create a "symbolic link" (similar to a shortcut) from your Linux home directory to your Windows files by running: ln -s /mnt/c/Users/[insert your Windows username here]/Documents ~/WindowsDocuments (e.g. ln -s /mnt/c/Users/tilo/Documents ~/WindowsDocuments)
- Whenever you want to open a new Ubuntu terminal, you can Windows search "Ubuntu" and click the Ubuntu application.

Step 2: INSTALL THE CLANG COMPILER

• In an Ubuntu terminal, run sudo apt install clang

Step 3: INSTALL THE SDL2 DEVELOPMENT PACKAGE

• In an Ubuntu terminal, run sudo apt install libsdl2-dev

Step 4: INSTALL THE VCXSRV WINDOWS X-SERVER

- Open a web browser and go to https://sourceforge.net/projects/vcxsrv/files/latest/download to download the installer
- · Run the installer
- If your windows administrator password is required, provide it and press enter to confirm
- The installation window should open. Click "Next", then "Install", and finally "Close".

Step 5: INSTALL THE LXDE LINUX DESKTOP (Note: IF YOU ALREADY HAVE XFCE INSTALLED SKIP THIS STEP AT FIRST)

- In an Ubuntu terminal, run sudo apt install lxde
- If asked which display manager to use, select "lightdm"
- After some significant installation time, the LXDE Linux desktop should be installed

Step 6: RUNNING THE LINUX DESKTOP AND CHECKING SDL2

- Windows search "xlaunch" and click on "XLaunch" in the results. A display settings window should open.
- Select "One large window" and click "Next".
- Select "Start no client" and click "Next".
- Make sure "Clipboard", "Primary Selection", "Native opengl", and "Disable access control" are ticked, then click "Next".
- Click "Finish" and a black VcXsrv window should open
- If you get a security alert saying "Windows Defender Firewall has blocked some features of VcXsrv windows xserver on all public and private networks", under "Allow VcXsrv windows xserver to communicate on these networks:", make sure "Private networks" and "Public networks" are checked, then click "Allow access". Ideally this wouldn't be necessary, but it's been an open issue since 2019.
- In an Ubuntu terminal, run export DISPLAY=\$(grep -m 1 nameserver /etc/resolv.conf | awk '{print \$2}'):0
- Run export LibgL_ALWAYS_INDIRECT=1
- Run startlxde

- A Linux desktop should appear in the VcXsrv window
- Open a terminal on the Linux desktop by going to "System Tools" and selecting "LXTerminal"
- Download the program hellosdl.c and save it into a new folder, e.g. you could make a folder called "SDL-Test" in your local "Documents" folder and save it there.
- In your Ubuntu terminal, change directory to folder where you just saved the file, e.g. if you saved it in "Documents\SDL-Test" and you set up the "WindowsDocuments" symlink earlier, you could run cd ~/WindowsDocuments/SDL-Test
- Compile the program in that folder by running <code>clang -std=cll -Wall hellosdl.c -I</code> /usr/include/SDL2 -1 SDL2 -o hellosdl, where the 'I' (uppercase i) in -I /usr/include/SDL2 stands for "Include" and the 'I' (lowercase L) in -1 SDL2 stands for "link".
- Run the compiled program by running ./hellosdl if you see a sky blue window appear then SDL2 is working properly!
- Note that some parts of the SDL library unfortunately have memory leaks, but there's nothing you can do about them, so don't be alarmed if you see some warnings.