FLASH[®] LITE[®] 1.x ACTIONSCRIPT[®] LANGUAGE REFERENCE



© 2007 Adobe Systems Incorporated. All rights reserved.

Adobe® Flash® Lite™ 1.x ActionScript™ Language Reference

If this guide is distributed with software that includes an end user agreement, this guide, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. Except as permitted by any such license, no part of this guide may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Adobe Systems Incorporated. Please note that the content in this guide is protected under copyright law even if it is not distributed with software that includes an end user license agreement.

The content of this guide is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Adobe Systems Incorporated. Adobe Systems Incorporated assumes no responsibility or liability for any errors or inaccuracies that may appear in the informational content contained in this guide.

Please remember that existing artwork or images that you may want to include in your project may be protected under copyright law. The unauthorized incorporation of such material into your new work could be a violation of the rights of the copyright owner. Please be sure to obtain any permission required from the copyright owner.

Any references to company names in sample templates are for demonstration purposes only and are not intended to refer to any actual organization.

Adobe, the Adobe logo, Flash Lite, and Flash are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries.

Third-Party Information

This guide contains links to third-party websites that are not under the control of Adobe Systems Incorporated, and Adobe Systems Incorporated is not responsible for the content on any linked site. If you access a third-party website mentioned in this guide, then you do so at your own risk. Adobe Systems Incorporated provides these links only as a convenience, and the inclusion of the link does not imply that Adobe Systems Incorporated endorses or accepts any responsibility for the content on those third-party sites.

Sorenson Spark.

Sorenson™ Spark™ video compression and decompression technology licensed from Sorenson Media, Inc.

Fraunhofer-IIS/Thomson Multimedia: MPEG Layer-3 audio compression technology licensed by Fraunhofer IIS and Thomson Multimedia (http://www.iis.fhg.de/amm/).

Independent JPEG Group: This software is based in part on the work of the Independent JPEG Group.

Nellymoser, Inc.: Speech compression and decompression technology licensed by Nellymoser, Inc. (http://www.nelly-moser.com).

Opera * browser Copyright © 1995-2002 Opera Software ASA and its suppliers. All rights reserved.

Macromedia Flash 8 video is powered by On2 TrueMotion video technology. © 1992-2005 On2 Technologies, Inc. All Rights Reserved. http://www.on2.com.

Visual SourceSafe is a registered trademark or trademark of Microsoft Corporation in the United States and/or other countries.

Updated Information/Additional Third Party Code Information available at http://www.adobe.com/go/thirdparty/.

Adobe Systems Incorporated, 345 Park Avenue, San Jose, California 95110, USA.

Notice to U.S. Government End Users. The Software and Documentation are "Commercial Items," as that term is defined at 48 C.F.R. §2.101, consisting of "Commercial Computer Software" and "Commercial Computer Software Documentation," as such terms are used in 48 C.F.R. §12.212 or 48 C.F.R. §227.7202, as applicable. Consistent with 48 C.F.R. §12.212 or 48 C.F.R. §\$227.7202-1 through 227.7202-4, as applicable, the Commercial Computer Software and Commercial Computer Software Documentation are being licensed to U.S. Government end users (a) only as Commercial Items and (b) with only those rights as are granted to all other end users pursuant to the terms and conditions herein. Unpublished-rights reserved under the copyright

laws of the United States. Adobe Systems Incorporated, 345 Park Avenue, San Jose, CA 95110-2704, USA. For U.S. Government End Users, Adobe agrees to comply with all applicable equal opportunity laws including, if appropriate, the provisions of Executive Order 11246, as amended, Section 402 of the Vietnam Era Veterans Readjustment Assistance Act of 1974 (38 USC 4212), and Section 503 of the Rehabilitation Act of 1973, as amended, and the regulations at 41 CFR Parts 60-1 through 60-60, 60-250, and 60-741. The affirmative action clause and regulations contained in the preceding sentence shall be incorporated by reference.

Contents

Introduction	9
Sample entry for most ActionScript elements	9
Samples folder	
Typographical conventions	
71 3 1	
Chapter 1: Flash Lite Global Functions	11
call()	13
chr()	
duplicateMovieClip()	
eval ()	
getProperty()	
getTimer()	17
getURL()	18
gotoAndPlay()	
gotoAndStop()	
ifFrameLoaded()	
int()	
length()	
loadMovie()	
loadMovieNum()	
loadVariables()	
loadVariablesNum()	
mbchr()	
mblength()	
mbord()	
mbsubstring()	
nextFrame()	
nextScene()	
Number()	
on()	
ord()	
play()	
prevFrame()	
prevScene()	
random()	
removeMovieClip()	. 39

set()	
setProperty()	
stop()	. 42
stopAllSounds()String()	
substring()	
tellTarget()	.44
toggleHighQuality()	
trace()	
unloadMovie()	
unloadMovieNum()	
, and the second	
Chapter 2: Flash Lite Properties	
/ (Forward slash)	.50
_alpha	. 51
_currentframe	
_focusrect	
_framesloaded	
_height	. 54
_highquality	
_level	
maxscroll	. 56
_name	. 57
scroll	. 57
_target	. 50
_totalframes	
_visible	59
_width	
_x	
_ _xscale	
_y	
_yscale	. 63
Chapter 3: Flash Lite Statements	
break	
case	
continue	. 68
dowhile	
else	
else if	
for	
ifswitch	. /4
while	

Chapter 4: Flash Lite Operators	79
add (string concatenation)	82
+= (addition assignment)	83
and	
= (assignment)	
/* (block comment)	
, (comma)	86
// (comment)	
?: (conditional)	88
(decrement)	88
/ (divide)	
/= (division assignment)	
. (dot)	
++ (increment)	
&& (logical AND)	
! (logical NOT)	
(logical OR)	
% (modulo)	
%= (modulo assignment)	
*= (multiplication assignment)	
* (multiply)	
+ (numeric add)	
== (numeric equality)	
> (numeric greater than)	
>= (numeric greater than or equal to)	
♦ (numeric inequality)	
<(numeric less than)	
(= (numeric less than or equal to)	102
() (parentheses)	103
" (string delimiter)	
eq (string equality)	
gt (string greater than)ge (string greater than or equal to)	
ne (string inequality)	
It (string less than)	
le (string less than or equal to)	1109 110
- (subtract)	
-= (subtraction assignment)	112
- (Subtraction assignment)	
Chapter 5: Flash Lite Specific Language Elements	113
Capabilities	
fscommand()	
fscommand2()	126
Index	150
IIIUGA	139

Introduction

This manual describes the syntax and use of ActionScript elements as you use them to develop applications for Macromedia® Flash® Lite™ 1.0 and Macromedia® Flash® Lite™ 1.1 software from Adobe, collectively referred to as Flash Lite 1.x. Flash Lite 1.x. ActionScript is based on the version of ActionScript that was used in Adobe's Macromedia® Flash® 4. To use examples in a script, copy the code example from this manual, and paste it into the Script pane or into an external script file. The manual lists all ActionScript elements—operators, keywords, statements, commands, properties, functions, classes, and methods.

Sample entry for most ActionScript elements

The following sample entry explains the conventions used for all ActionScript elements.

Entry title

Entries are listed alphabetically within a chapter. The alphabetization ignores capitalization, leading underscores, and so on.

Availability

Unless otherwise noted, the Availability section tells which versions of Flash Lite support the element.

Usage

This section provides correct syntax for using the ActionScript element in your code. The required portion of the syntax is in code font. Both the code that you provide and data type information are in <code>italicized code font</code>. Data types can be distinguished from code that you provide by the colon (:) that always precedes data type information. Brackets ([]) indicate optional parameters.

Operands

This section describes any parameters listed in the syntax.

Description

This section identifies the type of element (for example, operator, function, and so on), what values if any that the element returns, and then describes how to use the element.

Example

This section provides a code sample demonstrating how to use the element.

See also

This section lists related ActionScript dictionary entries.

Samples folder

For samples of complete Flash Lite projects with working ActionScript code, see the Flash Lite Samples and Tutorials page at www.adobe.com/go/learn_flt_samples_and_tutorials. Locate the .zip file for your ActionScript version, download and decompress the .zip file, and then navigate to the Samples folder to access the sample files.

Typographical conventions

The following typographical conventions are used in this book:

- *Italic font* indicates a value that should be replaced (for example, in a folder path).
- Code font indicates ActionScript code.
- Code font italic indicates an ActionScript parameter.
- **Bold font** indicates a verbatim entry.
- Double quotation marks (" ") in code examples indicate delimited strings. However, programmers can also use single quotation marks.

1

Flash Lite Global Functions

This section describes the syntax and use of the Adobe's Macromedia Flash Lite 1.1 ActionScript global functions. It includes the following functions:

Function	Description
call()	Executes the script in the called frame without moving the playhead to that frame.
chr()	Converts ASCII code numbers to characters.
<pre>duplicateMovieClip()</pre>	Creates an instance of a movie clip while the SWF file plays.
eval ()	Accesses variables, properties, objects, or movie clips by name.
getProperty()	Returns the value of the specified property for the specified movie clip.
<pre>getTimer()</pre>	Returns the number of milliseconds that elapsed since the SWF file started playing.
getURL()	Loads a document from a specific URL into a window or passes variables to another application at a defined URL.
gotoAndPlay()	Sends the playhead to the specified frame in a scene and begins playing from that frame. If no scene is specified, the playhead moves to the specified frame in the current scene.
gotoAndStop()	Sends the playhead to the specified frame in a scene and stops it. If no scene is specified, the playhead is sent to the frame in the current scene.
ifFrameLoaded()	Checks whether the contents of a specific frame are available locally
int()	Truncates a decimal number to an integer value.
length()	Returns the number of characters of the specified string or variable name.
loadMovie()	Loads a SWF file into Flash Lite while the original SWF file plays.
loadMovieNum()	Loads a SWF file into a level in Flash Lite while the originally loaded SWF file plays.

Function	Description
loadVariables()	Reads data from an external file, such as a text file or text generated by a ColdFusion, CGI ASP, PHP, or Perl script, and sets the values for variables in a Flash Lite level. This function can also update variables in the active SWF file with new values.
loadVariablesNum()	Reads data from an external file, such as a text file or text generated by a ColdFusion, CGI, ASP, PHP, or Perl script, and sets the values for variables in a Flash Lite level. This function can also update variables in the active SWF file with new values.
mbchr()	Converts an ASCII code number to a multibyte character.
mblength()	Returns the length of the multibyte character string.
mbord()	Converts the specified character to a multibyte number.
<pre>mbsubstring()</pre>	Extracts a new multibyte character string from a multibyte character string.
nextFrame()	Sends the playhead to the next frame and stops it.
nextScene()	Sends the playhead to Frame 1 of the next scene and stops it.
Number()	Converts an expression to a number and returns a value.
on()	Specifies the user event or keypress that triggers an event.
ord()	Converts characters to ASCII code numbers.
play()	Moves the playhead forward in the timeline.
<pre>prevFrame()</pre>	Sends the playhead to the previous frame and stops it. If the current frame is Frame 1, the playhead does not move.
prevScene()	Sends the playhead to Frame 1 of the previous scene and stops it.
removeMovieClip()	Deletes the specified movie clip that was originally created using duplicateMovieClip().
set()	Assigns a value to a variable.
setProperty()	Changes a property value of a movie clip as the movie plays.
stop()	Stops the SWF file that is currently playing.
stopAllSounds()	Stops all sounds currently playing in a SWF file without stopping the playhead.
String()	Returns a string representation of the specified parameter.
substring()	Extracts part of a string.
tellTarget()	Applies the instructions specified in the $statement(s)$ parameter to the timeline specified in the $target$ parameter.

Function	Description
toggleHighQuality()	Turns anti-aliasing on and off in Flash Lite. Anti-aliasing smooths the edges of objects but slows down SWF file playback.
trace()	Evaluates the expression and shows the result in the Output panel in test mode.
unloadMovie()	Removes a movie clip from Flash Lite that was loaded using <code>loadMovie() loadMovieNum()</code> , or <code>duplicateMovieClip()</code> .
unloadMovieNum()	Removes a movie clip that was loaded using <code>loadMovie()</code> <code>loadMovieNum()</code> , or <code>duplicateMovieClip()</code> from a level in Flash Lite.

call()

Availability

Flash Lite 1.0.

Usage

call(frame)

call(movieClipInstance:frame)

Operands

frame The label or number of a frame in the timeline.

movieClipInstance The instance name of a movie clip.

Description

Function; executes the script in the called frame without moving the playhead to that frame. Local variables do not exist after the script executes. The call() function can take two possible forms:

- The default form executes the script on the specified frame of the same timeline where the call() function was executed, without moving the playhead to that frame.
- The specified clip instance form executes the script on the specified frame of the movie clip instance, without moving the playhead to that frame.



The call() function operates synchronously; any ActionScript that follows a call() function does not execute until all of the ActionScript at the specified frame has completed.

Example

The following examples execute the script in the myScript frame:

```
// to execute functions in frame with label "myScript"
thisFrame = "myScript";
trace ("Calling the script in frame: " add thisFrame);
// to execute functions in any other frame on the same timeline
call("myScript");
```

chr()

Availability

Flash Lite 1.0.

Usage

chr(number)

Operands

number An ASCII code number.

Description

String function; converts ASCII code numbers to characters.

Example

The following example converts the number 65 to the letter A and assigns it to the variable my Var:

```
myVar = chr(65);
trace (myVar);// Output: A
```

duplicateMovieClip()

Availability

Flash Lite 1.0.

Usage

duplicateMovieClip(target, newname, depth)

Operands

target The target path of the movie clip to duplicate.

newname A unique identifier for the duplicated movie clip.

depth A unique depth level for the duplicated movie clip. The depth level indicates a stacking order for duplicated movie clips. This stacking order is much like the stacking order of layers in the timeline; movie clips with a lower depth level are hidden under clips that have a higher depth level. You must assign to each duplicated movie clip a unique depth level so that it does not overwrite existing movie clips on occupied depth levels.

Description

Function; creates an instance of a movie clip while the SWF file plays. Returns nothing. The playhead in a duplicate movie clip always starts at Frame 1, regardless of where the playhead is in the original (parent) movie clip. Variables in the parent movie clip are not copied into the duplicate movie clip. If the parent movie clip is deleted, the duplicate movie clip is also deleted. Use the removeMovieClip() function or method to delete a movie clip instance created with duplicateMovieClip(). Reference the new movie clip by using the string passed in as the newname operand.

Example

The following example duplicates a movie clip named originalClip to create a new clip named newClip, at a depth level of 10. The new clip's x position is set to 100 pixels.

```
duplicateMovieClip("originalClip", "newClip", 10);
setProperty("newClip", _x, 100);
```

The following example uses duplicateMovieClip() in a for loop to create several new movie clips at once. An index variable keeps track of the highest occupied stacking depth. Each duplicate movie clip's name contains a numeric suffix that corresponds to its stacking depth (clip1, clip2, clip3).

```
for (i = 1; i <= 3; i++) {
  newName = "clip" add i;
  duplicateMovieClip("originalClip", newName); }</pre>
```

See also

removeMovieClip()

eval()

Availability

Flash Lite 1.0.

Usage

eval(expression)

Operands

expression A string containing the name of a variable, property, object, or movie clip to retrieve.

Description

Function; accesses variables, properties, objects, or movie clips by name. If *expression* is a variable or a property, the value of the variable or property is returned. If *expression* is an object or movie clip, a reference to the object or movie clip is returned. If the element named in *expression* cannot be found, undefined is returned.

You can use eval() to simulate arrays, or to dynamically set and retrieve the value of a variable.

Example

The following example uses eval() to determine the value of the expression "piece" + x. Because the result is a variable name, piece3, eval() returns the value of the variable and assigns it to y:

```
piece3 = "dangerous";
x = 3;
y = eval("piece" add x);
trace(y);// Output: dangerous.
```

The following example demonstrates how an array could be simulated:

```
name1 = "mike";
name2 = "debbie";
name3 = "logan";
for(i = 1; i <= 3; i++) {
   trace (eval("name" add i));// Output: mike, debbie, logan
}</pre>
```

getProperty()

Availability

Flash Lite 1.0.

Usage

```
getProperty(my_mc, property)
```

Operands

my_mc The instance name of a movie clip for which the property is being retrieved. property A property of a movie clip.

Description

Function; returns the value of the specified property for the *my_mc* movie clip.

Example

The following example retrieves the horizontal axis coordinate (_x) for the my_mc movie clip in the root movie timeline:

```
xPos = getProperty("person_mc", _x);
trace (xPos); // output: -75
```

See also

setProperty()

getTimer()

Availability

Flash Lite 1.0.

Usage

getTimer()

Operands

None.

Description

Function; returns the number of milliseconds that elapsed since the SWF file started playing.

Example

The following example sets the timeElapsed variable to the number of milliseconds that elapsed since the SWF file started playing:

```
timeElapsed = getTimer();
trace (timeElapsed);// Output: milliseconds of time movie has been playing
```

getURL()

Availability

Flash Lite 1.0.

Usage

```
getURL(url [ , window [, "variables"]])
```

Operands

ur1 The URL from which to obtain the document.

window An optional parameter that specifies the window or HTML frame that the document should load into.



The window parameter is not specified for Flash Lite applications, because browsers on cell phones do not support multiple windows.

You can enter an empty string, or the name of a specific window, or choose from the following reserved target names:

- _self specifies the current frame in the current window.
- _blank specifies a new window.
- _parent specifies the parent of the current frame.
- _top specifies the top-level frame in the current window.

variables A GET or POST method for sending variables. If there are no variables, omit this parameter. The GET method appends the variables to the end of the URL and is used for small numbers of variables. The POST method sends the variables in a separate HTTP header and is used for sending long strings of variables.

Description

Function; loads a document from a specific URL into a window or passes variables to another application at a defined URL. To test this function, make sure the file you want to load is in the specified location. To use an absolute URL (for example, http://www.myserver.com), you need a network connection.

Flash Lite 1.0 recognizes only the HTTP, HTTPS, mailto, and tel protocols. Flash Lite 1.1 recognizes these protocols, and in addition, the file, SMS (short message service), and MMS (multimedia message service) protocols.

Flash Lite passes the call to the operating system, and the operating system handles the call with the registered default application for the specified protocol.

Only one getURL() function is processed per frame or per event handler.

Certain handsets restrict the getURL() function to key events only, in which case the getURL() call is processed only if it is triggered in a key event handler. Even under such circumstances, only one getURL() function is processed per event handler.

Example

In the following ActionScript, the Flash Lite player opens mobile.example.com in the default browser:

```
myURL = "http://mobile.example.com";
  on(keyPress "1") {
    getURL(myURL);
}
```

You can also use GET or POST for sending variables from the current timeline. The following example uses the GET method to append variables to a URL:

```
firstName = "Gus";
lastName = "Richardson";
age = 92;
getURL("http://www.example.com", "_blank", "GET");
```

The following ActionScript uses POST to send variables in an HTTP header:

```
firstName = "Gus";
lastName = "Richardson";
age = 92;
getURL("http://www.example.com", "POST");
```

You can assign a button function to open an e-mail composition window with the address, subject, and body text fields already populated. Use one of the following methods to assign a button function: Method 1 for either Shift-JIS or English character encoding; Method 2 only for English character encoding.

Method 1: Set variables for each of the desired parameters, as in this example:

```
on (release, keyPress "#"){
subject = "email subject";
body = "email body";
getURL("mailto:somebody@anywhere.com", "", "GET");
}
```

```
Method 2: Define each parameter within the getURL() function, as in this example:
```

```
on (release, keyPress "\#")\{ getURL("mailto:somebody@anywhere.com?cc=cc@anywhere.com&bcc=bcc@anywhere.com&subject=I am the email subject&body=I am the email body"); }
```

Method 1 results in automatic URL encoding, while Method 2 preserves the spaces in the strings. For example, the strings that result from using Method 1 are as follows:

```
email+subject
email+body
```

In contrast, Method 2 results in the following strings:

```
email subject email body
```

The following example uses the tel protocol:

```
on (release, keyPress "#"){
  getURL("tel:117");
}
```

In the following example, getURL() is used to send an SMS message:

```
mySMS = "sms:4156095555?body=sample sms message";
on(keyPress "5") {
   getURL(mySMS);
}
```

In the following example, getURL() is used to send an MMS message:

```
// mms example
myMMS = "mms:4156095555?body=sample mms message";
on(keyPress "6") {
   getURL(myMMS);
}
```

In the following example, getURL() is used to open a text file stored on the local file system:

```
// file protocol example
filePath = "file://c:/documents/flash/myApp/myvariables.txt";
on(keyPress "7") {
   getURL(filePath);
}
```

gotoAndPlay()

Availability

Flash Lite 1.0.

Usage

```
gotoAndPlay([scene,] frame)
```

Operands

scene An optional string specifying the name of the scene to which the playhead is sent.

frame A number representing the frame number, or a string representing the label of the frame, to which the playhead is sent.

Description

Function; sends the playhead to the specified frame in a scene and begins playing from that frame. If no scene is specified, the playhead moves to the specified frame in the current scene.

You can use the *scene* parameter only on the root timeline, not within timelines for movie clips or other objects in the document.

Example

In the following example, when the user clicks a button to which <code>gotoAndPlay()</code> is assigned, the playhead moves to Frame 16 in the current scene and starts to play the SWF file:

```
on(keyPress "7") {
  gotoAndPlay(16);
```

gotoAndStop()

Availability

Flash 1.0.

Usage

```
gotoAndStop([scene,] frame)
```

Operands

scene An optional string specifying the name of the scene to which the playhead is sent.

frame A number representing the frame number, or a string representing the label of the frame, to which the playhead is sent.

Description

Function; sends the playhead to the specified frame in a scene and stops it. If no scene is specified, the playhead is sent to the frame in the current scene.

You can use the *scene* parameter only on the root timeline, not within timelines for movie clips or other objects in the document.

Example

In the following example, when the user clicks a button to which <code>gotoAndStop()</code> is assigned, the playhead is sent to Frame 5 in the current scene, and the SWF file stops playing:

```
on(keyPress "8") {
  gotoAndStop(5);
}
```

ifFrameLoaded()

Availability

Flash Lite 1.0.

Usage

```
ifFrameLoaded([scene,] frame) {
   statement(s);
}
```

Operands

scene An optional string specifying the name of the scene to be loaded.

frame The frame number or frame label to be loaded before the next statement can execute. statement(s) The instructions to execute if the specified frame, or scene and frame, are loaded.

Description

Function; checks whether the contents of a specific frame are available locally. Use the <code>ifFrameLoaded</code> function to start playing a simple animation while the rest of the SWF file downloads to the local computer. You can also use the <code>_framesloaded</code> property to check the download progress of an external SWF file. The difference between using <code>_framesloaded</code> and <code>ifFrameLoaded</code> is that <code>_framesloaded</code> lets you add custom <code>if</code> or <code>else</code> statements.

Example

The following example uses the <code>ifFrameLoaded</code> function to check if Frame 10 of the SWF file is loaded. If the frame is loaded, the <code>trace()</code> command prints "frame number 10 is loaded" to the Output panel. The output variable is also defined with a variable of <code>frame</code>

```
loaded: 10.
ifFrameLoaded(10) {
   trace ("frame number 10 is loaded");
   output = "frame loaded: 10";
}
```

See also

_framesloaded

int()

Availability

Flash Lite 1.0.

Usage

int(value)

Operands

value A number or string to be truncated to an integer.

Description

Function; truncates a decimal number to an integer value.

Example

The following example truncates the numbers in the distance and myDistance variables:

```
distance = 6.04 - 3.96;
//trace ("distance = " add distance add " and rounded to:" add
  int(distance));
// Output: distance = 2.08 and rounded to: 2
myDistance = "3.8";
//trace ("myDistance = " add int(myDistance));
// Output: 3
```

length()

Availability

Flash Lite 1.0.

Usage

```
length(expression)
length(variable)
```

Operands

```
expression A string.

variable The name of a variable.
```

Description

String function; returns the number of characters of the specified string or variable name.

Example

```
The following example returns the length of the string "Hello": length("Hello");
```

The result is 5.

The following example validates an e-mail address by checking that it contains at least six characters:

```
email = "someone@example.com";
if (length(email) > 6) {
   //trace ("email appears to have enough characters to be valid");
}
```

loadMovie()

Availability

Flash Lite 1.1.

Usage

```
loadMovie(url, target [, method])
```

Operands

url A string specifying the absolute or relative URL of the SWF file to load. A relative path must be relative to the SWF file at level 0. Absolute URLs must include the protocol reference, such as http:// or file:///.

target A reference to a movie clip or a string representing the path to a target movie clip. The target movie clip is replaced by the loaded SWF file.

method An optional string parameter specifying an HTTP method for sending variables. The parameter must be the string GET or POST. If there are no variables to be sent, omit this parameter. The GET method appends the variables to the end of the URL and is used for small numbers of variables. The POST method sends the variables in a separate HTTP header and is used for long strings of variables.

Description

Function; loads a SWF file into Flash Lite while the original SWF file plays.

To load a SWF file into a specific level, use the loadMovieNum() function instead of loadMovie().

When a SWF file is loaded into a target movie clip, you can use the target path of that movie clip to target the loaded SWF file. A SWF file loaded into a target inherits the position, rotation, and scale properties of the targeted movie clip. The upper-left corner of the loaded image or SWF file aligns with the registration point of the targeted movie clip. However, if the target is the root timeline, the upper-left corner of the image or SWF file aligns with the upper-left corner of the Stage.

Use the unloadMovie() function to remove SWF files that were loaded with loadMovie().

Example

The following example loads the SWF file circle.swf from the same directory and replaces a movie clip called mySquare that already exists on the Stage:

```
loadMovie("circle.swf", "mySquare");
// Equivalent statement: loadMovie("circle.swf", _level0.mySquare);
```

See also

```
_level, loadMovieNum(), unloadMovie(), unloadMovieNum()
```

loadMovieNum()

Availability

Flash Lite 1.1.

Usage

loadMovieNum(url, level [, method])

Operands

ur1 A string specifying the absolute or relative URL of the SWF file to be loaded. A relative path must be relative to the SWF file at level 0. For use in the stand-alone Flash Lite player or for use in test mode in the Flash authoring application, all SWF files must be stored in the same folder and the filenames cannot include folder or drive specifications.

Teve7 An integer specifying the level in Flash Lite where the SWF file loads.

method An optional string parameter specifying an HTTP method for sending variables. It must have the value GET or POST. If there are no variables to be sent, omit this parameter. The GET method appends the variables to the end of the URL and is used for small numbers of variables. The POST method sends the variables in a separate HTTP header and is used for long strings of variables.

Description

Function; loads a SWF file into a level in Flash Lite while the originally loaded SWF file plays.

Normally, Flash Lite displays a single SWF file and then closes. The <code>loadMovieNum()</code> function lets you display several SWF files at once and switch among SWF files without loading another HTML document.

To specify a target instead of a level, use the <code>loadMovie()</code> function instead of <code>loadMovieNum()</code>.

Flash Lite has a stacking order of levels starting with level 0. These levels are like layers of acetate; they are transparent except for the objects on each level. When you use <code>loadMovieNum()</code>, you must specify a level in Flash Lite where the SWF file will load. When a SWF file is loaded into a level, you can use the syntax <code>_levelN</code>, where <code>N</code> is the level number, to target the SWF file.

When you load a SWF file, you can specify any level number. You can load SWF files into a level that already has a SWF file loaded into it, and the new SWF file replaces the existing file. If you load a SWF file into level 0, every level in Flash Lite is unloaded, and level 0 is replaced with the new file. The SWF file in level 0 sets the frame rate, background color, and frame size for all other loaded SWF files.

Use unloadMovieNum() to remove SWF files or images that were loaded with loadMovieNum().

Example

The following example loads the SWF file into level 2:

```
loadMovieNum("http://www.someserver.com/flash/circle.swf", 2);
```

See also

```
_level, loadMovie(), unloadMovieNum()
```

loadVariables()

Availability

Flash Lite 1.1.

Usage

```
loadVariables(url, target [, variables])
```

Operands

ur1 A string representing an absolute or relative URL where the variables are located. If the SWF file issuing this call is running in a web browser, *ur1* must be in the same domain as the SWF file.

target The target path to a movie clip that receives the loaded variables.

variables An optional string parameter specifying an HTTP method for sending variables. The parameter must be the string GET or POST. If there are no variables to be sent, omit this parameter. The GET method appends the variables to the end of the URL and is used for small numbers of variables. The POST method sends the variables in a separate HTTP header and is used for long strings of variables.

Description

Function; reads data from an external file, such as a text file or text generated by a ColdFusion, CGI, Active Server Pages (ASP), PHP, or Perl script, and sets the values for variables in a target movie clip. This function can also update variables in the active SWF file with new values.

The text at the specified URL must be in the standard MIME format *application/x-www-form-urlencoded* (a standard format used by CGI scripts). Any number of variables can be specified. For example, the following phrase defines several variables:

company=Adobe&address=600+Townsend&city=San+Francisco&zip=94103

To load variables into a specific level, use the <code>loadVariablesNum()</code> function instead of the <code>loadVariables()</code> function.

Example

The following examples load variables from a text file and from a server:

```
// load variables from text file on local file system (Symbian Series 60)
on(release, keyPress "1") {
  filePath = "file://c:/documents/flash/myApp/myvariables.txt";
  loadVariables(filePath, _root);
}

// load variables (from server) into a movieclip
urlPath = "http://www.someserver.com/myvariables.txt";
loadVariables(urlPath, "myClip_mc");
```

See also

loadMovieNum(), loadVariablesNum(), unloadMovie()

loadVariablesNum()

Availability

Flash Lite 1.1.

Usage

loadVariablesNum(url, level [, variables])

Operands

ur1 A string representing an absolute or relative URL where the variables to be loaded are located. If the SWF file issuing this call is running in a web browser, *ur1* must be in the same domain as the SWF file; for more information, see the following Description section.

1eve1 An integer that specifies the level in Flash Lite to receive the variables.

variables An optional string parameter specifying an HTTP method for sending variables. The parameter must be the string GET or POST. If there are no variables to be sent, omit this parameter. The GET method appends the variables to the end of the URL and is used for small numbers of variables. The POST method sends the variables in a separate HTTP header and is used for long strings of variables.

Description

Function; reads data from an external file, such as a text file or text generated by a ColdFusion, CGI, ASP, PHP, or Perl script, and sets the values for variables in a Flash Lite level. This function can also update variables in the active SWF file with new values.

The text at the specified URL must be in the standard MIME format *applicationlx-www-form-urlencoded* (a standard format used by CGI scripts). Any number of variables can be specified. The following example phrase defines several variables:

```
company=Adobe&address=600+Townsend&city=San+Francisco&zip=94103
```

Normally, Flash Lite displays a single SWF file, and then closes. The <code>loadVariablesNum()</code> function lets you display several SWF files at once and switch among SWF files without loading another HTML document.

To load variables into a target movie clip, use the <code>loadVariables()</code> function instead of the <code>loadVariablesNum()</code> function.

See also

```
getURL(), loadMovie(), loadMovieNum(), loadVariables()
```

mbchr()

Availability

Flash Lite 1.0.

Usage

mbchr(*number*)

Operands

number The number to convert to a multibyte character.

Description

String function; converts an ASCII code number to a multibyte character.

Example

The following example converts ASCII code numbers to their mulitibyte character equivalents:

```
trace (mbchr(65));// Output: A
trace (mbchr(97));// Output: a
trace (mbchr(36));// Output: $

myString = mbchr(51) - mbchr(49);
trace ("result = " add myString);// Output: result = 2
```

See also

mblength(), mbsubstring()

mblength()

Availability

Flash Lite 1.0.

Usage

mblength(string)

Operands

string A string.

Description

String function; returns the length of the multibyte character string.

Example

The following example displays the length of the string in the myString variable:

```
myString = mbchr(36) add mbchr(50);
trace ("string length = " add mblength(myString));
// Output: string length = 2
```

See also

```
mbchr(), mbsubstring()
```

mbord()

Availability

Flash Lite 1.0.

Usage

mbord(character)

Operands

character The character to convert to a multibyte number.

Description

String function; converts the specified character to a multibyte number.

Example

The following examples convert the characters in the myString variable to multibyte numbers:

```
myString = "A";
trace ("ord = " add mbord(myString));// Output: 65

myString = "$120";
for (i=1; i<=length(myString); i++)
    char = substring(myString, i, 1);
    trace ("char ord = " add mbord(char));// Output: 36, 49, 50, 48
}</pre>
```

See also

```
mbchr(), mbsubstring()
```

mbsubstring()

Availability

Flash Lite 1.0.

Usage

```
mbsubstring(value, index, count)
```

Operands

value The multibyte string from which to extract a new multibyte string.

index The number of the first character to extract.

count The number of characters to include in the extracted string, not including the index character.

Description

String function; extracts a new multibyte character string from a multibyte character string.

Example

The following example extracts a new multibyte character string from the string contained in the myString variable:

```
myString = mbchr(36) add mbchr(49) add mbchr(50) add mbchr(48); trace (mbsubstring(myString, 0, 2));// Output: $1
```

See also

mbchr()

nextFrame()

Availability

Flash Lite 1.0.

Usage

nextFrame()

Operands

None.

Description

Function; sends the playhead to the next frame and stops it.

Example

In the following example, when the user clicks the button, the playhead moves to the next frame and stops:

```
on (release) {
  nextFrame();
}
```

See also

prevFrame()

nextScene()

Availability

Flash Lite 1.0.

Usage

nextScene()

Operands

None.

Description

Function; sends the playhead to Frame 1 of the next scene and stops it.

Example

In the following example, when a user releases the button, the playhead moves to Frame 1 of the next scene:

```
on(release) {
  nextScene();
}
```

See also

prevScene()

Number()

Availability

Flash Lite 1.0.

Usage

Number(expression)

Operands

expression An expression to convert to a number.

Description

Function; converts the parameter *expression* to a number and returns a value as described in the following list:

- If expression is a number, the return value is expression.
- If expression is a Boolean value, the return value is 1 if expression is true; 0 if expression is false.
- If *expression* is a string, the function attempts to parse *expression* as a decimal number with an optional trailing exponent (that is, 1.57505e-3).
- If expression is undefined, the return value is -1.

Example

The following example converts the string in the myString variable to a number, stores the number in the myNumber variable, adds 5 to the number, and stores the result in the variable myResult. The final line shows the result when you call Number() on a Boolean value.

```
myString = "55";
myNumber = Number(myString);
myResult = myNumber + 5;
trace (myResult); // Output: 60
trace (Number(true));// Output: 1
```

on()

Availability

Flash Lite 1.0.

Usage

```
on(event) {
   // statement(s)
}
```

Operands

statement(s) The instructions to execute when event occurs.

event This trigger is called an event. When a user event occurs, the statements following it within curly braces ({}) execute. Any of the following values can be specified for the event parameter:

- press The button is pressed while the pointer is over the button.
- release The button is released while the pointer is over the button.
- rollout The pointer rolls outside the button area.
- rollover The pointer rolls over the button.
- keyPress "key" The specified key is pressed. For the key portion of the parameter, specify a key code or key constant.

Description

Event handler; specifies the user event or keypress that triggers a function. Not all events are supported.

Example

The following code, which scrolls the myText field down one line when the user presses the 8 key, tests against maxscroll before scrolling:

```
on (keyPress "8") {
  if (myText.scroll < myText.maxscroll) {
    myText.scroll++;
  }
}</pre>
```

ord()

Availability

Flash Lite 1.0.

Usage

ord(character)

Operands

character The character to convert to an ASCII code number.

Description

String function; converts characters to ASCII code numbers.

Example

The following example uses the ord() function to display the ASCII code for the character A: trace ("multibyte number = " add ord("A"));// Output: multibyte number = 65

play()

Availability

Flash Lite 1.0.

Usage

play()

Operands

None.

Description

Function; moves the playhead forward in the timeline.

The following example uses an if statement to check the value of a name that the user enters. If the user enters Steve, the play() function is called, and the playhead moves forward in the timeline. If the user enters anything other than Steve, the SWF file does not play, and a text field with the variable name alert appears.

```
stop();
if (name == "Steve") {
  play();
} else {
  alert="You are not Steve!";
}
```

prevFrame()

Availability

Flash Lite 1.0.

Usage

prevFrame()

Operands

None.

Description

Function; sends the playhead to the previous frame and stops it. If the current frame is Frame 1, the playhead does not move.

Example

When the user clicks a button that has the following handler attached to it, the playhead is sent to the previous frame:

```
on(release) {
  prevFrame();
}
```

See also

nextFrame()

prevScene()

Availability

Flash Lite 1.0.

Usage

prevScene()

Operands

None.

Description

Function; sends the playhead to Frame 1 of the previous scene and stops it.

Example

In this example, when the user clicks a button that has the following handler attached to it, the playhead is sent to the previous scene:

```
on(release) {
  prevScene();
}
```

See also

nextScene()

random()

Availability

Flash Lite 1.0.

Usage

random(value)

Operands

value An integer.

Description

Function; returns a random integer between 0 and one less than the integer specified in the *value* parameter.

The following examples generate a number based on an integer specifying the range:

```
//pick random number between 0 and 5
myNumber = random(5);
trace (myNumber);// Output: could be 0,1,2,3,4

//pick random number between 5 and 10
myNumber = random(5) + 5;
trace (myNumber);// Output: could be 5,6,7,8,9
```

The following examples generate a number, and then concatenate it onto the end of a string being evaluated as a variable name. This is an example of how Flash Lite 1.1 syntax can be used to simulate arrays.

```
// select random name from list
myNames1 = "Mike";
myNames2 = "Debbie";
myNames3 = "Logan";

ran = random(3) + 1;
ranName = "myNames" add ran;
trace (eval(ranName));// Output: will be mike, debbie, or logan
```

removeMovieClip()

Availability

Flash Lite 1.0.

Usage

removeMovieClip(target)

Operands

target The target path of a movie clip instance created with duplicateMovieClip().

Description

Function; deletes the specified movie clip that was originally created using duplicateMovieClip().

Example

The following example deletes the duplicate movie clip named second_mc:

```
duplicateMovieClip("person_mc", "second_mc", 1);
second_mc:_x = 55;
second_mc:_y = 85;
removeMovieClip("second_mc");
```

set()

Availability

Flash Lite 1.0.

Usage

```
set(variable, expression)
```

Operands

variable An identifier to hold the value of the expression parameter.

expression A value assigned to the variable.

Description

Statement; assigns a value to a variable. A *variable* is a container that holds data. The container is always the same, but the contents can change. By changing the value of a variable as the SWF file plays, you can record and save information about what the user has done, record values that change as the SWF file plays, or evaluate whether a condition is true or false.

Variables can hold any data type (for example, String, Number, Boolean, or MovieClip). The timeline of each SWF file and movie clip has its own set of variables, and each variable has its own value that is independent of variables on other timelines.

Example

The following example sets a variable called orig_x_pos, which stores the original x axis position of the ship movie clip to reset the ship to its starting location later in the SWF file:

```
on(release) {
   set("orig_x_pos", getProperty("ship", _x));
}
```

The preceding code gives the same result as the following code:

```
on(release) {
  orig_x_pos = ship._x;
```

setProperty()

Availability

Flash Lite 1.0.

Usage

```
setProperty(target, property, value/expression)
```

Operands

target The path to the instance name of the movie clip whose property is to be set.

property The property to be set.

value The new literal value of the property.

expression An equation that evaluates to the new value of the property.

Description

Function; changes a property value of a movie clip as the movie plays.

Example

The following statement sets the _alpha property of the star movie clip to 30 percent when the user clicks the button associated with this event handler:

```
on(release) {
   setProperty("star", _alpha, "30");
```

See also

getProperty()

stop()

Availability

Flash Lite 1.0.

Usage

stop()

Operands

None.

Description

Function; stops the SWF file that is currently playing. The most common use of this function is to control movie clips with buttons.

Example

The following statement calls the stop() function when the user clicks the button associated with this event handler:

```
on(release) {
  stop();
}
```

stopAllSounds()

Availability

Flash Lite 1.0.

Usage

stopAllSounds()

Operands

None.

Description

Function; stops all sounds currently playing in a SWF file without stopping the playhead. Sounds set to stream will resume playing as the playhead moves over the frames that contain them.

The following code could be applied to a button that when clicked, stops all sounds in the SWF file:

```
on(release) {
  stopAllSounds();
}
```

String()

Availability

Flash Lite 1.0.

Usage

String(expression)

Operands

expression An expression to convert to a string.

Description

Function; returns a string representation of the specified parameter as described in the following list:

- If *expression* is a number, the return string is a text representation of the number.
- If expression is a string, the return string is expression.
- If expression is a Boolean value, the return string is true or false.
- If *expression* is a movie clip, the return value is the target path of the movie clip in slash (/) notation.

Example

The following example sets birthYearNum to 1976, converts it to a string using the String() function, and then compares it to the string "1976" by using the eq operator.

```
birthYearNum = 1976;
birthYearStr = String(birthYearNum);
if (birthYearStr eq "1976") {
   trace ("birthYears match");
}
```

substring()

Availability

Flash Lite 1.0.

Usage

```
substring(string, index, count)
```

Operands

string The string from which to extract the new string.

index The number of the first character to extract.

count The number of characters to include in the extracted string, not including the index character.

Description

Function; extracts part of a string. This function is one-based, whereas the String class methods are zero-based.

Example

The following example extracts the first five characters from the string "Hello World":

```
origString = "Hello World!";
newString = substring(origString, 0, 5);
trace (newString);// Output: Hello
```

tellTarget()

Availability

Flash Lite 1.0.

Usage

```
tellTarget(target) {
    statement(s);
}
```

Operands

target A string that specifies the target path of the timeline to control.

statement(s) The instructions to execute if the condition evaluates to true.

Description

Function; applies the instructions specified in the <code>statement(s)</code> parameter to the timeline specified in the <code>target</code> parameter. The <code>tellTarget()</code> function is useful for navigation controls. Assign <code>tellTarget()</code> to buttons that stop or start movie clips elsewhere on the Stage. You can also make movie clips go to a particular frame in that clip. For example, you might assign <code>tellTarget()</code> to buttons that stop or start movie clips on the Stage or prompt movie clips to move to a particular frame.

Example

In the following example, tellTarget() controls the ball movie clip instance on the main timeline. Frame 1 of the ball instance is blank and has a stop() function so that it isn't visible on the Stage. When the user presses the 5 key, tellTarget() tells the playhead in ball to go to Frame 2 where the animation starts.

```
on(keyPress "5") {
  tellTarget("ball") {
    gotoAndPlay(2);
  }
}
```

toggleHighQuality()

Availability

Flash Lite 1.0.

Usage

toggleHighQuality()

Operands

None.

Description

Function; turns anti-aliasing on and off in Flash Lite. Anti-aliasing smooths the edges of objects but slows down SWF file playback. This function affects all SWF files in Flash Lite.

Example

The following code could be applied to a button that when clicked, would toggle anti-aliasing on and off:

```
on(release) {
  toggleHighQuality();
}
```

trace()

Availability

Flash Lite 1.0.

Usage

trace(expression)

Operands

expression An expression to evaluate. When a SWF file opens in the Flash authoring tool (by means of the Test Movie command), the value of the *expression* parameter appears in the Output panel.

Description

Function; evaluates the expression and shows the result in the Output panel in test mode.

Use this function to record programming notes or to display messages in the Output panel while testing a SWF file. Use the *expression* parameter to check if a condition exists, or to display values in the Output panel. The trace() function is similar to the alert function in JavaScript.

You can use the Omit Trace Actions command in publish settings to remove trace() functions from the exported SWF file.

Example

The following example uses the trace() function to observe the behavior of a while loop:

```
i = 0;
while (i++ < 5){
   trace("this is execution " add i);
}</pre>
```

unloadMovie()

Availability

Flash Lite 1.0.

Usage

unloadMovie(target)

Operands

target The target path of a movie clip.

Description

Function; removes a movie clip from Flash Lite that was loaded by means of loadMovie(), loadMovieNum(), or "duplicateMovieClip()".

Example

When the user presses the 3 key, the following code responds by unloading the draggable_mc movie clip on the main timeline and loading movie.swf into level 4 of the document stack:

```
on (keypress "3") {
  unloadMovie ("/draggable_mc");
  loadMovieNum("movie.swf", 4);
}
```

When the user presses the 3 key, the following example unloads the movie that was loaded into level 4:

```
on (keypress "3") {
    unloadMovieNum(4);
}
```

See also

loadMovie()

unloadMovieNum()

Availability

Flash Lite 1.0.

Usage

unloadMovieNum(*level*)

Operands

level The level (_level N) of a loaded movie.

Description

Function; removes a movie clip from Flash Lite that was loaded by means of loadMovie(), loadMovieNum(), or "duplicateMovieClip()".

Normally, Flash Lite displays a single SWF file, and then closes. The unloadMovieNum() function lets you affect several SWF files at once and switch among SWF files without loading another HTML document.

See also

loadMovieNum()

2

Flash Lite Properties

This section describes the properties that Adobe's Macromedia Flash Lite 1.x recognizes. The entries are listed alphabetically, ignoring any leading underscores. The properties are summarized in the following table:

Property	Description
/ (Forward slash)	Specifies or returns a reference to the main movie timeline.
_alpha	Returns the alpha transparency value of a movie clip.
_currentframe	Returns the number of the frame in which the playhead is located in the timeline.
_focusrect	Specifies whether a yellow rectangle appears around the button or text field that has the current focus.
_framesloaded	Returns the number of frames that have been loaded from a dynamically loaded SWF file.
_height	Specifies the height of the movie clip, in pixels.
_highquality	Specifies the level of anti-aliasing applied to the current SWF file.
_level	Returns a reference to the root timeline of <code>_level</code> \(. You must use the <code>loadMovieNum()</code> function to load SWF files into the Flash Lite player before you use the <code>_level</code> property to target them. You can also use <code>_level</code> \(to target a loaded SWF file at the level assigned by \(\text{\(N \)}. \)
maxscroll	Indicates the line number of the first visible line of text in a scrollable text field when the last line in the field is also visible.
_name	Returns the instance name of a movie clip. It applies only to movie clips and not to the main timeline.
_rotation	Returns the rotation of the movie clip, in degrees, from its original orientation.
scroll	Controls the display of information in a text field associated with a variable. The scroll property defines where the text field begins displaying content; after you set it, Flash Lite updates it as the user scrolls through the text field.

Property	Description
_target	Returns the target path of the movie clip instance.
_totalframes	Returns the total number of frames in a movie clip.
_visible	Indicates whether a movie clip is visible.
_width	Returns the width of the movie clip, in pixels.
_x	Contains an integer that sets the x coordinate of a movie clip.
_xscale	Sets the horizontal scale (percentage) of the movie clip, as applied from the registration point of the movie clip.
_y	Contains an integer that sets the y coordinate of a movie clip, relative to the local coordinates of the parent movie clip.
_yscale	Sets the vertical scale (percentage) of the movie clip, as applied from the registration point of the movie clip.

/ (Forward slash)

Availability

Flash Lite 1.0

Usage

/

/targetPath

/:varName

Description

Identifier; specifies or returns a reference to the main movie timeline. The functionality provided by this property is similar to that provided by the _root property in Flash 5.

Example

To specify a variable on a timeline, use slash syntax (/) combined with the colon (:).

Example 1: The car variable on the main Timeline:

/:car

Example 2: The car variable in the movie clip instance mc1 that resides on the main Timeline:

/mc1/:car

Example 3: The car variable in the movie clip instance mc2 nested in the movie clip instance mc1 that resides on the main Timeline:

```
/mc1/mc2/:car
```

Example 4: The car variable in the movie clip instance mc2 that resides on the current Timeline:

mc2/:car

_alpha

Availability

Flash Lite 1.0.

Usage

```
my_mc:_alpha
```

Property; the alpha transparency value of the movie clip specified by the *my_mc* variable. Valid values are 0 (fully transparent) to 100 (fully opaque), which is the default value. Objects in a movie clip with _alpha set to 0 are active, even though they are invisible. For example, you can click a button in a movie clip whose _alpha property is set to 0.

Example

The following code for a button event handler sets the _alpha property of the my_mc movie clip to 30% when the user clicks the button:

```
on(release) {
  tellTarget("my_mc") {
    _alpha = 30;
  }
}
```

_currentframe

Availability

Flash Lite 1.0.

Usage

my_mc:_currentframe

Description

Property (read-only); returns the number of the frame in which the playhead is located in the timeline that the *my_mc* variable specifies.

Example

The following example uses the _currentframe property and the <code>gotoAndStop()</code> function to direct the playhead of the <code>my_mc</code> movie clip to advance five frames ahead of its current location:

```
tellTarget("my_mc") {
   gotoAndStop(_currentframe + 5);
}
```

See also

gotoAndStop()

_focusrect

Availability

Flash Lite 1.0.

Usage

```
_focusrect = Boolean;
```

Description

Property (global); specifies whether a yellow rectangle appears around the button or text field that has the current focus. The default value, true, displays a yellow rectangle around the currently focused button or text field as the user presses the Up or Down Arrow keys on their phone or mobile device to navigate through objects in a SWF file. Specify false if you do not want the yellow rectangle to appear.

Example

The following example disables the yellow focus rectangle from appearing in the application: _focusrect = false;

_framesloaded

Availability

Flash Lite 1.0.

Usage

my_mc:_framesloaded

Description

Property (read-only); the number of frames that have been loaded from a dynamically loaded SWF file. This property is useful for determining whether the contents of a specific frame, and all the frames before it, have loaded and are available locally in the browser. It is also useful as a monitor while large SWF files download. For example, you might want to display a message to users indicating that the SWF file is loading until a specified frame in the SWF file finishes loading.

The following example uses the _framesloaded property to start a SWF file when all the frames are loaded. If all the frames aren't loaded, the _xscale property of the movie clip instance loader is increased proportionally to create a progress bar.

```
if (_framesloaded >= _totalframes) {
  gotoAndPlay ("Scene 1", "start");
} else {
  tellTarget("loader") {
    _xscale = (_framesloaded/_totalframes)*100;
  }
}
```

_height

Availability

Flash Lite 1.0.

Usage

my_mc:_height

Description

Property (read-only); the height of the movie clip, in pixels.

Example

The following example of event handler code sets the height of a movie clip when the user clicks the mouse button:

```
on(release) {
  tellTarget("my_mc") {
    _height = 200;
  }
}
```

_highquality

Availability

Flash Lite 1.0.

Usage

_highquality

Description

Property (global); specifies the level of anti-aliasing applied to the current SWF file. Specify 2 for best quality anti-aliasing. Specify 1 for high quality anti-aliasing. Specify 0 to prevent anti aliasing.

Example

The following statement applies high quality anti-aliasing to the current SWF file:

```
_{highquality} = 1;
```

See also

toggleHighQuality()

level

Availability

Flash Lite 1.0.

Usage

_level*N*

Description

Identifier; a reference to the root timeline of _level N. You must use the loadMovieNum() function to load SWF files into the Flash Lite player before you use the _level property to target them. You can also use _level N to target a loaded SWF file at the level assigned by N.

The initial SWF file that loads into an instance of the Flash Lite player automatically loads into _level0. The SWF file in _level0 sets the frame rate, background color, and frame size for all subsequently loaded SWF files. SWF files are then stacked in higher-numbered levels above the SWF file in _level0.

You must assign a level to each SWF file that you load into the Flash Lite player by using the <code>loadMovieNum()</code> function. You can assign levels in any order. If you assign a level that already contains a SWF file (including <code>_level0</code>), the SWF file at that level is unloaded and replaced by the new SWF file.

The following example loads a SWF file into Level 1, and then stops the playhead of the loaded SWF file on Frame 6:

```
loadMovieNum("mySWF.swf", 1);
// at least 1 frame later
tellTarget(_level1) {
   gotoAndStop(6);
}
```

See also

loadMovie()

maxscroll

Availability

Flash Lite 1.1

Usage

variable_name:maxscroll

Description

Property (read-only); indicates the line number of the first visible line of text in a scrollable text field when the last line in the field is also visible. The maxscroll property works with the scroll property to control how information appears in a text field. This property can be retrieved but not modified.

Example

The following code, which scrolls the myText text field down one line when the user presses the 8 key, tests against maxscroll before scrolling:

```
on(keyPress "8") {
  if (myText:scroll < myText:maxscroll) {
    myText:scroll++;
  }
}</pre>
```

See also

scroll

name

Availability

Flash Lite 1.0.

Usage

my_mc:_name

Description

Property; the instance name of the movie clip that my_mc specifies. It applies only to movie clips and not to the main timeline.

Example

The following example displays the name of the bigRose movie clip in the Output panel as a string:

```
trace(bigRose:_name);
```

_rotation

Availability

Flash Lite 1.0.

Usage

```
my_mc:_rotation
```

Description

Property; the rotation of the movie clip, in degrees, from its original orientation. Values from 0 to 180 represent clockwise rotation; values from 0 to -180 represent counterclockwise rotation. Values outside this range are added to or subtracted from 360 to obtain a value within the range. For example, the statement my_mc:_rotation = 450 is the same as my_mc:_rotation = 90.

Example

The following example rotates the my_mc movie clip 15 degrees clockwise when the user presses the 2 key:

```
on (keyPress "2") {
  my_mc:_rotation += 15;
```

scroll

Availability

Flash Lite 1.1.

Usage

textFieldVariableName:scroll

Description

Property; controls the display of information in a text field associated with a variable. The scroll property defines where the text field begins displaying content; after you set it, Flash Lite updates it as the user scrolls through the text field. You can use the scroll property to create a scrolling text field or to direct a user to a specific paragraph in a long passage.

Example

The following code scrolls the myText text field up one line each time the user clicks the 2 key:

```
on(keyPress "2") {
  if (myText:scroll > 1) {
    mvText:scroll--:
```

See also

maxscrol1

_target

Availability

Flash Lite 1.0.

Usage

my_mc:_target

Description

Property (read-only); returns the target path of the movie clip instance that my_mc specifies.

_totalframes

Availability

Flash Lite 1.0.

Usage

```
my_mc:_totalframes
```

Description

Property (read-only); returns the total number of frames in the *my_mc* movie clip.

Example

The following code loads mySWF.swf into Level 1, and then 25 frames later, checks to see whether it is loaded:

```
loadMovieNum("mySWF.swf", 1);

// 25 frames later in the main timeline
if (_level1._framesloaded >= _level1._totalframes) {
   tellTarget("_level1/") {
      gotoAndStop("myLabel");
   }
} else {
   // loop...
}
```

_visible

Availability

Flash Lite 1.0.

Usage

```
my_mc:_visible
```

Description

Property; a Boolean value that indicates whether the movie clip that my_mc specifies is visible. Movie clips that are not visible (_visible property set to false) are disabled. For example, a button in a movie clip with _visible set to false cannot be clicked. Movie clips are visible unless explicitly made invisible in this manner.

The following code disables the my_mc movie clip when the user presses the 3 key, and enables it when the user presses the 4 key:

```
on(keyPress "3") {
  my_mc:_visible = 0;
}
on(keyPress "4") {
  my_mc:_visible = 1;
}
```

_width

Availability

Flash Lite 1.0.

Usage

```
my_mc:_width
```

Description

Property; the width of the movie clip, in pixels.

Example

The following example sets the width properties of a movie clip when the user presses the 5 key:

```
on(keyPress "5") {
  my_mc:_width = 10;
}
```



Availability

Flash Lite 1.0.

Usage

```
my_mc:_x
```

Description

Property; an integer that sets the x coordinate of a movie clip (represented here by my_mc), relative to the local coordinates of the parent movie clip. If a movie clip is in the main timeline, its coordinate system refers to the upper-left corner of the Stage as (0, 0).

If the movie clip is inside another movie clip that has transformations, the movie clip is in the local coordinate system of the enclosing movie clip. For example, if a movie clip is rotated 90 degrees counterclockwise, the child movie clips inherit a coordinate system that is rotated 90 degrees counterclockwise. The movie clip's coordinates refer to the registration point position.

Example

The following example changes the horizontal position of the my_mc movie clip when the user presses the 6 key:

```
on(keyPress "6") {
   my_mc:_x = 10;
}
```

See also

```
_xscale, _y, _yscale
```

xscale

Availability

Flash Lite 1.0.

Usage

my_mc:_xscale

Description

Property; sets the horizontal scale (*percentage*) of the movie clip, as applied from the registration point of the movie clip. The default registration point is (0, 0).

Scaling the local coordinate system affects the _x and _y property settings, which are defined in pixels. For example, if the parent movie clip is scaled to 50%, setting the _x property moves an object in the movie clip by half of the number of pixels that it would if the movie were set at 100%.

The following example changes the horizontal scale of the my_mc movie clip when the user presses the 7 key:

```
on(keyPress "7") {
  my_mc:_xscale = 10;
}
```

See also

```
_x, _y, _yscale
```



Availability

Flash Lite 1.0.

Usage

 $my_mc:_y$

Description

Property; an integer that sets the *y* coordinate of a movie clip (represented here by *my_mc*), relative to the local coordinates of the parent movie clip. If a movie clip is in the main Timeline, its coordinate system refers to the upper-left corner of the Stage as (0, 0).

If the move clip is inside another movie clip that has transformations, the movie clip is in the local coordinate system of the enclosing movie clip. For example, if a movie clip is rotated 90 degrees counterclockwise, the child movie clips inherit a coordinate system that is rotated 90 degrees counterclockwise. The movie clip's coordinates refer to the registration point position.

Example

The following code sets the y coordinates of the my_mc movie clip 10 pixels below the (0, 0) coordinate of is parent clip when the user presses the 1 key:

```
on(keyPress "1") {
   my_mc:_y = 10;
}
```

See also

```
_x, _xscale, _yscale
```

_yscale

Availability

Flash Lite 1.0.

Usage

```
my_mc:_yscale
```

Description

Property; sets the vertical scale (*percentage*) of the movie clip, as applied from the registration point of the movie clip. The default registration point is (0, 0).

Scaling the local coordinate system affects the _x and _y property settings, which are defined in pixels. For example, if the parent movie clip is scaled to 50%, setting the _y property moves an object in the movie clip by half the number of pixels as it would if the movie were set at 100%.

Example

The following example changes the vertical scale of the my_mc movie clip to 10% when the user presses the 1 key:

```
on(keyPress "1") {
  my_mc:_yscale = 10;
}
```

See also

```
_x, _xscale, _y
```

3

Flash Lite Statements

This section describes the syntax and use of Adobe's Macromedia Flash Lite 1.x ActionScript statements, which are language elements that perform or specify an action. The statements are summarized in the following table:

Statement	Description
break	Instructs Flash Lite to skip the rest of the loop body, stop the looping action, and execute the statement following the loop statement.
case	Defines a condition for the switch statement. The statements in the statements parameter execute if the expression parameter that follows the case keyword equals the expression parameter of the switch statement.
continue	Jumps past all remaining statements in the innermost loop and starts the next iteration of the loop as if control had passed normally through to the end of the loop.
dowhile	Executes the statements, and then evaluates the condition in a loop for as long as the condition is true.
else	Specifies the statements to run if the condition in the if statement evaluates to $false$.
else if	Evaluates a condition and specifies the statements to run if the condition in the initial if statement returns a false value.
for	Evaluates the <i>init</i> (initialize) expression once, and then begins a looping sequence by which, as long as the <i>condition</i> evaluates to true, <i>statement</i> is executed, and the next expression is evaluated.
if	Evaluates a condition to determine the next action in a SWF file. If the condition is true, Flash Lite runs the statements that follow the condition inside curly braces ({}). If the condition is false, Flash Lite skips the statements inside the curly braces and runs the statements following the braces.

Statement	Description
switch	Similar to the if statement, the switch statement tests a condition and executes statements if the condition evaluates to true.
while	Tests an expression and runs a statement or series of statements repeatedly in a loop as long as the expression is ${\tt true}$.

break

Availability

Flash Lite 1.0.

Usage

break

Parameters

None.

Description

Statement; appears within a loop (for, do..while or while) or within a block of statements associated with a particular case within a switch statement. The break statement instructs Flash Lite to skip the rest of the loop body, stop the looping action, and execute the statement following the loop statement. When using the break statement, the ActionScript interpreter skips the rest of the statements in that case block and jumps to the first statement following the enclosing switch statement. Use this statement to break out of a series of nested loops.

Example

The following example uses the break statement to exit an otherwise infinite loop:

```
i = 0;
while (true) {
   if (i >= 100) {
      break;
   }
   i++;
}
```

See also

```
case, do..while, for, switch, while
```

case

Availability

Flash Lite 1.0.

Usage

```
case expression: statements
```

Parameters

```
expression Any expression.statements Any statements.
```

Description

Statement; defines a condition for the switch statement. The statements in the *statements* parameter execute if the *expression* parameter that follows the case keyword equals the *expression* parameter of the switch statement.

If you use the case statement outside a switch statement, it produces an error and the code doesn't compile.

Example

In the following example, if the myNum parameter evaluates to 1, the trace() statement that follows case 1 executes; if the myNum parameter evaluates to 2, the trace() statement that follows case 2 executes; and so on. If no case expression matches the number parameter, the trace() statement that follows the default keyword executes.

```
switch (myNum) {
  case 1:
    trace ("case 1 tested true");
    break;
  case 2:
    trace ("case 2 tested true");
    break;
  case 3:
    trace ("case 3 tested true");
    break;
  default:
    trace ("no case tested true")
}
```

In the following example, no break occurs in the first case group, so if the number is 1, both A and B appear in the Output panel:

```
switch (myNum) {
   case 1:
        trace ("A");
   case 2:
        trace ("B");
        break;
   default:
        trace ("D")
}
```

See also

switch

continue

Availability

Flash Lite 1.0.

Usage

continue

Parameters

None.

Description

Statement; jumps past all remaining statements in the innermost loop and starts the next iteration of the loop as if control had passed through to the end of the loop normally. It has no effect outside a loop.

- In a while loop, continue causes the Flash interpreter to skip the rest of the loop body and jump to the top of the loop, where the condition is tested.
- In a do..while loop, continue causes the Flash interpreter to skip the rest of the loop body and jump to the bottom of the loop, where the condition is tested.
- In a for loop, continue causes the Flash interpreter to skip the rest of the loop body and jump to the evaluation of the for loop's post-expression.

In the following while loop, continue causes Flash Lite to skip the rest of the loop body and jump to the top of the loop, where the condition is tested:

```
i = 0;
while (i < 10) {
   if (i % 3 == 0) {
      i++;
      continue;
   }
   trace(i);
   i++;
}</pre>
```

In the following do..while loop, continue causes Flash Lite to skip the rest of the loop body and jump to the bottom of the loop, where the condition is tested:

```
i = 0;
do {
   if (i % 3 == 0) {
      i++;
      continue;
   }
   trace(i);
   i++;
} while (i < 10);</pre>
```

In a for loop, continue causes Flash Lite to skip the rest of the loop body. In the following example, if i modulo 3 equals 0, the trace(i) statement is skipped:

```
for (i = 0; i < 10; i++) {
  if (i % 3 == 0) {
    continue;
  }
  trace(i);
}</pre>
```

See also

```
do..while, for, while
```

do..while

Availability

Flash Lite 1.0.

Usage

```
do {
   statement(s)
} while (condition)
```

Parameters

statement(s) The statement(s) to execute as long as the condition parameter evaluates
to true.

condition The condition to evaluate.

Description

Statement; executes the statements, and then evaluates the condition in a loop for as long as the condition is true.

Example

The following example increments the index variable as long as the variable's value is less than 10:

See also

break, continue, for, while

else

Availability

Flash Lite 1.0.

Usage

```
if (condition){
   t-statement(s);
} else {
   f-statement(s);
}
```

Parameters

condition An expression that evaluates to true or false.

t-statement(s) The instructions to execute if the condition evaluates to true.

f-statement(s) An alternative series of instructions to execute if the condition evaluates to false.

Description

Statement; specifies the statements to run if the condition in the if statement evaluates to false.

Example

The following example shows the use of the else statement with a condition. An actual example would include code to take some action based on the condition.

```
currentHighestDepth = 1;
if (currentHighestDepth == 2) {
   //trace ("currentHighestDepth is 2");
} else {
   //trace ("currentHightestDepth is not 2");
}
```

See also

if

else if

Availability

Flash Lite 1.0.

Usage

```
if (condition){
  statement(s):
} else if (condition){
  statement(s);
```

Parameters

condition An expression that evaluates to true or false.

statement(s) A series of statements to run if the condition specified in the if statement is false.

Description

Statement; evaluates a condition and specifies the statements to run if the condition in the initial if statement returns a false value. If the else if condition returns a true value, the Flash interpreter runs the statements that follow the else if condition inside curly braces ({}). If the else if condition is false, Flash skips the statements inside the curly braces and runs the statements following the curly braces. Use the else if statement to create branching logic in your scripts.

Example

The following example uses else if statements to check whether each side of an object is within a specific boundary:

```
person_mc.xPos = 100;
leftBound = 0:
rightBound = 100;
if (person mc.xPos <= leftBound) {</pre>
  //trace ("Clip is to the far left");
} else if (person_mc.xPos >= rightBound) {
  //trace ("Clip is to the far right");
  //trace ("Your clip is somewhere in between");
```

See also

if

72

for

Availability

Flash Lite 1.0.

Usage

```
for (init; condition; next) {
   statement(s);
}
```

Parameters

init An expression to evaluate before beginning the looping sequence, typically an assignment expression.

condition An expression that evaluates to true or false. The condition is evaluated before each loop iteration; the loop exits when the condition evaluates to false.

next An expression to evaluate after each loop iteration; usually an assignment expression using the increment (++) or decrement (--) operator.

statement(s) One or more instructions to execute in the loop.

Description

Statement; a loop construct that evaluates the *init* (initialize) expression once and then begins a looping sequence by which, as long as the *condition* evaluates to true, *statement* is executed, and the next expression is evaluated.

Some properties cannot be enumerated by the for or for..in statements. For example, movie clip properties, such as _x and _y, are not enumerated.

Example

The following example uses the for loop to sum the numbers from 1 to 100:

```
sum = 0;
for (i = 1; i <= 100; i++) {
   sum = sum + i;
}</pre>
```

```
++ (increment), -- (decrement), do..while, while
```

if

Availability

Flash Lite 1.0.

Usage

```
if (condition) {
    statement(s);
}
```

Parameters

condition An expression that evaluates to true or false.

statement(s) The instructions to execute if the condition evaluates to true.

Description

Statement; evaluates a condition to determine the next action in a SWF file. If the condition is true, Flash Lite runs the statements that follow the condition inside curly braces ({}}). If the condition is false, Flash Lite skips the statements inside the curly braces and runs the statements following the braces. Use the if statement to create branching logic in your scripts.

Example

In the following example, the condition inside the parentheses evaluates the variable name to see if it has the literal value "Erica". If it does, the play() function runs.

```
if(name eq "Erica"){
  play();
}
```

switch

Availability

Flash Lite 1.0.

Usage

```
switch (expression){
  caseClause:
  [defaultClause:]
```

Parameters

expression Any numeric expression.

caseClause A case keyword followed by an expression, a colon, and a group of statements to execute if the expression matches the switch expression parameter.

defaultClause An optional default keyword followed by statements to execute if none of the case expressions match the switch expression parameter.

Description

Statement; creates a branching structure for ActionScript statements. Similar to the if statement, the switch statement tests a condition and executes statements if the condition evaluates to true.

Switch statements contain a fallback option called default. If no other statements are true, the default statement is executed.

In the following example, if the myNum parameter evaluates to 1, the trace() statement that follows case 1 executes; if the myNum parameter evaluates to 2, the trace() statement that follows case 2 executes; and so on. If no case expression matches the number parameter, the trace() statement that follows the default keyword executes.

```
switch (myNum) {
  case 1:
    trace ("case 1 tested true");
    break;
  case 2:
    trace ("case 2 tested true");
    break;
  case 3:
    trace ("case 3 tested true");
    break;
  default:
    trace ("no case tested true")
```

In the following example, the first case group doesn't contain a break, so if the number is 1, both A and B appear in the Output panel:

```
switch (myNum) {
   case 1:
        trace ("A");
   case 2:
        trace ("B");
        break;
   default:
        trace ("D")
}
```

See also

case

while

Availability

Flash Lite 1.0.

Usage

```
while(condition) {
   statement(s);
}
```

Parameters

 ${\it condition} \quad \text{The expression that is evaluated each time the while statement executes.}$

statement(s) The instructions to execute when the condition evaluates to true.

Description

Statement; tests an expression and runs a statement or series of statements repeatedly in a loop as long as the expression is true.

Before the statement block is run, the condition is tested; if the test returns true, the statement block is run. If the condition is false, the statement block is skipped and the first statement after the while statement's statement block is executed.

Looping is commonly used to perform an action when a counter variable is less than a specified value. At the end of each loop, the counter is incremented until the specified value is reached. At that point, the condition is no longer true, and the loop ends.

The while statement performs the following series of steps. Each repetition of steps 1 through 4 is called an *iteration* of the loop. The condition is tested at the beginning of each iteration:

- **1.** The expression *condition* is evaluated.
- **2.** If *condition* evaluates to true or a value that converts to the Boolean value true, such as a nonzero number, go to step 3.

Otherwise, the while statement completes and execution resumes at the next statement after the while loop.

- **3.** Run the statement block statement(s).
- **4.** Go to step 1.

The following example executes a loop as long as the value of the index variable \dagger is less than 10:

```
i = 0;
while(i < 10) {
   trace ("i = " add ++i);// Output: 1,2,3,4,5,6,7,8,9
}
```

```
continue, do..while, for
```

4

Flash Lite Operators

This section describes the syntax and use of Adobe's Macromedia Flash Lite 1.x ActionScript operators. All entries are listed alphabetically. However, some operators are symbols and are alphabetized by their text descriptions.

The operators in this section are summarized in the following table:

Operator	Description
add (string concatenation)	Concatenates (combines) two or more strings.
<pre>+= (addition assignment)</pre>	Assigns expression1 the value of expression1 + expression2.
and	Performs a logical AND operation.
= (assignment)	Assigns the value of <i>expression2</i> (the operand on the right) to the variable or property in <i>expression1</i> .
/* (block comment)	Indicates one or more lines of script comments. Any characters that appear between the opening comment tag (/*) and the closing comment tag (*/) are interpreted as a comment and ignored by the ActionScript interpreter.
, (comma)	Evaluates <i>expression1</i> , then <i>expression2</i> , and returns the value of <i>expression2</i> .
// (comment)	Indicates the beginning of a script comment. Any characters that appear between the comment delimiter (//) and the end-of-line character are interpreted as a comment and ignored by the ActionScript interpreter.
?: (conditional)	Instructs Flash Lite to evaluate <code>expression1</code> , and if the value of <code>expression1</code> is true, the operator returns the value of <code>expression2</code> ; otherwise, it returns the value of <code>expression3</code> .

Operator	Description
(decrement)	Subtracts 1 from <i>expression</i> . The pre-decrement form of the operator (expression) subtracts 1 from <i>expression</i> and returns the result as a number. The post-decrement form of the operator (<i>expression</i>) subtracts 1 from <i>expression</i> and returns the initial value of <i>expression</i> (the value before the subtraction).
/ (divide)	Divides expression1 by expression2.
<pre>/= (division assignment)</pre>	Assigns expression1 the value of expression1 / expression2.
. (dot)	Used to navigate movie clip hierarchies to access nested (child) movie clips, variables, or properties.
++ (increment)	Adds 1 to <i>expression</i> . The expression can be a variable, element in an array, or property of an object. The pre-increment form of the operator (++expression) adds 1 to <i>expression</i> and returns the result as a number. The post-increment form of the operator (<i>expression</i> ++) adds 1 to <i>expression</i> and returns the initial value of <i>expression</i> (the value before the addition).
&& (logical AND)	Evaluates <i>expression1</i> (the expression on the left side of the operator) and returns false if the expression evaluates to false. If <i>expression1</i> evaluates to true, <i>expression2</i> (the expression on the right side of the operator) is evaluated. If <i>expression2</i> evaluates to true, the final result is true; otherwise, it is false.
! (logical NOT)	Inverts the Boolean value of a variable or expression. If expression is a variable with the absolute or converted value of true, the value of ! expression is false. If the expression x && y evaluates to false, the expression! (x && y) evaluates to true.
(logical OR)	Evaluates <i>expression1</i> and <i>expression2</i> . The result is true if either or both expressions evaluate to true; the result is false only if both expressions evaluate to false. You can use the logical OR operator with any number of operands; if any operand evaluates to true, the result is true.
% (modulo)	Calculates the remainder of <i>expression1</i> divided by <i>expression2</i> . If an <i>expression</i> operand is non-numeric, the modulo operator attempts to convert it to a number.
%= (modulo assignment)	Assigns expression1 the value of expression1 % expression2.
<pre>*= (multiplication assignment)</pre>	Assigns expression1 the value of expression1 * expression2.
* (multiply)	Multiples two numeric expressions.

Operator	Description
+ (numeric add)	Adds numeric expressions.
<pre>== (numeric equality)</pre>	Tests for equality; if $expression1$ is equal to $expression2$, the result is true.
<pre>> (numeric greater than)</pre>	Compares two expressions and determines whether $expression1$ is greater than $expression2$; if it is, the operator returns $true$. If $expression1$ is less than or equal to $expression2$, the operator returns false.
>= (numeric greater than or equal to)	Compares two expressions and determines whether <code>expression1</code> is greater than or equal to <code>expression2</code> (true) or whether <code>expression1</code> is less than <code>expression2</code> (false).
<pre><> (numeric inequality)</pre>	Tests for inequality; if <code>expression1</code> is equal to <code>expression2</code> , the result is <code>false</code> .
<pre>< (numeric less than)</pre>	Compares two expressions and determines whether <code>expression1</code> is less than <code>expression2</code> ; if so, the operator returns <code>true</code> . If <code>expression1</code> is greater than or equal to <code>expression2</code> , the operator returns <code>false</code> .
<pre><= (numeric less than or equal to)</pre>	Compares two expressions and determines whether <code>expression1</code> is less than or equal to <code>expression2</code> . If it is, the operator returns <code>true</code> ; otherwise, it returns <code>false</code> .
() (parentheses)	Groups one or more parameters, performs sequential evaluation of expressions, or surrounds one or more parameters and passes them as parameters to a function outside the parentheses.
" "(string delimiter)	When used before and after a sequence of zero or more characters, quotation marks indicate that the characters have a literal value and are considered a string; they are not a variable, numeric value, or other ActionScript element.
eq (string equality)	Compares two expressions for equality and returns true if the string representation of <i>expression1</i> is equal to the string representation of <i>expression2</i> ; otherwise, the operation returns false.
gt (string greater than)	Compares the string representation of <i>expression1</i> to the string representation of <i>expression2</i> and returns true if <i>expression1</i> is greater than <i>expression2</i> ; otherwise, it returns false.
ge (string greater than or equal to)	Compares the string representation of <code>expression1</code> to the string representation of <code>expression2</code> and returns a true value if <code>expression1</code> is greater than or equal to <code>expression2</code> ; otherwise, it returns <code>false</code> .
ne (string inequality)	Compares the string representations of <i>expression1</i> to <i>expression2</i> and returns true if <i>expression1</i> is not equal to <i>expression2</i> ; otherwise, it returns false.

Operator	Description
lt (string less than)	Compares the string representation of <i>expression1</i> to the string representation of <i>expression2</i> and returns a true value if <i>expression1</i> is less than <i>expression2</i> ; otherwise, it returns false.
le (string less than or equal to)	Compares the string representation of <i>expression1</i> to the string representation of <i>expression2</i> and returns a true value if <i>expression1</i> is less than or equal to <i>expression2</i> ; otherwise, it returns false.
- (subtract)	Used for negating or subtracting.
-= (subtraction assignment)	Assigns expression1 the value of expression1 - expression2.

add (string concatenation)

Availability

Flash Lite 1.0.

Usage

string1 add string2

Operands

string1, string2 Strings.

Description

Operator; concatenates (combines) two or more strings.

Example

The following example combines two string values to produce the string *catalog*.

```
conStr = "cat" add "alog";
trace (conStr);// output: catalog
```

See also

+ (numeric add)

+= (addition assignment)

Availability

Flash Lite 1.0.

Usage

```
expression1 += expression2
```

Operands

expression1, expression2 Numbers or strings.

Description

Operator (arithmetic compound assignment); assigns <code>expression1</code> the value of <code>expression1 + expression2</code>. For example, the following two statements have the same result:

```
x += y;

x = x + y;
```

All the rules of the addition (+) operator apply to the addition assignment (+=) operator.

Example

The following example uses the addition assignment (+=) operator to increase the value of x by the value of y:

```
x = 5;
y = 10;
x += y;
trace(x);// output: 15
```

See also

```
+ (numeric add)
```

and

Availability

Flash Lite 1.0.

Usage

condition1 and condition2

Operands

condition1, condition2 Conditions or expressions that evaluate to true or false.

Description

Operator; performs a logical AND operation.

Example

The following example uses the and operator to test whether a player has won the game. The turns variable and the score variable are updated when a player takes a turn or scores points during the game. The following script shows "You Win the Game!" in the Output panel when the player's score reaches 75 or higher in three turns or less.

```
turns = 2;
score = 77;
winner = (turns <= 3) and (score >= 75);
if (winner) {
   trace("You Win the Game!");
} else {
   trace("Try Again!");
}
// output: You Win the Game!
```

See also

```
&& (logical AND)
```

= (assignment)

Availability

Flash Lite 1.0.

Usage

```
expression1 = expression2
```

Operands

```
expression1 A variable or a property.
expression2 A value.
```

Description

Operator; assigns the value of *expression2* (the operand on the right) to the variable or property in *expression1*.

The following example uses the assignment (=) operator to assign a numeric value to the variable weight:

```
weight = 5;
```

The following example uses the assignment (=) operator to assign a string value to the variable greeting:

```
greeting = "Hello, " and personName;
```

/* (block comment)

Availability

Flash Lite 1.0

Usage

```
/* comment */
/* comment
comment */
```

Operands

comment Any characters.

Description

Comment delimiter; indicates one or more lines of script comments. Any characters that appear between the opening comment tag (/*) and the closing comment tag (*/) are interpreted as a comment and ignored by the ActionScript interpreter.

Use the // (comment delimiter) to identify single-line comments. Use the /* comment delimiter to identify comments on multiple successive lines. Leaving off the closing tag (*/) when using this form of comment delimiter returns an error message. Attempting to nest comments also returns an error message.

After you use an opening comment tag (/*), the first closing comment tag (*/) will end the comment, regardless of the number of opening comment tags (/*) placed between them.

```
// (comment)
```

, (comma)

Availability

Flash Lite 1.0.

Usage

```
expression1, expression2
```

Operands

expression1, expression2 Numbers or expressions that evaluate to numbers.

Description

Operator; evaluates expression1, then expression2, and returns the value of expression2.

Example

The following example uses the comma (,) operator without the parentheses () operator and illustrates that the comma operator returns only the value of the first expression without the parentheses () operator:

```
v = 0;
v = 4, 5, 6;
trace(v); // output: 4
```

The following example uses the comma (,) operator with the parentheses () operator and illustrates that the comma operator returns the value of the last expression when used with the parentheses () operator:

```
v = 0;

v = (4, 5, 6);

trace(v); // output: 6
```

The following example uses the comma (,) operator without the parentheses () operator and illustrates that the comma operator sequentially evaluates all of the expressions but returns the value of the first expression. The second expression, z++, is evaluated and z is incremented by 1.

```
v = 0;
z = 0;
v = v + 4 , z++, v + 6;
trace(v); // output: 4
trace(z); // output: 1
```

The following example is identical to the previous example except for the addition of the parentheses () operator and illustrates once again that when used with the parentheses () operator, the comma (,) operator returns the value of the last expression in the series:

```
v = 0;
z = 0;
v = (v + 4, z++, v + 6);
trace(v); // output: 6
trace(z); // output: 1
```

See also

for,() (parentheses)

// (comment)

Availability

Flash Lite 1.0

Usage

// comment

Operands

comment Any characters.

Description

Comment delimiter; indicates the beginning of a script comment. Any characters that appear between the comment delimiter (//) and the end-of-line character are interpreted as a comment and ignored by the ActionScript interpreter.

Example

The following example uses comment delimiters to identify the first, third, fifth, and seventh lines as comments:

```
// Record the X position of the ball movie clip.
ballX = ball._x;
// Record the Y position of the ball movie clip.
ballY = ball._y;
// Record the X position of the bat movie clip.
batX = bat._x;
// Record the Y position of the bat movie clip.
batY = bat._y;
```

```
/* (block comment)
```

?: (conditional)

Availability

Flash Lite 1.0.

Usage

```
expression1 ? expression2 : expression3
```

Operands

expression 1 An expression that evaluates to a Boolean value, usually a comparison expression, such as $x \le 5$.

expression2, expression3 Values of any type.

Description

Operator; instructs Flash Lite to evaluate *expression1*, and if the value of *expression1* is true, it returns the value of *expression2*; otherwise, it returns the value of *expression3*.

Example

The following example assigns the value of variable x to variable z because *expression1* evaluates to true:

```
x = 5;

y = 10;

z = (x < 6) ? x: y;

trace (z);// output: 5
```

-- (decrement)

Availability

Flash Lite 1.0.

Usage

```
--expression expression--
```

Operands

None.

Description

Operator (arithmetic); a pre-decrement and post-decrement unary operator that subtracts 1 from *expression*. The pre-decrement form of the operator (*--expression*) subtracts 1 from *expression* and returns the result as a number. The post-decrement form of the operator (*expression--*) subtracts 1 from *expression* and returns the initial value of *expression* (the value before the subtraction).

Example

The following example shows the pre-decrement form of the operator, decrementing a Width to 2 (a Width -1 = 2) and returning the result as bWidth:

```
aWidth = 3;
bWidth = --aWidth;
// The bWidth value is equal to 2.
```

The next example shows the post-decrement form of the operator decrementing a Width to 2 (a Width -1 = 2) and returning the original value of a Width as the result b Width:

```
aWidth = 3;
bWidth = aWidth--;
// The bWidth value is equal to 3.
```

/ (divide)

Availability

Flash Lite 1.0.

Usage

expression1 / expression2

Operands

expression1, expression2 Numbers or expressions that evaluate to numbers.

Description

Operator (arithmetic); divides *expression1* by *expression2*. The result of the division operation is a double-precision floating-point number.

Example

The following statement divides the floating-point number 22.0 by 7.0 and then shows the result in the Output panel:

```
trace(22.0 / 7.0):
```

The result is 3.1429, which is a floating-point number.

/= (division assignment)

Availability

Flash Lite 1.0.

Usage

```
expression1 /= expression2
```

Operands

expression1, expression2 Numbers or expressions that evaluate to numbers.

Description

Operator (arithmetic compound assignment); assigns expression1 the value of expression1 / expression2. For example, the following two statements are equivalent:

```
x = x / y
```

Example

The following example uses the /= operator with variables and numbers:

```
x = 10:
y = 2;
\chi /= y;
// The expression x now contains the value 5.
```

. (dot)

Availability

Flash Lite 1.0.

Usage

```
instancename.variable
instancename.childinstance.variable
```

Operands

instancename The instance name of a movie clip.

childinstance A movie clip instance that is a child of, or nested in, another movie clip. variable A variable on the timeline of the specified movie clip instance name.

Description

Operator; used to navigate movie clip hierarchies to access nested (child) movie clips, variables, or properties.

Example

The following example identifies the current value of the variable hairColor in the movie clip person_mc:

```
person_mc.hairColor
```

This is equivalent to the following slash notation syntax:

```
/person_mc:hairColor
```

See also

/ (Forward slash)

++ (increment)

Availability

Flash Lite 1.0.

Usage

++expression

expression++

Operands

None.

Description

Operator (arithmetic); a pre-increment and post-increment unary operator that adds 1 to *expression*. The expression can be a variable, element in an array, or property of an object. The pre-increment form of the operator (++expression) adds 1 to *expression* and returns the result as a number. The post-increment form of the operator (*expression*++) adds 1 to *expression* and returns the initial value of *expression* (the value before the addition).

The following example uses ++ as a post-increment operator to make a while loop run five times:

```
i = 0;
while (i++ < 5){
   trace("this is execution " + i);
}</pre>
```

The following example uses ++ as a pre-increment operator:

```
a = "";
i = 0;
while (i < 10) {
    a = a add (++i) add ",";
}
trace(a);// output: 1,2,3,4,5,6,7,8,9,10,</pre>
```

This script shows the following result in the Output panel:

```
1,2,3,4,5,6,7,8,9,10,
```

The following example uses ++ as a post-increment operator:

```
a = "";
i = 0;
while (i < 10) {
    a = a add (i++) add ",";
}
trace(a);// output: 0,1,2,3,4,5,6,7,8,9,</pre>
```

This script shows the following result in the Output panel:

```
0,1,2,3,4,5,6,7,8,9,
```

&& (logical AND)

Availability

Flash Lite 1.0.

Usage

expression1 && expression2

Operands

expression1, expression2 Boolean values or expressions that convert to Boolean values.

Description

Operator (logical); performs a Boolean operation on the values of one or both of the expressions. The operator evaluates <code>expression1</code> (the expression on the left side of the operator) and returns <code>false</code> if the expression evaluates to <code>false</code>. If <code>expression1</code> evaluates to <code>true</code>, <code>expression2</code> (the expression on the right side of the operator) is evaluated. If <code>expression2</code> evaluates to <code>true</code>, the final result is <code>true</code>; otherwise, it is <code>false</code>.

Example

The following example uses the && operator to perform a test to determine if a player has won the game. The turns variable and the score variable are updated when a player takes a turn or scores points during the game. The following script shows "You Win the Game!" in the Output panel when the player's score reaches 75 or higher in three turns or less.

```
turns = 2;
score = 77;
winner = (turns <= 3) && (score >= 75);
if (winner) {
   trace("You Win the Game!");
} else {
   trace("Try Again!");
}
```

The following example demonstrates testing to see if an imaginary x position is in between a range:

```
xPos = 50;
if (xPos >= 20 && xPos <= 80) {
  trace ("the xPos is in between 20 and 80");
}</pre>
```

! (logical NOT)

Availability

Flash Lite 1.0.

Usage

!expression

Operands

None.

Description

Operator (logical); inverts the Boolean value of a variable or expression. If *expression* is a variable with the absolute or converted value of true, the value of ! *expression* is false. If the expression x && y evaluates to false, the expression !(x && y) evaluates to true.

The following expressions show the result of using the ! operator:

```
! true returns false
! false returns true
```

Example

In the following example, the variable happy is set to false. The if condition evaluates the condition !happy, and if the condition is true, the trace() function sends a string to the Output panel.

```
happy = false;
if (!happy) {
  trace("don't worry, be happy");
}
```

|| (logical OR)

Availability

Flash Lite 1.0.

Usage

```
expression1 || expression2
```

Operands

expression1, expression2 Boolean values or expressions that convert to Boolean values.

Description

Operator (logical); evaluates *expression1* and *expression2*. The result is true if either or both expressions evaluate to true; the result is false only if both expressions evaluate to false. You can use the logical OR operator with any number of operands; if any operand evaluates to true, the result is true.

With non-Boolean expressions, the logical OR operator causes Flash Lite to evaluate the expression on the left; if it can be converted to true, the result is true. Otherwise, it evaluates the expression on the right, and the result is the value of that expression.

Example

Usage 1: The following example uses the || operator in an if statement. The second expression evaluates to true, so the final result is true:

```
theMinimum = 10;
theMaximum = 250;
start = false;
if (theMinimum > 25 || theMaximum > 200 || start){
  trace("the logical OR test passed");
}
```

% (modulo)

Availability

Flash Lite 1.0.

Usage

expression1 % expression2

Operands

expression1, expression2 Numbers or expressions that evaluate to numbers.

Description

Operator (arithmetic); calculates the remainder of *expression1* divided by *expression2*. If an *expression* operand is non-numeric, the modulo operator attempts to convert it to a number. The expression can be a number or string that converts to a numeric value.

When targeting Flash Lite 1.0 or 1.1, the Flash compiler expands the % operator in the published SWF file by using the following formula:

```
expression1 - int(expression1/expression2) * expression2
```

The performance of this approximation might not be as fast or as accurate as versions of Flash Player that natively support the modulo operator.

The following code shows a numeric example that uses the modulo (%) operator:

```
trace (12 % 5);// output: 2
trace (4.3 % 2.1);// output: 0.0999...
```

%= (modulo assignment)

Availability

Flash Lite 1.0.

Usage

```
expression1 %= expression2
```

Operands

expression1, expression2 Numbers or expressions that evaluate to numbers.

Description

Operator (arithmetic compound assignment); assigns *expression1* the value of *expression1* % *expression2*. For example, the following two expressions are equivalent:

```
x \% = y

x = x \% y
```

Example

The following example assigns the value 4 to the variable x:

```
x = 14;
y = 5;
trace(x %= y);// output: 4
```

See also

```
% (modulo)
```

*= (multiplication assignment)

Availability

Flash Lite 1.0.

Usage

```
expression1 *= expression2
```

Operands

expression1, expression2 Numbers or expressions that evaluate to numbers.

Description

Operator (arithmetic compound assignment); assigns *expression1* the value of *expression1* * *expression2*.

For example, the following two expressions are the same:

Example

Usage 1: The following example assigns the value 50 to the variable x:

```
x = 5;

y = 10;

trace (x *= y);// output: 50
```

Usage 2: The second and third lines of the following example calculate the expressions on the right side of the equals sign (=) and assign the results to \times and y:

```
i = 5;
x = 4 - 6;
y = i + 2;
trace(x *= y);// output: -14
```

* (multiply)

Availability

Flash Lite 1.0.

Usage

```
expression1 * expression2
```

Operands

expression1, expression2 Numeric expressions.

Description

Operator (arithmetic); multiplies two numeric expressions. If both expressions are integers, the product is an integer. If either or both expressions are floating-point numbers, the product is a floating-point number.

Usage 1: The following statement multiplies the integers 2 and 3:

```
2 * 3
```

The result is 6, which is an integer.

Usage 2: The following statement multiplies the floating-point numbers 2.0 and 3.1416:

```
2.0 * 3.1416
```

The result is 6.2832, which is a floating-point number.

+ (numeric add)

Availability

Flash Lite 1.0.

Usage

```
expression1 + expression2
```

Operands

expression1, expression2 Numbers.

Description

Operator; adds numeric expressions. The + is a numeric operator only; it cannot be used for string concatenation.

If both expressions are integers, the sum is an integer; if either or both expressions are floating-point numbers, the sum is a floating-point number.

Example

The following example adds the integers 2 and 3; the resulting integer, 5, appears in the Output panel:

```
trace (2 + 3):
```

The following example adds the floating-point numbers 2.5 and 3.25; the result, 5.75, a floating-point number, appears in the Output panel:

```
trace (2.5 + 3.25);
```

```
add (string concatenation)
```

== (numeric equality)

Availability

Flash Lite 1.0.

Usage

```
expression1 == expression2
```

Operands

expression1, expression2 Numbers, Boolean values, or variables.

Description

Operator (comparison); tests for equality; the exact opposite of the <> operator. If expression1 is equal to expression2, the result is true. As with the <> operator, the definition of equal depends on the data types being compared:

- Numbers and Boolean values are compared by value.
- Variables are compared by reference.

Example

The following examples show true and false return values:

```
trees = 7;
bushes = "7";
shrubs = "seven";

trace (trees == "7");// output: 1(true)
trace (trees == bushes);// output: 1(true)
trace (trees == shrubs);// output: 0(false)
```

```
eq (string equality)
```

> (numeric greater than)

Availability

Flash Lite 1.0.

Usage

expression1 > expression2

Operands

expression1, expression2 Numbers or expressions that evaluate to numbers.

Operator (comparison); compares two expressions and determines whether *expression1* is greater than *expression2*; if it is, the operator returns true. If *expression1* is less than or equal to *expression2*, the operator returns false.

Example

The following examples show true and false results for numeric comparisons:

```
trace(3.14 > 2);// output: 1(true)

trace(1 > 2);// output: 0(false)
```

See also

gt (string greater than)

>= (numeric greater than or equal to)

Availability

Flash Lite 1.0.

Usage

expression1 >= expression2

Operands

expression1, expression2 Integers or floating-point numbers.

Description

Operator (comparison); compares two expressions and determines whether *expression1* is greater than or equal to *expression2* (true) or whether *expression1* is less than *expression2* (false).

The following examples show true and false results:

```
trace(3.14 \geq= 2);// output: 1(true) trace(3.14 \geq= 4);// output: 0(false)
```

See also

```
ge (string greater than or equal to)
```

(numeric inequality)

Availability

Flash Lite 1.0.

Usage

```
expression1 <> expression2
```

Operands

expression1, expression2 Numbers, Boolean values, or variables.

Description

Operator (comparison); tests for inequality; the exact opposite of the equality (==) operator. If *expression1* is equal to *expression2*, the result is false. As with the equality (==) operator, the definition of *equal* depends on the data types being compared:

- Numbers and Boolean values are compared by value.
- Variables are compared by reference.

Example

The following examples show true and false returns:

```
trees = 7;
B = "7";

trace(trees <> 3);// output: 1(true)
trace(trees <> B);// output: 0(false)
```

```
ne (string inequality)
```

<(numeric less than)</pre>

Availability

Flash Lite 1.0.

Usage

expression1 < expression2

Operands

expression1, expression2 Numbers.

Description

Operator (comparison); compares two expressions and determines whether expression1 is less than expression2; if so, the operator returns true. If expression1 is greater than or equal to expression2, the operator returns false. The < (less than) operator is a numeric operator.

Example

The following examples show true and false results for both numeric and string comparisons:

```
trace (3 < 10);// output: 1(true)
trace (10 < 3);// output: 0(false)
```

See also

lt (string less than)

<= (numeric less than or equal to)

Flash Lite 1.0.

Usage

expression1 <= expression2

Operands

expression1, expression2 Numbers.

Description

Operator (comparison); compares two expressions and determines whether expression1 is less than or equal to expression2. If it is, the operator returns true; otherwise, it returns false. This operator is for numeric comparison only.

The following examples show true and false results for numeric comparisons:

```
trace(5 <= 10);// output: 1(true)
trace(2 <= 2);// output: 1(true)
trace (10 <= 3);// output: 0 (false)</pre>
```

See also

le (string less than or equal to)

() (parentheses)

Availability

Flash Lite 1.0.

Usage

```
(expression1 [, expression2])
(expression1, expression2)
```

expression1, expression2 Numbers, strings, variables, or text.

parameter1,..., parameterN A series of parameters to execute before the results are passed as parameters to the function outside the parentheses.

Description

Operator; groups one or more parameters, performs sequential evaluation of expressions, or surrounds one or more parameters and passes them as parameters to a function outside the parentheses.

Usage 1: Controls the order in which the operators execute in the expression. Parentheses override the normal precedence order and cause the expressions within the parentheses to be evaluated first. When parentheses are nested, the contents of the innermost parentheses are evaluated before the contents of the outer ones.

Usage 2: Evaluates a series of expressions, separated by commas, in sequence, and returns the result of the final expression.

Usage 1: The following statements show the use of parentheses to control the order in which expressions are executed (the value of each expression appears in the Output panel):

```
trace((2 + 3) * (4 + 5)); // displays 45
trace(2 + (3 * (4 + 5))); // // displays 29
trace(2 + (3 * 4) + 5); // displays 19
```

Usage 1: The following statements show the use of parentheses to control the order in which expressions are executed (the value of each expression is written to the log file):

```
trace((2 + 3) * (4 + 5)); // writes 45

trace(2 + (3 * (4 + 5))); // writes 29

trace(2 + (3 * 4) + 5); // writes 19
```

" " (string delimiter)

Availability

Flash Lite 1.0.

Usage

"text"

Operands

text Zero or more characters.

Description

String delimiter; when used before and after a sequence of zero or more characters, quotation marks indicate that the characters have a literal value and are considered a *string*; they are not a variable, numeric value, or other ActionScript element.

Example

This example uses quotation marks to indicate that the value of the variable yourGuess is the literal string "Prince Edward Island" and not the name of a variable. The value of province is a variable, not a literal; to determine the value of province, the value of yourGuess must be located.

```
yourGuess = "Prince Edward Island";
on(release){
  province = yourGuess;
  trace(province);// output: Prince Edward Island
}
```

eq (string equality)

Availability

Flash Lite 1.0.

Usage

expression1 eq expression2

Operands

expression1, expression2 Numbers, strings, or variables.

Description

Comparison operator; compares two expressions for equality and returns true if the string representation of *expression1* is equal to the string representation of *expression2*; otherwise, the operation returns false.

Example

The following examples show true and false results:

```
word = "persons";
figure = "55";

trace("persons" eq "people");// output: 0(false)
trace("persons" eq word);// output: 1(true)
trace(figure eq 50 + 5);// output: 1(true)
trace(55.0 eq 55);// output: 1(true)
```

```
== (numeric equality)
```

gt (string greater than)

Availability

Flash Lite 1.0.

Usage

expression1 gt expression2

Operands

expression1, expression2 Numbers, strings, or variables.

Description

Operator (comparison); compares the string representation of *expression1* to the string representation of *expression2* and returns a true value if *expression1* is greater than *expression2*; otherwise, it returns a false value. Strings are compared using alphabetical order; digits precede all letters, and all capital letters precede lowercase letters.

Example

The following examples show true and false results:

```
animals = "cats";
breeds = 7;

trace ("persons" gt "people");// output: 1(true)
trace ("cats" gt "cattle");// output: 0(false)
trace (animals gt "cats");// output: 0(false)
trace (animals gt "Cats");// output: 1(true)
trace (breeds gt "5");// output: 1(true)
trace (breeds gt 7);// output: 0(false)
```

```
> (numeric greater than)
```

ge (string greater than or equal to)

Availability

Flash Lite 1.0.

Usage

expression1 ge expression2

Operands

expression1, expression2 Numbers, strings, or variables.

Description

Operator (comparison); compares the string representation of *expression1* to the string representation of *expression2* and returns a true value if *expression1* is greater than or equal to *expression2*; otherwise, it returns a false value. Strings are compared using alphabetical order; digits precede all letters, and all capital letters precede lowercase letters.

Example

The following examples show true and false results:

```
animals = "cats";
breeds = 7;

trace ("cats" ge "cattle");// output: O(false)
trace (animals ge "cats");// output: 1(true)
trace ("persons" ge "people");// output: 1(true)
trace (animals ge "Cats");// output: 1(true)
trace (breeds ge "5");// output: 1(true)
trace (breeds ge 7);// output: 1(true)
```

```
>= (numeric greater than or equal to)
```

ne (string inequality)

Availability

Flash Lite 1.0.

Usage

expression1 ne expression2

Operands

expression1, expression2 Numbers, strings, or variables.

Description

Operator (comparison); compares the string representations of expression1 to expression2 and returns true if expression1 is not equal to expression2; otherwise, it returns false.

Example

The following examples show true and false results:

```
word = "persons";
figure = "55";

trace ("persons" ne "people");// output: 1(true)
trace ("persons" ne word);// output: 0(false)
trace (figure ne 50 + 5);// output: 0(false)
trace (55.0 ne 55); // output: 0(false)
```

```
<> (numeric inequality)
```

It (string less than)

Availability

Flash Lite 1.0.

Usage

expression1 lt expression2

Operands

expression1, expression2 Numbers, strings, or variables.

Description

Operator (comparison); compares the string representation of *expression1* to the string representation of *expression2* and returns a true value if *expression1* is less than *expression2*; otherwise, it returns a false value. Strings are compared using alphabetical order; digits precede all letters, and all capital letters precede lowercase letters.

Example

The following examples show the output of various string comparisons. In the last line, notice that <code>lt</code> does not return an error when you compare a string to an integer because ActionScript 1.0 syntax tries to convert the integer data type to a string and returns <code>false</code>.

```
animals = "cats";
breeds = 7;

trace ("persons" lt "people");// output: O(false)
trace ("cats" lt "cattle");// output: 1(true)
trace (animals lt "cats");// output: O(false)
trace (animals lt "Cats");// output: O(false)
trace (breeds lt "5");// output: O(false)
trace (breeds lt 7);// output: O(false)
```

See also

```
< (numeric less than)
```

le (string less than or equal to)

Availability

Flash Lite 1.0.

Usage

expression1 le expression2

Operands

expression1, expression2 Numbers, strings, or variables.

Description

Operator (comparison); compares the string representation of *expression1* to the string representation of *expression2* and returns a true value if *expression1* is less than or equal to *expression2*; otherwise, it returns a false value. Strings are compared using alphabetical order; digits precede all letters, and all capital letters precede lowercase letters.

Example

The following examples show the output of various string comparisons:

```
animals = "cats";
breeds = 7;

trace ("persons" le "people");// output: 0(false)
trace ("cats" le "cattle");// output: 1(true)
trace (animals le "cats");// output: 1(true)
trace (animals le "Cats");// output: 0(false)
trace (breeds le "5");// output: 0(false)
trace (breeds le 7);// output: 1(true)
```

See also

```
<= (numeric less than or equal to)</pre>
```

- (subtract)

Availability

Flash Lite 1.0.

Usage

```
(Negation) -expression
(Subtraction) expression1 - expression2
```

Operands

expression1, expression2 Numbers or expressions that evaluate to numbers.

Description

Operator (arithmetic); used for negating or subtracting.

Usage 1: When used for negating, it reverses the sign of the numeric expression.

Usage 2: When used for subtracting, it performs an arithmetic subtraction on two numeric expressions, subtracting *expression2* from *expression1*. When both expressions are integers, the difference is an integer. When either or both expressions are floating-point numbers, the difference is a floating-point number.

Example

Usage 1: The following statement reverses the sign of the expression 2 + 3:

```
trace(-(2 + 3));
// output: -5.
```

Usage 2: The following statement subtracts the integer 2 from the integer 5:

```
trace(5 - 2);
// output: 3.
```

The result, 3, is an integer.

Usage 3: The following statement subtracts the floating-point number 1.5 from the floating-point number 3.25:

```
trace(3.25 - 1.5); // output: 1.75.
```

The result, 1.75, is a floating-point number.

-= (subtraction assignment)

Availability

Flash Lite 1.0.

Usage

```
expression1 -= expression2
```

Operands

expression1, expression2 Numbers or expressions that evaluate to numbers.

Description

Operator (arithmetic compound assignment); assigns *expression1* the value of *expression1* - *expression2*. No value is returned.

For example, the following two statements are the same:

```
x = y;

x = x - y;
```

String expressions must be converted to numbers; otherwise, -1 is returned.

Example

Usage 1: The following example uses the -= operator to subtract 10 from 5 and assign the result to the variable x:

```
x = 2;
y = 3;
x -= y
trace(x);// output: -1
```

Usage 2: The following example shows how strings are converted to numbers:

```
x = "2";
y = "5";
x -= y;
trace(x);// output: -3
```

Flash Lite Specific Language Elements

This section describes both the platform capabilities and variables that Adobe's Macromedia Flash Lite 1.1 recognizes, and the Flash Lite commands you can execute using the fscommand() and fscommand2() functions. The functionality described in this section is specific to Flash Lite.

The contents of this section are summarized in the following table:

Language element	Description
_capCompoundSound	Indicates whether Flash Lite can process compound sound.
_capEmail	Indicates whether the Flash Lite client can send e-mail messages using the <code>GetURL()</code> ActionScript command.
_capLoadData	Indicates whether the host application can dynamically load additional data through calls to the <code>loadMovie()</code> , <code>loadMovieNum()</code> , <code>loadVariables()</code> , and <code>loadVariablesNum()</code> functions.
_capMFi	Indicates whether the device can play sound data in the Melody Format for i-mode (MFi) audio format
_capMIDI	Indicates whether the device can play sound data in the Musical Instrument Digital Interface (MIDI) audio format.
_capMMS	Indicates whether Flash Lite can send Multimedia Messaging Service (MMS) messages by using the GetURL() ActionScript command.
_capMP3	Indicates whether the device can play sound data in the MPEG Audio Layer 3 (MP3) audio format.
_capSMAF	Indicates whether the device can play multimedia files in the Synthetic music Mobile Application Format (SMAF).
_capSMS	Indicates whether Flash Lite can send Short Message Service (SMS) messages by using the <code>GetURL()</code> ActionScript command.
_capStreamSound	Indicates whether the device can play streaming (synchronized) sound.

Language element	Description	
_cap4WayKeyAS	Indicates whether Flash Lite executes ActionScript expressions attached to key event handlers associated with the Right, Left, Up, and Down Arrow keys.	
<pre>\$version</pre>	Contains the version number of Flash Lite.	
<pre>fscommand()</pre>	A function used to execute the Launch command (see next entry)	
Launch	(The only command supported for fscommand()) Allows the SWF file to communicate with either Flash Lite or the host environment, such as the phone's or device's operating system.	
fscommand2()	A function used to execute the commands in this table, except for ${\tt fscommand()}.$	
Escape	Encodes an arbitrary string into a format that is safe for network transfer.	
FullScreen	Sets the size of the display area to be used for rendering.	
GetBatteryLevel	Returns the current battery level.	
GetDateDay	Returns the day of the current date as a numeric value.	
GetDateMonth	Returns the month of the current date as a numeric value.	
GetDateWeekday	Returns the number of the day of the current date as a numeric value.	
GetDateYear	Returns a four-digit numeric value that is the year of the current date.	
GetDevice	Sets a parameter that identifies the device on which Flash Lite is running.	
GetDeviceID	Sets a parameter that represents the unique identifier of the device; for example, the serial number.	
GetFreePlayerMemory	Returns the amount of heap memory, in kilobytes, currently available to Flash Lite.	
GetLanguage	Sets a parameter that identifies the language currently used by the device.	
GetLocaleLongDate	Sets a parameter to a string that represents the current date, in long form, formatted according to the currently defined locale.	
GetLocaleShortDate	Sets a parameter to a string that represents the current date, in abbreviated form, formatted according to the currently defined locale.	
GetLocaleTime	Sets a parameter to a string that represents the current time, formatted according to the currently defined locale.	

Language element	Description
GetMaxBatteryLevel	Returns the maximum battery level of the device.
GetMaxSignalLevel	Returns the maximum signal strength level.
GetMaxVolumeLevel	Returns the maximum volume level of the device as a numeric value.
GetNetworkConnectStatus	Returns a value that indicates the current network connection status.
GetNetworkName	Sets a parameter to the name of the current network.
GetNetworkRequestStatus	Returns a value that indicates the status of the most recent HTTP request.
GetNetworkStatus	Returns a value that indicates the network status of the phone (that is, whether there is a network registered and whether the phone is currently roaming).
GetPlatform	Sets a parameter that identifies the current platform, which broadly describes the class of device. For devices with open operating systems, this identifier is typically the name and version of the operating system.
GetPowerSource	Returns a value that indicates whether the power source is currently supplied from a battery or from an external power source.
GetSignalLevel	Returns the current signal strength as a numeric value.
GetTimeHours	Returns the hour of the current time of day, based on a 24-hour clock as a numeric value.
GetTimeMinutes	Returns the minute of the current time of day as a numeric value.
GetTimeSeconds	Returns the second of the current time of day as a numeric value.
GetTimeZoneOffset	Sets a parameter to the number of minutes between the local time zone and universal time (UTC).
GetTotalPlayerMemory	Returns the total amount of heap memory, in kilobytes, allocated to Flash Lite.
GetVolumeLevel	Returns the current volume level of the device as a numeric value.
Quit	Causes the Flash Lite player to stop playback and exit.
ResetSoftKeys	Resets the soft keys to their original settings.
SetInputTextType	Specifies the mode in which the input text field should be opened.
SetQuality	Sets the rendering quality of the animation.

Language element	Description	
SetSoftKeys	Remaps the Left and Right soft keys of the device, provided that they can be accessed and remapped.	
StartVibrate	Starts the phone's vibration feature.	
StopVibrate	Stops the current vibration, if any.	
Unescape	Decodes an arbitrary string that was encoded to be safe for network transfer into its normal, unencoded form.	

Capabilities

This section describes the platform capabilities and variables that Macromedia Flash Lite 1.1 recognizes. The entries are listed alphabetically, ignoring any leading underscores.

_capCompoundSound

Availability

Flash Lite 1.1.

Usage

_capCompoundSound

Description

Numeric variable; indicates whether Flash Lite can process compound sound data. If so, this variable is defined and has a value of 1; if not, this variable is undefined.

As an example, a single Flash file can contain the same sound represented in both MIDI and MFi formats. The player will then play back data in the appropriate format based on the format supported by the device. This variable defines whether the Flash Lite player supports this ability on the current handset.

In the following example, useCompoundSound is set to 1 in Flash Lite 1.1, but is undefined in Flash Lite 1.0:

```
useCompoundSound = _capCompoundSound;
if (useCompoundSound == 1) {
  gotoAndPlay("withSound");
} else {
  gotoAndPlay("withoutSound");
```

_capEmail

Availability

Flash Lite 1.1.

Usage

```
_capEmail
```

Description

Numeric variable; indicates whether the Flash Lite client can send e-mail messages by using the GetURL() ActionScript command. If so, this variable is defined and has a value of 1; if not, this variable is undefined.

Example

If the host application can send e-mail messages by using the GetURL() ActionScript command, the following example sets canEmail to 1:

```
canEmail = _capEmail;
if (canEmail == 1) {
   getURL("mailto:someone@somewhere.com?subject=foo&body=bar");
}
```

_capLoadData

Availability

Flash Lite 1.1.

Usage

_capLoadData

Description

Numeric variable; indicates whether the host application can dynamically load additional data through calls to the <code>loadMovie()</code>, <code>loadMovieNum()</code>, <code>loadVariables()</code>, and <code>loadVariablesNum()</code> functions. If so, this variable is defined and has a value of 1; if not, this variable is undefined.

If the host application can perform dynamic loading of movies and variables, the following example sets iCanLoad to 1:

```
canLoad = _capLoadData;
if (canLoad == 1) {
  loadVariables("http://www.somewhere.com/myVars.php", GET);
} else {
  trace ("client does not support loading dynamic data");
}
```

_capMFi

Availability

Flash Lite 1.1.

Usage

_capMFi

Description

Numeric variable; indicates whether the device can play sound data in the Melody Format for i-mode (MFi) audio format. If so, this variable is defined and has a value of 1; if not, this variable is undefined.

Example

If the device can play MFi sound data, the following example sets canMfi to 1:

```
canMFi = _capMFi;
if (canMFi == 1) {
   // send movieclip buttons to frame with buttons that trigger events sounds
   tellTarget("buttons") {
      gotoAndPlay(2);
   }
}
```

_capMIDI

Availability

Flash Lite 1.1.

Usage

_capMIDI

Description

Numeric variable; indicates whether the device can play sound data in the Musical Instrument Digital Interface (MIDI) audio format. If so, this variable is defined and has a value of 1; if not, this variable is undefined.

Example

If the device can play MIDI sound data, the following example sets canMidi to 1:

```
canMIDI = _capMIDI;

if (canMIDI == 1) {
    // send movieclip buttons to frame with buttons that trigger events sounds
    tellTarget("buttons") {
        gotoAndPlay(2);
    }
}
```

_capMMS

Availability

Flash Lite 1.1.

Usage

_capMMS

Description

Numeric variable; indicates whether Flash Lite can send Multimedia Messaging Service (MMS) messages by using the <code>GetURL()</code> ActionScript command. If so, this variable is defined and has a value of 1; if not, this variable is undefined.

The following example sets canMMS to 1 in Flash Lite 1.1, but leaves it undefined in Flash Lite 1.0 (however, not all Flash Lite 1.1 phones can send MMS messages, so this code is still dependent on the phone):

```
on(release) {
  canMMS = _capMMS;
  if (canMMS == 1) {
    // send an MMS
    myMessage = "mms:4156095555?body=sample mms message";
  } else {
    // send an SMS
    myMessage = "sms:4156095555?body=sample sms message";
  }
  getURL(myMessage);
}
```

_capMP3

Availability

Flash Lite 1.1.

Usage

_capMP3

Description

Numeric variable; indicates whether the device can play sound data in the MPEG Audio Layer 3 (MP3) audio format. If so, this variable is defined and has a value of 1; if not, this variable is undefined.

Example

If the device can play MP3 sound data, the following example sets canMP3 to 1:

```
canMP3 = _capMP3;
if (canMP3 == 1) {
  tellTarget("soundClip") {
    gotoAndPlay(2);
  }
}
```

_capSMAF

Availability

Flash Lite 1.1.

Usage

_capSMAF

Description

Numeric variable; indicates whether the device can play multimedia files in the Synthetic music Mobile Application Format (SMAF). If so, this variable is defined and has a value of 1; if not, this variable is undefined.

Example

The following example sets canSMAF to 1 in Flash Lite 1.1, but leaves it undefined in Flash Lite 1.0 (however, not all Flash Lite 1.1 phones can send SMAF messages, so this code is still dependent on the phone):

```
canSMAF = _capSMAF;

if (canSMAF) {
    // send movieclip buttons to frame with buttons that trigger events sounds
    tellTarget("buttons") {
        gotoAndPlay(2);
    }
}
```

_capSMS

Availability

Flash Lite 1.1.

Usage

_capSMS

Description

Numeric variable; indicates whether Flash Lite can send *Short Message Service* (SMS) messages by using the GetURL() ActionScript command. If so, this variable is defined and has a value of 1; if not, this variable is undefined.

The following example sets canSMS to 1 in Flash Lite 1.1, but leaves it undefined in Flash Lite 1.0 Flash Lite 1.0 (however, not all Flash Lite 1.1 phones can send SMS messages, so this code is still dependent on the phone):

```
on(release) {
  canSMS = _capSMS;
  if (canSMS) {
    // send an SMS
    myMessage = "sms:4156095555?body=sample sms message";
    getURL(myMessage);
  }
}
```

_capStreamSound

Availability

Flash Lite 1.1.

Usage

_capStreamSound

Description

Numeric variable; indicates whether the device can play streaming (synchronized) sound. If so, this variable is defined and has a value of 1; if not, this variable is undefined.

Example

The following example plays streaming sound if canStreamSound is enabled:

```
on(press) {
  canStreamSound = _capStreamSound;
  if (canStreamSound) {
    // play a streaming sound in a movieclip with this button
    tellTarget("music") {
      gotoAndPlay(2);
    }
  }
}
```

_cap4WayKeyAS

Availability

Flash Lite 1.1.

Usage

cap4WayKeyAS

Description

Numeric variable; indicates whether Flash Lite executes ActionScript expressions attached to key event handlers associated with the Right, Left, Up, and Down Arrow keys. This variable is defined and has a value of 1 only when the host application uses four-way key navigation mode to move between Flash controls (buttons and input text fields). Otherwise, this variable is undefined.

When one of the four-way keys is pressed, if the value of this variable is 1, Flash Lite first looks for a handler for that key. If it finds none, Flash control navigation occurs. However, if an event handler is found, no navigation action occurs for that key. For example, if a key press handler for the Down Arrow key is found, the user cannot navigate.

Example

The following example sets canUse4Way to 1 in Flash Lite 1.1, but leaves it undefined in Flash Lite 1.0 (however, not all Flash Lite 1.1 phones support four-way keys, so this code is still dependent on the phone):

```
canUse4Way = _cap4WayKeyAS;
if (canUse4Way == 1) {
  msg = "Use your directional joypad to navigate this application";
} else {
  msg = "Please use the 2 key to scroll up, the 6 key to scroll right, the
  8 key to scroll down, and the 4 key to scroll left.";
}
```

Sversion

Availability

Flash Lite 1.1.

Usage

\$version

Description

String variable; contains the version number of Flash Lite. It contains a major number, minor number, build number, and an internal build number, which is generally 0 in all released versions.

The major number reported for all Flash Lite 1.x products is 5. Flash Lite 1.0 has a minor number of 1: Flash Lite 1.1 has a minor number of 2.

Example

In the Flash Lite 1.1 player, the following code sets the value of my Version to "5, 2, 12, 0": my Version = \$version;

fscommand()

Availability

Flash Lite 1.1.

Usage

```
status = fscommand("Launch", "application-path, arg1, arg2,..., argn")
```

Parameters

"Launch" The command specifier. The Launch command is the only command that you use the fscommand() function to execute.

"application-path, arg1, arg2,..., argn" The name of the application being started and the parameters to it, separated by commas.

Description

Function; allows the SWF file to communicate with either Flash Lite or the host environment, such as the phone's or device's operating system.

See also

fscommand2()

Launch

Availability

Flash Lite 1.1.

Usage

```
status = fscommand("Launch", "application-path, arg1, arg2,..., argn")
```

Parameters

"Launch" The command specifier. In Flash Lite, you use the fscommand() function only to execute the Launch command.

"application-path, arg1, arg2,..., argn" The name of the application being started and the parameters to it, separated by commas.

Description

Command executed through the fscommand() function; launches another application on the device. The name of the application being launched and the parameters to it are passed in as a single argument.



This feature is operating-system dependent.

This command is supported only when the Flash Lite player is running in stand-alone mode. It is not supported when the player is running in the context of another application (for example, as a plug-in to a browser).

Example

The following example would open wap.yahoo.com on the services/Web browser on Series 60 phones:

```
on(keyPress "9") {
  status = fscommand("launch",
  "z:\\system\\apps\\browser\\browser.app,http://wap.yahoo.com");
}
```

See also

fscommand2()

fscommand2()

Availability

Flash Lite 1.1.

Usage

returnValue = fscommand2(command [, expression1 ... expressionN])

Parameters

command A string passed to the host application for any use or a command passed to Flash Lite.

parameter1...parameterN A comma-delimited list of strings passed as parameters to the command specified by command.

Description

Function; allows the SWF file to communicate with either Flash Lite or the host environment, such as the phone or device's operating system. The value that fscommand2() returns depends on the specific command.

The fscommand2() function is similar to the fscommand() function, with the following differences:

- The fscommand2() function can take an arbitrary number of arguments.
- Flash Lite executes fscommand2() immediately, whereas fscommand() is executed at the end of the frame being processed.
- The fscommand2() function returns a value that can be used to report success, failure, or the result of the command.

The strings and expressions that you pass to the function as commands and parameters are described in the tables in this section.

The tables have the following three columns:

- The Command column shows the string literal parameter that identifies the command.
- The Parameters column explains what kinds of values to pass for the additional parameters, if any.
- The Value returned column explains the expected return values.

Examples are provided with the specific commands that you execute using the fscommand2() function, which are described in the rest of this section.

See also

fscommand()

Escape

Availability

Flash Lite 1.1.

Description

Encodes an arbitrary string into a format that is safe for network transfer. Replaces each nonalphanumeric character with a hexadecimal escape sequence (%xx, or %xx%xx in the case of multibyte characters).

Command	Parameters	Value returned
"Escape"	original String to be encoded into a format safe for URLs. encoded Resulting encoded string. These parameters are either names of variables or constant string values (for example, "Encoded_String").	0: Failure. 1: Success.

Example

The following example shows the conversion of a sample string to its encoded form:

```
original_string = "Hello, how are you?";
status = fscommand2("escape", original_string, "encoded_string");
trace (encoded_string); // output: Hello%2C%20how%20are%20you%3F
```

See also

Unescape

FullScreen

Availability

Flash Lite 1.1.

Description

Sets the size of the display area to be used for rendering. The size can be full screen or less-than full screen.

This command is supported only when Flash Lite is running in stand-alone mode. It is not supported when the player is running in the context of another application (for example, as a plug-in to a browser).

Command	Parameters	Value returned
"FullScreen"	size Either a defined variable or a constant string value, with one of these values: true (full screen) or false (less than full screen). Any other value is treated as the value false.	-1: Not supported. 0: Supported.

Example

The following example attempts to set the display area to full screen. If the returned value is other than 0, it sends the playback head to the frame labeled smallScreenMode:

```
status = fscommand2("FullScreen", true);
if(status != 0) {
  gotoAndPlay("smallScreenMode");
}
```

GetBatteryLevel

Availability

Flash Lite 1.1.

Description

Returns the current battery level. It is a numeric value that ranges from 0 to the maximum value returned by the GetMaxBatteryLevel variable.

Command	Parameters	Value returned
"GetBatteryLevel"	None.	-1: Not supported. Other numeric values: The current battery level.

The following example sets the battLevel variable to the current level of the battery:

```
battLevel = fscommand2("GetBatteryLevel");
```

See also

GetMaxBatteryLevel

GetDateDay

Availability

Flash Lite 1.1.

Description

Returns the day of the current date. It is a numeric value (without a leading 0). Valid days are 1 through 31.

Command	Parameters	Value returned
"GetDateDay"	None.	-1: Not supported. 1 to 31: The day of the month.

Example

The following example collects the date information and constructs a complete date string:

```
today = fscommand2("GetDateDay");
weekday = fscommand2("GetDateWeekday");
thisMonth = fscommand2("GetDateMonth");
thisYear = fscommand2("GetDateYear");
when = weekday add ", " add ThisMonth add " " add today add ", " add
thisYear:
```

See also

GetDateMonth, GetDateWeekday, GetDateYear

GetDateMonth

Availability

Flash Lite 1.1.

Description

Returns the month of the current date as a numeric value (without a leading 0).

Command	Parameters	Value returned
"GetDateMonth"	None.	-1: Not supported. 1 to 12: The number of the current month.

Example

The following example collects the date information and constructs a complete date string:

```
today = fscommand2("GetDateDay");
weekday = fscommand2("GetDateWeekday");
thisMonth = fscommand2("GetDateMonth");
thisYear = fscommand2("GetDateYear");
when = weekday add ", " add thisMonth add " " add today add ", " add
thisYear;
```

See also

GetDateDay, GetDateWeekday, GetDateYear

GetDateWeekday

Availability

Flash Lite 1.1.

Description

Returns a numeric value that is the name of the day of the current date, represented as a numeric value.

Command	Parameters	Value returned	
"GetDateWeekday"	None.	-1: Not supported.0: Sunday.1: Monday.2: Tuesday.3: Wednesday.4: Thursday.5: Friday.	
		6: Saturday.	

Example

The following example collects the date information and constructs a complete date string:

```
today = fscommand2("GetDateDay");
weekday = fscommand2("GetDateWeekday");
thisMonth = fscommand2("GetDateMonth");
thisYear = fscommand2("GetDateYear");
when = weekday add ", " add thisMonth add " " add today add ", " add
thisYear;
```

See also

GetDateDay, GetDateMonth, GetDateYear

GetDateYear

Returns a four-digit numeric value that is the year of the current date.

Command	Parameters	Value returned
"GetDateYear"	None.	-1: Not supported. O to 9999: The current year.

Availability

Flash Lite 1.1.

Example

The following example collects the date information and constructs a complete date string:

```
today = fscommand2("GetDateDay");
weekday = fscommand2("GetDateWeekday");
thisMonth = fscommand2("GetDateMonth");
thisYear = fscommand2("GetDateYear");
when = weekday add ", " add thisMonth add " " add today add ", " add
thisYear:
```

See also

GetDateDay, GetDateMonth, GetDateWeekday

GetDevice

Sets a parameter that identifies the device on which Flash Lite is running. This identifier is typically the model name.

Command	Parameters	Value returned
"GetDevice"	device String to receive the identifier of the device. It can be either the name of a variable or a string value that contains the name of a variable.	-1: Not supported. 0: Supported.

Availability

Flash Lite 1.1.

The following code example assigns the device identifier to the statusdevice variable, and then updates a text field with the generic device name.

These are some sample results and the devices they signify:

```
D506i A Mitsubishi 506i phone.
DFOMA1 A Mitsubishi FOMA1 phone.
F506i A Fujitsu 506i phone.
FFOMA1 A Fujitsu FOMA1 phone.
N506i An NEC 506i phone.
NFOMA1 An NEC FOMA1 phone.
Nokia 3650 A Nokia 3650 phone.
p506i A Panasonic 506i phone.
PFOMA1 A Panasonic FOMA1 phone.
SH506i A Sharp 506i phone.
SHFOMA1 A Sharp FOMA1 phone.
S0506i A Sony 506iphone.
statusdevice = fscommand2("GetDevice", "devicename");
switch(devicename) {
  case "D506i":
    /:myText += "device: Mitsubishi 506i" add newline;
    break:
  case "DFOMA1":
    /:myText += "device: Mitsubishi FOMA1" add newline;
    break:
  case "F506i":
    /:myText += "device: Fujitsu 506i" add newline;
  case "FFOMA1":
    /:myText += "device: Fujitsu FOMA1" add newline;
    break;
  case "N506i":
    /:myText += "device: NEC 506i" add newline;
    break:
  case "NFOMA1":
    /:myText += "device: NEC FOMA1" add newline;
    break:
  case "Nokia 3650":
    /:myText += "device: Nokia 3650" add newline;
    break:
```

```
case "P506i":
    /:myText += "device: Panasonic 506i" add newline;
    break;
case "PF0MA1":
    /:myText += "device: Panasonic F0MA1" add newline;
    break;
case "SH506i":
    /:myText += "device: Sharp 506i" add newline;
    break;
case "SHF0MA1":
    /:myText += "device: Sharp F0MA1" add newline;
    break;
case "S0506i":
    /:myText += "device: Sony 506i" add newline;
    break;
```

GetDeviceID

Sets a parameter that represents the unique identifier of the device (for example, the serial number).

Command	Parameters	Value returned	
"GetDeviceID"	id A string to receive the unique identifier of the device. It can be either the name of a variable or a string value that contains the name of a variable.	-1: Not supported. 0: Supported.	

Availability

Flash Lite 1.1.

Example

The following example assigns the unique identifier to the deviceID variable:

```
status = fscommand2("GetDeviceID". "deviceID"):
```

GetFreePlayerMemory

Returns the amount of heap memory, in kilobytes, currently available to Flash Lite.

Command	Parameters	Value returned
"GetFreePlayerMemory"	None.	-1: Not supported. O or positive value: Available kilobytes of heap memory.

Availability

Flash Lite 1.1.

Example

The following example sets status equal to the amount of free memory:

status = fscommand2("GetFreePlayerMemory");

See also

GetTotalPlayerMemory

GetLanguage

Availability

Flash Lite 1.1.

Sets a parameter that identifies the language currently used by the device. The language is returned as a string in a variable that is passed in by name.

Command	Parameters	Value returned
"GetLanguage"	language String to receive the language code. It can be either the name of a variable or a string value that contains the name of a variable. The value returned is one of the following: cs: Czech. da: Danish. de: German. en-UK: UK or international English. en-US: US English. es: Spanish. fi: Finnish. fr: French. hu: Hungarian. it: Italian. ja: Japanese. ko: Korean. n1: Dutch. no: Norwegian. p1: Polish. pt: Portuguese. ru: Russian. sv: Swedish. tr: Turkish. xu: an undetermined language. zh-CN: simplified Chinese.	-1: Not supported. O: Supported.
	zh-TW: traditional Chinese.	

NOTE

When Japanese phones are set to display English, en_US is returned for language.

The following example assigns the language code to the language variable, and then updates a text field with the language recognized by the Flash Lite player:

```
statuslanguage = fscommand2("GetLanguage", "language");
switch(language) {
  case "cs":
    /:myText += "language is Czech" add newline;
    break:
  case "da":
    /:myText += "language is Danish" add newline;
    break:
  case "de":
    /:myText += "language is German" add newline;
    break:
  case "en-UK":
    /:myText += "language is UK" add newline;
    break;
  case "en-US":
    /:myText += "language is US" add newline;
    break:
  case "es":
    /:myText += "language is Spanish" add newline;
    break:
  case "fi":
    /:myText += "language is Finnish" add newline;
    break:
  case "fr":
    /:myText += "language is French" add newline;
    break:
  case "hu":
    /:myText += "language is Hungarian" add newline;
    break:
  case "it":
    /:myText += "language is Italian" add newline;
    break:
  case "jp":
    /:myText += "language is Japanese" add newline;
    break:
  case "ko":
    /:myText += "language is Korean" add newline;
    break:
  case "nl":
    /:myText += "language is Dutch" add newline;
    break;
  case "no":
    /:myText += "language is Norwegian" add newline;
    break:
```

```
case "pl":
  /:myText += "language is Polish" add newline;
  break:
case "pt":
  /:myText += "language is Portuguese" add newline;
  break;
case "ru":
  /:myText += "language is Russian" add newline;
  break:
case "sv":
  /:myText += "language is Swedish" add newline;
case "tr":
  /:myText += "language is Turkish" add newline;
  break:
case "xu":
  /:myText += "language is indeterminable" add newline;
  break:
case "zh-CN":
  /:myText += "language is simplified Chinese" add newline;
  break:
case "zh-TW":
  /:myText += "language is traditional Chinese" add newline;
```

GetLocaleLongDate

Availability

Flash Lite 1.1.

Description

Sets a parameter to a string that represents the current date, in long form, formatted according to the currently defined locale.

Command	Parameters	Value returned
"GetLocaleLongDate"	form of the value of the current date, such as "October 16, 2004" or "16 October 2004". It can be either the name of a variable or a string value that contains the name of a variable. The value returned in longdate is a multicharacter, variable-length string. The actual formatting depends on the device and the locale.	-1: Not supported. O: Supported.

The following example attempts to return the long form of the current date in the longDate variable. It also sets the value of status to report whether it was able to do so.

See also

GetLocaleShortDate, GetLocaleTime

GetLocaleShortDate

Availability

Flash Lite 1.1.

Description

Sets a parameter to a string that represents the current date, in abbreviated form, formatted according to the currently defined locale.

Command	Parameters	Value returned
"GetLocaleShortDate"	shortdate String variable to receive the long form of the value of the current date, such as "10/16/2004" or "16-10-2004". It can be either the name of a variable or a string value that contains the name of a variable. The value returned in shortdate is a multicharacter, variable-length string. The actual formatting depends on the device and the locale.	-1: Not supported. O: Supported.

Example

The following example attempts to get the short form of the current date into the shortDate variable. It also sets the value of status to report whether it was able to do so.

See also

GetLocaleLongDate, GetLocaleTime

GetLocaleTime

Availability

Flash Lite 1.1.

Description

Sets a parameter to a string representing the current time, formatted according to the currently defined locale.

Command	Parameters	Value returned
"GetLocaleTime"	time String variable to receive the value of the current time, such as "6:10:44 PM" or "18:10:44". It can be either the name of a variable or a string value that contains the name of a variable. The value returned in time is a multicharacter, variable-length string. The actual formatting depends on the device and the locale.	

Example

The following example attempts to get the current local time into the time variable. It also sets the value of status to report whether it was able to do so.

See also

GetLocaleLongDate, GetLocaleShortDate

GetMaxBatteryLevel

Availability

Flash Lite 1.1.

Description

Returns the maximum battery level of the device. It is a numeric value greater than 0.

Command	Parameters	Value returned
"GetMaxBatteryLevel"	None.	-1: Not supported. other values: The maximum battery level.

The following example sets the maxBatt variable to the maximum battery level: maxBatt = fscommand2("GetMaxBatteryLevel");

GetMaxSignalLevel

Availability

Flash Lite 1.1.

Description

Returns the maximum signal strength level. It is a numeric value greater than 0.

Command	Parameters	Value returned
"GetMaxSignalLevel"	None.	-1: Not supported. Other numeric values: The maximum signal level.

Example

The following example assigns the maximum signal strength to the sigStrengthMax variable: sigStrengthMax = fscommand2("GetMaxSignalLevel");

GetMaxVolumeLevel

Availability

Flash Lite 1.1.

Description

Returns the maximum volume level of the device as a numeric value.

Command	Parameters	Value returned
"GetMaxVolumeLevel"	None.	-1: Not supported. Other values: The maximum volume level.

The following example sets the maxvolume variable to the maximum volume level of the device:

```
maxvolume = fscommand2("GetMaxVolumeLevel");
trace (maxvolume);  // output: 80
```

See also

GetVolumeLevel

GetNetworkConnectStatus

Availability

Flash Lite 1.1.

Description

Returns a value that indicates the current network connection status.

Command	Parameters	Value returned
"GetNetworkConnectStatus"	None.	-1: Not supported. O: There is currently an active network connection. 1: The device is attempting to connect to the network. 2: There is currently no active network connection. 3: The network connection is suspended. 4: The network connection cannot be determined.

The following example assigns the network connection status to the connects tatus variable, and then uses a switch statement to update a text field with the status of the connection:

```
connectstatus = fscommand2("GetNetworkConnectStatus");
switch (connectstatus) {
  case -1 :
    /:myText += "connectstatus not supported" add newline;
    break:
  case 0 :
    /:myText += "connectstatus shows active connection" add newline;
  case 1 :
    /:myText += "connectstatus shows attempting connection" add newline;
  case 2 :
    /:myText += "connectstatus shows no connection" add newline;
    break:
    /:myText += "connectstatus shows suspended connection" add newline;
    break:
  case 4:
    /:myText += "connectstatus shows indeterminable state" add newline;
    break:
```

GetNetworkName

Availability

Flash Lite 1.1.

Description

Sets a parameter to the name of the current network.

Command	Parameters	Value returned
"GetNetworkName"	networkName String representing the network name. It can be either the name of a variable or a string value that contains the name of a variable. If the network is registered and its name can be determined, networkname is set to the network name; otherwise, it is set to the empty string.	 Network is registered, but network name is not known. Network is registered, and

The following example assigns the name of the current network to the myNetName variable and a status value to the netNameStatus variable:

netNameStatus = fscommand2("GetNetworkName", myNetName);

GetNetworkRequestStatus

Availability

Flash Lite 1.1.

Description

Command

Returns a value indicating the status of the most recent HTTP request.

• • • • • • • • • • • • • • • • • • •	· urumotoro	Value l'otalillea
"GetNetworkRequestStatus"	None.	-1: The command is not supported. O: There is a pending request, a network connection has been established, the server's host name has been resolved, and a connection to the server has been made. 1: There is a pending request, and a network connection is being established. 2: There is a pending request, but a network connection has not yet been established. 3: There is a pending request, a network connection has been established, and the server's host name is being resolved. 4: The request failed because of a network error. 5: The request failed because of a failure in connecting to the server.
		6: The server has returned an HTTP error (for example, 404).
		7: The request failed because of a failure in accessing the DNS server or in resolving the server name.

8: The request has been successfully fulfilled. 9: The request failed because of a timeout. 10: The request has not yet been made.

Parameters Value returned

The following example assigns the status of the most recent HTTP request to the requesttatus variable, and then uses a switch statement to update a text field with the status:

```
requeststatus = fscommand2("GetNetworkRequestStatus");
switch (requeststatus) {
  case -1:
    /:myText += "requeststatus not supported" add newline;
    break:
  case 0:
    /:myText += "connection to server has been made" add newline;
  case 1:
    /:myText += "connection is being established" add newline;
    break:
  case 2:
    /:myText += "pending request, contacting network" add newline;
    break:
  case 3:
    /:myText += "pending request, resolving domain" add newline;
    break:
  case 4:
    /:myText += "failed, network error" add newline;
    break:
  case 5:
    /:myText += "failed, couldn't reach server" add newline;
    break:
    /:myText += "HTTP error" add newline;
    break:
  case 7:
    /:myText += "DNS failure" add newline;
    break:
  case 8:
    /:myText += "request has been fulfilled" add newline;
  case 9:
    /:myText += "request timedout" add newline;
    break:
  case 10:
    /:myText += "no HTTP request has been made" add newline;
    break:
```

GetNetworkStatus

Availability

Flash Lite 1.1.

Description

Returns a value indicating the network status of the phone (that is, whether there is a network registered and whether the phone is currently roaming).

Command	Parameters Value returned		
"GetNetworkStatus"	None.	-1: The command is not supported.0: No network registered.1: On home network.2: On extended home network.3: Roaming (away from home network).	

Example

The following example assigns the status of the network connection to the networkstatus variable, and then uses a switch statement to update a text field with the status:

```
networkstatus = fscommand2("GetNetworkStatus");
switch(networkstatus) {
  case -1:
    /:myText += "network status not supported" add newline;
  case 0:
    /:myText += "no network registered" add newline;
    break:
    /:myText += "on home network" add newline;
    break:
    /:myText += "on extended home network" add newline;
    break:
  case 3:
    /:myText += "roaming" add newline;
    break:
```

GetPlatform

Availability

Flash Lite 1.1.

Description

Sets a parameter that identifies the current platform, which broadly describes the class of device. For devices with open operating systems, this identifier is typically the name and version of the operating system.

Command	Parameters	Value returned
"GetPlatform"	platform String to receive the identifier of the platform. It can be either the name of a variable or a string value that contains the name of a variable.	-1: Not supported. O: Supported.

Example

The following code example assigns the platform identifier to the statusplatform variable, and then updates a text field with the generic platform name.

These are some sample results for my Platform and the classes of device they signify:

506i A 506i phone.

FOMA1 A FOMA1 phone.

Symbian6.1_s60.1 A Symbian 6.1, Series 60 version 1 phone.

Symbian 7.0 A Symbian 7.0 phone

```
statusplatform = fscommand2("GetPlatform", "platform");
switch(platform){
   case "506i":
     /:myText += "platform: 506i" add newline;
     break;
   case "FOMA1":
     /:myText += "platform: FOMA1" add newline;
     break;
   case "Symbian6.1-Series60v1":
     /:myText += "platform: Symbian6.1, Series 60 version 1 phone" add newline;
     break;
   case "Symbian7.0":
     /:myText += "platform: Symbian 7.0" add newline;
     break;
   case "Symbian7.0":
     /:myText += "platform: Symbian 7.0" add newline;
     break;
```

GetPowerSource

Availability

Flash Lite 1.1.

Description

Returns a value that indicates whether the power source is currently supplied from a battery or from an external power source.

Command	Parameters	Value returned
"GetPowerSource"	None.	-1: Not supported.0: Device is operating on battery power.1: Device is operating on an external power source.

Example

The following example sets the myPower variable to indicate the power source, or to -1 if it was unable to do so:

myPower = fscommand2("GetPowerSource");

GetSignalLevel

Availability

Flash Lite 1.1.

Description

Returns the current signal strength as a numeric value.

Command	Parameters	Value returned
"GetSignalLevel"	None.	-1: Not supported. Other numeric values: The current signal level, ranging from 0 to the maximum value returned by GetMaxSignalLevel.

Example

The following example assigns the signal level value to the sigLevel variable:

sigLevel = fscommand2("GetSignalLevel");

GetTimeHours

Availability

Flash Lite 1.1.

Description

Returns the hour of the current time of day, based on a 24-hour clock. It is a numeric value (without a leading 0).

Command	Parameters	Value returned
"GetTimeHours"	None.	-1: Not supported. O to 23: The current hour.

Example

The following example sets the hour variable to the hour portion of the current time of day, or to -1:

See also

 ${\tt GetTimeMinutes, GetTimeSeconds, GetTimeZoneOffset}$

GetTimeMinutes

Availability

Flash Lite 1.1.

Description

Returns the minute of the current time of day. It is a numeric value (without a leading 0).

Command	Parameters	Value returned
"GetTimeMinutes"	None.	-1: Not supported. O to 59: The current minute.

The following example sets the minutes variable to the minute portion of the current time of day, or to -1:

```
minutes = fscommand2("GetTimeMinutes");
trace (minutes);  // output: 38
```

See also

GetTimeHours, GetTimeSeconds, GetTimeZoneOffset

GetTimeSeconds

Availability

Flash Lite 1.1.

Description

Returns the second of the current time of day. It is a numeric value (without a leading 0).

Command	Parameters	Value returned
"GetTimeSeconds"	None.	-1: Not supported. O to 59: The current second.

Example

The following example sets the seconds variable to the seconds portion of the current time of day, or to -1:

```
seconds = fscommand2("GetTimeSeconds");
trace (seconds); // output: 41
```

See also

GetTimeHours, GetTimeMinutes, GetTimeZoneOffset

GetTimeZoneOffset

Availability

Flash Lite 1.1.

Description

Sets a parameter to the number of minutes between the local time zone and universal time (UTC).

Command	Parameters	Value returned
"GetTimeZoneOffset"	timezoneOffset Number of minutes between the local time zone and UTC. It can be either the name of a variable or a string value that contains the name of a variable. A positive or a negative numeric value is returned, such as the following: 540: Japan standard time -420: Pacific daylight saving time	• • • • • • • • • • • • • • • • • • • •

Example

The following example either assigns the minutes of offset from UTC to the timezoneoffset variable and sets status to 0 or else sets status to -1:

```
status = fscommand2("GetTimeZoneOffset", "timezoneoffset");
trace (timezoneoffset);// output: 300
```

See also

GetTimeHours, GetTimeMinutes, GetTimeSeconds

GetTotalPlayerMemory

Availability

Flash Lite 1.1.

Description

Returns the total amount of heap memory, in kilobytes, allocated to Flash Lite.

Command	Parameters	Value returned
"GetTotalPlayerMemory"	None.	-1: Not supported. O or positive value: Total kilobytes of heap memory.

Example

The following example sets the status variable to the total amount of heap memory: status = fscommand2("GetTotalPlayerMemory");

See also

GetFreePlayerMemory

GetVolumeLevel

Availability

Flash Lite 1.1.

Description

Returns the current volume level of the device as a numeric value.

Command	Parameters	Value returned
"GetVolumeLevel"	None.	-1: Not supported. Other numeric values: The current volume level, ranging from 0 to the value returned by fscommand2("GetMaxVolumeLevel").

The following example assigns the current volume level to the volume variable:

See also

GetVolumeLevel

Quit

Availability

Flash Lite 1.1.

Description

Causes the Flash Lite player to stop playback and exit.

This command is supported only when Flash Lite is running in stand-alone mode. It is not supported when the player is running in the context of another application (for example, as a plug-in to a browser).

Command	Parameters	Value returned
"Quit"	None.	-1: Not supported.

Example

The following example causes Flash Lite to stop playback and quit when running in standalone mode:

```
status = fscommand2("Quit");
```

ResetSoftKeys

Availability

Flash Lite 1.1.

Description

Resets the soft keys to their original settings.

This command is supported only when Flash Lite is running in stand-alone mode. It is not supported when the player is running in the context of another application (for example, as a plug-in to a browser).

Command	Parameters	Value returned	
"ResetSoftKeys"	None.	-1: Not supported. O: Supported.	

Example

The following statement resets the soft keys to their original settings:

status = fscommand2("ResetSoftKeys");

See also

SetSoftKeys

SetInputTextType

Availability

Flash Lite 1.1.

Description

Specifies the mode in which the input text field should be opened:

Command	Parameters	Value returned
"SetInputTextType"	variableName Name of the input text field. It can be either the name of a variable or a string value that contains the name of a variable. type One of the values Numeric, Alpha, Alphanumeric, Latin, NonLatin, Or NoRestriction.	1: Success.

Flash Lite supports input text functionality by asking the host application to start the generic device-specific text input interface, often referred to as the *front-end processor* (FEP). When the SetInputTextType command is not used, the FEP is opened in default mode.

The following table shows what effect each mode has, and what modes are substituted:

Mode specified	Sets the FEP to one of these mutually exclusive modes	If not supported on current device, opens the FEP in this mode
Numeric	Numbers only (0 to 9)	Alphanumeric
Alpha	Alphabetic characters only (A to Z, a to z)	Alphanumeric
Alphanumeric	Alphanumeric characters only (0 to 9, A to Z, a to z)	Latin
Latin	Latin characters only (alphanumeric and punctuation)	NoRestriction
NonLatin	Non-Latin characters only (for example, Kanji and Kana)	NoRestriction
NoRestriction	Default mode (sets no restriction on the FEP)	



Not all mobile phones support these input text field types. For this reason, you must validate the input text data.

Example

The following line of code sets the input text type of the field associated with the input1 variable to receive numeric data:

```
status = fscommand2("SetInputTextType", "input1", "Numeric");
```

SetQuality

Availability

Flash Lite 1.1.

Description

Sets the quality of the rendering of the animation.

Command	Parameters	Value returned
"SetQuality"	quality The rendering quality; must be "high", "medium", or "low".	-1: Not supported. 0: Supported.

Example

The following example sets the rendering quality to low:

```
status = fscommand2("SetQuality", "low");
```

SetSoftKeys

Availability

Flash Lite 1.1.

Description

Remaps the Left and Right soft keys of the device, provided that they can be accessed and remapped.

After this command is executed, pressing the left key generates a PageUp keypress event, and pressing the right key generates a PageDown keypress event. ActionScript associated with the PageUp and PageDown keypress events is executed when the respective key is pressed.

This command is supported only when Flash Lite is running in stand-alone mode. It is not supported when the player is running in the context of another application (for example, as a plug-in to a browser).

Command	Parameters	Value returned
"SetSoftKeys"	Text to be displayed for the Left soft key. right Text to be displayed for the Right soft key. These parameters are either names of variables or constant string values (for example, "Previous").	-1: Not supported. 0: Supported.

Example

The following example directs that the Left soft key be labeled Previous and the Right soft key be labeled Next:

```
status = fscommand2("SetSoftKeys", "Previous", "Next");
```

See also

ResetSoftKeys

StartVibrate

Availability

Flash Lite 1.1.

Description

Starts the phone's vibration feature. If a vibration is already occurring, Flash Lite stops that vibration before starting the new one. Vibrations also stop when playback of the Flash application is stopped or paused, and when Flash Lite player quits.

Command	Parameters	Value returned
"StartVibrate"	time_on Amount of time, in milliseconds (to a maximum of 5 seconds), that the vibration is on. time_off Amount of time, in milliseconds (to a maximum of 5 seconds), that the vibration is off. repeat Number of times (to a maximum of 3) to repeat this vibration.	O: Vibration was started. 1: An error occurred and vibration could not

Example

The following example attempts to start a vibration sequence of 2.5 seconds on, 1 second off, repeated twice. It assigns a value to the status variable that indicates success or failure.

```
status = fscommand2("StartVibrate", 2500, 1000, 2);
```

See also

StopVibrate

StopVibrate

Availability

Flash Lite 1.1.

Description

Stops the current vibration, if any.

Command	Parameters	Value returned
"StopVibrate"	None.	-1: Not supported.O: The vibration stopped.

The following example calls StopVibrate and saves the result (not supported or vibration stopped) in the status variable:

```
status = fscommand2("StopVibrate");
```

See also

StartVibrate

Unescape

Availability

Flash Lite 1.1.

Description

Decodes an arbitrary string that was encoded to be safe for network transfer into its normal, unencoded form. All characters that are in hexadecimal format, that is, a percent character (%) followed by two hexadecimal digits, are converted into their decoded form.

Command	Parameters	Value returned
"Unescape"	original String to be decoded from a format safe for URLs to a normal form. decoded Resulting decoded string. (This parameter can be either the name of a variable or a string value that contains the name of a variable.)	0: Failure. 1: Success.

Example

The following example shows the decoding of an encoded string:

```
encoded_string = "Hello%2C%20how%20are%20you%3F";
status = fscommand2("unescape", encoded_string, "normal_string");
trace (normal_string); // output: Hello, how are you?
```

See also

Escape

Index

Symbols
! (logical NOT) operator 94
" " (string delimiter) operator 104
\$version variable 124
% (modulo) operator 95
%= (modulo assignment) operator 96
&& (logical AND) operator 92
(logical OR) operator 94
* (multiply) operator 97
*= (multiplication assignment) operator 96
+ (numeric add) operator 98
++ (increment) operator 91
+= (addition assignment) operator 83
, (comma) operator 86
-= (subtraction assignment) operator 112
. (dot) operator 90
/ (divide) operator 89
/ (forward slash - root timeline) property 50
/* (block comment) operator 85
// (comment) operator 87
/= (division) operator 90
< (numeric less than or equal to) operator 102
< (numeric less than) operator 102
<> (numeric inequality) operator 101
= (assignment) operator 84
== (numeric equality) operator 99
> (greater than or equal to) operator 100
> (greater than) operator 100
? (conditional) operator 88
_alpha variable 51
_cap4WayKeyAS variable 123
_capCompoundSound variable 116
_capEmail variable 117
_capLoadData variable 117
_capMFi variable 118
_capMIDI variable 119
_capMMS variable 119

_capSMAF variable 121
_capSMS variable 121
_capStreamSound variable 122
_currentframe property 52
_focusrect property 53
_framesloaded property 53
_height property 54
highquality property 54
_level property 55
_name property 57
rotation property 57
_scroll property 58
_target property 58
_visible property 59
_width property 60
_x property 60
xscale property 61
_y property 62
_yscale property 63
– (subtract) operator 111
— (decrement) operator 88

Δ

add (string concatenation) operator 82 addition assignment operator 83 _alpha variable 51 AND operator 92 and operator 83 assignment operator 84

В

block comment operator 85 break statement 66

С	F
call 13	_focusrect property 53
_cap4WayKeyAS variable 123	for loop 73
_capCompoundSound variable 116	for statement 73
_capEmail variable 117	_framesloaded property 53
_capLoadData variable 117	fscommand() command 124
_capMFi variable 119	functions
_capMMS variable 119	chr() 14
_capSMAF variable 121	duplicateMovieClip() 14
_capSMS variable 121	eval() 16
_capStreamSound variable 122	fscommand() 124
case statement 67	getProperty() 17
chr() function 14	getTimer() 17
comma operator 86	getURL() 18
comments	gotoAndPlay() 21
block 85	gotoAndStop() 21
one-line 87	ifFrameLoaded() 22
concatenation 82	int() 23
conditional operator 88	length() 24
conditions 74	loadMovie() 24
continue statement 68	loadMovieNum() 26
_currentframe property 52	loadVariables() 27
	loadVariablesNum() 28
Б	mbchr() 29
D	mbsubstring() 32
division 89	nextFrame() 32
division assignment operator 90	nextScene() 33
dowhile statement 70	Number() 34
dot operator 90	on() 35
duplicateMovieClip() function 14	ord() 36
1 1 0	play() 36
_	prevFrame() 37
E	prevScene() 38
e-mail capability variable 117	random() 38
else if statement 72	removeMovieClip() 39
else statement 71	set() 40
eq (string equal) operator 105	setProperty() 41
eval() function 16	stop() 42
evanty runetion 10	stopAllSounds() 42
	String() 43
	substring() 44
	tellTarget() 44
	toggleHighQuality() 45
	trace() 46
	unloadMovie() 47
	unloadMovieNum() 48

G	MMS messaging 119
ge (string greater than or equal to) operator 107	modulo assignment 96
getProperty() function 17	modulo operator 95
getTimer() function 17	multiplication 97
getURL() function 18	
gotoAndPlay() function 21	N
gotoAndStop() function 21	14
greater than operator 100	_name property 57
greater than or equal to operator 100	ne (string not equal) operator 108
gt (string greater than) operator 106	nextFrame() function 32
ge (string greater than) operator 100	nextScene() function 33
	NOT operator 94
Н	Number() function 34
1 • 1 • 64	numeric addition 98
_height property 54	
_highquality property 54	
	O
	on() function 35
ı	operators
if statement 74	addition assignment 83
ifFrameLoaded() function 22	and 83
increment operator 91	assignment 84
inequality operator 101	block comment 85
int() function 23	comma 86
	comment 87
I	conditional 88
L	division 89
le (string less than or equal to) operator 110	division assignment 90
length() function 24	dot 90
less than operator 102	greater than 100
less than or equal to operator 102	greater than or equal to 100
_level property 55	increment 91
loadMovie() function 24	logical AND 92
loadMovieNum() function 26	logical NOT 94
loadVariables() function 27	logical OR 94
loadVariablesNum() function 28	modulo 95
logical AND operator 92	modulo assignment 96
logical NOT operator 94	multiply 97
logical OR operator 94	numeric add 98
lt (string less than) operator 109	numeric equality 99
	numeric inequality 101
N.A.	numeric less than 102
IVI	numeric less than or equal to 102
maxscroll property 56	string concatenation 82
mbchr() function 29	string delimiter 104
mbsubstring() function 32	string equal 105
messaging variables 119, 121	string greater than 106
MFI sound 118	string greater than or equal to 107
MIDI sound 119	

string less than or equal to 110	continue 68
string not equal 108	dowhile 70
subtraction assignment 112	else 71
OR operator 94	else if 72
ord() function 36	for 73
old() function 50	
	if 74
D	logical NOT 94
Γ	switch 75
play() function 36	while 77
	stop() function 42
prevFrame() function 37	stopAllSounds() functions 42
prevScene() function 38	-
properties	string delimiter operator 104
_alpha 51	string equal operator 105
_currentframe 52	string greater than operator 106
_focusrect 53	string greater than or equal to 107
_framesloaded 53	string less than or equal to 110
	String() function 43
_height 54	
_highquality 54	substring() function 44
_level 55	subtraction assignment operator 112
_name 57	switch statement 75
_rotation 57	
_scroll 58	т
_target 58	Т
_visible 59	_target property 58
width 60	tellTarget() function 44
-	
_x 60	toggleHighQuality() function 45
_xscale 61	_totalframes property 59
_y 62	trace() function 46
_yscale 63	
forward slash 50	1.1
maxscroll 56	U
scroll 58	unloadMovie() function 47
	-
	unloadMovieNum() function 48
R	
	\/
random() function 38	V
removeMovieClip() function 39	variables
root timeline identifier 50	\$version 124
_rotation property 57	
_iotation property //	_alpha 51
	_cap4WayKeyAS 123
S	_capCompoundSound 116
0	_capEmail 117
scroll property 58	_capLoadData 117
set() function 40	_capMFi 118
setProperty() function 41	_capMIDI 119
sound variables 116, 118, 119, 121, 122	_capMMS 119
statements	_capSMAF 121
break 66	_capSMS 121
case 67	_capStreamSound 122

```
arrow key navigation 123
  capability to load data 117
  e-mail capability 117
  version number of Flash Lite 124
variables, messaging
  _capMMS 119
  _capSMS 121
variables, sound
  _capCompoundSound 116
  _capMFi 118
  _capMIDI 119
  _capSMAF 121
  _capStreamSound 122
_visible property 59
W
while loop 70
while statement 77
_width property 60
X
_x property 60
_xscale property 61
_y property 62
_yscale property 63
```