



**GT.M** 

Publication date June 9, 2015

Copyright © 2012-2015 Fidelity National Information Services, Inc. and/or its subsidiaries. All rights reserved.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts and no Back-Cover Texts.

 $GT.M^{TM}$  is a trademark of Fidelity National Information Services, Inc. Other trademarks are the property of their respective owners.

This document contains a description of GT.M and the operating instructions pertaining to the various functions that comprise the system. This document does not contain any commitment of FIS. FIS believes the information in this publication is accurate as of its publication date; such information is subject to change without notice. FIS is not responsible for any errors or defects.

Revision History		
Revision V6.2-002	June 9, 2015	The following messages were added:
		1. ARCTLMAXHIGH
		2. ARCTLMAXLOW
		3. INVTMPDIR
		4. INVZBREAK
		5. JOBLVNDETAIL
		6. LASTWRITERBYPAS
		7. NODFRALLOCSUPP
		8. PREALLOCATEFAIL
		9. REPLSRCEXITERR
		10. TRIGUPBADLABEL
		11. WEIRDSYSTIME
		The following messages were revised:
		1. INVLINKTMPDIR
		2. NOPRINCIO
		3. RECLOAD
		4. REPLLOGOPN
		5. RESRCINTRLCKBYPAS
		6. TPRESTART
		7. TRIGINVCHSET

FIS V6.2-002

Revision V6.2-001 and V6.2-000	01 January 2015	The following messages were added:
		1. AIMGBLKFAIL
		2. BLKINVALID
		3. CANTBITMAP
		4. CHSETALREADY
		5. COLTRANSSTR2LONG
		6. CONNSOCKREQ
		7. CORRUPTNODE
		8. CREDNOTPASSED
		9. CRYPTBADWRTPOS
		10. CRYPTKEYTOOBIG
		11. CRYPTNOAPPEND
		12. CRYPTNOKEYSPEC
		13. CRYPTNOOVERRIDE
		14. CRYPTNOSEEK
		15. CRYPTNOTRUNC
		16. DSEMAXBLKSAV
		17. DSENOTOPEN
		18. GTMDISTUNVERIF
		19. HLPPROC
		20. INVLINKTMPDIR
		21. INVOBJFILE
		22. JOBLVN2LONG
		23. LABELNOTFND
		24. LOCALSOCKREQ
		25. MPROFRUNDOWN
		26. NEEDTRIGUPGRD
		27. NOEDITOR
		28. NOGTCMDB
		29. NOSOCKHANDLE
		30. NOUSERDB

31. PEERPIDMISMATCH

- 32. RECLOAD
- 33. RELINKCTLERR
- 34. RELINKCTLFULL
- 35. REMOTEDBNOTRIG
- 36. REPLNOHASHTREC
- 37. REQRLNKCTLRNDWN
- 38. RLNKCTLRNDWNFL
- 39. RLNKCTLRNDWNSUC
- 40. RLNKRECLATCH
- 41. RLNKSHMLATCH
- 42. SDSEEKERR
- 43. SEFCTNEEDSFULLB
- 44. SOCKACCEPT
- 45. SOCKNOTPASSED
- 46. SOCKPASS
- 47. SOCKPASSDATAMIX
- 48. TLSPARAM
- 49. TRIGLOADFAIL
- 50. UPDPROC
- 51. ZPEEKNOJNLINFO
- 52. ZSOCKETATTR
- 53. ZSOCKETNOTSOCK

The following messages were revised:

- 1. ACTIVATEFAIL
- 2. DBCOLLREQ
- 3. INSNOTJOINED
- 4. KEYWRDBAD
- 5. LDBINFMT
- 6. LDSPANGLOINCMP
- 7. LITNONGRAPH

		8. MAXBTLEVEL
		9. NOTGBL
		10. REORGINC
		11. REPLINSTNOSHM
		12. TPRESTART
		13. TRESTNOT
		14. TRIGZBREAKREM
Revision V6.1-000	30 December 2013	The following messages were added:
		1. ACTCOLLMISMTCH
		2. DEVPARMTOOSMALL
		3. FILEOPENFAIL
		4. FILTERTIMEDOUT
		5. GBLNAMCOLLRANGE
		6. GBLNAMCOLLUNDEF
		7. GBLNAMEIS
		8. GVSUBSERR
		9. INVCTLMNE
		10. INVMNEMCSPC
		11. ISSPANGBL
		12. JOBSETUP
		13. JOBSTARTCMDFAIL
		14. MISSINGDELIM
		15. NAMENDBAD
		16. NAMGVSUBOFLOW
		17. NAMGVSUBSMAX
		18. NAMLPARENNOTBEG
		19. NAMNOTSTRSUBS
		20. NAMNUMSUBSOFLOW
		21. NAMONECOLON
		22. NAMRANGELASTSUB
		23. NAMRANGEORDER

V6.2-002 MR Manual June 09, 2015, Page 5

24. NAMRANGEOVERLAP
25. NAMRPARENNOTEND
26. NAMSTARSUBSMIX

27. NAMSTRSUBSCHARG

28. NAMSTRSUBSCHINT

29. NAMSTRSUBSFUN

30. NAMSUBSBAD

31. NAMSUBSEMPTY

32. NCTCOLLSPGBL

33. REMOTEDBNOSPGBL

34. REPLINSTMISMTCH

35. REPLINSTNOSHM

36. REPLNOTLS

37. SETITIMERFAILED

38. STDNULLCOLLREQ

39. STRMISSQUOTE

40. TLSCONNINFO

41. TLSCONVSOCK

42. TLSDLLNOOPEN

43. TLSHANDSHAKE

44. TLSINIT

45. TLSIOERROR

46. TLSRENEGOTIATE

47. TPNOSUPPORT

48. TRIGNOSPANGBL

The following messages were revised:

1. INSTFRZDEFER

2. KEYFORBLK

3. KEYWRDBAD

4. LITNONGRAPH

5. MERGEDESC

		6. MURNDWNOVRD
		7. NOENDIANCVT
		8. NOSOCKETINDEV
		9. OPENCONN
		10. PARFILSPC
		11. PROTNOTSUP
		12. RECORDSTAT
		13. SOCKBIND
		14. SOCKETEXIST
		15. SOCKINIT
		16. SOCKNOTFND
		17. SOCKWAIT
		18. SOCKWRITE
		19. TMPSTOREMAX
		20. VALUEBAD
		The following messages were deprecated:
		1. IPADDRREQ
		2. SOCKPARMREQ
Revision V6.0-003	13 August 2013	The following messages were added:
		1. GETADDRINFO
		2. GETNAMEINFO
		3. INSTFRZDEFER
		4. JNLORDBFLU
		5. MURNDWNOVRD
		6. REGOPENFAIL
		7. REGOPENRETRY
		8. SOCKBIND
		Updated Appendix A: "Error Message Quick Reference" (page 355) and Message Categorization Index for V6.0-003.
		Marked the following messages as deprecated:

		1. DBMAX RSEXBL
		2. GETCWD
		3. JNLDSKALIGN
		4. JNLEOFPREZERO
		5. JNLNOTFOUND
		6. JNLQIOLOCKED
		7. MAXTRACEHEIGHT
		8. MAXTRACELEVEL
		9. RECNOCREJNL
		10. TPLOCKRESTMAX
		11. TRUNCATE
		Removed the following message:
		• JNLSTRESTFL
Revision V6.0-002	13 August 2013	The following messages were added:
		1. BADZPEEKARG
		2. BADZPEEKFMT
		3. BADZPEEKRANGE
		4. DBMBMINCFREFIXED
		5. FALLINTOFLST
		6. FREEBLKSLOW
		7. FTOKKEY
		8. GTMSECSHRDMNSTARTED
		9. GTMSECSHRGETSEMFAIL
		10. GTMSECSHRREMFILE
		11. GTMSECSHRREMSEM
		12. GTMSECSHRREMSEMFAIL
		13. GTMSECSHRREMSHM
		14. GTMSECSHRSEMGET
		15. GTMSECSHRSHMCONCPROC
		16. GTMSECSHRUPDDBHDR
		17. HOSTCONFLICT

FIS V6.2-002

		18. JNI
		19. JNLQIOSALVAGE
		20. MALLOCMAXUNIX
		21. MALLOCMAXVMS
		22. MMREGNOACCESS
		23. MUUSERECOV
		24. MUUSERLBK
		25. NULLENTRYREF
		26. SECSHRCHDIRFAILED
		27. SECSHRCLEARENVFAILED
		28. SECSHREXECLFAILED
		29. SECSHRGTMDBGLVL2LONG
		30. SECSHRGTMDIST2LONG
		31. SECSHRGTMTMP2LONG
		32. SECSHRNOGTMDIST
		33. SECSHRNOTOWNEDBYROOT
		34. SECSHRNOTSETUID
		35. SECSHRPERMINCRCT
		36. SECSHRSETGTMDISTFAILED
		37. SECSHRSETGTMTMPFAILED
		38. SECSHRSETUIDFAILED
		39. SECSHRSTATFAILED
		40. SECSHRWRITABLE
		41. SEMID
		42. ZPEEKNORPLINFO
		The following messages were revised:
		1. DBBADFREEBLKCTR
		2. INDRCOMPFAIL
		3. MMFILETOOLARGE
Revision V6.0-001	04 April 2013	Added Appendix A: "Error Message Quick Reference" (page 355) and the Message Categorization Index.

V6.2-002 MR Manual June 09, 2015, Page 9 The following messages were added: 1. BKUPRUNNING 2. CRYPTBADCONFIG 3. CRYPTDLNOOPEN2 4. CRYPTINIT2 5. DBCOLLREQ 6. GTMEISDIR 7. JNLFILRDOPN 8. MUNOTALLINTEG 9. MUSIZEFAIL 10. MUSIZEINVARG 11. NOTALLDBRNDWN 12. REQROLLBACK 13. SEQNUMSEARCHTIMEOUT 14. SETEXTRENV 15. SIDEEFFECTEVAL 16. SPCLZMSG 17. TPRESTNESTERR The following messages were revised: 1. CRYPTDLNOOPEN 2. CRYPTHASHGENFAILED 3. CRYPTINIT 4. CRYPTKEYFETCHFAILED 5. GTMSECSHRSRVF 6. JNLCNTRL 7. JNLEXTEND 8. JNLPROCSTUCK 9. JNLFSYNCLSTCK The following messages was deprecated: • CRYPTKEYFETCHFAILEDNF

Revision V6.0-000/3	21 November 2012	Updated REPLSTATEOFF, JNLACCESS, JNLFILOPN, and REPLWARN messages for V6.0-000.
Revision V6.0-000/2	19 November 2012	Improved the descriptions of the JNLTMQUAL3 message and updated the TPNOTACID message for V6.0-000.
Revision V6.0-000/1	18 October 2012	Added the EXTRFILEXISTS message and improved the description of the following messages:
		1. DSKNOSPCAVAIL
		2. NOSPACEEXT
Revision V6.0-000	28 September 2012	Updated "MUPIP INTEG Errors" (page liv) and "MUPIP LOAD Errors" (page liii) for V6.0-000 error messages.
		The following messages were added:
		1. CUSTERRNOTFND
		2. CUSTERRSYNTAX
		3. CUSTOMFILOPERR
		4. DBDATAMX
		5. DBFHEADERRANY
		6. DBIOERR
		7. DBSPANCHUNKORD
		8. DBSPANGLOINCMP
		9. DSKNOSPCAVAIL
		10. DSKNOSPCBLOCKED
		11. DSKSPCAVAILABLE
		12. ENOSPCQIODEFER
		13. GTMSECSHRBADDIR
		14. GTMSECSHRISNOT
		15. GTMSECSHRNOARG0
		16. INITORRESUME
		17. JNLBUFFDBUPD
		18. JNLBUFFREGUPD
		19. KEYFORBLK

V6.2-002 MR Manual June 09, 2015, Page 11

20. LDSPANGLOINCMP

21. LOCKINCR2HIGH

22. LOCKIS

23. LOCKSUB2LONG

24. MUFILRNDWNFL2

25. MUINSTFROZEN

26. MUINSTUNFROZEN

27. MUTEXLCKALERT

28. ORLBKINPROG

29. REPLINSTFREEZECOMMENT

30. REPLINSTFROZEN

31. REPLINSTUNFROZEN

32. REQRECOV

33. REQROLLBACK

34. RESCRCWAIT

35. RESRCINTRLCKBYPAS

The following messages were revised:

1. DBRSIZMN

2. DBRSIZMX

3. GTMSECSHRSRVF

4. GTMSECSHRSRVFID

5. GTMSECSHRSRVFIL

6. INVCMD

7. REQRUNDOWN

The following messages were deprecated:

1. GTMSECSHRDEFLOG

2. GTMSECSHRLOGF

3. GTMSECSHRLOGSWH

4. JNLBUFFTOOLG

5. JNLBUFFTOOSM

FIS

		6. RCVR2MANY
		7. RLBKCONFIGBNDRY
		8. RNDWNSKIPCNT
Revision 1	23 May 2012	The following messages were changed:
		MUTEXLCKALERT
		• BADCHAR
Revision V5.5-000	27 February 2012	The following messages were added:
		BADREGION
		COREINPROGRESS
		DBROLLEDBACK
		DSEWCREINIT
		• GTMASSERT2
		• IGNBMPMRKFREE
		• INSNOTJOINED
		• INSROLECHANGE
		• INSUNKNOWN
		• INVTRCGRP
		JIUNHNDINT
		• JNLALLOCGROW
		• JNLNOREPL
		• JRTNULLFAIL
		• JNLRECINCMPL
		LOCKSPACEINFO
		• LOCKSPACEUSE
		MAXSEMGETRETRY
		• MUINFOUINT6
		MUTRUNC1ATIME
		MUTRUNCBACKINPROG
		MUTRUNCERROR
		MUTRUNCFAIL
		MUTRUNCNOSPACE

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 13

- MUTRUNCNOTBG
- MUTRUNCNOV4
- MUTRUNCPERCENT
- MUTRUNCSSINPROG
- MUTRUNCSUCCESS
- NOLOCKMATCH
- NONASCII
- NORESYNCSUPPLONLY
- NORESYNCUPDATERONLY
- NOSUPPLSUPPL
- ORLBKCMPLT
- ORLBKFRZOVER
- ORLBKFRZPROG
- ORLBKNOSTP
- ORLBKNOV4BLK
- ORLBKSTART
- ORLBKTERMNTD
- PERMGENDIAG
- PERMGENFAIL
- RCVR2MANY
- RCVRMANYSTRMS
- REPL2OLD
- REPLINSTDBSTRM
- REPLINSTMISMTCH
- REPLUPGRADESEC
- RESOLVESEQNO
- RESOLVESEQSTRM
- RESUMESTRMNUM
- REUSEINSTNAME
- RLBKCONFIGBNDRY
- RLBKSTRMSEQ

- RNDWNSKIPCNT
- RSYNCSTRMSUPPLONLY
- RSYNCSTRMVAL
- SECNOTSUPPLEMENTARY
- STRMNUMMISMTCH1
- STRMNUMMISMTCH2
- STRMSEQMISMTCH
- SUPRCVRNEEDSSUPSRC
- SRVLCKWT2LNG
- STRMNUMIS
- TRIGMODREGNOTRW
- UPDSYNC2MTINS
- UPDSYNCINSTFILE
- ZDATEBADDATE
- ZDATEBADTIME
- ZTRIGNOTRW

The following messages were marked as deprecated ( ).

- ACTLSTEXP
- FMLLSTPRESENT

The following messages were changed:

- DBFLCORRP
- JOBEXAMFAIL
- DBCDBNOCERTIFY
- LOCKSPACEFULL
- NOREPLCTDREG
- PRIMARYISROOT
- REPLINSTMISMTCH
- REPLUPGRADEPRI
- REPLUPGRADESEC
- SEMWT2LONG

		SHMREMOVED
Revision 1	13 January 2012	Improved the description of UNIMPLOP.
Revision V5.4-002B	26 December 2011	Conversion to documentation revision history reflecting GT.M releases with revision history for each chapter.
		• Marked deprecated messages as •.

FIS V6.2-002

# **Table of Contents**

About This Manual	. li
Intended Audience	. li
Purpose of the Manual	. li
How to Use This Manual	. li
Conventions Used in This Manual	li
Following Up on Suggested Actions	liii
MUPIP LOAD Errors	liii
Plug-in Errors	liv
MUPIP INTEG Errors	liv
1. Error Messages	
ABNCOMPTINC	
ACOMPTBINC	1
ACTCOLLMISMTCH	1
ACTIVATEFAIL	1
ACTLSTEXP	
ACTLSTTOOLONG	2
ACTOFFSET	2
ACTRANGE	2
ADDRTOOLONG	. 3
AIMGBLKFAIL	3
ALIASEXPECTED	3
AMBISYIPARAM	3
ANCOMPTINC	4
ARCTLMAXHIGH 🔮	4
ARCTLMAXLOW <b>♀</b>	4
ARROWNTDSP	
ASSERT	4
BACKUPCTRL	
BACKUPKILLIP	
BADACCMTHD	
BADCASECODE	
BADCHAR	6
BADCHSET	6
BADDBVER	6
BADGBLSECVER	
BADGTMNETMSG	7
BADJPIPARAM	7
BADLKIPARAM	
BADQUAL	
BADREGION	
BADSRVRNETMSG	
BADSYIPARAM	
BADTAG	
BADTRNPARAM	

BADZPEEKARG	. 8
BADZPEEKFMT	. 9
BADZPEEKRANGE	9
BCKUPBUFLUSH	9
BEGINST	10
BEGSEQGTENDSEQ	10
BFRQUALREQ	10
BIGNOACL	10
BINHDR	11
BITMAPSBAD	11
BKUPRUNNING	11
BKUPTMPFILOPEN	11
BKUPTMPFILWRITE	12
BLKCNT	12
BLKCNTEDITFAIL	12
BLKINVALID	12
BLKSIZ512	13
BLKTOODEEP	13
BLKWRITERR	13
BOMMISMATCH	
BOOLSIDEFFECT	13
BOVTMGTEOVTM	14
BOVTNGTEOVTN	14
BREAK	14
BREAKDEA	14
BREAKZBA	
BREAKZST	
BTFAIL	
BUFFLUFAILED	
BUFOWNERSTUCK	
BUFRDTIMEOUT	
BUFSIZIS	
BUFTOOSMALL	
CALLERID	
CALLINAFTERXIT	
CANTBITMAP	
CEBIGSKIP	
CENOINDIR	
CETOOLONG	
CETOOMANY	
CEUSRERROR	
CHNGTPRSLVTM	
CHSETALREADY	
CIDIRECTIVE	
CIENTNAME	
CIMAXLEVELS	
CIMAXPARAM	19

CINOENTRY	20
CIPARTYPE	20
CIRCALLNAME	20
CIRPARMNAME	20
CIRTNTYP	20
CITABENV	21
CITABOPN	21
CITPNESTED	21
CIUNTYPE	21
CLIERR	22
CLOSEFAIL	22
CLSTCONFLICT	22
CMD	22
CMEXCDASTLM	22
CMICHECK	23
CMINTQUE	23
CMSYSSRV	23
CNOTONSYS	23
COLLARGLONG	23
COLLATIONUNDEF	24
COLLDATAEXISTS	24
COLLFNMISSING	24
COLLTYPVERSION	24
COLON	25
COLTRANSSTR2LONG	25
COMMA	25
COMMAORRPAREXP	25
COMMENT	25
COMMITWAITPID	26
COMMITWAITSTUCK	26
COMPILEQUALS	26
CONNSOCKREQ	26
COREINPROGRESS	27
CORRUPT	27
CORRUPTNODE	27
CPBEYALLOC	27
CREDNOTPASSED	27
CRITRESET	28
CRITSEMFAIL	28
CRYPTBADCONFIG	28
CRYPTBADWRTPOS	28
CRYPTDLNOOPEN	29
CRYPTDLNOOPEN2	29
CRYPTHASHGENFAILED	29
CRYPTINIT	29
CRYPTINIT2	29
CRYPTINLWRONGHASH	30

CRYPTKEYFETCHFAILED	30
CRYPTKEYFETCHFAILEDNF	30
CRYPTKEYTOOBIG	30
CRYPTNOAPPEND	31
CRYPTNOKEYSPEC	31
CRYPTNOMM	31
CRYPTNOOVERRIDE	31
CRYPTNOPSWDINTP	32
CRYPTNOSEEK	32
CRYPTNOTRUNC	32
CRYPTNOV4	. 32
CRYPTOPFAILED	33
CTLMNEMAXLEN	33
CTLMNEXPECTED	33
CTRAP	33
CTRLC	33
CTRLY	34
CURRSOCKOFR	34
CUSTERRNOTFND	34
CUSTERRSYNTAX	34
CUSTOMFILOPERR	34
DBADDRALIGN	35
DBADDRANGE	35
DBADDRANGE8	35
DBBADFREEBLKCTR	35
DBBADKYNM	
DBBADNSUB	36
DBBADPNTR	36
DBBADUPGRDSTATE	36
DBBDBALLOC	37
DBBFSTAT	37
DBBLEVMN	37
DBBLEVMX	37
DBBMBARE	37
DBBMINV	. 38
DBBMLCORRUPT	38
DBBMMSTR	38
DBBMSIZE	38
DBBNPNTR	38
DBBPLMGT2K	39
DBBPLMLT512	. 39
DBBPLNOT512	
DBBSIZMN	
DBBSIZMX	39
DBBSIZZRO	
DBBTUFIXED	40
DBBTUWRNG	40

DBCBADFILE	40
DBCCERR	. 41
DBCCMDFAIL	41
DBCDBCERTIFIED	. 41
DBCDBNOCERTIFY	. 41
DBCINTEGERR	. 41
DBCKILLIP	42
DBCLNUPINFO	. 42
DBCMODBLK2BIG	42
DBCMPBAD	42
DBCMPMX	. 43
DBCMPNZRO	. 43
DBCNOEXTND	. 43
DBCNOFINISH	43
DBCNOTSAMEDB	. 44
DBCNTRLERR	44
DBCOLLREQ	44
DBCOMMITCLNUP	44
DBCOMPTOOLRG	. 45
DBCREC2BIG	45
DBCREC2BIGINBLK	45
DBCREINCOMP	. 45
DBCRERR	. 46
DBCRERR8	46
DBCSCNNOTCMPLT	. 46
DBDANGER	46
DBDATAMX	46
DBDIRTSUBSC	47
DBDSRDFMTCHNG	. 47
DBENDIAN	47
DBFGTBC	. 47
DBFHEADERR	
DBFHEADERR4	48
DBFHEADERR8	48
DBFHEADERRANY	. 48
DBFILERR	. 48
DBFILEXT	49
DBFILOPERR	49
DBFLCORRP	. 49
DBFRZRESETFL	. 49
DBFRZRESETSUC	. 50
DBFSTBC	
DBFSTHEAD	
DBFSYNCERR	
DBGTDBMAX	
DBHEADINV	. 51
DBIDMISMATCH	51

DBINCLVL	51
DBINCRVER	51
DBINVGBL	51
DBIOERR	52
DBJNLNOTMATCH	52
DBKEYGTIND	52
DBKEYMN	
DBKEYMX	53
DBKEYORD	53
DBKGTALLW	53
DBLOCMBINC	
DBLRCINVSZ	53
DBLTSIBL	54
DBLVLINC	54
DBMAXKEYEXC	54
DBMAXNRSUBS	54
DBMAXREC2BIG	54
DBMAXRSEXBL	55
DBMBMINCFRE	55
DBMBMINCFREFIXED	55
DBMBPFLDIS	55
DBMBPFLDLBM	55
DBMBPFLINT	56
DBMBPFRDLBM	56
DBMBPFRINT	56
DBMBPINCFL	56
DBMBSIZMN	56
DBMBSIZMX	57
DBMBTNSIZMX	57
DBMINRESBYTES	57
DBMISALIGN	57
DBMRKBUSY	57
DBMRKFREE	58
DBMXRSEXCMIN	58
DBNAMEMISMATCH	58
DBNOCRE	58
DBNOREGION	58
DBNOTDB	59
DBNOTGDS	59
DBNOTMLTP	59
DBOPNERR	59
DBPREMATEOF	60
DBPRIVERR	60
DBPTRMAP	60
DBPTRMX	60
DBPTRNOTPOS	60
DBOUELINK	61

DDDD D TO	
DBRBNNEG	61
DBRBNTOOLRG	61
DBRDERR	61
DBRDONLY	62
DBREADBM	62
DBREMOTE	62
DBRLEVLTONE	62
DBRLEVTOOHI	62
DBRNDWN	63
DBRNDWNWRN	63
DBROLLEDBACK	63
DBROOTBURN	
DBRSIZMN	
DBRSIZMX	64
DBSHMNAMEDIFF	
DBSPANCHUNKORD	
DBSPANGLOINCMP	
DBSTARCMP	
DBSTARSIZ	
DBSVBNMIN	
DBSZGT64K	
DBTN	
DBTNLTCTN	
DBTNNEQ	
DBTNRESET	
DBTNRESETINC	
DBTNTOOLG	
DBTOTBLK	
DBTTLBLK0	
DBUNDACCMT	
DBVERPERFWARN1	
DBVERPERFWARN2	
DBWCVERIFYEND	
DBWCVERIFYSTART	
DCNINPROG	
DEVPARPROT	
	70
DELIMSIZNA DELIMWIDTH DEVICEREADONLY DEVICEWRITEONLY DEVNOTIMP DEVOPENFAIL DEVPARINAP DEVPARMNEG DEVPARMTOOSMALL	69 69 69 69 70 70

DEVPARUNK	. 71
DEVPARVALREQ	71
DIRONLY	. 71
DISTPATHMAX	. 71
DIVZERO	. 71
DLCKAVOIDANCE	. 72
DLLCHSETM	. 72
DLLCHSETUTF8	. 72
DLLNOCLOSE	. 72
DLLNOOPEN	. 72
DLLNORTN	. 73
DLLVERSION	. 73
DLRCILLEGAL	. 73
DLRCTOOBIG	
DLRCUNXEOR	
DSEBLKRDFAIL	
DSEFAIL	
DSEINVLCLUSFN	
DSEMAXBLKSAV	
DSENOFINISH	
DSENOTOPEN	
DSEONLYBGMM	
DSEWCINITCON	
DSEWCREINIT	
DSKNOSPCAVAIL	
DSKNOSPCBLOCKED	
DSKSPACEFLOW	
DSKSPCAVAILABLE	
DUPTN	
DUPTOKEN	
DVIKEYBAD	
DYNUPGRDFAIL	
DZTRIGINTRIG	
DZWRNOALIAS	
DZWRNOPAREN	
ECLOSTMID	
ENDIANCVT	
ENOSPCQIODEFER	
EORNOTFND	
EPOCHTNHI	
EQUAL	
ERRCALL	
ERRORSUMMARY	
ERRWETRAP	
ERRWEXC	
ERRWIOEXC	
ERRWZBRK	

ERRWZINTR	81
ERRWZTRAP	81
EVENTLOGERR	81
EXCLUDEREORG	81
EXECOM	81
EXPR	82
EXTGBLDEL	82
EXTRACTCTRLY	82
EXTRACTFILERR	82
EXTRCLOSEERR	82
EXTRFAIL	83
EXTRFILEXISTS	83
EXTRFMT	83
EXTRIOERR	83
EXTSRCLIN	83
EXTSRCLOC	84
FALLINTOFLST	84
FCHARMAXARGS	84
FCNSVNEXPECTED	84
FILECREATE	84
FILEDEL	85
FILEDELFAIL	85
FILEEXISTS	85
FILEIDGBLSEC	85
FILEIDMATCH	86
FILENAMETOOLONG	86
FILENOTCREATE	86
FILENOTFND	86
FILEOPENFAIL	86
FILEPARSE	87
FILERENAME	87
FILTERBADCONV	87
FILTERCOMM	87
FILTERNOTALIVE	87
FILTERTIMEDOUT	88
FMLLSTMISSING	88
FMLLSTPRESENT	88
FNARGINC	88
FNNAMENEG	89
FNOTONSYS	89
FNUMARG	89
FORCEDHALT	89
FORCTRLINDX	89
FOROFLOW	90
FREEBLKSLOW	90
FREEMEMORY	90
FRFF ZF	90

FREEZECTRL	91
FREEZEERR	91
FSEXP	91
FSYNCTIMOUT	91
FTOKERR	91
FTOKKEY	92
GBLEXPECTED	92
GBLMODFAIL	92
GBLNAMCOLLRANGE	92
GBLNAMCOLLUNDEF	92
GBLNAMCOLLVER	93
GBLNAME	93
GBLNAMEIS	93
GBLNOEXIST	93
GBLNOMAPTOREG	93
GBLOFLOW	94
GBLSECNOTGDS	94
GDCREATE	94
GDECHECK	94
GDINVALID	95
GDNOTSET	95
GDREADERR	95
GDUNKNFMT	95
GDUPDATE	95
GDUSEDEFS	96
GETADDRINFO	96
GETCWD	96
GETNAMEINFO	96
GETSOCKNAMERR	
GETSOCKOPTERR	
GOQPREC	
GTMASSERT	97
GTMASSERT2	
GTMCHECK	
GTMDISTUNDEF	98
GTMDISTUNVERIF	98
GTMDUMPFAIL	98
GTMEISDIR	
GTMERREXIT	
GTMSECSHR	
GTMSECSHRBADDIR	
GTMSECSHRCHDIRF	
GTMSECSHRDEFLOG	
GTMSECSHRDMNSTARTED	
GTMSECSHRFORKF	
GTMSECSHRGETSEMFAIL	
GTMSECSHRISNOT	100

GTMSECSHRLOGF	101
GTMSECSHRLOGSWH	101
GTMSECSHRNOARG0	101
GTMSECSHROPCMP	101
GTMSECSHRPERM	101
GTMSECSHRRECVF	102
GTMSECSHRREMFILE	102
GTMSECSHRREMSEM	102
GTMSECSHRREMSEMFAIL	102
GTMSECSHRREMSHM	102
GTMSECSHRSCKSEL	103
GTMSECSHRSEMGET	103
GTMSECSHRSENDF	103
GTMSECSHRSGIDF	103
GTMSECSHRSHMCONCPROC	103
GTMSECSHRSHUTDN	104
GTMSECSHRSOCKET	104
GTMSECSHRSRVF	104
GTMSECSHRSRVFID	104
GTMSECSHRSRVFIL	104
GTMSECSHRSSIDF	105
GTMSECSHRSTART	105
GTMSECSHRSUIDF	105
GTMSECSHRTMOUT	105
GTMSECSHRTMPPATH	105
GTMSECSHRUPDDBHDR	106
GVDATAFAIL	106
GVDATAGETFAIL	106
GVFAILCORE	106
GVGETFAIL	107
GVINCRFAIL	107
GVINCRISOLATION	107
GVINVALID	107
GVIS	107
GVKILLFAIL	108
GVNAKED	108
GVNAKEDEXTNM	108
GVNEXTARG	108
GVORDERFAIL	108
GVPUTFAIL	109
GVQUERYFAIL	109
GVQUERYGETFAIL	109
GVREPLERR	109
GVRUNDOWN	109
GVSUBOFLOW	110
GVSUBSERR	110
GVINDEF	110

GVZPREVFAIL	110
GVZTRIGFAIL	110
HLPPROC	111
HOSTCONFLICT	111
HTEXPFAIL	111
HTOFLOW	111
HTSHRINKFAIL	112
ICUERROR	112
ICUSYMNOTFOUND	112
ICUVERLT36	112
IFBADPARM	113
IFNOTINIT	113
IGNBMPMRKFREE	113
ILLCHAR	113
ILLESOCKBFSIZE	113
IMAGENAME	114
INDEXTRACHARS	114
INDMAXNEST	114
INDRCOMPFAIL	114
INDRMAXLEN	114
INITORRESUME	115
INPINTEG	115
INSFFBCNT	115
INSNOTJOINED	115
INSROLECHANGE	116
INSTFRZDEFER	116
INSUNKNOWN	116
INTEGERRS	117
INVACCMETHOD	117
INVADDRSPEC	117
INVALIDRIP	117
INVBITLEN	117
INVBITPOS	
INVBITSTR	118
INVCMD	118
INVCTLMNE	118
INVDLRCVAL	
INVECODEVAL	
INVERRORLIM	
INVFCN	
INVGBLDIR	
INVGLOBALQUAL	
INVGTMEXIT	
INVICUVER	
INVIDQUAL	
INVINTMSG	120

INVLINKTMPDIR 🛕	121
INVMEMRESRV	121
INVMNEMCSPC	121
INVMVXSZ	121
INVNETFILNM	122
INVOBJ	122
INVOBJFILE	122
INVPORTSPEC	122
INVPROT	122
INVQUALTIME	123
INVREDIRQUAL	123
INVROLLBKLVL	123
INVSPECREC	123
INVSTACODE	123
INVSTRLEN	124
INVSVN	124
INVTMPDIR 🔮	124
INVTRCGRP	124
INVTRNSQUAL	
INVZBREAK 🔮	125
INVZDIRFORM	
INVZROENT	
INVZSTEP	
IOEOF	
IOERROR	
IONOTOPEN	
IORUNDOWN	
IOWRITERR	
IPADDRREQ	
IPCNOTDEL	
ISOLATIONSTSCHN	127
ISSPANGBL	127
IVTIME	127
JIUNHNDINT	128
	128
JNLACCESS	128
JNLACTINCMPLT	128
JNLALIGNSZCHG	129
JNLALIGNTOOSM	
JNLALLOCGROW	129
JNLBADLABEL	129
JNLBADRECFMT	
JNLBUFFDBUPD	130
JNLBUFFREGUPD	
JNLBUFFTOOLG	130
INLBUFFTOOSM	130

JNLBUFINFO	. 131
JNLCLOSE	131
JNLCLOSED	. 131
JNLCNTRL	. 132
JNLCREATE	. 132
JNLCREATERR	. 132
INLCRESTATUS	. 132
INLCYCLE	132
JNLDBERR	. 133
JNLDBTNNOMATCH	
JNLDISABLE	. 133
INLDSKALIGN	
JNLENDIANBIG	
JNLENDIANLITTLE	
JNLEOFPREZERO	
INLEXTEND	
INLEXTR	
JNLFILECLOSERR	
JNLFILEDUP	
JNLFILEOPNERR	
JNLFILEXTERR	
JNLFILNOTCHG	
JNLFILOPN	
JNLFILRDOPN	
JNLFLUSH	
JNLFLUSHNOPROG	
INLFNF	
JNLFSYNCERR	
JNLFSYNCLSTCK	
JNLINVALID	
JNLINVALLOC	
INLINVEXT	
JNLINVSWITCHLMT	
JNLMEMDSK	
JNLMINALIGN	
JNLMOVED	
JNLNAMLEN	
JNLNEWREC	
JNLNMBKNOTPRCD	
JNLNOBIJBACK	
JNLNOCREATE	
JNLNOREPL	
INLNOTFOUND	
JNLOPNERR	
JNLORDBFLU	
JNLPOOLBADSLOT	
INI POOI SETUP	141

JNLPREVRECOV	141
JNLPROCSTUCK	142
JNLPVTINFO	142
JNLQIOLOCKED	142
JNLQIOSALVAGE	142
JNLRDERR	143
JNLRDONLY	143
JNLREAD	143
JNLREADBOF	143
JNLREADEOF	143
JNLRECFMT	144
INLRECINCMPL	144
JNLRECTYPE	144
JNLSENDOPER	
JNLSETDATA2LONG	
JNLSPACELOW	
JNLSTATE	
JNLSTATEOFF	
JNLSUCCESS	
JNLSWITCHSZCHG	
INLSWITCHTOOSM	
JNLTMQUAL1	
JNLTMQUAL2	
JNLTMQUAL3	
JNLTMQUAL4	
JNLTNOUTOFSEQ	
JNLTPNEST	
JNLTRANS2BIG	
JNLTRANSGTR	
INLTRANSLSS	
JNLUNXPCTERR	
INLVSIZE	
JNLWRERR	
JNLWRTDEFER	
JOBACTREF	
JOBARGMISSING	
JOBEXAMDONE	
JOBEXAMFAIL	
JOBFAIL	
JOBLABOFF	
JOBLVN2LONG	
JOBLVNDETAIL •	
JOBPARM	
JOBPARNOVAL	
JOBPARNUM	
IOBPARSTR	152

JOBPARTOOLONG	152
JOBPARUNK	152
JOBPARVALREQ	. 153
JOBSETUP	. 153
JOBSTARTCMDFAIL	. 153
JRTNULLFAIL	153
JUSTFRACT	153
KEY2BIG	. 154
KEYFORBLK	. 154
KEYSIZIS	154
KEYTOOBIG	154
KEYWRDAMB	154
KEYWRDBAD	. 155
KILLABANDONED	. 155
KILLBYSIG	155
KILLBYSIGSINFO1	155
KILLBYSIGSINFO2	156
KILLBYSIGSINFO3	156
KILLBYSIGUINFO	. 156
KRNLKILL	. 156
LABELEXPECTED	. 156
LABELMISSING	157
LABELNOTFND	157
LABELONLY	157
LABELUNKNOWN	. 157
LASTFILCMPLD	. 157
LASTWRITERBYPAS O	. 158
LCKGONE	. 158
LCKSCANCELLED	158
LCKSGONE	. 158
LCKSTIMOUT	
LDBINFMT	. 159
LDGOQFMT	
LDSPANGLOINCMP	
LINKVERSION	
LISTENPASSBND	
LITNONGRAPH	160
LKENOFINISH	
LKNAMEXPECTED	
LKRUNDOWN	161
LKSECINIT	161
LNKNOTIDLE	
LOADABORT	
LOADBGSZ	
LOADBGSZ2	
LOADCTRLY	

LOADEDBG	162
LOADEDSZ	162
LOADEDSZ2	162
LOADEOF	163
LOADFILERR	163
LOADFMT	163
LOADGD	163
LOADINVCHSET	163
LOADRUNNING	164
LOCALSOCKREQ	164
LOCKINCR2HIGH	
LOCKIS	164
LOCKSPACEFULL	
LOCKSPACEINFO	
LOCKSPACEUSE	
LOCKSUB2LONG	
LOGOFF	
LOGON	
LOGTOOLONG	
LOWSPACECRE	
LPARENMISSING	
LPARENREQD	
LQLENGTHNA	
LSEXPECTED	
LVNULLSUBS	
LVORDERARG	
LVSTARALON	
MALLOCMAXUNIX	
MALLOCMAXVMS	
MAPBAD	
MAPDUP	
MAXACTARG	
MAXARGCNT MAXBTLEVEL	
MAXFORARGS	
MAXGTMPATH	
MAXNRSUBSCRIPTS  MAYSEMOETRETRY	
MAXSEMGETRETRY	
MAXSSREACHED	
MAXSTRLEN	
MAXTRACEHEIGHT	
MAXTRACELEVEL	
MAXTRIGNEST	
MBXRDONLY	
MBXWRTONLY	
MEMORY	
MEMORYRECURSIVE	172

MERGEDESC	172
MERGEINCOMPL	173
MISSINGDELIM	173
MMBEFOREJNL	173
MMFILETOOLARGE	173
MMNOBEFORIMG	174
MMNOBFORRPL	174
MMNODYNDWNGRD	174
MMNODYNUPGRD	174
MMREGNOACCESS	174
MPROFRUNDOWN	175
MRTMAXEXCEEDED	175
MTANSIFOR	175
MTANSILAB	175
MTBLKTOOBIG	176
MTBLKTOOSM	176
MTDOSFOR	176
MTDOSLAB	176
MTFIXRECSZ	176
MTINVLAB	177
MTIOERR	177
MTIS	177
MTNOSKIP	177
MTRDBADBLK	177
MTRDONLY	178
MTRDTHENWRT	178
MTRECGTRBLK	178
MTRECTOOBIG	178
MTRECTOOSM	178
MUBCKNODIR	179
MUDWNGRDNOTPOS	
MUDWNGRDNRDY	
MUDWNGRDTN	179
MUFILRNDWNFL	
MUFILRNDWNFL2	
MUFILRNDWNSUC	180
MUINFOSTR	
MUINFOUINT4	
MUINFOUINT6	
MUINFOUINT8	
MUINSTFROZEN	
MUINSTUNFROZEN	
MUJNLDBMISSING	
MUJNLPREVGEN	
MUJNLSTAT	
MUJPOOLRNDWNFL	
MUJPOOLRNDWNSUC	182

MUKILLIP	182
MULOGNAMEDEF	183
MULTFORMPARM	183
MULTLAB	183
MUNOACTION	183
MUNODBNAME	183
MUNODWNGRD	184
MUNOFINISH	184
MUNOSTRMBKUP	184
MUNOTALLINTEG	184
MUNOTALLSEC	184
MUNOUPGRD	185
MUPCLIERR	185
MUPGDERR	185
MUPGRDSUCC	185
MUPIPINFO	
MUPIPSIG	186
MUPJNLINTERRUPT	186
MUPRECFLLCK	186
MUPRESTERR	186
MUQUALINCOMP	186
MURAIMGFAIL	187
MUREORGFAIL	187
MUREPLPOOL	187
MUREPLSECDEL	187
MUREPLSECNOTDEL	187
MUREUPDWNGRDEND	188
MURNDWNOVRD	188
MURPOOLRNDWNFL	188
MURPOOLRNDWNSUC	188
MUSECDEL	188
MUSECNOTDEL	189
MUSELFBKUP	189
MUSIZEFAIL	189
MUSIZEINVARG	189
MUSTANDALONE	189
MUTEXERR	190
MUTEXFRCDTERM	190
MUTEXLCKALERT	190
MUTEXRELEASED	191
MUTEXRSRCCLNUP	192
MUTNWARN	192
MUTRUNC1ATIME	192
MUTRUNCBACKINPROG	192
MUTRUNCERROR	192
MUTRUNCFAIL	193
MUTRUNCNOSPACE	193

MUTRUNCNOTBG	. 193
MUTRUNCNOV4	193
MUTRUNCPERCENT	193
MUTRUNCSSINPROG	193
MUTRUNCSUCCESS	194
MUUPGRDNRDY	194
MUUSERECOV	. 194
MUUSERLBK	. 194
NAMEEXPECTED	194
NAMENDBAD	195
NAMGVSUBOFLOW	195
NAMGVSUBSMAX	. 195
NAMLPARENNOTBEG	. 195
NAMNOTSTRSUBS	195
NAMNUMSUBSOFLOW	196
NAMONECOLON	
NAMRANGELASTSUB	196
NAMRANGEORDER	
NAMRANGEOVERLAP	
NAMRPARENNOTEND	
NAMSTARSUBSMIX	
NAMSTARTBAD	
NAMSTRSUBSCHARG	
NAMSTRSUBSCHINT	
NAMSTRSUBSFUN	
NAMSUBSBAD	
NAMSUBSEMPTY	
NCTCOLLDIFF	
NCTCOLLSPGBL	
NEEDTRIGUPGRD	
NEGFRACPWR	
NESTFORMP	
NETDBOPNERR	
NETFAIL	
NETLCKFAIL	
NEWJNLFILECREAT	
NLMISMATCHCALC	
NOACTION	
NOALIASLIST	
NOCANONICNAME	
NOCCPPID	
NOCHLEFT	
NODFRALLOCSUPP •	
NOEDITOR	
NOENDIANCVT	202
	7117

NOEXCNOZTRAP	203
NOEXIT	203
NOFORKCORE	203
NOGTCMDB	203
NOJNL	204
NOJNLPOOL	204
NOLBRSRC	204
NOLOCKMATCH	204
NOLOG	205
NONASCII	205
NONEGATE	205
NONUTF8LOCALE	205
NOPINI	206
NOPLACE	206
NOPREVLINK	206
NOPRINCIO A	206
NORECVPOOL	207
NOREGION	207
NOREPLCTDREG	207
NORESYNCSUPPLONLY	207
NORESYNCUPDATERONLY	208
NOSELECT	208
NOSOCKETINDEV	208
NOSOCKHANDLE	208
NOSPACECRE	208
NOSPACEEXT	209
NOSTARFILE	209
NOSUBSCRIPT	209
NOSUCHPROC	209
NOSUPPLSUPPL	209
NOTALLDBOPN	210
NOTALLDBRNDWN	210
NOTALLJNLEN	210
NOTALLREPLON	210
NOTERMENTRY	210
NOTERMENV	211
NOTERMINFODB	211
NOTEXTRINSIC	211
NOTGBL	211
NOTPOSITIVE	212
NOTPRINCIO	212
NOTREPLICATED	212
NOTRNDMACC	212
NOTTOEOFONPUT	212
NOUSERDB	213
NOVALUE	213

NOZBRK	. 213
NOZTRAPINTRIG	213
NULLCOLLDIFF	213
NULLENTRYREF	214
NULSUBSC	214
NUMOFLOW	214
NUMPROCESSORS	. 214
NUMUNXEOR	. 214
OBJDUP	. 215
OBJFILERR	. 215
OBJNOTADD	. 215
OBJNOTCHG	. 215
OBJNOTFND	. 215
OBJREQD	. 216
OFFSETINV	. 216
OLDBINEXTRACT	216
OMISERVHANG	216
OPCOMMISSED	. 216
OPENCONN	. 217
OPRCCPSTOP	. 217
ORDER2	. 217
ORLBKCMPLT	217
ORLBKFRZOVER	. 217
ORLBKFRZPROG	218
ORLBKINPROG	. 218
ORLBKNOSTP	. 218
ORLBKNOV4BLK	218
ORLBKSTART	
ORLBKTERMNTD	
OUTOFSPACE	
PADCHARINVALID	
PARBUFSM	. 219
PARFILSPC	219
PARNORMAL	
PATCLASS	
PATCODE	. 220
PATLIT	. 220
PATLOAD	
PATMAXLEN	
PATNOTFOUND	
PATTABNOTFND	
PATTABSYNTAX	
PATUPPERLIM	
PCONDEXPECTED	
PEERPIDMISMATCH	
PERMGENDIAG	
PERMGENFAIL	222

PRCNAMLEN	222
PREALLOCATEFAIL 4	223
PREFIXBAD	223
PREMATEOF	223
PREVJNLLINKCUT	
PREVJNLLINKSET	
PREVINLNOEOF	
PRIMARYISROOT	
PRIMARYNOTROOT	
PROCTERM	
PROTNOTSUP	
QUALBAD	
QUALDUP	
QUALEXP	
QUALREQD	
QUALVAL	
QUITALSINV	
QUITARGLST	
QUITARGREQD	
QUITARGUSE	
RANDARGNEG	
RBWRNNOTCHG	
RCVR2MANY	
RCVRANYSTRMS	
RDFLTOOLONG	
RDFLTOOLONG RDFLTOOSHORT	
REC2BIG	
RECCNT	
RECLOAD 🛕	
RECNOCREJNL	
RECORDSTAT	
RECSIZENOTEVEN	
RECSIZIS	230
RECTOOBIG	230
RECVPOOLSETUP	
REGIS	230
REGNTFND	231
REGOPENFAIL	231
REGOPENRETRY	231
REGSSFAIL	231
RELINKCTLERR	232
RELINKCTLFULL	232
REMOTEDBNOSPGBL	232
REMOTEDBNOTRIG	232
RENAMEFAIL	233
REORGCTRLY	233

REORGINC	233
REPL2OLD	233
REPLACCSEM	234
REPLBRKNTRANS	234
REPLCOMM	234
REPLERR	234
REPLEXITERR	234
REPLFILIOERR	235
REPLFILTER	235
REPLFTOKSEM	235
REPLGBL2LONG	235
REPLINFO	235
REPLINSTACC	236
REPLINSTCLOSE	236
REPLINSTCREATE	236
REPLINSTDBMATCH	236
REPLINSTDBSTRM	237
REPLINSTFMT	237
REPLINSTFREEZECOMMENT	238
REPLINSTFROZEN	238
REPLINSTMISMTCH	238
REPLINSTNMLEN	239
REPLINSTNMSAME	239
REPLINSTNMUNDEF	239
REPLINSTNOHIST	239
REPLINSTNOSHM	240
REPLINSTOPEN	240
REPLINSTREAD	240
REPLINSTSECLEN	241
REPLINSTSECMTCH	241
REPLINSTSECNONE	241
REPLINSTSECUNDF	241
REPLINSTSEQORD	242
REPLINSTSTNDALN	242
REPLINSTUNDEF	243
REPLINSTUNFROZEN	243
REPLINSTWRITE	243
REPLJNLCLOSED	243
REPLJNLCNFLCT	244
REPLLOGOPN 🛕	244
REPLNOBEFORE	
REPLNOHASHTREC	
REPLNOMULTILINETRG	
REPLNOTLS	
REPLNOTON	
PEDI NOVENDIAN	246

REPLOFFJNLON	246
REPLPOOLINST	246
REPLRECFMT	247
REPLREQROLLBACK	
REPLREQRUNDOWN	247
REPLSRCEXITERR 4	247
REPLSTATE	248
REPLSTATEERR	248
REPLSTATEOFF	248
REPLTRANS2BIG	248
REPLUPGRADEPRI	248
REPLUPGRADESEC	249
REPLWARN	249
REPLXENDIANFAIL	249
REQ2RESUME	250
REQDVIEWPARM	250
REQRECOV	250
REQRLNKCTLRNDWN	250
REQROLLBACK	251
REQRUNDOWN	251
RESCRCWAIT	251
RESOLVESEQNO	251
RESOLVESEQSTRM	252
RESRCINTRLCKBYPAS	252
RESUMESTRMNUM	252
REUSEINSTNAME	253
RHMISSING	253
RLBKCONFIGBNDRY	253
RLBKJNLNOBIMG	253
RLBKJNSEQ	254
RLBKLOSTTNONLY	254
RLBKNOBIMG	254
RLBKSTRMSEQ	254
RLNKCTLRNDWNFL	254
RLNKCTLRNDWNSUC	255
RLNKRECLATCH	255
RLNKSHMLATCH	255
RMBIGSHARE	255
RMNOBIGRECORD	256
RMSRDONLY	256
RMWIDTHPOS	256
RMWIDTHTOOBIG	256
RNDWNSEMFAIL	256
RNDWNSKIPCNT	256
ROLLBKINTERRUPT	257
ROUTINEUNKNOWN	257

RPAREN	257
RPARENMISSING	257
RPARENREQD	258
RSVDBYTE2HIGH	258
RSYNCSTRMSUPPLONLY	258
RSYNCSTRMVAL	258
RTNNAME	258
RTSLOC	259
RUNPARAMERR	259
RWARG	259
RWFORMAT	259
SCNDDBNOUPD	259
SDSEEKERR	260
SECNODZTRIGINTP	260
SECNOTSUPPLEMENTARY	260
SECONDAHEAD	260
SECSHRCHDIRFAILED	261
SECSHRCLEARENVFAILED	261
SECSHREXECLFAILED	261
SECSHRGTMDBGLVL2LONG	261
SECSHRGTMDIST2LONG	261
SECSHRGTMTMP2LONG	261
SECSHRNOGTMDIST	262
SECSHRNOTOWNEDBYROOT	262
SECSHRNOTSETUID	262
SECSHRPERMINCRCT	262
SECSHRSETGTMDISTFAILED	262
SECSHRSETGTMTMPFAILED	263
SECSHRSETUIDFAILED	263
SECSHRSTATFAILED	263
SECSHRWRITABLE	263
SEFCTNEEDSFULLB	263
SEGIS	264
SELECTFALSE	264
SELECTSYNTAX	264
SEMID	264
SEMKEYINUSE	264
SEMREMOVED	265
SEMWT2LONG	265
SEQNUMSEARCHTIMEOUT	265
SERVERERR	265
SETECODE	265
SETEXTRENV	266
SETINSETTRIGONLY	
SETINTRIGONLY	266
SETITIMERFAILED	266
SETREG2RESYNC	267

SETSOCKOPTERR	267
SETZDIR	267
SHMPLRECOV	267
SHMREMOVED	267
SHRMEMEXHAUSTED	268
SIDEEFFECTEVAL	268
SIGACCERR	268
SIGADRALN	268
SIGADRERR	269
SIGBADSTK	269
SIGCOPROC	269
SIGFLTDIV	269
SIGFLTINV	270
SIGFLTOVF	270
SIGFLTRES	270
SIGFLTUND	270
SIGILLADR	271
SIGILLOPC	271
SIGILLOPN	271
SIGILLTRP	271
SIGINTDIV	271
SIGINTOVF	272
SIGMAPERR	272
SIGOBJERR	272
SIGPRVOPC	272
SIGPRVREG	273
SIZENOTVALID4	273
SIZENOTVALID8	273
SNAPSHOTNOV4	
SOCKACCEPT	
SOCKACPT	
SOCKACTNA	
SOCKBFNOTEMPTY	274
SOCKBIND	
SOCKETEXIST	
SOCKINIT	275
SOCKLISTEN	275
SOCKMAX	275
SOCKNOTFND	275
SOCKNOTPASSED	
SOCKPARMREQ	
SOCKPASS	
SOCKPASSDATAMIX	
SOCKWAIT	
SOCKWRITE	
SPCLZMSG	
SPOREOL	277

SRCFILERR	277
SRCLIN	. 277
SRCLNNTDSP	. 278
SRCLOC	. 278
SRCLOCUNKNOWN	. 278
SRCNAM	. 278
SRCSRVEXISTS	. 278
SRCSRVNOTEXIST	279
SRCSRVTOOMANY	. 279
SRVLCKWT2LNG	. 279
SSATTACHSHM	. 279
SSFILCLNUPFAIL	. 279
SSFILOPERR	. 280
SSPREMATEOF	. 280
SSSHMCLNUPFAIL	. 280
SSTMPCREATE	. 280
SSTMPDIRSTAT	. 281
SSTMPFILOPEN	. 281
SSV4NOALLOW	. 281
STACKCRIT	. 281
STACKOFLOW	281
STACKUNDERFLO	. 282
STARFILE	282
STATCNT	. 282
STDNULLCOLLREQ	. 282
STOPTIMEOUT	. 282
STPEXPFAIL	. 283
STRINGOFLOW	. 283
STRMISSQUOTE	. 283
STRMNUMIS	. 283
STRMNUMMISMTCH1	. 283
STRMNUMMISMTCH2	. 284
STRMSEQMISMTCH	. 284
STRNOTVALID	. 284
STRUNXEOR	. 284
STUCKACT	. 285
SUB2LONG	. 285
SUPRCVRNEEDSSUPSRC	285
SUSPENDING	. 285
SVNEXPECTED	. 286
SVNONEW	286
SVNOSET	. 286
SYSCALL	286
TCGETATTR	286
TCOMMITDISALLOW	287
TCSETATTR	. 287
TERMASTQUOTA	. 287

TEXT
TIMEDHANDI ED
TIMENTANDER
TIMEROVFL
TIMRBADVAL
TLSCONNINFO
TLSCONVSOCK
TLSDLLNOOPEN
TLSHANDSHAKE
TLSINIT
TLSIOERROR
TLSPARAM
TLSRENEGOTIATE
TLVLZERO
TMPFILENOCRE
TMPSTOREMAX
TNTOOLARGE
TNWARN
TOOMANYCLIENTS
TOTALBLKMAX
TPFAIL
TPLOCK
TPLOCKRESTMAX
TPMIXUP
TPNOSUPPORT
TPNOTACID
TPQUIT
TPRESTART
TPRESTNESTERR
TPSTACKCRIT
TPSTACKOFLOW
TPTIMEOUT
TPTOODEEP
TRACEON
TRACEON
TRACEON 296 TRACINGON 296 TRANS2BIG 296
TRACEON       296         TRACINGON       296         TRANS2BIG       296         TRANSMINUS       296
TRACEON       296         TRACINGON       296         TRANS2BIG       296         TRANSMINUS       296         TRANSNEST       296
TRACEON       296         TRACINGON       296         TRANS2BIG       296         TRANSMINUS       296         TRANSNEST       296         TRANSNOSTART       297
TRACEON       296         TRACINGON       296         TRANS2BIG       296         TRANSMINUS       296         TRANSNEST       296         TRANSNOSTART       297         TRESTLOC       297
TRACEON       296         TRACINGON       296         TRANS2BIG       296         TRANSMINUS       296         TRANSNEST       296         TRANSNOSTART       297         TRESTLOC       297         TRESTMAX       297
TRACEON       296         TRACINGON       296         TRANS2BIG       296         TRANSMINUS       296         TRANSNEST       297         TRESTLOC       297         TRESTMAX       297         TRESTNOT       297
TRACEON       296         TRACINGON       296         TRANS2BIG       296         TRANSMINUS       296         TRANSNEST       296         TRANSNOSTART       297         TRESTLOC       297         TRESTMAX       297

TRIGDEFBAD	298
TRIGDEFNOSYNC	299
TRIGINVCHSET	299
TRIGIS	299
TRIGLOADFAIL	299
TRIGMODINTP	300
TRIGMODREGNOTRW	300
TRIGNAMBAD	300
TRIGNAMENF	300
TRIGNAMEUNIQ	301
TRIGNOSPANGBL	301
TRIGREPLSTATE	301
TRIGSUBSCRANGE	301
TRIGTCOMMIT	302
TRIGTLVLCHNG	302
TRIGUPBADLABEL 3	302
TRIGZBREAKREM	
TRNLOGFAIL	
TROLLBK2DEEP	
TRUNCATE	303
TRUNCATEFAIL	
TSTRTPARM	304
TTINVFILTER	304
TTLENGTHTOOBIG	304
TTWIDTHTOOBIG	304
TXTNEGLIN	304
TXTSRCFMT	305
TXTSRCMAT	305
UIDMSG	305
UIDSND	305
UNDEF	305
UNIMPLOP	306
UNKNOWNFOREX	306
UNSDCLASS	306
UNSDDTYPE	306
UNSOLCNTERR	307
UPDATEFILEOPEN	307
UPDPROC	307
UPDREPLSTATEOFF	307
UPDSYNC2MTINS	307
UPDSYNCINSTFILE	308
USRIOINIT	308
VALTOOBIG	308
VALTOOLONG	308
VALTOOSMALL	309
VALUERAD	309

VALUEREQD	309
VAREXPECTED	309
VARRECBLKSZ	309
VERIFY	310
VERMISMATCH	310
VERSION	310
VIEWAMBIG	310
VIEWARGCNT	310
VIEWCMD	
VIEWFN	311
VIEWGVN	
VIEWLVN	
VIEWNOTFOUND	
VMSMEMORY	
VMSMEMORY2	
WAITDSKSPACE	
WCBLOCKED	
WCERRNOTCHG	
WCFAIL	
WCWRNNOTCHG	
WEIRDSYSTIME •	
WIDTHTOOSMALL	
WILDCARD	
WRITEERROR	
WRITERSTUCK	
WRITEWAITPID	
XCVOIDRET	
XKILLCNTEXC	
XTRNRETSTR	
XTRNRETVAL	
XTRNTRANSDLL	
XTRNTRANSERR	
ZATTACHERR	
ZBREAKFAIL	
ZCALLTABLE	
ZCARGMSMTCH	
ZCCLNUPRTNMISNG	
ZCCOLON	
ZCCONNERT	
ZCCONVERT	
ZCCSQRBR	
ZCCTENV	
ZCCTNULLF	
ZCCTOPN	
ZCENTNAME	
ZCINPUTREQ	319

ZCINVALIDKEYWORD	319
ZCMAXPARAM	319
ZCMLTSTATUS	319
ZCNOPREALLOUTPAR	319
ZCOPT0	320
ZCPOSOVR	320
ZCPREALLNUMEX	320
ZCPREALLVALINV	320
ZCPREALLVALPAR	320
ZCRCALLNAME	321
ZCRPARMNAME	321
ZCRTENOTF	321
ZCRTNTYP	
ZCSTATUS	321
ZCSTATUSRET	322
ZCUNAVAIL	
ZCUNKMECH	322
ZCUNKQUAL	322
ZCUNKTYPE	
ZCUNTYPE	323
ZCUSRRTN	323
ZCVECTORINDX	323
ZCWRONGDESC	323
ZDATEBADDATE	. 323
ZDATEBADTIME	. 324
ZDATEFMT	324
ZDIROUTOFSYNC	. 324
ZEDFILSPEC	324
ZFF2MANY	325
ZFILENMTOOLONG	325
ZFILKEYBAD	325
ZFILNMBAD	325
ZGBLDIRACC	325
ZGOCALLOUTIN	326
ZGOTOINVLVL	326
ZGOTOINVLVL2	. 326
ZGOTOLTZERO	. 326
ZGOTOTOOBIG	. 326
ZINTDIRECT	327
ZINTRECURSEIO	327
ZLINKFILE	327
ZLKIDBADARG	327
ZLMODULE	328
ZLNOOBJECT	328
ZPARSETYPE	328
ZPARSFLDBAD	. 328
ZPEEKNOINI INFO	328

2	ZPEEKNORPLINFO	329
2	ZPIDBADARG	329
2	ZPRIVARGBAD	329
,	ZPRIVSYNTAXERR	329
,	ZPRTLABNOTFND	330
,	ZROSYNTAX	330
,	ZSETPRVARGBAD	330
2	ZSETPRVSYNTAX	330
	ZSHOWBADFUNC	
	ZSHOWGLOSMALL	
	ZSOCKETATTR	
2	ZSOCKETNOTSOCK	331
2	ZSRCHSTRMCT	331
2	ZSTEPARG	331
,	ZTRIGINVACT	332
7	ZTRIGNOTP	332
	ZTRIGNOTRW	
	ZTWORMHOLE2BIG	
	ZWRSPONE	
	age Categorization Index	
	ror Message Quick Reference	
	Standard Error Codes	
	ZMESSAGE Codes	
	ference Implementation Error messages	
	Cannot find DB keys file <path></path>	
	Cannot find MUMPS executable in <path></path>	
	Cannot open DB keys file - <path></path>	
	DB keys file of unknown file type : <path></path>	
	Database file <path> missing in DB keys file or does not exist</path>	
	Database file <path> not found</path>	
	Encryption handle corrupted	
	Encryption key file <path> not found</path>	
	Encryption library has not been initialized	
	Environment variable <environment_variable> not set</environment_variable>	
	Environment variable gtm_dbkeys set to empty string	
	Environment variable gtm_dbkeys undefined. Cannot find <path>/.gtm_dbkeys</path>	414
	Environment variable gtm_passwd set to empty string. Password prompting not allowed for	
	utilities	415
	Error initializing GpgME: <reason_for_error>/<specific_gpg_me_error></specific_gpg_me_error></reason_for_error>	415
	Error parsing database key file. At line <li>line_number&gt;: No matching 'dat' entry found in</li>	
	<contents_of_line></contents_of_line>	415
	Error parsing database key file. At line <li>line_number&gt;: <li>line_contents&gt; does not start with</li></li>	415
	'dat' / 'key'	415
	Error parsing database key file. At line <li>line_number&gt;: No matching 'key' entry found in</li>	44.
	<contents_of_line></contents_of_line>	
	Incorrect password	
	libgcrypt version mismatch. Expected <expected_version>, found <found_version></found_version></expected_version>	416

Matching encryption key <hash> not found in database key file</hash>	416
No entries found in DB keys file	416
Symmetric key <path> found to be empty</path>	416

FIS V6.2-002

# **About This Manual**

The GT.M Message and Recovery Procedures Reference Manual describes the meaning of messages issued by GT.M components, including the M compiler, the run-time system, and utility programs. It serves OpenVMS and UNIX versions of GT.M.

This manual is organized alphabetically according to the message identifier. The meaning of each message is provided as well as suggestions for locating and addressing the cause of error-type messages.

#### **Intended Audience**

This manual is for programmers and system managers who use GT.M.

# Purpose of the Manual

The GT.M Message and Recovery Procedures Reference Manual helps you understand and act on GT.M messages. This manual complements the other GT.M manuals.

# How to Use This Manual

The GT.M Message and Recovery Procedures Reference Manual is intended to be used primarily to determine the nature of a message and interpret its meaning. Therefore, Messages are listed in alphabetical order, according to the mnemonic that precedes them. Cross references to additional information are provided in individual entries, as appropriate. The manual does not include a table of contents or index.

## **Conventions Used in This Manual**

References to other GT.M documents are implemented as relative hypertext links to PDF files in the same directory. These links work correctly in a browser that uses a plug-in component to display PDF files. For example, for Firefox you could use MozPlugger to plug in the Evince PDF reader. The links also work correctly offline if you download all related GT.M documents to the same local directory.

GT.M messages are identified by a signature of the form GTM-s-abcdef where -s- is a severity indicator and abcdef is an identifier. The severity indicators are: -I- for informational messages, -W- for warnings, -E- for errors and -F- for events that cause a GT.M process to terminate abnormally. For more information on monitoring GT.M messages, refer to "Appendix B: Monitoring GT.M Messages" in the Administration and Operations Guide.

Each entry in this manual is presented in the following format as illustrated by the NOPRINCIO message.

## 1. NOTPRINCIO

- 2. NOTPRINCIO, Output currently directed to device xxxx
- 3. Run Time Warning: This message displays the current device when the process enters Direct Mode and the current device xxxx is not the principal device.
- 4. Action: To redirect all I/O to the terminal, note the current device or save it in a temporary variable and USE \$P. If you decide to resume program execution, restore the current device with a USE command.

#### where

- 1. Indicates the unique mnemonic preceding the error message and is the component by which the entry is alphabetized.
- 2. Indicates the mnemonic and the actual message that accompanies it.
- 3. Indicates the GT.M component that generates the message, its severity, and a short description of its implication(s).
- 4. Suggests action(s) to take when the message appears.

This manual can be used with GT.M on any of its supported platforms. However, because in some instances the suggested actions are more useful when platform-specific information is provided, the following conventions are used, as necessary.

<u>UNIX</u>: The term UNIX is used here in the general sense of all platforms for which GT.M uses a POSIX API. As of this date, this includes: AIX; HP-UX on IA64 and PA-RISC; GNU/Linux on IA64, x86 and x86 64; Solaris on SPARC; z/OS.

<u>Platform Identifier</u>: If an entire statement is either UNIX- or OpenVMS- specific, it is preceded by the phrase "In UNIX," or "In OpenVMS,". The following example illustrates this convention. Action: In OpenVMS, relink your image to include the missing routine. In UNIX, relink your external call descriptor image to include the missing routine.

If a phrase or word is either UNIX- or OpenVMS- specific, it is suffixed by "(UNIX)" or "(VMS)". The following examples illustrates this convention.

Run Time Error: Strings longer than 32,767 (UNIX) or 65,535 (OpenVMS) bytes have been used with alternative collation and only gtm\_ac\_xform and gtm\_ac\_xback are defined in the collation library.

Compile Time Error: This indicates that translation of the indicated environment variable (UNIX) or logical name (OpenVMS) failed. Examine the accompanying message to find out the failure type and the reason of the error.

Although the terms "host shell command" and "file-specification" have some platform-specification connotations, they are used in their most generic sense throughout this manual. The former describes commands that originate from the host operating system, rather than from GT.M. The latter may refer to a simple file name or a full directory path to that file.

Henceforth, the term "originating instance" is used where previously "primary instance" or "originating primary instance" were used, and the term "replicating instance" is used where previously "secondary

instance" and "originating secondary instance" were used. Since it is easier to change documentation than it is to change software, and given our tradition of maintaining compatibility especially for existing programs and scripts, the former terms will remain in the software for a long time to come, even as they are supplemented with the new terms in the code, and replaced in the documentation.

We have changed the terminology because "initiating" and "replicating" describe roles that currently exist and will continue to exist as GT.M evolves, while "primary" and "secondary" are both more and less precise and will become less useful as we add capabilities to GT.M. An "initiating instance" is always the instance that first records a transaction (including non-TP mini-transactions). A "replicating instance" is always following the action of an "originating instance", previously called "root primary". We have called secondaries that replicate propagating primaries, but they are not originating instances.

The circle-shaped icon (②) with the "+" sign denotes messages that newly introduced in or since the last major release.

The octagon-shaped icon ( ) with the "-" sign denotes deprecated messages.

The square-shaped icon  $(\Delta)$  with the delta symbol denotes messages revised in or since the last major release.

At a major release, square-shaped and circle-shaped icons of and since the preceding major release are removed.

# Following Up on Suggested Actions

When the suggested action is to "Report the error to the group responsible for database integrity at your operation," you may also refer to the Maintaining Database Integrity chapter in the Administration and Operations Guide.

For information about utility-generated messages, refer to the chapter that describes that utility in the Administration and Operations Guide.

The OpenVMS edition of GT.M uses the OpenVMS standard message facility as well as other OpenVMS system components. Therefore, some errors issued by GT.M originate in OpenVMS and are described in this manual.

#### MUPIP LOAD Errors

If a MUPIP LOAD error occurs, ensure that the proper media is loaded and that the command input includes the proper file-specification.

If the input file is FORMAT=GO or ZWR, the database should contain the correct content to the point where the failure occurred and should be usable. You can edit and possibly correct the input file.

If the input file is FORMAT=BIN, the database is probably corrupt. Fix the database intergrity issues and EXTRACT the file again.

For more information on LOAD and EXTRACT, refer to the General Database Management chapter in the Administration and Operations Guide.

V6.2-002 MR Manual June 09, 2015, Page liii About This Manual Plug-in Errors

For information on salvaging damaged extracts, refer to the *Maintaining Database Integrity* chapter in the Administration and Operations Guide.

For details on the internals of spanning nodes, refer to the *GT.M Database Structure (GDS)* chapter in the Administration and Operations Guide.

# **Plug-in Errors**

GT.M's plug-in architecture allows you to choose your preferred encryption software. Some plugin errors that you may encounter are as follows:

# Database file <path> not found

Plugin error: The plugin is unable to find the specified database file.

Action: Verify that the database file exists, the corresponding entry in the master key file points to the database file, and appropriate authorizations exist in the directory path and the database file.

## **Encryption handle corrupted**

Plugin error: The plugin detected an internal error.

Action: This error indicates that there is a communication error between GT.M and the gtmcrypt plugin. Replace the process with undamaged one. Report the entire incident context to your GT.M support channel.

## Encryption key file <path> not found

Plugin error: The plugin was not able to find the key file on the specified path.

Action: Verify that the master key file entry for this key file points to the correct path. Verify that the key file itself exists. Verify proper authorizations on directory path and file.

#### Encryption library has not been initialized

Plugin error: A gtmcrypt function was called before gtmcrypt\_init().

Action: Call gtmcrypt init() before calling any other encryption functions.

For more information on the plug-in errors and their fixes, see the documentation of your preferred encryption software.

Appendix B: Reference Implementation Error messages lists some errors that the GT.M team encountered while testing GT.M's plug-in architecture with GNU Privacy Guard, the widely available implementation of Pretty Good Privacy (see "PGP: Pretty Good Privacy" by Simson Garfinkel).

#### MUPIP INTEG Errors

Database errors reported by MUPIP INTEG differ in impact and severity. Some require an immediate action to prevent extending the damage, action on other less severe errors may be delayed.

FIS V6.2-002

**MUPIP INTEG Errors About This Manual** 

The following table outlines the MUPIP INTEG error messages with their severity using the codes as listed below:

A	Access: Prevents database access
В	Benign: Presents no risk of additional damage and has little or no effect on database performance
D	Dangerous: Presents a high risk that continuing updates may cause significant additional damage
I	Index: If the block is an index block, continuing updates will be quite dangerous: treat as a D; if the block is a datablock, continuing updates can only cause limited additional damage
T	Transient: Usually cleared by an update to the database

MUPIP INTEG Error Messages				
Error Name	Message	Severity	Section*	
DBBADKYNM	Bad Kay Name	I	K1	
DBBADNSUB	Bad numeric subscript	I	K1	
DBBADPNTR	Bad pointer value in directory	D	K4	
DBBDBALLOC	Block doubly allocated	D	K3	
DBBFSTAT	Block busy/free status unknown (local bitmap corrupted)	D	M1	
DBBNPNTR	Bit map block number as pointer	D	K4	
DBBPLMGT2K	Blocks per local map is greater than 2K	D	I3	
DBBPLMLT512	Blocks per local map is less than 512	D	I3	
DBBPLNOT512	Blocks per local map is not 512	D	I3	
DBBSIZZRO	Block size equals zero	A	I3	
DBCOMPTOOLRG	Record has too large compression count	I	O2	
DBDATAMX	Record too large	В	O5	
DBFGTBC	File size larger than block count would indicate	В	I4	
DBFSTBC	File size smaller than block count would indicate	D	I4	
DBFSTHEAD	File smaller than database header	A	I3	
DBGTDBMAX	Key larger than database maximum	I	K7	

Section\*: Refers to the specified section in Managing Database Integrity chapter of Administration and Operations Guide. The section details a description along with the action item to be taken on encountering the error message.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page lv **About This Manual MUPIP INTEG Errors** 

MUPIP INTEG Erro	r Messages		
Error Name	Message	Severity	Section*
DBHEADINV	Header size not valid for database	A	I3
DBINCLVL	Block at incorrect level	D	O1
DBINCRVER	Incorrect version of GT.M database	A	I2
DBINVGBL	Invalid mixing of global names	D	K3
DBKEYGTIND	Key greater than index key	I or B	K2 or O5
DBKGTALLW	Key larger than maximum allowed length	I	K1
DBLOCMBINC	Local bit map incorrect	В	M1
DBLRCINVSZ	Last record of block has invalid size	I	K5
DBLTSIBL	Key less than sibling's index key	I	K2
DBLVLINC	Local map block level incorrect	В	M2
DBMAXKEYEXC	Maximum key size for database exceeds design maximum	D	I3
DBMAXRSEXBL	Maximum record size for database exceeds what the block size can support	D	I3
DBMBMINCFREZ	Master bit map incorrectly asserts this local map has free space	В	M1
DBMBPFLDIS	Master bit map shows this map full, in disagreement with both disk and INTEG results	В	M1
DBMBPFLDLBM	Master bit map shows this map full, agreeing with disk local map	В	M1
DBMBPFLINT	Master bit map shows this map full, agreeing with MUPIP INTEG	В	M1
DBMBPFRDLBM	Master bit map shows this map has space, agreeing with disk local map	В	M1
DBMBPFRINT	Master bit map shows this map has space, agreeing with MUPIP INTEG	В	M1
DBMBPINCFL	Master bit map incorrectly marks this local map full	В	M1
DBMBSIZMN	Map block too small	В	M2

Section\*: Refers to the specified section in Managing Database Integrity chapter of Administration and Operations Guide. The section details a description along with the action item to be taken on encountering the error message.

MUPIP INTEG Errors About This Manual

MUPIP INTEG Error Messages				
Error Name	Message	Severity	Section*	
DBMBSIZMX	Map block too large	В	M2	
DBMBTNSIZMX	Map block transaction number too large	Т	I6	
DBMRKBUSY	Block incorrectly marked busy	В	M1	
DBMRKFREE	Block incorrectly marked free	D	M1	
DBMXRSEXCMIN	Maximum record size for database is less than the design minimum	D	I3	
DBNOTDB	File does not have a valid GDS file header	A	I3	
DBNOTMLTP	Block size not a multiple of 512 bytes	A	I3	
DBRBNLBMN	Root block number is a local bit map number	D	K4	
DBRBNNEG	Root block number negative	D	K4	
DBRBNTOOLRG	Root block number greater than last block number in file	D	K4	
DBREADBM	Read error on bitmap	D	H7	
DBRLEVLTONE	Root level less than one	D	O1	
DBRLEVTOOHI	Root level higher than maximum	D	O1	
DBSPANCHUNKORD	Chunk of blocks is out of order	В	O5	
DBSPANGLOINCMP	Spanning node is missing	В	O5	
DBSVBNMIN	Start VBN smaller than possible	A	I3	
DBSZGT64K	Block size is greater than 64K	A	I3	
DBTNNEQ	Current tn and early tn are not equal	Т	I6	
DBTNTOOLG	Block transaction number too large	Т	I6	
DBTTLBLK0	Total blocks equal zero	A	I4	
DBUNDACCMT	Cannot determine access method; trying with BG	Т	I6	

Section\*: Refers to the specified section in *Managing Database Integrity* chapter of Administration and Operations Guide. The section details a description along with the action item to be taken on encountering the error message.

MR Manual V6.2-002
GT.M Message and Recovery Procedures Manual June 09, 2015, Page lvii

This page is intentionally left blank.

MR Manual FIS GT.M Message and Recovery Procedures Manual

# **Chapter 1. Error Messages**

#### **ABNCOMPTINC**

**ABNCOMPTINC**, Deviceparameter xxxx and deviceparameter yyyy are not compatible in the zzzz command

Compile Time Error: The command specifies incompatible deviceparameters (e.g., specifying both FIXED and VARIABLE).

Action: Refer to the Chapter 9 Input Output Processing in the Programmer's Guide and modify the list.

# **ACOMPTBINC**

ACOMPTBINC, Deviceparameter xxxx is compatible with only yyyy in the command zzzz

Run Time Error: An OPEN, USE, or CLOSE command specifies a deviceparameter that does not apply to the command.

Action: Look for deviceparameters that should be on other I/O commands. For example, the deviceparameter DELETE is valid on CLOSE but produces this error if it is applied to the USE command.

#### **ACTCOLLMISMTCH**

**ACTCOLLMISMTCH**, Global ^gggg inherits alternative collation sequence #nnnn from global directory but database file dddd contains different collation sequence #mmmm for this global

Run Time Error: This indicates that the global gggg inherits collation nnnn from the global directory (globals that span multiple regions inherit collation 0 by default) but the directory tree in database file dddd contains a different collation sequence mmmm for this global.

Action: If nnnn is the right collation sequence to use, fix the database file dddd by using a temporary global directory that maps all names to dddd, extract the global, KILL it, use \$\$set^%GBLDEF to fix the alternative collation for gggg from mmmm to nnnn, reload the global from the extract, switch back to the regular global directory. If mmmm is the right collation sequence to use, recreate the global directory and define GBLNAME gggg to have that collation instead.

## **ACTIVATEFAIL**

**ACTIVATEFAIL**, Cannot activate passive source server on instance iiii while a receiver server and/or update process is running

MUPIP Error: MUPIP REPLIC -SOURCE -ACTIVATE -ROOTPRIMARY (or -UPDOK) issues this error when the command attempts to activate a passive source server (and switch the instance from being a

replicating secondary instance to an originating primary) while a receiver server and/or update process is already running

Action: Shutdown the receiver and/or update process and reissue the MUPIP REPLIC -SOURCE - ACTIVATE -ROOTPRIMARY (or -UPDOK) command. Note that any other GT.M or MUPIP process that was running before the activation does not need to be shut down for the activation to succeed.

#### **ACTLSTEXP**

Last used version: V5.4-002B

# ACTLSTEXP, Actuallist expected

Run Time Error: This indicates that the DO command, without an actuallist of parameters, failed because its entryref argument specified a label that has a formallist of parameters.

Action: Review the interface between the DO and the subroutine. Add the actuallist to the DO, remove the formallist from the label, or identify another subroutine to invoke, as appropriate.

## **ACTLSTTOOLONG**

ACTLSTTOOLONG, More actual parameters than formal parameters: xxxx

Compile Time/Run Time Error: This indicates that the label xxxx with a formallist; is invoked from within a routine with a longer actuallist (during compile-time). At run-time, a similar error can occur when a longer actuallist is supplied by an invocation from another routine.

Action: Review the interface between the DO command and the subroutine. Modify the actuallist, formallist, and/or label, as appropriate.

## **ACTOFFSET**

ACTOFFSET, Actuallist not allowed with offset

Compile Time Error: This indicates that a DO command or extrinsic specified an actuallist and an entryref that includes an offset.

Action: Look for an inappropriate offset.

#### **ACTRANGE**

**ACTRANGE**, Alternate Collating Type xxxx is out of range

Run Time Error: The alternate collation sequence type does not fall in the expected range of 0 to 255.

Action: Define a new collation sequence type that has a value between 0 and 255 inclusive. For more information, refer the "Internationalization" chapter of the Programmer's Guide.

FIS V6.2-002

#### **ADDRTOOLONG**

ADDRTOOLONG, Socket address xxxx of length aaaa is longer than the maximum permissible length bbbb

Run Time Error: This indicates that the address value supplied with the CONNECT or LISTEN deviceparameters exceeds the maximum acceptable length.

Action: Examine the value and shorten the length of the address value.

#### **AIMGBLKFAIL**

AIMGBLKFAIL, AIMGBLKFAIL, After image build for block bbbb in region rrrr failed in DSE or **MUPIP** 

GT.CM/DSE/MUPIP Error: MUPIP/DSE/GT.CM Error: DSE creates after images of blocks as a result of its physical manipulation of blocks and in MUPIP processes them in the course of RECOVER or ROLLBACK. This error indicates that such a manipulation failed on the block and region indicated.

Action: Action: If you get this error from DSE, you may be working with a block with a damaged state that your DSE action does not sufficiently address - analyze the situation and consider other approaches. If you get this error from MUPIP, it may mean your journal or replication has damage, in which case you should investigate the state of block bbbb.

## **ALIASEXPECTED**

Last used version: V4.4-000

**ALIASEXPECTED**, Alias or alias container variable expected in this context

Compile Time/Run Time Error: This indicates the argument for a SET \* or KILL \* command used a nonalias local variable where the syntax requires an alias or alias container variable.

Action: Correct the code in or investigate the logic to determine why the local variable in question is not in the expected state.

### **AMBISYIPARAM**

AMBISYIPARAM, Parameter xxxx is ambiguous to \$ZGETSYI()

Run Time Error: This indicates that the argument xxxx is ambiguous to \$ZGETSYI() because it does not have enough characters.

Action: Add enough characters to make the argument unambiguous.

V6.2-002 MR Manual

## **ANCOMPTINC**

**ANCOMPTINC**, Deviceparameter xxxx is not compatible with any other deviceparameters in the yyyy command

Compile Time Error: This indicates that the specified deviceparameter can only be used by itself.

Action: Remove conflicting deviceparameters from the command.

## **ARCTLMAXHIGH**

**ARCTLMAXHIGH**, The environment variable XXXX = YYYY is too high. Assuming the maximum acceptable value of ZZZZ

Run Time Warning: The environment variable named XXXX that controls the maximum number of auto-relink routine entries is assigned a value (YYYY) that is too high. MUMPS will set maximum routine count to ZZZZ and continue normal operation.

Action: Please set environment variable XXXX to a value between 1,000 and 16,000,000.

# **ARCTLMAXLOW**

**ARCTLMAXLOW**, The environment variable XXXX = YYYY is too low. Assuming the minimum acceptable value of ZZZZ

Run Time Warning: The environment variable named XXXX that controls the maximum number of auto-relink routine entries is assigned a value (YYYY) that is too low. MUMPS will set maximum routine count to ZZZZ and continue normal operation.

Action: Please set environment variable XXXX to a value between 1,000 and 16,000,000.

## **ARROWNTDSP**

ARROWNTDSP, Unable to display ^----- due to length of source line

Compile Time Error: Displayed instead of the arrow indicating where compilation error occurred due to a long line source line.

Action: Refer to the source code. the line number and column number in the associated messages identify the position of the problem. Consider shortening the line, at least until the error is found and corrected.

## **ASSERT**

**ASSERT**, Assert failed xxxx line yyyy

Run Time Error: An internal GT.M consistency check failed. This error occurs only in some special versions of GT.M software.

Action: Report the entire incident context to your GT.M support channel.

## **BACKUPCTRL**

BACKUPCTRL, Control Y or control C encountered during backup, aborting backup

MUPIP Warning: This indicates that BACKUP terminated because of an operator <CTRL>-C or <CTRL>-Y.

Action: Do not rely on the result of this BACKUP. If appropriate, investigate whether any of the BACKUP output files are complete and therefore potentially useable.

#### **BACKUPKILLIP**

BACKUPKILLIP, Kill in progress indicator is set for file ffff, backup database could have incorrectly marked busy integrity errors

MUPIP Warning: This indicates that one or more active process are performing KILL cleanup in database file ffff. Generally, BACKUP can wait for this to finish in order to get a consistent copy of the database. However, this indicates it waited several minute and is proceeding The resulting backup almost surely contains blocks incorrectly marked busy.

Action: Wait and perform the BACKUP when there are no large KILL operations triggering extensive cleanup. If this is not desirable, fix the errors in the backup copy (reported by an INTEG NOMAP) with DSE MAP FREE. If there are many such blocks you can edit the INTEG output to create a script to drive the DSE operations. Alternatively, if you can get standalone access, to the database you may use DSE MAP RESTORE. Do not use MAP RESTORE on an active database.

# **BADACCMTHD**

BADACCMTHD, Invalid access method was specified, file not created

MUPIP Warning: This indicates that CREATE encountered an invalid access method for the dynamic segment in the current Global Directory, which is defined by the logical name GTM\$GBLDIR / environment variable gtmgbldir.

Action: Use the Global Directory Editor (GDE) to verify the access method for the Global Directory. Look for the use of GT.M components with different version numbers.

#### **BADCASECODE**

**BADCASECODE**, xxxx is not a valid case conversion code.

V6.2-002 MR Manual June 09, 2015, Page 5 Run Time Error: The two-argument form of \$ZCONVERT() reports this error if the case conversion specifier (second argument) is not one of the valid codes (U,u,L,l,T and t).

Action: Choose a valid case designation code.

### **BADCHAR**

**BADCHAR**, XXX is not a valid character in the YYY encoding form.

Run Time Error: GT.M triggers this error when it encounters a byte sequence that is not legal according to the given character set of the current device.

Action: Correct your application or its configuration to handle this situation. Depending on application requirements, the code may need handle the illegal byte sequence or disable the triggering of BADCHAR error by VIEW "NOBADCHAR" command. If the error is from a READ or WRITE command to a device other than \$PRINCIPAL, the application can perform I/O in M-mode and then handle any needed conversion, correction, or other manipulation. For more information, refer to ther Programmer's Guide.

## **BADCHSET**

**BADCHSET**, xxxx is not a valid character mapping in this context.

Run Time Error: When GT.M recognizes that the expr in ICHSET=expr or OCHSET=expr is not one of the supported character set names ("M", "UTF-8", "UTF-16", "UTF-16LE" or "UTF-16BE"), it reports this error. Note that not all modes are supported under all conditions.

Action: Choose the proper designation for a supported character set.

#### **BADDBVER**

BADDBVER, Incorrect database version: xxxx

Run Time Error: This indicates that the database version is not compatible with the current GT.M version.

Action: Upgrade the database. For more information, refer to the release notes for the current GT.M version and any intervening versions back to the last prior version used.

## **BADGBLSECVER**

BADGBLSECVER, Global section xxxx does not match the current database version

Run Time Error: In attempting to startup a database file, GT.M encountered a shared memory section containing a database version older than the current database version.

FIS V6.2-002

Action: Do not attempt to access the same database files simultaneously with different versions of GT.M. Perform a MUPIP RUNDOWN with the prior version of database existing in the shared memory section. If needed, contact your system administrator for help.

#### BADGTMNETMSG

BADGTMNETMSG, Invalid message sent to GT.CM server, type: xxxx

GT.CM Error: The GT.CM Server received an invalid message. Possible causes include an undetected network error, a message originating from a process that is inappropriately intruding on the GT.CM environment, or a protocol failure in a legitimate process.

Action: Retry the action that resulted in the error notification. If the problem persists, contact the group responsible for database operations on your network.

# **BADIPIPARAM**

**BADJPIPARAM**, xxxx is not a legal parameter for \$ZGETJPI()

Run Time Error: This indicates that the argument xxxx is not a valid keyword for \$ZGETJPI().

Action: Refer to the Programmer's Guide for correct keyword usage.

# **BADLKIPARAM**

**BADLKIPARAM**, xxxx is not a legal parameter for \$ZGETLKI()

Run Time Error: This indicates that the argument xxxx is not a valid keyword for \$ZGETLKI().

Action: Refer to the Programmer's Guide for correct keyword usage.

# **BADQUAL**

BADQUAL, Unrecognized qualifier: xxxx

Run Time Error: This indicates that a SET of \$ZROUTINES specified xxxx, which is an unknown qualifier.

Action: Use an accepted qualifier: SRC= or NOSRC.

## **BADREGION**

**BADREGION**, Region is not BG, MM, or CM

LKE Error: The current global directory attempted to map a region with an access method other than those listed.

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 7 Action: Use LKE only with database mapped to one of the listed database access methods.

## **BADSRVRNETMSG**

**BADSRVRNETMSG**, Invalid message received from GT.CM server

Run Time Error: This indicates that a GT.M process received an invalid message. Possible causes include an undetected network error, a message originating from a process that is inappropriately intruding on the GT.CM environment, or a protocol failure in a legitimate process.

Action: Retry the action that resulted in the notification error. If the problem persists, contact the group responsible for database operations on your network. Stop and restart the server to attempt to resolve the problem.

## **BADSYIPARAM**

**BADSYIPARAM**, xxxx is not a legal parameter to \$ZGETSYI()

Run Time Error: This indicates that the argument xxxx for \$ZGETSYI() is not a valid keyword.

Action: Refer to the Programmer's Guide for correct keyword usage.

### **BADTAG**

BADTAG, BADTAG Unable to use file ffff (CCSID tttt) with CCSID uuuu

Run Time Error: This z/OS specific error indicates the device or file ffff had a tag tttt incompatible with the tag uuuu implied by chset associated with OPEN command.

Action: Change the [i/o]chset to match the device or file, or use iconv to convert the file to an appropriate character set, or possibly use chtag to [re]tag the file.

#### **BADTRNPARAM**

BADTRNPARAM, xxxx is not a legal parameter to \$ZTRNLNM

Run Time Error: This indicates that the argument xxxx for \$ZTRNLNM() is not a valid keyword.

Action: Refer to the Programmer's Guide for correct keyword usage.

#### **BADZPEEKARG**

BADZPEEKARG, Missing, invalid or surplus xxxx parameter for \$ZPEEK()

Run Time Error: One of the parameters specified to \$ZPEEK() is incorrect. Possible values of xxxx:

• mnemonic type - The mnemonic in the first argument is unknown.

FIS V6.2-002 GT.M Message and Recovery Procedures Manual BADZPEEKFMT Chapter 1. Error Messages

• mnemonic argument - An argument for the given mnemonic (specified after a ":" character) is expected and missing, is present and unexpected, or not in its proper form.

- mnemonic argument (region name) Expected a region name argument which is either missing or not available.
- mnemonic argument (array index) Expected a numeric array index argument which is either missing or out of range.
- mnemonic argument (peek base address) Expected an address in the form 0xHHHHHHHH... which is either missing or invalid.
- offset Expected non-negative numeric value which is either missing or invalid.
- length Expected non-negative numeric value which is either missing or invalid.
- format Expected a single character format code which is either missing or invalid.

Action: Review the invocation and correct the defective parameter.

## **BADZPEKEMT**

BADZPEEKFMT, \$ZPEEK() value length inappropriate for selected format

Run Time Error: The format code specified is not valid for the length specified. For example, format code 'I' works with 1, 2, 4, and 8 byte fields. A field length of 3 would raise this error.

Action: Review the invocation and correct the defective length and/or format character.

#### **BADZPEEKRANGE**

BADZPEEKRANGE, Access exception raised in memory range given to \$ZPEEK()

Run Time Error: Some combination of base address, offset, length and/or alignment caused GT.M to raise a memory access exception when fetching the requested value.

Action: Review the invocation and correct the defective parameter.

# **BCKUPBUFLUSH**

BCKUPBUFLUSH, Unable to flush buffer for online backup

MUPIP Error: This indicates that the online BACKUP was unable to flush the buffer data to disk. The most likely cause is that MUPIP does not have write access to the database file.

Action: Run the BACKUP from a process with write authorization, or wait until other processes have completed the buffer flush. MUPIP sets the repair flag if there is a serious problem. Run a MUPIP INTEG using the FA[ST] qualifier to reset this flag. Report to your System Administrator.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 9

## **BEGINST**

**BEGINST**, Beginning LOAD at record number: xxxx

MUPIP Information: This indicates that the LOAD command with the FORMAT=BINARY qualifier started with record number xxxx.

Action: -

# **BEGSEQGTENDSEQ**

BEGSEQGTENDSEQ, Journal file xxxx has beginning sequence number aaaa greater than end sequence number bbbb

MUPIP Error: This indicates that the beginning sequence number aaaa of the journal file xxxx is greater than end sequence number bbbb.

Action: Report the entire incident context with appropriate log messages to your GT.M support channel.

# **BFRQUALREQ**

BFRQUALREQ, The [NO]BEFORE qualifier is required for this command

MUPIP Error: Any MUPIP SET command with JOURNAL=ON must specify either BEFORE IMAGE or NOBEFORE\_IMAGE journaling.

Action: Add the argument and select either BEFORE\_IMAGE or NOBEFORE\_IMAGE journaling for the database in question.

#### **BIGNOACL**

BIGNOACL, Existing file found when BIGRECORD specified with UDF format but no GT.M ACE, perhaps lost during COPY

Run Time Error: An existing file with an RMS record format of undefined (UDF) was opened by an OPEN command with a BIGRECORD parameter but no Access Control Entry containing information GT.M needs to access the file. The ACE may have been lost when copying such a file with the OpenVMS DCL COPY command.

Action: BIGRECORD format files should always be copied using the OpenVMS DCL BACKUP command which preserves the Access Control Entries on files. If the record format (VARIABLE or FIXED) and RECORDSIZE specified when creating the file are known, the ACE can be restored using the following OpenVMS DCL command: SET SECURITY <filename.ext>/ACL=(APPLICATION,SIZE=20,FLAGS=%X0A01,ACCESS=%X00F60001,DATA= %X424D5447,<format>,<recordsize>) Replacing "<filename.ext>" by the name of the file, "<format>" by "2" if the format is VARIABLE or "1" if FIXED, and "<recordsize>" by the RECORDSIZE originally specified.

#### **BINHDR**

BINHDR, gggg Date: dddd TIME: tttt Extract Region Characteristics rrrr Blk Size: xxxx Rec Size: yyyy Key Size: kkkk

MUPIP Information: This message displays header information for a binary format file. gggg is the global loaded. dddd is the date on which the region was extracted. tttt is the time when the region was extracted. rrrr is the region that contains the global. xxxx is the block size specified for the region. yvyy is the record size specified for the block. kkkk is the key size specified for the record.

Action: -

#### **BITMAPSBAD**

BITMAPSBAD, Database bit maps are incorrect

Run Time Error: This indicates that a database operation encountered a corrupt bit map.

Action: GT.M uses bit maps in database files to determine whether a block is free or in use. Report this database structure error to the group responsible for database integrity at your operation.

#### **BKUPRUNNING**

**BKUPRUNNING**, Process dddd is currently backing up region xxxx. Cannot start another backup.

MUPIP Error: MUPIP BACKUP -ONLINE only supports one backup at a time and this error indicates an attempt to start one before a previously started backup finished.

Action: Cancel the running BACKUP or reschedule this BACKUP to a time after the running BACKUP completes.

#### **BKUPTMPFILOPEN**

BKUPTMPFILOPEN, Open of backup temporary file aaaa failed

Run Time Error: When an online backup is in progress, a GT.M process doing updates to the database is saving away the pre-update images of the blocks it updates in a special backup area used to make sure the backups are consistent. Periodically, these blocks need to be flushed out to a temporary file and are flushed by the process needing the space to put its own changed blocks. This means every running process needs to have R/W access to the temporary file created by the backup. If the process cannot open the temporary file, this error is written to the operator log, the backup is flagged as having encountered an error and the process proceeds. So this error is only backup related. It is NOT an error in the process itself which proceeds as if backup were not running.

Action: Determine cause of why process could not open temporary file, fix, and restart backup.

V6.2-002 MR Manual June 09, 2015, Page 11

# **BKUPTMPFILWRITE**

**BKUPTMPFILWRITE**, Write to backup temporary file aaaa failed

Run Time Error: When an online backup is in progress, a GT.M process doing updates to the database is saving away the pre-update images of the blocks it updates in a special backup area used to make sure the backups are consistent. Periodically, these blocks need to be flushed out to a temporary file and are flushed by the process needing the space to put its own changed blocks. This means every running process needs to have R/W access to the temporary file created by the backup. If the database write generates an error, the BKUPTFWFAIL error is written to the operator log, the backup is flagged as having encountered an error and the process proceeds. So this error is only backup related. It is NOT an error in the process itself which proceeds as if backup were not running.

Action: Determine cause of why the write failed, fix, and restart backup.

#### **BLKCNT**

Last used version: V4.4-000

BLKCNT, Last LOAD Block/RMS Record number: xxxx

MUPIP Information: This indicates that a LOAD command with the FORMAT=BINARY qualifier completed at record number xxxx. Indicates the last block or record number successfully processed by MUPIP LOAD. This information may be useful for auditing the LOAD, or if a restart is required after a LOAD is stopped prematurely.

Action: -

## **BLKCNTEDITFAIL**

Last used version: V4.4-000

BLKCNTEDITFAIL, MUPIP recover or rollback failed to correct the block count field in the file header for file xxxx

GDE/DSE Information: This indicates that rollback should correct the block count field in the file header. This message is an informational message issued by Recovery/Rollback process and no action is required. This error is benign.

Action: -

## **BLKINVALID**

BLKINVALID, BLKINVALID, bbbb is not a valid block as database file ffff has nnnn total blocks

DSE Error: DSE Error: The block (bbbb) you selected is not currently a valid block in the database file (ffff) for the region in which you are working.

Action: Action: Select a block less than nnnn or move to a different region

## BLKSIZ512

BLKSIZ512, Block size xxxx rounds to yyyy

GDE/DSE Information: This indicates that an ADD, CHANGE, or TEMPLATE command defined the BLOCKSIZE qualifier equal to xxxx, which is not divisible by 512. GDE adjusted the block size to yyyy, which is the next largest multiple of 512.

Action: If yyyy is not acceptable, modify the BLOCKSIZE qualifier value so that it is divisible by 512.

# **BLKTOODEEP**

**BLKTOODEEP**, Block level too deep

Compile Time Error: This indicates that the line starts with too many level-indicator delimiters (.) for the level of nesting associated with the argumentless DO on the previous line.

Action: Remove inappropriate level indicator(s).

# **BLKWRITERR**

**BLKWRITERR**, Unable to queue disk write for block XXXX. Will keep trying.

Run Time Information: This indicates that the disk is offline or not working because of a hardware or software problem in the disk subsystem.

Action: Check the disk subsystem operation.

#### **BOMMISMATCH**

**BOMMISMATCH**, XXX Byte Order Marker found when YYY character set specified.

Run Time Error: A Byte Order Marker (BOM) for character set XXX was found at the beginning of a file specified as containing data in character set YYY.

Action: Specify the proper character set when opening the file. For UTF-16 data, specifying CHSET="UTF-16" will use the BOM to determine whether the data is Little Endian or Big Endian. If no BOM is found, GT.M assumes Big Endian.

#### **BOOLSIDEFFECT**

BOOLSIDEFFECT, Extrinsic (\$\$), External call (\$&) or \$INCREMENT() with potential side effects in Boolean expression

V6.2-002 MR Manual June 09, 2015, Page 13 Compile Time Warning: This optional message, accompanied by a line and column pointing to the issue, indicates a Boolean expression that contains a side effect in a term other than its first. By default, GT.M may skip evaluating such terms.

Action: Revise the code to your standards and use the VIEW (arguments [NO]FULL BOOLEAN or FULLBOOL WARN) command and / or the environment variable (gtm boolean) to select the appropriate setting for GT.M handling of this construct.

#### **BOVTMGTEOVTM**

BOVTMGTEOVTM, Journal file xxxx has beginning timestamp aaaa greater than end timestamp bbbb

MUPIP Error: This indicates that the beginning time stamp aaaa of the journal file xxxx is greater than the ending timestamp bbbb. This could be due to something that changed the system time while journaling was going on.

Action: Changing system time during GT.M Run-time is not allowed. Contact your GT.M support channel for further assistance.

#### **BOVTNGTFOVTN**

**BOVTNGTEOVTN**, Journal file xxxx has beginning transaction yyyy which is greater than end transaction zzzz

MUPIP Error: This indicates that MUPIP JOURNAL command has found that journal file xxxx has beginning transaction yvvy which is greater than end transaction zzzz.

Action: Report the error with appropriate log messages to your GT.M support channel.

#### **BREAK**

BREAK, Break instruction encountered

Run Time Information: This indicates that GT.M encountered a BREAK command within a routine and entered Direct Mode.

Action: All commands entered at the Direct Mode prompt are compiled and executed as they are entered. To continue program execution, enter the ZCONTINUE command. This message can be supressed using VIEW BREAKMSG value.

### **BREAKDEA**

**BREAKDEA**, Break instruction encountered during Device error action

Run Time Information: This indicates that GT.M encountered a BREAK command within a device EXCEPTION string and entered Direct Mode.

Action: GT.M activates EXCEPTION strings for deviceparameters when a device reports an exception condition. All commands entered at the Direct Mode prompt are compiled and executed as they are entered. To continue program execution, enter the ZCONTINUE command. It is important to ensure the EXCEPTIONS in production code are thoroughly debugged.

#### **BREAK7BA**

**BREAKZBA**, Break instruction encountered during ZBREAK action

Run Time Information: This indicates that GT.M encountered a BREAK command within a ZBREAK action string and entered Direct Mode. The ZBREAK command sets or clears breakpoints during debugging. All commands entered at the Direct Mode prompt are compiled and executed as they are entered.

Action: To continue program execution, enter the ZCONTINUE command.

### **BREAKZST**

BREAKZST, Break instruction encountered during ZSTEP action

Run Time Information: This indicates that GT.M encountered a BREAK command within a ZSTEP action string and entered Direct Mode.

Action: The ZSTEP command causes GT.M to proceed to the beginning of the next line of M code that matches the characteristic specified by the ZSTEP argument. GT.M compiles and executes all commands entered at the Direct Mode prompt as they are entered. To continue program execution, enter the ZCONTINUE command.

### **BTFAIL**

**BTFAIL**, The database block table is corrupt; error type xxxx

Run Time Error: This indicates that a database operation failed because the tables of recently used blocks are damaged. GT.M uses the block tables to control and optimize database traffic.

Action: Report this database cache error to the group responsible for database integrity at your operation.

#### **BUFFLUFAILED**

BUFFLUFAILED, Errors flushing buffers from uuuu for database file dddd

DSE/MUPIP Error: MUPIP or DSE (uuuu) could not flush the buffers for database file dddd completely. In the case of MUPIP, this typically means that some process is not releasing the critical section. In the case of DSE, this typically means there is some error in the global buffer cache which needs to be fixed.

V6.2-002 MR Manual June 09, 2015, Page 15 Action: In the case of MUPIP, wait approximately 20 seconds and retry. In the case of DSE, try DSE CACHE RECOVER to fix the cache. If the error persists, report it to the group responsible for database integrity at your operation as soon as possible.

#### **BUFOWNERSTUCK**

BUFOWNERSTUCK, PID xxxx waiting for PID yyyy to finish disk read of block zzzz. Been waiting for aaaa minutes.

Run Time Warning: Poor response time from the I/O subsystem could cause this error, or if the process performing the disk-read was suspended.

Action: If the disk-reading process is found to be in a process-suspended state, un-suspend it. If it is not suspended, examine the I/O subsystem performance characteristics for behavior problems. Report the full error message, along with the GT.M operator log messages during the specific timeframe, to your GT.M support channel.

#### **BUFRDTIMEOUT**

**BUFRDTIMEOUT**, Pid xxxx timed out waiting for buffered read by process yvyy to complete in database file zzzz

Run Time Information: This indicates that a process requiring buffer transfer began but did not complete. The system cancelled the process.

Action: The failed process must be run again. Other errors may appear in the operators log with this one to indicate why the process failed.

#### **BUFSIZIS**

**BUFSIZIS**, Journal Buffer size is xxxx

GDE Information: This message reports xxxx as the size of the journal buffer.

Action: Review the accompanying message(s) for additional information.

#### **BUFTOOSMALL**

**BUFTOOSMALL**, But block size xxxx requires buffer size yyyy

GDE Information: This indicates that an ADD, CHANGE, or TEMPLATE command specified an xxxx argument definition for the BUFFER SIZE qualifier, which is incompatible with the definition of the BLOCKSIZE. yyyy specifies the minimum buffer size that can support this block size.

Action: Modify the block size and/or buffer size so they are compatible. Review the accompanying message(s) for the buffer size.

V6.2-002 GT.M Message and Recovery Procedures Manual

## **CALLERID**

**CALLERID**, Routine xxxx called from yyyy

Run Time Error: This message provides the error location. Typically this error displays with other errors.

Action: Review the accompanying message(s) for additional information. Include this information if reporting the error to your GT.M support channel.

## **CALLINAFTERXIT**

**CALLINAFTERXIT**, After a gtm exit, a process can never create a valid GT.M context

Run Time Error: Once a call-in has done a call to gtm exit(), a process can no longer do GT.M call-ins

Action: Either move or remove the inappropriate call-ins or move the gtm exit call to a later point.

### **CANTBITMAP**

**CANTBITMAP**, CANTBITMAP, Can't perform this operation on a bit map (block at a 200 hexadecimal boundary)

DSE Error: The selected DSE operation does not apply to bit maps (blocks divisible by 0x200).

Action: Select an appropriate block for the operation or an appropriate operation for a bit map.

#### **CEBIGSKIP**

**CEBIGSKIP**, Compiler escape user routine skip count is too large

Compile Time/Run Time Error: This indicates that the skip count exceeded the maximum line length.

Action: Verify the user-supplied escape-handling routine(s).

### **CENOINDIR**

**CENOINDIR**, Indirection type information not available for compiler escape feature

Compile Time/Run Time Error: This indicates that GT.M does not currently support this feature.

Action: -

### **CETOOLONG**

**CETOOLONG**, Compiler escape substitution exceeds maximum line size

Compile Time/Run Time Error: This indicates that the length of the substitution string exceeds the maximum line length.

Action: Determine whether the input source file can be modified to have less source on the line in question. If this is not possible, modify the substitution mechanism design or implementation.

### **CETOOMANY**

**CETOOMANY**, Too many compiler escape substitutions in a single statement

Compile Time/Run Time Error: This indicates that the program being compiled contained more nested substitutions than allowed; that is 1024.

Action: Reduce the number of substitutions to less than 1024.

## **CEUSRERROR**

**CEUSRERROR**, Compiler escape user routine returned error code xxxx

Compile Time/Run Time Error: This indicates that the compiler encountered the error specified by error code xxxx.

Action: Use the error code as the function argument of \$ZMESSAGE() to determine the text associated with the error and the appropriate corrective action.

#### **CHNGTPRSLVTM**

CHNGTPRSLVTM, Mupip will change tp\_resolve\_time from xxxx to yyyy because expected EPOCH or EOF record was not found in Journal File zzzz.

MUPIP Information: At startup, backward recovery/rollback internally computes a time called the tp resolve time which is until when backward processing will be performed across journal files of all regions. During backward processing it is possible in very rare cases that recovery does not see an EPOCH record or an EOF record as the last record in the journal file of those regions that had not been updated for quite a long time. In such cases recovery reduces the tp resolve time further by taking into account the timestamp of the last journal record. This effectively causes further backward processing but is necessary for a clean recovery. A CHNGTPRSLVTM message is printed whenever such journal files are encountered by backward recovery.

Action: None necessary

### CHSETALREADY

CHSETALREADY, CHSETALREADY, CHSET xxxx already specified for socket device

Run Time Error: The code specified a CHSET for a SOCKET device different than the CHSET previously assigned to it.

Action: If different CHSETs are needed for different sockets, place them in different SOCKET devices.

### **CIDIRECTIVE**

**CIDIRECTIVE**, Invalid directive parameter passing. Expected I, O or IO.

Syntax Error: This indicates that a missing directive or syntactically invalid directive found for the parameter, pointed to by the previous messages EXTSRCLIN and EXTSRCLOC.

Action: One of the directives I, O or IO should be specified for the parameter in the entry displayed.

# **CIENTNAME**

**CIENTNAME**, No label reference found for this entry in call-in table

Syntax/Call in Error: This indicates that a label reference to the M routine is missing or syntactically invalid for an entry in the call-in table (specified by GTMCI environment variable)

Action: Correct the syntax errors in the call-in table entry, at the location pointed to by the two previous messages (EXTSRCLIN and EXTSRCLOC), displaying the line and the column number respectively.

Make sure a valid M label reference is bound to the C call-name specified for this entry.

### **CIMAXLEVELS**

CIMAXLEVELS, Too many nested Call-ins. Nested resources exhaused at level !UL.>/error/fao=1!/ ansi=0

Call in/Run Time Error: This indicates that GT.M runs out of its internal condition handlers stack due to too many levels of nested call-ins.

Action: Ensure that the call-in application is not nested more than the limit (xxxx) that GT.M supports. The number of nested call-ins can be reduced by not using call-ins, wherever possible, from external call functions.

### **CIMAXPARAM**

**CIMAXPARAM**, Exceeded maximum number of parameters in the call-in table entry. An M routine cannot accept more than 32 parameters.

Call in/Run Time Error: This indicates that the call-in table specified by \$GTMCI contains more than 32 parameters. Since an M formallist can only accept up-to 32 parameters, user cannot pass more than 32 arguments to gtm ci(), excluding <c-call-name> and <ret-type>.

Action: Reduce the number of parameters to be less than 32, in the call-in table as well in the M routine.

#### **CINOENTRY**

**CINOENTRY**, No entry specified for xxxx in the call-in table

Run Time Error: This indicates that the call-name invoked by the C program does not have a corresponding entry in the call-in table specified by GTMCI environment variable.

Action: Add an entry to the call-in table for the call-name. Refer to the External Calls chapter in Programmer's Guide.

#### **CIPARTYPE**

CIPARTYPE, Invalid type specification for O/IO directive - expected pointer type

Syntax/Call in Error: This indicates that non-pointer types specified for the parameters to be passed by output-only (O) and input-output (IO) convention.

Action: Make sure one of the valid pointer types is specified for O and IO parameters. Refer to the External Calls chapter in Programmer's Guide.

#### **CIRCALLNAME**

**CIRCALLNAME**, Call-in routine name expected but not found

Syntax/Call in Error: This indicates that a call-name, which is to be bound to an M routine, is either missing or syntactically invalid for an entry in the call-in table file.

Action: Make sure a valid call-name is specified in the call-in table entry, at the location pointed to by the two previous messages: EXTSRCLIN and EXTSRCLOC, displaying the line and the column number respectively.

#### **CIRPARMNAME**

**CIRPARMNAME**, Invalid parameter specification for call-in table

Syntax/Call in Error: This indicates that a syntax error was found in parameter specification in the call-in table.

Action: Correct the syntax errors and make sure the parameters are correctly specified. Refer to the External Calls chapter in Programmer's Guide.

### **CIRTNTYP**

**CIRTNTYP**, Invalid return type

Syntax/Call in Error: This indicates that the return type specified in the call-in entry is either missing or found invalid.

Action: Correct the return type syntax errors in the call-in table entry, at the location pointed to by the two previous messages: EXTSRCLIN and EXTSRCLOC, displaying the line and the column number respectively. Make sure a valid return type is specified for this entry.

## **CITABENV**

CITABENV. Environment variable for call-in table xxxx not set

Call in/Run Time Error: This indicates that the environment variable GTMCI is not defined when an external C routine is about to call an M routine through GT.M call-in mechanism

Action: Check if GTMCI is defined to a valid file path to a call-in table. The call-in table file should contain a list of entries, each entry describing the parameter types, their passing convention of each M routine and its binding to a C routine.

#### **CITABOPN**

CITABOPN, Unable to open call-in table: xxxx

Call in/Run Time Error: This indicates that the call-in table defined by the environment variable GTMCI could not be opened.

Action: Check if the file path specified by GTMCI is correct and has at least read permissions for the user running GT.M. Check for secondary message(s) accompanying this error.

### **CITPNESTED**

**CITPNESTED**, Call-ins can not be used inside a TP transaction

Call in/Run Time Error: This indicates that a nested call-in (gtm ci()) was invoked from an external call function that was called within a TSTART/TCOMMIT fence.

Action: GT.M currently does not handle TP support across multiple call-in invocations. Make sure all external call C functions, that invoke call-in functionality are not fenced within a TSTART/TCOMMIT boundar

### **CIUNTYPE**

CIUNTYPE, Unknown parameter type encountered

Syntax/Call in Error: This indicates that missing or invalid parameter type specified for the entry displayed by the previous messages EXTSRCLIN and EXTSRCLOC.

Action: Make sure one of the valid parameter types is specified for the parameter in the entry displayed. Refer to the External Calls chapter in Programmer's Guide.

### **CLIFRR**

#### CLIERR, xxxx

Run Time Error: This indicates that an invalid command has been entered. xxxx provides further detail to the invalid command entered.

Action: Review the error and enter valid command.

### **CLOSEFAIL**

**CLOSEFAIL**, Error while closing file descriptor dddd

Run Time Error: GT.M records this error in the syslog whenever it attempts to close an open file descriptor dddd and the close returns with an error. After recording this error, the GT.M process resumes normal operation.

Action: Report the above error message along with the accompanying GTM-I-CALLERID message to your GT.M support channel, as it may be a symptom of out-of-design operation.

#### **CLSTCONFLICT**

**CLSTCONFLICT**, Cluster conflict opening database file xxxx; could not secure access. Already open on node yyyy.

Run Time Error: This indicates that the process attempted to access non-clustered database xxxx, which was opened by node vvvv.

Action: Review the accompanying message(s) for additional information. Move the process to the appropriate node or use GDE to change the mapping in the Global Directory.

This error message can also occur after a database is improperly shut down. Perform a MUPIP RUNDOWN with a FILE or REGION qualifier.

#### **CMD**

CMD, Command expected but not found

Compile Time Error: This indicates that GT.M encountered something other than a command- the next valid syntax element. This error can occur when there is an invalid character in the middle of a variable name or keyword, such as in the M line S X=Y \$B or in the command W "this is a tab <TAB>".

Action: Verify the line syntax. Replace the line if it contains invisible (non-graphic) characters because diagnosing the line syntax may prove time consuming.

## **CMEXCDASTLM**

CMEXCDASTLM, Exceeded AST limit. Cannot open database.

**CMICHECK** Chapter 1. Error Messages

GT.CM Error: This indicates that the GT.CM server exceeded its quota of asynchronous system traps (ASTs).

Action: Increase the ASTLIM for the GT.CM server by modifying GTCMSTART.COM, shut down and restart the GT.CM server. Review SYSGEN factors and user authorizations for AST limits.

### **CMICHECK**

**CMICHECK**, Internal CMI error. Report to GT.M Support.

GT.CM Error: This indicates that the GT.CM and DECNET cannot communicate properly. See GTMCHECK.

Action: Report the entire incident context to your GT.M support channel.

# **CMINTQUE**

CMINTQUE, Interlock failure accessing GT.CM server queue

GT.CM Error: This indicates that interlock cannot move data onto the queue interlock bit.

Action: Accompanying messages should indicate the hardware or software problem, which caused the interlock failure.

#### **CMSYSSRV**

**CMSYSSRV**, Error doing system service, status:

GT.CM Error: This indicates that the GT.CM server could not successfully perform some system service. This message is followed by a secondary error message that describes the nature of the failure.

Action: Retry the action that resulted in the error. If the problem persists, contact the group responsible for database operations on your network.

#### **CNOTONSYS**

**CNOTONSYS**, command is not supported by this operating system

Compile Time Error: This indicates that the operating system does not support the command.

Action: Check the operating system documentation for a supported command.

### **COLLARGLONG**

**COLLARGLONG**, Collation sequence nnn does not contain routines for long strings

Run Time Error: Strings longer than 32,767 (UNIX) or 65,535 (OpenVMS) bytes have been used with alternative collation and only gtm ac xform and gtm ac xback are defined in the collation library.

Action: Define gtm\_ac\_xfrom\_1 and gtm\_ac\_xback\_1 routines in the collation library.

## **COLLATIONUNDEF**

**COLLATIONUNDEF**, Collation type xxxx is not defined

Run Time Error: This indicates that an attempt was made to reference a collation sequence that is not available.

Action: Ensure that the environment variable GTM COLLATE n in UNIX and logical name gtm collate n in OpenVMS is properly defined, where n is the identification number of the failing collation type. Ensure that the file referencing GTM COLLATE n / gtm collate n is available to the process. Use host shell commands to verify its location and protections. Examine the executable (and/or the objects that comprise it) to determine whether it has the proper entry points. For more information, refer to the "Internationalization" chapter of the Programmer's Guide.

### **COLLDATAEXISTS**

**COLLDATAEXISTS**, Collation type cannot be changed while data exists

Run Time Error: This indicates that an attempt was made to change the local collation type while local variables exist.

Action: KILL or NEW the local variables before you change the local collation type.

### **COLLFNMISSING**

**COLLFNMISSING**, Routine xxx is not found for collation sequence nnn

Run Time Error: Required transformation back routine is missing in collation library.

Action: If gtm\_ac\_xfrom\_1 is defined, also define gtm\_ac\_xback\_1. Or if gtm\_ac\_xform is defined, also define gtm ac xback in the collation library.

#### **COLLTYPVERSION**

**COLLTYPVERSION**, Collation type xxxx, version yyyy mismatch

Run Time Error: This indicates that the user image with collation type xxxx does not accept the version of collation for an existing global. yvyy is the version associated with the global.

Action: Review the implementation history of the current collation algorithm. Modify or replace the image, if appropriate. If the version should change, temporarily RESTORE the older matching module, COLON Chapter 1. Error Messages

unLOAD and KILL any globals using the older algorithms, RESTORE the new algorithms, and reLOAD the global.

#### **COLON**

**COLON**, Colon (:) expected in this context

Compile Time Error: This indicates that GT.M did not encounter a colon where expected.

Action: Look for a \$SELECT() function that does not have a colon separating the conditional expression from its corresponding value expression. Also, look for a ZGOTO that is missing a colon between the level and an entry reference.

### **COLTRANSSTR2LONG**

**COLTRANSSTR2LONG**, COLTRANSSTR2LONG, Output string after collation transformation is too long

Run Time Error: an alternative collation transform or reverse transform attempted to use more bytes than the configuration permits.

Action: Adjust the implementation of the collation transform to minimize key expansion; increase the maximum permitted key size if appropriate. Note the current supported maximum is 1019 bytes. If the key size is already maxed out and the transformation algorithm is optimal, you must modify the application to reduce the key size.

#### **COMMA**

**COMMA**, comma expected in this context

Compile Time Error: This indicates that GT.M did not encounter a comma where expected.

Action: Look for a missing argument or comma in a function that requires multiple arguments.

### **COMMAORRPAREXP**

**COMMAORRPAREXP**, Comma or right parenthesis expected but not found

Compile Time Error: This indicates that GT.M did not encounter a comma or right parenthesis where expected.

Action: Look for a list of improperly formatted subscripts, arguments, or parameters.

### **COMMENT**

**COMMENT**, Comment line. Placed zbreak at next executable line.

V6.2-002 MR Manual June 09, 2015, Page 25 Run Time Information: This indicates that a ZBREAK specified a line that had no active code. Therefore, GT.M set the ZBREAK at the next line containing source code.

Action: -

#### COMMITWAITPID

**COMMITWAITPID**, Pid wwww waited tttt minute(s) for pid pppp to finish commits in database file dddd

Run Time Warning: This warning message in the operator log indicates the total amount of time that the process wwww waited for another process pppp to finish database transaction commit. If the \$gtm\_procstuckexec mechanism is enabled, this message invokes it. If a process waits for more than one process to finish database transaction commits, it issues this message for each one it encounters.

Action: If the process pppp is still running, get a C-stack trace of the process (using a debugger) and report to your GT.M support channel with system log and operator log information.

### COMMITWAITSTUCK

**COMMITWAITSTUCK**, Pid wwww timed out after waiting tttt minute(s) for nnnn concurrent GT.M process(es) to finish commits in database file dddd

Run Time Error: This error message indicates that a process could not finish database transaction commit and timed out waiting for other concurrent processes to finish.

Action: Check the operator log for accompanying COMMITWAITPID messages. Every concurrent GT.M processes reported with the COMMITWAITSTUCK messages would have accompanying COMMITWAITPID message(s). If so, review those messages. If not, report to your GT.M support channel with system log and operator log information.

# **COMPILEQUALS**

**COMPILEQUALS**, Error in compiler qualifiers: xxxx

Compile Time/Run Time Error: This indicates that a run-time compilation specified an invalid qualifier (xxxx). Qualifiers for a run-time compilation can be specified with ZLINK or by setting \$ZCOMPILE to a qualifier string that GT.M uses for auto-ZLINKs with no qualifiers.

Action: Review the qualifiers in the ZLINK sub-argument or those being SET into \$ZCOMPILE.

### **CONNSOCKREQ**

CONNSOCKREO, CONNSOCKREO, Socket not connected

Run Time Error: The operation attempted requires a socket in the CONNECTED state, and the provided socket was not connected.

V6.2-002 GT.M Message and Recovery Procedures Manual **COREINPROGRESS** Chapter 1. Error Messages

Action: Make sure the correct socket is being used and that the socket is connected. ZSHOW "D" may provide useful details on the current socket state.

## **COREINPROGRESS**

**COREINPROGRESS**, Previous core attempt failed; core generation bypassed.

Run Time Error: This indicates that the process, which failed, was unable to create a memory dump file and tried to create another one.

Action: Report the entire incident context to your GT.M support channel for further analysis.

## **CORRUPT**

**CORRUPT**, Corrupt input in Blk #xxxx, Key #yyyy; resuming with next global block

MUPIP Warning: This indicates that LOAD encountered bad data in the input file.

Action: Refer to the topic MUPIP LOAD Errors in "About This Manual" section.

#### **CORRUPTNODE**

**CORRUPTNODE**, Corrupt input in Record # rrrr, Key #yyyy; resuming with next global node

MUPIP Error: This message reports record rrrr with apparent key kkkk does not have a valid format for MUPIP LOAD.

Action: USE %GO or MUPIP EXTRACT to recapture the problematic node(s), or, use an editor to create valid copies of the nodes in an LOAD file.

### **CPBEYALLOC**

**CPBEYALLOC**, Attempt to copy beyond the allocated buffer

DSE Error: This indicates that DSE tried to add a record that did not fit into the block size and/or the balanced tree structure.

Action: Check the block size. Move or create the record in a different location.

#### **CREDNOTPASSED**

CREDNOTPASSED, CREDNOTPASSED, Socket message contained no passed credentials

Run Time Error: WRITE /PASS or WRITE /ACCEPT was given a process id to verify, but GT.M was unable to obtain the peerprocess id.

Action: See the accompanying ENO error for details.

#### **CRITRESET**

**CRITRESET**, The critical section crash count for region xxxx has been incremented

Run Time Fatal: This indicates that the critical section for region xxxx was reset by the DSE command CRITICAL with the qualifiers INIT and RESET, while this process was accessing that database.

Action: Wait until the DSE repair operations are complete before retrying or restarting the process.

#### **CRITSEMFAIL**

CRITSEMFAIL, Error with semaphores for region xxxx

Run Time Error: This indicates that GT.M encountered a missing or damaged semaphore. This typically indicates that an agent external to GT.M has deleted or modified the semaphores GT.M uses to manage database and LOCK interactions.

Action: Investigate the state of the GT.M semaphores and all previous actions that might have damaged them.

### **CRYPTBADCONFIG**

**CRYPTBADCONFIG**, Could not retrieve data from encrypted file ffff due to bad encryption configuration. eeee

Run Time Error: The error occurs when a GT.M utility program starts with a bad encryption configuration (like a bad password) and attempts to read a block corresponding to file ffff (either from memory or disk).

Action: Look at accompanying message (or prior messages related to encryption) for more details on what encryption configuration parameter is incorrect.

### **CRYPTBADWRTPOS**

**CRYPTBADWRTPOS**, CRYPTBADWRTPOS, Encrypted WRITE disallowed from a position different than where the last WRITE completed

Run Time Error: A WRITE attempt to an encrypted device violates the integrity of the produced ciphertext. This is the case, for example, when trying to WRITE to a previously encrypted and CLOSEd file. Because encryption ciphers rely on state machine algorithms, GT.M prohibits WRITEs performed in non-sequential fashion or when they threaten to overlay already encrypted data.

Action: Revise your M code to avoid illegal I/O operations with encryption. Note, in particular, that when using encryption non-empty files cannot be opened in APPEND mode; the SEEK deviceparameter is prohibited; and the TRUNCATE is only permitted at the beginning or end of a file.

## **CRYPTDLNOOPEN**

**CRYPTDLNOOPEN**, Failed to load encryption library while opening encrypted file ffff. eeee

Run Time Error: GT.M failed to load the gtmcrypt plug-in or one of its related libraries.

Action: Refer to the accompanying detail (eeee) and verify that the gtmcrypt plug-in and related libraries are properly installed and that \$LD LIBRARY PATH and \$LIBPATH are properly set.

### CRYPTDLNOOPEN2

**CRYPTDLNOOPEN2**, Failed to load encryption library dddd. Eeee

Run Time Error: GT.M failed to load the gtmcrypt plug-in or one of its related libraries during GT.M startup.

Action: Refer to the accompanying details (eeee). Verify that the gtmcrypt plug-in and related libraries are properly installed and the LD LIBRARY PATH and LIBPATH environment variables are properly set.

#### **CRYPTHASHGENFAILED**

**CRYPTHASHGENFAILED**, Failed to generate cryptographic hash for symmetric key corresponding to file ffff. eeee

Run Time Error: gtmcrypt plug-in reports there is problem with the hash function.

Action: Examine the message (eeee) from the plug-in and take the appropriate action.

### **CRYPTINIT**

**CRYPTINIT**, Failed to initialize encryption library while opening encrypted file ffff. eeee

Run Time Error: The gtmcrypt plug-in reports it is unable to initialize one or more of its related libraries.

Action: Examine the detailed message (eeee) from the plug-in and take appropriate action.

#### **CRYPTINIT2**

**CRYPTINIT2**, Failed to initialize encryption library during GT.M startup. eeee

Run Time Error: The gtmcrypt plug-in reports it is unable to initialize one or more of its related libraries during GT.M startup.

Action: Examine the detailed message (eeee) from the plug-in and take appropriate action.

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual

# **CRYPTINLWRONGHASH**

**CRYPTJNLWRONGHASH**, Encryption key hash mismatch between journal file jijj and corresponding database file dddd

Run Time Error: gtmcrypt plug-in reports the hash of the key in the header of database file dddd does not match the hash stored in the header of journal file jjjj. This is most likely caused by inappropriate operator action such as replacing the current journal file with an older journal file.

Action: Correct the error that caused the incorrect journal file to be pointed to by the database file. If the correct journal file has been inadvertently deleted, create new journal files with the -nopreyjnl switch. Take a backup as soon as possible thereafter. Depending on your situation, you may need to refresh secondary instances.

### **CRYPTKEYFETCHFAILED**

CRYPTKEYFETCHFAILED, Failed to retrieve encryption key corresponding to file ffff. eeee

Run Time Error: gtmcrypt plug-in reports it was unable to obtain an encryption key for file ffff.

Action: Examine the message (eeee) from the plug-in and take the needed action: for example, verify encryption key for this file is pointed to by the database key file, verify proper permissions on the directory path and the file, and so on. Also, make sure that there is an appropriate maximum process limit because obtaining an encryption key may fork other processes.

### **CRYPTKEYFETCHFAILEDNF**

Last used version: V6.0-001

**CRYPTKEYFETCHFAILEDNF**, Cannot obtain encryption key. xxxx

Run Time Error: gtmcrypt plug-in reports it was unable to obtain an encryption key based upon matching the hash of an encryption key.

Action: Examine the message (xxxx) from the plug-in and take the needed action: for example, verify encryption keys for all database files are pointed to by the database key file. For extracts and backups, verify all the keys from the databases that provided records are in the database key file.

### **CRYPTKEYTOOBIG**

**CRYPTKEYTOOBIG**, CRYPTKEYTOOBIG, Specified key has length xxxx, which is greater than the maximum allowed key length yyyy

Run Time Error: A key name value specified with the [I|O]KEY deviceparameter on an OPEN or USE command is too long.

V6.2-002 GT.M Message and Recovery Procedures Manual **CRYPTNOAPPEND** Chapter 1. Error Messages

Action: Verify that the key name portion of the [I|O]KEY deviceparameter's value (substring before the first space, if any) corresponds to an existing field name in the 'database.keys' or 'files' section of the configuration file and does not exceed yyyy characters in length.

#### **CRYPTNOAPPEND**

**CRYPTNOAPPEND**, CRYPTNOAPPEND, APPEND disallowed on the encrypted file xxxx

Run Time Error: An OPEN command specifies both an APPEND deviceparameter and a non-empty value for the [I|O]KEY deviceparameter.

Action: Because encryption algorithms maintain state as they process text, APPENDing encrypted data to a non-empty file is prohibited; revise your application code accordingly.

#### **CRYPTNOKEYSPEC**

**CRYPTNOKEYSPEC**, Key name needs to be specified with KEY, IKEY, or OKEY device parameter for encrypted I/O

Run Time Error: A key name value specified with the [I|O]KEY deviceparameter on an OPEN or USE command is empty while the initialization vector (IV) is not.

Action: If enabling encryption or modifying encryption attributes, be sure to include an appropriate key name; if disabling encryption, leave the IV portion of the [I|O]KEY deviceparameter's value (substring after the first space) empty.

#### **CRYPTNOMM**

**CRYPTNOMM**, is an encrypted database. Cannot support MM access method.

GDE/MUPIP Error: This error is triggered by an attempt to mark an MM database as encrypted with GDE or to switch an encrypted database from BG to MM with MUPIP SET. The MM access method is not supported for encrypted databases.

Action: Use the BG access method for encrypted files.

#### **CRYPTNOOVERRIDE**

**CRYPTNOOVERRIDE**, Cannot override IVEC and/or key without compromising integrity

Run Time Error: An OPEN or USE command attempts to change the encryption attributes - that is: attempted to enable or disable encryption or change the key name, initialization vector (IV), or both, after a prior encrypted READ or WRITE.

Action: Because encryption algorithms maintain state as they process text, changing encryption attributes of a device is prohibited if an encrypted READ or WRITE has already occurred, so revise your application code accordingly.

### **CRYPTNOPSWDINTP**

**CRYPTNOPSWDINTP**, Cannot prompt for password inside a TP transaction.

Run Time Error: This error occurs if the process used an external call to set the gtm passwd environment variable to null string after startup and then accessed an encrypted database file for the first time within a TP transaction.

Action: If possible, set the gtm\_passwd environment variable to the obfuscated password. Otherwise, revise the logic to touch a global mapped to each encrypted database, for example, \$DATA(myglobal), to ensure the prompting happens before entering any TP transaction.

#### **CRYPTNOSEEK**

CRYPTNOSEEK, SEEK disallowed on the encrypted file ffff

Run Time Error: An OPEN or USE command specifies a SEEK deviceparameter on an encryptionenabled device.

Action: Because encryption algorithms maintain state as they process text, SEEKs are prohibited with encrypted devices, so revise your application code accordingly.

### **CRYPTNOTRUNC**

**CRYPTNOTRUNC**, Not positioned at file start or EOF. TRUNCATE disallowed on the encrypted file ffff

Run Time Error: An OPEN or USE command specifies a TRUNCATE deviceparameter on a encryptionenabled device which is not positioned at the end of a file.

Action: When using encryption, because encryption algorithms maintain state as they process text, a TRUNCATE is only permitted at the beginning or end of a file, the former deleting the entire contents, and the latter effectively a no-op.

### **CRYPTNOV**4

**CRYPTNOV4**, ffff is an encrypted database. Cannot downgrade(to V4) with Encryption option enabled.>/error/fao=2!/ansi=0

MUPIP Error: An attempt to downgrade ffff which is an encrypted database to the V4 (GT.M version 4) format failed because the V4 format does not support encrypted database files.

Action: Use the database in the current format. If a V4 format is required, extract the data in unencrypted ZWRite format with MUPIP EXTRACT and load it into a newly created V4 database.

V6.2-002 GT.M Message and Recovery Procedures Manual

## **CRYPTOPFAILED**

CRYPTOPFAILED, Encrypt/Decrypt operation failed for file ffff. eeee

Run Time Error: gtmcrypt plug-in reports there is problem with encryption or decryption.

Action: Examine the message (eeee) from the plug-in and take appropriate action.

### **CTLMNEMAXLEN**

CTLMNEMAXLEN, The maximum length of a control mnemonic has been exceeded

Run Time Error: This indicates that GT.M encountered a controlmnemonic that exceeds the supported maximum length.

Action: Modify the controlmnemonic so that it does not exceed the permitted length.

#### **CTLMNEXPECTED**

CTLMNEXPECTED, Control mnemonic is expected in this context

Run Time Error: This indicates that GT.M requires a control mnemonic in this context.

Action: Modify the spelling of the control mnemonic. Refer to the Input Output Processing chapter in the GT.M Programmer's Manual.

#### **CTRAP**

**CTRAP**, Character trap \$C(xxxx) encountered

Run Time Error: This indicates that the current device encountered character xxxx in its input stream while xxxx was defined as an exception by a CTRAP deviceparameter.

Action: Determine why this character was defined as an error or why an EXCEPTION string was not defined to address it.

### **CTRLC**

CTRLC, CTRL C encountered

Run Time Information: This indicates that the principal device encountered a <CTRL>-C in its input stream and GT.M put the process into Direct Mode.

Action: GT.M compiles and executes all commands entered at the Direct Mode prompt as they are entered. To continue program execution, enter the ZCONTINUE command. Response to <CTRL>-C is controlled with the [NO]CENABLE and CTRAP = deviceparameters.

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual

#### **CTRLY**

**CTRLY**, User interrupt encountered

Run Time Information: This indicates that the principal device encountered a <CTRL>-Y in its input stream, and GT.M gave control to the OpenVMS CLI. The normal CLI is DCL.

Action: You can resume operation with a CONTINUE command if your actions do not invoke other images. For more information on commands that invoke images, refer to the OpenVMS DCL Dictionary.

### **CURRSOCKOFR**

CURRSOCKOFR, Current socket of index xxxx is out of range. There are only yyyy sockets.

Run Time Error: This indicates that an OPEN, USE, READ or WRITE attempted to select a socket outside the range of available sockets.

Action: Review the socket management logic and revise to use only available sockets.

#### **CUSTERRNOTEND**

**CUSTERRNOTFND**, Error mnemonic eeee specified in custom errors file is not valid for this version of GT.M

Run Time Error: This error indicates that the GT.M runtime did not recognize the error mnemonic eeee in the file referenced by \$gtm custom errors.

Action: Modify the file so that it no longer contains the invalid mnemonic or set the gtm\_custom\_errors environment variable to point to an appropriate file.

### **CUSTERRSYNTAX**

CUSTERRSYNTAX, Syntax error in file ffff at line number nnnn

Run Time Error: This error indicates that the custom errors file ffff contains an inappropriate syntax on line nnnn.

Action: Modify the file ffff so that it contains a single valid error mnemonic on line nnnn or set the gtm\_custom\_errors environment variable to point to an appropriate file.

### **CUSTOMFILOPERR**

CUSTOMFILOPERR, Error while doing oooo operation on file ffff

**DBADDRALIGN** Chapter 1. Error Messages

Run Time Error: This indicates that the operating system reported an error while performing operation 0000 on custom errors file ffff.

Action: Check that ffff is a proper path to the custom errors file. If it is incorrect, set the gtm custom errors environment variable to point to the correct file. If the file path is correct, verify that the user has access to the file and correct any permissions issues.

#### **DBADDRALIGN**

**DBADDRALIGN**, Database file xxxx, element location aaaa: blk = bbbb: [yyyy] control cccc was unaligned relative to base dddd and element size eeee

Run Time Information: This indicates that a control structure in the database cache is damaged.

Action: None needed. GT.M fixes this error as part of cache recovery, which follows the cache verification. If this message shows up frequently or is reproducible, contact your GT.M support channel.

#### **DBADDRANGE**

**DBADDRANGE**, Database file xxxx, element location yvyy: control zzzz was outside aaaa range bbbb to cccc

Run Time Information: This indicates that a process was abnormally terminated. Database control structures may be damaged.

Action: GT.M often fixes this error unless there is a serious problem causing this error. If there is a serious problem, the accompanying messages identify the cause.

#### **DBADDRANGE8**

DBADDRANGE8, Database file xxxx, element location yyyy: control zzzz was outside aaaa range bbbb to cccc.

Run Time Error: This message is the same as a DBADDRANGE message except that bbb8 and ccc8 are 8-byte quantities (as opposed to 4-byte quantitites in DBADDRANGE).

Action: GT.M often fixes this error unless there is a serious problem causing this error. If there is a serious problem, the accompanying messages identify the cause.

### **DBBADFREEBLKCTR**

**DBBADFREEBLKCTR**, Database xxxx free blocks counter in file header: oooo appears incorrect; should be nnnn. Auto-corrected.

Run Time Warning: This indicates that during a file extension, because they differed, GT.M adjusted the free blocks counter (0000) in the file header to agree with free blocks indicated by the master map

V6.2-002 MR Manual

(nnnn). Because this may indicate a master bitmap integrity error (DBMBPINCFL), check the next MUPIP INTEG carefully.

Action: Run MUPIP INTEG; if it reports a DBMBPINCFL integrity error, use DSE to correct it, and to increase the file header free blocks counter by the amount GT.M reduced it in the DBBADFREEBLKCTR message. Run an additional INTEG to confirm the corrections.

### **DBBADKYNM**

**DBBADKYNM**, xxxx is an invalid key name

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

#### **DBBADNSUB**

DBBADNSUB, xxxx Bad numberic subscript

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

#### **DBBADPNTR**

DBBADPNTR, xxxx Bad pointer value in directory

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

#### **DBBADUPGRDSTATE**

**DBBADUPGRDSTATE**, Correcting conflicting values for fields describing database version upgrade state in the file header for region rrrr (ffff) - make fresh backups with new journal files immediately.

Run Time Warning: This warning message in the operator log indicates region rrrr (file ffff) had an out-of-design combination of database upgrade conditions, which may have caused defective journal files and -online BACKUPs. GT.M automatically corrects this condition, but you should investigate the possible causes for such file header damage.

Action: Make fresh backups with new journal files immediately.

## **DBBDBALLOC**

DBBDBALLOC, xxxx Block doubly allocated

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBBFSTAT**

**DBBFSTAT**, xxxx Block busy/free status unknown (local bitmap corrupted)

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBBLEVMN**

DBBLEVMN, xxxx Block level less than zero

Run Time Information: This indicates that a database operation failed. The level specified for block xxxx is less than zero.

Action: Report this database structure error to the group responsible for database integrity at your operation.

#### **DBBLEVMX**

DBBLEVMX, xxxx Block level higher than maximum

Run Time Information: This indicates that a database operation failed. The level specified for block xxxx exceeds the maximum allowed during a block certification or a DSE integrity check.

Action: Report this database structure error to the group responsible for database integrity at your operation.

#### **DBBMBARE**

**DBBMBARE**, xxxx Bit map does not protect itself

DSE/Run Time Information: This indicates that a bitmap error was encountered during a block certification or a DSE integrity check.

Action: Report this database structure error to the group responsible for database integrity at your operation.

V6.2-002 MR Manual

#### **DRRMINV**

**DBBMINV**, xxxx Bit map contains an invalid pattern

DSE/Run Time Information: This indicates that a bitmap error was encountered during a block certification or a DSE integrity check.

Action: Report this database structure error to the group responsible for database integrity at your operation.

### **DBBMLCORRUPT**

**DBBMLCORRUPT**, Database xxxx: Bitmap blk yyyy is corrupt (Size = aaaa, levl = bbbb, tn = cccc: Dbtn = dddd): Database integrity errors likely

Run Time Error: This indicates that a local bitmap block was found corrupted in the global buffers. In the event that the message is followed by a GTMASSERT in the operator log, a dump-file/core may also be produced.

Action: MUPIP RUNDOWN the indicated database and check for integrity errors, check for bitmap related errors and fix them before resuming operations on the database. Report to your GT.M support channel with the operator log information and dump- cores/files, if any.

#### **DBBMMSTR**

**DBBMMSTR**, xxxx Bit map does not match master map

Run Time Information: This indicates that a bitmap error was encountered during a block certification or a DSE integrity check.

Action: Report this database structure error to the group responsible for database integrity at your operation.

### **DBBMSIZE**

**DBBMSIZE**, xxxx Bit map has incorrect size

DSE/Run Time Information: This indicates that a bitmap error was encountered during a block certification or a DSE integrity check.

Action: Report this database structure error to the group responsible for database integrity at your operation.

#### **DBBNPNTR**

**DBBNPNTR**, Bit map block number as pointer

DBBPLMGT2K Chapter 1. Error Messages

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### DBBPLMGT2K

DBBPLMGT2K, Blocks per local map is greater than 2k

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

## **DBBPLMLT512**

**DBBPLMLT512**, Blocks per local map is less than 512

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

#### **DBBPLNOT512**

**DBBPLNOT512**, Blocks per local map is not 512

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBBSIZMN**

DBBSIZMN, xxxx Block too small

Run Time Warning: This indicates that during block certification or DSE/MUPIP integrity check the size of block xxxx was found to be less than the minimum allowed.

Action: Report this database structure error to the group responsible for database integrity at your operation.

### **DBBSIZMX**

DBBSIZMX, xxxx Block larger than file block size

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 39 Run Time Warning: This indicates that during block certification or DSE/MUPIP integrity check the size of block xxxx was found to exceed the block size for the database region.

Action: Report this database structure error to the group responsible for database integrity at your operation.

#### **DBBSIZZRO**

DBBSIZZRO, Block size equals zero

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

#### **DBBTUFIXED**

**DBBTUFIXED**, The blocks-to-upgrade file-header field has been changed to the correct value

MUPIP Information: MUPIP INTEG has corrected the blocks-to-upgrade field.

Action: Report this to the group responsible for database integrity at your operation.

## **DBBTUWRNG**

**DBBTUWRNG**, The blocks-to-upgrade file-header field is incorrect. Expected xxxx, found yyyy

MUPIP Error: The "Blocks to Upgrade" counter was found to be incorrect by MUPIP INTEG (this is only checked for non-FAST integs).

Action: If there are no other integrity errors, MUPIP INTEG will repair the counter. If there are other integrity errors, fix those errors first, then rerun MUPIP INTEG which will repair the counter if it is still found to be in error. Although this error is not indicative of any specific kind of database damage it does represent an out-of-design condition (except following a system crash in which before image journaling was not in use) that your GT.M support channel would like to know about.

### **DBCBADFILE**

**DBCBADFILE**, Source file xxx does not appear to have been generated by DBCERTIFY SCAN - rerun SCAN or specify correct file

DBCERTIFY Error: V5CBSU and DBCERTIFY CERTIFY require the output file from DBCERTIFY SCAN. The file which was specified is not in the correct format.

Action: Specify the file created by DBCERTIFY SCAN. Rerun DBCERTIFY SCAN if needed.

### **DBCCERR**

**DBCCERR**, Interlock instruction failure in critical mechanism for region xxxx

Run Time Error: This indicates that an interlocked operation for the specified region failed.

Action: Report this database concurrency error to the group responsible for database integrity at your operation.

#### **DBCCMDFAIL**

**DBCCMDFAIL**, Executed command failed with return code xxxx yyyy which executed yyyy yyyy

DBCERTIFY Error: During processing, the DBCERTIFY attempts to execute certain DSE and/or MUPIP commands in temporary command scripts that DBCERTIFY creates. The specified command failed to execute.

Action: The action to take depends on the code returned by the attempt and if any associated messages were created on either the console or the operator log. Some common causes of problems could be that \$gtm dist (UNIX) or GTM\$DIST (OpenVMS) are not properly pointing to the current GT.M V4 version or DBCERTIFY has no access or access to the wrong global directory for which it is executing commands.

## **DBCDBCERTIFIED**

**DBCDBCERTIFIED**, Database xxx has been certified for use with xxxx

DBCERTIFY Information: DBCERTIFY CERTIFY has successfully completed and marked the database as certified for use by the specified GT.M version.

Action: Either keep running GT.M V4 version or proceed immediately to GT.M V5 MUPIP UPGRADE at user's discretion.

### **DBCDBNOCERTIFY**

**DBCDBNOCERTIFY**, Database xxxx HAS NOT been certified due to the preceding errors - rerun **DBCERTIFY SCAN** 

MUPIP Error: MUPIP UPGRADE for V5 triggers this error if it finds the DBCERTIFY CERTIFY command has not run to completion on database xxx.

Action: Complete the scan phase of DBCERTIFY by executing the DBCERTIFY SCAN command.

### **DBCINTEGERR**

**DBCINTEGERR**, Encountered integrity error in database xxxx

DBCERTIFY Error: DBCERTIFY discovered what appears to be an integrity error while processing the specified database. This error is accompanied by a secondary message giving an explanation of what the error is.

Action: Run a MUPIP INTEG (not FAST integ) on the database in question; fix damage, then re-run the phase reporting the error. If the integrity error persists, contact your GT.M support channel.

## **DBCKILLIP**

**DBCKILLIP**, Cannot proceed with kill-in-progress indicator set for database xxx

DBCERTIFY Error: DBCERTIFY discovered that the kill in progress indicator was on for the specified database. DBCERTIFY will not process a database with this indicator on.

Action: Run a MUPIP INTEG (FAST integ is OK) on the database in question; correct errors, then re-run the phase reporting the error. If the error persists, contact your GT.M support channel.

### **DBCLNUPINFO**

**DBCLNUPINFO**, Database file xxxx / yyyy

Run Time Information: When a process that holds the critical sectionlock on one or more databases gets abnormally terminated, it dumps information pertaining to its current state into the global sections for each of the concerned databases. The next process that references the concerned database notices the previous abnormal termination and uses the dumped information to update the global buffers and takes the database to a safe and consistent state. During this transition, the process displays a subset of the dumped information in the operator log to be used for debugging purposes by your GT.M support channel, in case database integrity errors are experienced later.

Action: The message text describes the cause of this error. Report any database structure errors to the group responsible for database integrity at your operation.

#### **DBCMODBLK2BIG**

DBCMODBLK2BIG, Block 0xaaa has been modified since DCERTIFY SCAN but is still too large or has an earlier TN than in DCERTIFY SCAN - Rerun scan

DBCERTIFY Error: DBCERTIFY reports this error when the block it is processing has a different TN than it did in the scan phase yet the block is still too large.

Action: This condition indicates that something has been done to the database since the scan phase was run - either it was restored from an earlier backup or the reserved bytes value was (even temporarily) reduced. DBCERTIFY SCAN must be rerun.

## **DBCMPBAD**

DBCMPBAD, xxxx yyyy Compression count not maximal

Run Time Warning: This indicates that a database operation failed because block xxxx contains a record at offset yvyy with a compression count that is too low.

Action: Report this database structure error to the group responsible for database integrity at your operation.

#### **DBCMPMX**

**DBCMPMX**, xxxx yyyy Record compression count is too large

Run Time Warning: This indicates that during block certification or DSE/MUPIP integrity check, the block xxxx was found to contain a record at offset yyyy that exceeds the compression count.

Action: Report this database structure error to the group responsible for database integrity at your operation.

### **DBCMPNZRO**

**DBCMPNZRO**, xxxx yyyy First record of block has nonzero compression count

Run Time Warning: This indicates that during block certification or DSE/MUPIP integrity check the first record at offset yyyy of block xxxx was found to have a nonzero compression count.

Action: Report this database structure error to the group responsible for database integrity at your operation.

#### **DBCNOEXTND**

DBCNOEXTND, Unable to extend database xxx

DBCERTIFY Error: DBCERTIFY attempted to use MUPIP EXTEND to extend the database but the attempt failed.

Action: Examine the accompanying messages from the MUPIP EXTEND attempt to see why the extend failed. Some common causes for this are that \$gtm\_dist on UNIX or GTM\$DIST on OpenVMS did not properly point to the currently installed V4 distribution, or there was insufficient disk space to perform the expansion.

# **DBCNOFINISH**

**DBCNOFINISH**, DBCERTIFY unable to finish all requested actions

DBCERTIFY Error: This indicates DBCERTIFY encountered an error, which prevented the requested action from completing. The action has partially completed.

Action: Review the accompanying message(s) for additional information to identify the cause.

#### **DBCNOTSAMEDB**

**DBCNOTSAMEDB.** Database has been moved or restored since DBCERTIFY SCAN - Rerun scan

DBCERTIFY Error: DBCERTIFY has noted that the unique database identifiers for the database have changed since DBCERTIFY SCAN was run.

Action: The database is required to have not been moved around or restored or recovered since DBCERTIFY SCAN was run. DBCERTIFY SCAN must be rerun.

#### **DBCNTRLERR**

**DBCNTRLERR**, Database file xxxx: control error suspected but not found

Run Time Error: This indicates that GT.M detected the possibility of damage to database cache structures and performed a cache verification and rebuild, but found no evidence of damage.

Action: Verify that there are no locked or runaway processes. Check disk loads for evidence of resource constraints.

# **DBCOLLREO**

**DBCOLLREQ**, JOURNAL EXTRACT proceeding without collation information for globals in database. eeee ffff.

MUPIP Warning: This is MUPIP JOURNAL EXTRACT Warning. This indicates that MUPIP process uses the default collation as it is not able to read the database file ffff because of error eeee

Action: Be aware that if the EXTRACT contains variables with alternative collation that this extract represents them as GT.M stores them, rather than as they are used by the application. Attempting to LOAD such an EXTRACT will produce incorrect results.

#### **DBCOMMITCLNUP**

**DBCOMMITCLNUP**, Pid dddd [hhhh] handled error (code = eeee) during commit of xxxx transaction in database file yyyy

Success Information: This message is output to the operator log and indicates that there was an error in the midst of committing a xxxx (TP or non-TP) transaction that involved the database file yyyy, but the process (pid = dddd in decimal and hhhh in hexadecimal) handled the error and completed the commit. If non-zero, the error code eeee is what triggered the error in the first place. If zero, accompanying syslog messages will contain information on the cause.

Action: In most cases the commit will be successfully completed. But in very rare cases, there might be errors that prevent the transaction from being successfully completed. To determine if there was any

error, examine the following operator log messages. If there are more then 3 (three) DBCLNUPINFO messages for the same database file from the same process-id, then that particular database is suspect and an integrity check of that database needs to be done at the earliest. In addition, contact your GT.M support channel with the operator log messages.

#### DBCOMPTOOLRG

DBCOMPTOOLRG, xxxx Record has too large compression count

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

## **DBCREC2BIG**

**DBCREC2BIG**, Record with key xxx is length yyy in block 0xaaa is greater than the maximum length yyy in database xxx

DBCERTIFY Error: DBCERTIFY has identified a record with the given key in the given block with a length that exceeds the maximum length allowed in the given database.

Action: This is typically due to the user reducing the maximum record length to meet the DBCERTIFY requirements but not verifying that no records exist that exceeds that length. The solution is to either delete or otherwise restructure the record or to MUPIP extract/load into a database with a larger blocksize.

#### DBCREC2BIGINBLK

DBCREC2BIGINBLK, A Record in block bbbb has a length greater than the maximum uuuuu in database dddd.

MUPIP Error: MUPIP UPGRADE for V5 triggers this error when the size of a record in block bbbb exceeds the maximum record size of uuuu in database region dddd.

Action: -

# **DBCREINCOMP**

**DBCREINCOMP**, xxxx Header indicates database file creation was interrupted before completion

Run Time/MUPIP Error: This is either a MUPIP Integ error, or this indicates that a database operation tried to activate a database file that was improperly initialized.

Action: Delete the damaged file and use MUPIP CREATE to recreate the database. Refer to 'MUPIP INTEG Error Messages' table in the Chapter 11-Maintaining Database Integrity, chapter of the Administration and Operations Guide of GT.M.

## **DBCRERR**

**DBCRERR**, Database file xxxx, cr location yyyy blk = zzzz error: aaaa was bbbb, expecting cccc --called from module xxx at line yyy

Run Time Error: This usually indicates that a process was abnormally terminated and left database control structures in an inconsistent state in shared memory.

Action: GT.M often fixes this error unless there is a more serious problem causing this error. If there is a more serious problem, accompanying messages identify the cause.

#### **DBCRERR8**

**DBCRERR8**, Database file xxxx, or location yyyy blk = zzzz error: aaaa was bbbb, expecting cccc -- called from module yyy at line xxx

Run Time Error: This message is the same as a DBCRERR message except that bbbb and cccc are 8-byte quantities (as opposed to 4-byte quantities in DBCRERR). See Error description for message DBCRERR.

Action: GT.M often fixes this error unless there is a more serious problem causing this error. If there is a more serious problem, accompanying messages identify the cause.

### **DBCSCNNOTCMPLT**

DBCSCNNOTCMPLT, Specified DBCERTIFY SCAN output file is not complete - Rerun scan

DBCERTIFY Error: DBCERTIFY CERTIFY has noted that the header of the scan phase output is not filled in indicating that the scan phase did not complete normally.

Action: Rerun DBCERTIFY SCAN to produce a complete output file for the certify phase to process.

#### **DBDANGER**

**DBDANGER**, Process pppp killed while committing update for database file xxxx. Possibility of damage to block yyyy.

Run Time Warning: This message is issued when a recovery of the database global buffer cache structures needs to be performed. It might discover that the cache recovery was necessary because of a GT.M process being killed (kill-9) while in the process of committing a change to the database. The cache recovery routine issues this message while proceeding with the recovery.

Action: This is a warning type message indicating possible database corruption due to process kills (kill-9). A database integrity check is recommended. Make sure that kill-9 or STOP/ID is not used to stop any GT.M processes.

### **DBDATAMX**

DBDATAMX, xxxx Record too large

MUPIP Error: This is a MUPIP INTEG error. Refer to the MUPIP INTEG Errors section.

Action: N/A

## **DBDIRTSUBSC**

DBDIRTSUBSC, <xxxx Directory tree block contains non name-level entries>

DSE/Run Time Information: This indicates that the specified database block has an internal structural damage since it contains subscripts global variable names even though this block is part of the directory tree.

Action: Report this database structure error to the group responsible for database integrity at your operation.

## **DBDSRDFMTCHNG**

**DBDSRDFMTCHNG**, Database file xxx, Desired DB Format set to yyy by zzz with pid ppp [0xppp] at transaction number [0xttt]

MUPIP Information: The desired database block format has been changed to version yyy for database file xxx by the zzz command with process number ppp at transaction number ttt.

Action: N/A

#### **DBENDIAN**

DBENDIAN, Database file xxxx is aaaa endian on a gggg endian system

Run Time/MUPIP Error: This indicates that the database file being opened is in the wrong endian format for the current system. This usually means that the file was copied from another system with the opposite endian format.

Action: To use the database file on the current system, change the endian format using the MUPIP ENDIANCVT command.

### **DBFGTBC**

**DBFGTBC**, xxxx File size larger than block count would indicate

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBFHFADERR**

Last used version: V5.3-001A

MR Manual V6.2-002 **DBFHEADERR**, Database file xxxx: control problem: yyyy was zzzz expecting aaaa

Run Time Error: This indicates that database cache recovery was triggered due to some abnormal event, and the recovery routine detected damage to the control structures in the database global buffer cache.

Action: The system automatically attempts to correct the problem. If this error continues to occur, attempt MUPIP RUNDOWN and if that fails too, restore database from backup and replay journal files. Report this error to your GT.M support channel if necessary.

#### **DBFHEADERR4**

DBFHEADERR4, DBFHEADERR4:Database file ffff: control problem: aaaa was xxxx expecting yyyy

Run Time Error: This indicates that database cache recovery was triggered due to some abnormal event, and the recovery routine detected damage to the control structures in the database global buffer cache.

Action: The system automatically attempts to correct the problem. If this error continues to occur, attempt MUPIP RUNDOWN and if that fails too, restore database from backup and replay journal files. Report the entire incident context to your GT.M support channel if necessary.

#### **DBFHEADERR8**

DBFHEADERR8, DBFHEADERR8: Database file ffff: control problem: aaaa was xxxx expecting yyyy

Run Time Error: This indicates that database cache recovery was triggered due to some abnormal event, and the recovery routine detected damage to the control structures in the database global buffer cache.

Action: The system automatically attempts to correct the problem. If this error continues to occur, attempt MUPIP RUNDOWN and if that fails too, restore database from backup and replay journal files. Report the entire incident context to your GT.M support channel if necessary.

#### **DBFHEADERRANY**

**DBFHEADERRANY**, Database file ffff: control problem: aaaa was xxxx expecting yyyy

Run Time Information: This indicates that database cache recovery was triggered due to an abnormal event and the recovery routine detected damage to the control structures in the database global buffer cache or the file header.

Action: The system automatically attempts to correct the problem. If this error continues to occur, attempt MUPIP RUNDOWN and if that fails too, restore database from backup and replay journal files. If necessary, report the entire incident context to your GT.M support channel.

#### **DBFILERR**

**DBFILERR**, Error with database file. xxxx.

Run Time Error: This indicates that an I/O operation on the database file encountered an error.

Action: Review the accompanying message(s) for a detailed error status.

### **DBFILEXT**

**DBFILEXT**, Database file xxxx extended from yyyy blocks to zzzz blocks at transaction aaaa

Run Time/MUPIP Information: This operator log message indicates that the specified database file extended as described by the message.

Action: -

#### **DBFILOPERR**

**DBFILOPERR**, Error doing database I/O to region xxxx

Run Time Error: This indicates that the database manager portion of the run-time system encountered an error when it attempted to open, read, write, or close a database file.

Action: Report this error to the group responsible for database integrity at your operation. Review the accompanying message(s) for additional information and analyze the system error log.

#### **DBFLCORRP**

**DBFLCORRP**, xxxx Header indicates database file is corrupt

Run Time/MUPIP Error: This indicates that a database operation tried to activate database file xxxx, which was previously marked as damaged.

Action: If ROLLBACK (either -NOONLINE or -ONLINE) terminates abnormally (say because of a kill -9), it leaves the database in a potentially inconsistent state indicated by the FILE corrupt field in the database file header. When an ROLLBACK terminates leaving this field set, all other processes receive DBFLCORRP errors any time they attempt to interact with the database. The best way to clear DBFLCORRP is by running another ROLLBACK. MUPIP SET -FILE -PARTIAL RECOV BYPASS and DSE CHANGE -FILE -CORRUPT=FALSE -NOCRIT can also clear this condition but these commands do not ensure that the database has consistent state so you should always run MUPIP INTEG after executing these commands.

### **DBFRZRESETFL**

**DBFRZRESETFL**. Freeze release failed on database file xxxx

MUPIP Error: This indicates that MUPIP failed to release the freeze on database file xxxx.

Action: Review the accompanying message(s) for additional information. Analyze DSE DUMP /FILE / ALL output.

#### **DBFRZRESETSUC**

**DBFRZRESETSUC**, Unfreeze successfully done on database file xxxx.

MUPIP Information: This indicates that RECOVER encountered a database file that had a state of FREEZE, and released the FREEZE.

Action: -

#### **DBFSTBC**

**DBFSTBC**, xxxx File size smaller than block count would indicate

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

## **DBFSTHEAD**

**DBFSTHEAD**, xxxx File smaller than database header

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

#### **DBFSYNCERR**

**DBFSYNCERR**, Error synchronizing database file xxxx to disk

Run Time Error: While using before-image journaling, the database is hardened to disk every time GT.M writes an epoch-record. If this operation returns an error, then the DBFSYNCERR error is issued to the user accompanied by system information about the cause of the system service error.

Action: Trouble shoot the file system, on which the database file resides, for issues related to FSYNC(). Report the entire incident context to your GT.M support channel along with any GT.M operator log messages within the same time frame.

### **DBGTDBMAX**

DBGTDBMAX, xxxx Key larger than database maximum

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBHEADINV**

**DBHEADINV**, xxxx Header size not valid for database

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBIDMISMATCH**

**DBIDMISMATCH**, Database file xxxx ID (region yyyy) does not match file ID in shared memory (ID=zzzz). Ensure region is properly rundown.

Run Time Error: When a GT.M process attaches to a database and finds the corresponding shared memory structures initialized already, it performs integrity checks on the shared memory contents to ensure that they correspond back to the database file. When the shared memory copy of the database file ID does not match with the actual file ID of the database, the above error is issued.

Action: Perform a MUPIP RUNDOWN on that region. If it fails with the same DBIDMISMATCH error, then the shared memory contents are corrupt. Consult your GT.M support channel before proceeding further.

# **DBINCLVL**

DBINCLVL, xxxx Block at incorrect level

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBINCRVER**

**DBINCRVER**, xxxx Incorrect version of GT.M database

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBINVGBL**

DBINVGBL, xxxx Invalid mixing of global names

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 51 MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBIOERR**

**DBIOERR**, Error while doing write operation on region rrrr (ffff)

Run Time Error: This error indicates that the process encountered an I/O error (other than ENOSPC) while trying to write to database file ffff (corresponding to region rrrr).

Action: Examine accompanying messages to identify the cause of the I/O error and take actions to rectify it.

# **DBJNLNOTMATCH**

**DBJNLNOTMATCH**, Database xxxx points to journal file name yyyy but the journal file points to database file zzzz

MUPIP Error: This indicates that there is a mismatch in the name of the database file xxxx and the name zzzz, saved in the journal file header yyyy.

Action: Contact your GT.M support channel if the cause of the error cannot be diagnosed. If appropriate change the database file name in the journal file using the command MUPIP SET /jnlfile / dbfilename=xxxx yyyy.

### **DBKEYGTIND**

**DBKEYGTIND**, xxxx Key greater than index key

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

#### **DBKEYMN**

**DBKEYMN**, xxxx Key too short

Run Time Warning: This indicates that a block certification or DSE/MUPIP integrity check failed on block xxxx since it contains a record at offset yvyy with a key that does not meet the minimum size requirement.

Action: Report this database structure error to the group responsible for database integrity at your operation.

# **DBKEYMX**

DBKEYMX, xxxx Key too long

Run Time Warning: This indicates that a block certification or DSE/MUPIP integrity check failed on block xxxx since it contains a record at offset yyyy whose key exceeds the allowable size.

Action: Report this database structure error to the group responsible for database integrity at your operation.

# **DBKEYORD**

DBKEYORD, xxxx Keys out of order

DSE/Run Time/MUPIP Warning: This indicates that a DSE/MUPIP INTEG command determined that the block contains a record at offset vyvy whose key is not in proper M collating sequence. This error is also reported at run-time if block certification failes on a particular block. Block certification is active if GDSCERT is enabled by a VIEW command.

Action: Report this database structure error to the group responsible for database integrity at your operation.

#### **DBKGTALLW**

**DBKGTALLW**, xxxx Key larger than maximum allowed length

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBLOCMBINC**

**DBLOCMBINC**, xxxx Local bit map incorrect

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBLRCINVSZ**

DBLRCINVSZ, xxxx Last record of block has invalid size

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 53

# **DBLTSIBL**

**DBLTSIBL**, xxxx Keys less than sibling's index key

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBLVLINC**

**DBLVLINC**, xxxx Local bitmap block level incorrect

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBMAXKEYEXC**

DBMAXKEYEXC, xxxx Maximum key size for database exceeds design maximum

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBMAXNRSUBS**

**DBMAXNRSUBS**, XXXX Maximum number of subscripts exceeded.

Compile Time Error: The subscripted variable required more than 31 subscripts.

Action: Modify the routine to observe this limit on subscripts in a single variable.

### DBMAXREC2BIG

**DBMAXREC2BIG**, Maximum record size (xxx) is too large for this block size (yyy) - Maximum is zzz

DBCERTIFY/MUPIP Error: DBCERTIFY and MUPIP UPGRADE report this error when the maximum record size is too close to the database blocksize and does not allow room for the expanded V5 block header.

Action: Reduce the maximum record size or mupip extract/load into a database with a larger blocksize. Note that if the maximum record size is reduced with DSE, it is possible that records that exceed the reduced size still exist in the database which is now an integrity error. DBCERTIFY SCAN will find these blocks and report on them if they exist.

# DBMAXRSFXBI

Last used version: V5.5-000

**DBMAXRSEXBL**, xxxx Maximum record size for database exceeds what the block size can support

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBMBMINCFRE**

**DBMBMINCFRE**, xxxx Master bit map incorrectly asserts this local map has free space

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBMBMINCFREFIXED**

**DBMBMINCFREFIXED**, Master bitmap incorrectly marks local bitmap 0xAAAA as free. Autocorrected

Run Time Warning: The above error is issued when the runtime engine detects an integrity error with the master map that indicates that the local bitmap 0xAAAA is free when in actually it is not. The error is also auto-corrected by the runtime engine by marking the local bitmap as full in the master bitmap.

Action: This error is entirely benign, but because it should not occur, be sure to check your next MUPIP INTEG output thoroughly and also check your operator logs prior to this warning for other unusual events.

### **DBMBPFLDIS**

**DBMBPFLDIS**, xxxx Master bit map shows this map full, in disagreement with both disk and INTEG results

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBMBPFLDLBM**

**DBMBPFLDLBM**, xxxx Master bit map shows this map full, agreeing with disk local map

V6.2-002 MR Manual June 09, 2015, Page 55 MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### DBMBPFLINT

**DBMBPFLINT**, xxxx Master bit map shows this map full, agreeing with MUPIP INTEG

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBMBPFRDLBM**

DBMBPFRDLBM, xxxx Master bit map shows this map has space, agreeing with disk local map

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBMBPFRINT**

**DBMBPFRINT**, xxxx Master bit map shows this map has space, agreeing with MUPIP INTEG

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBMBPINCFL**

**DBMBPINCFL**, xxxx Master bit map incorrectly marks this local map full

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBMBSIZMN**

**DBMBSIZMN**, xxxx Map block too small

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

FIS V6.2-002 GT.M Message and Recovery Procedures Manual Action: -

## **DBMBSIZMX**

DBMBSIZMX, xxxx Map block too large

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBMBTNSIZMX**

**DBMBTNSIZMX**, xxxx Map block transaction number too large

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBMINRESBYTES**

**DBMINRESBYTES**, Minimum RESERVED BYTES value required for certification/upgrade is xxx -Currently is yyy

DBCERTIFY/MUPIP Error: DBCERTIFY and MUPIP UPGRADE report this error when the reserved bytes field of the database file header (as shown by DSE DUMP -FILEHEADER) is not at a sufficient value for the GT.M V5 upgrade.

Action: Increase the reserved bytes value with either MUPIP or DSE so that the value is at least 8 bytes for UNIX and 9 bytes for OpenVMS. Note that the reserved bytes value is reduced by the above amounts by MUPIP UPGRADE.

### **DBMISALIGN**

**DBMISALIGN**, Database file xxxx has yyyy blocks which does not match alignment rules. Reconstruct the database from a backup or extend it by at least zzzz blocks.

MUPIP Error: This is an auxiliary message, and is preceded by a primary message.

Action: Follow the primary message description and action as specified in this manual.

# **DBMRKBUSY**

**DBMRKBUSY**, xxxx Block incorrectly marked busy

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 57 MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual

Action: -

### **DBMRKFREE**

**DBMRKFREE**, xxxx Block incorrectly marked free

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBMXRSEXCMIN**

**DBMXRSEXCMIN**, xxxx Maximum record size for database exceeds what the block size can support

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBNAMEMISMATCH**

**DBNAMEMISMATCH**, Database file xxxx (region (yyyy) referenced by shared memory (ID=zzzz) is not accessible. Ensure region is properly rundown

Run Time Warning: When a GT.M process attaches to a database and finds the corresponding shared memory structures already initialized, it performs integrity checks on the shared memory contents to ensure that they correspond back to the database file. When the shared memory points to a database file name that is not valid, this error is issued.

Action: This error means that the shared memory contents are corrupt; consult your GT.M support channel before proceeding further.

# **DBNOCRE**

**DBNOCRE**, Not all specified databases, or their associated journal files were created

MUPIP Warning: This indicates that MUPIP CREATE failed a task in creating the new database files.

Action: See accompanying messages for more detailed information on the failure.

# **DBNOREGION**

**DBNOREGION**, None of the database regions accessible

**DBNOTDB** Chapter 1. Error Messages

DSE/MUPIP Error: MUPIP INTEG or DSE can report this error. This indicates that none of the database files specified in the Global Directory could be opened (or they do not exist).

Action: Ensure the proper assignment for the environment variable, gtmglbdir/logical name GTM \$GBLDIR. Verify that the database file9s) specified in the Global Directory exist and that their protection allows access. Also, refer to the 'MUPIP INTEG Error Messages' table in the Chapter 11-Maintaining Database Integrity, chapter of the Administration and Operations Guide of GT.M.

### **DBNOTDB**

**DBNOTDB.** xxxx File does not have a valid GDS file header

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

#### **DBNOTGDS**

**DBNOTGDS**, xxxx - Unrecognized database file format

Run Time Error: This indicates that a database operation attempted to activate file xxxx, which is not a GDS file.

Action: Use GDE to ensure that the files in the Global Directory are properly named. It is likely that something other than GT.M or its utilities wrote to a database file or created a file with a name that coincides with one specified in the current Global Directory.

### **DBNOTMLTP**

**DBNOTMLTP**, xxxx Block size not a multiple of 512 bytes

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBOPNERR**

**DBOPNERR**, Error opening database file xxxx

Run Time Error: This indicates that a database operation tried to open the database file xxxx, which was inaccessible.

Action: Use GDE to ensure that the files in the Global Directory are properly named. Use the host shell command to ensure that the files exist and have proper security. Review the accompanying message(s) that indicate the reason for file-open failure.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 59

### **DBPREMATEOF**

**DBPREMATEOF.** Premature end of file with database file xxxx

Run Time Error: This indicates that the size of the database file is less than the size of the minimum required database file header. The file may not be a valid GT.M file.

Action: Investigate whether the file was properly created (with MUPIP) or inappropriately truncated. Also check whether the global directory points to a valid database.

# **DBPRIVERR**

**DBPRIVERR**, No privilege for attempted update operation for file: xxxx

Run Time Error: This indicates that the process did not have write access to database file xxxx.

Action: Disable application access to the function that resulted in the error or have the security manager grant write access to the appropriate user. Under some circumstances, security considerations may require moving some globals to other regions.

### **DBPTRMAP**

**DBPTRMAP**, xxxx Block pointer is a bit map block number

Run Time Error: This indicates that the block certification facility encountered a block pointer to a bitmap location (in the index block).

Action: Report this error to the group responsible for database integrity at your operation.

# **DBPTRMX**

**DBPTRMX**, xxxx Block pointer larger than file maximum

Run Time Warning: This indicates that a database operation failed because the block contains a record at offset vvvv whose block pointer points beyond the end of the file.

Action: Report this database structure error to the group responsible for database integrity at your operation.

# **DBPTRNOTPOS**

**DBPTRNOTPOS**, xxxx Block pointer negative

Run Time Warning: This indicates that xxxx block contains a record yyyy, which nests an invalid index pointer, and so failed block certification.

**DBQUELINK** Chapter 1. Error Messages

Action: Report this database structure error to the group responsible for database integrity at your operation.

# **DBQUELINK**

**DBOUELINK**, Database file xxxx, element location yyyy: blk = zzzz: control aaaa queue problem: was bbbb, expecting cccc

Run Time Error: This indicates that database cache recovery was triggered due to some abnormal event and the recovery routine detected damage to an internal GT.M queue control structure in the database global buffer cache.

Action: The system automatically attempts to correct the problem. If this error continues to occur, attempt MUPIP RUNDOWN and if that fails too, restore database from backup and replay the journal files. Report the error to your GT.M support channel if necessary.

# **DBRBNLBMN**

**DBRBNLBMN**, xxxx Root block number is a local bit map number

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBRBNNEG**

**DBRBNNEG**, xxxx Root block number negative

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBRBNTOOLRG**

**DBRBNTOOLRG**, xxxx Root block number greater than the last block number in file

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBRDERR**

**DBRDERR**, Cannot read database file xxxx after opening

MR Manual V6.2-002 June 09, 2015, Page 61 Run Time Error: This indicates that a database operation attempted reading the file xxxx without having the read access.

Action: Use the host shell commands to verify the file access and adjust it, if appropriate.

# **DBRDONLY**

**DBRDONLY**, Database file xxxx read only

Run Time Error: This indicates that a database operation tried to write to a read-only file or database.

Action: Verify the read and write privileges for the database and adjust it, if appropriate.

# **DBREADBM**

DBREADBM, xxxx Read error on bitmap

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBREMOTE**

**DBREMOTE**, Database region xxxx is remote; perform maintenance on the server node

DSE/MUPIP/LKE Error: This indicatest that a database maintenance operation was attempted on region xxxx. This node does not maintain the region directly; instead, it uses GT.CM to access the node as a client. This error is also reported by ^%GBLDEF if the target global is mapped to another node and served by GT.CM.

Action: Perform database maintenance on the server node.

# **DBRLEVLTONE**

DBRLEVLTONE, xxxx Root level less than one

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBRLEVTOOHI**

DBRLEVTOOHI, xxxx Root level higher than maximum

V6.2-002

**DBRNDWN** Chapter 1. Error Messages

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBRNDWN**

DBRNDWN, Error during global database rundown for region xxxx. Please notify those responsible for proper database operation.

Run Time Error: This indicates that a process encountered a problem attempting to rundown the database file xxxx.

Action: Refer to the associated messages for more information.

# **DBRNDWNWRN**

**DBRNDWNWRN**, Global database xxxx not rundown successfully by PID yyyy [zzzz]. Global section was not removed.

Run Time Error: When the last process attached to a GT.M database shared memory segment or global section detaches from the same, it normally removes the segment/section from the system. In case of an error while flushing the contents from the segment/section to the database file on disk, this removal is not done and this error is issued.

Action: Attempt a MUPIP RUNDOWN on that region. In case of an error, attempt corrective action corresponding to the displayed error.

#### **DBROLLEDBACK**

DBROLLEDBACK, Concurrent ONLINE ROLLBACK detected on one or more regions. The current operation is no longer valid

Run Time Error: This indicates a non-TP mini-transaction attempted to interact with the database and found that a concurrent online rollback had taken the database to a state earlier than the one at the end of the last mini-transaction by this process unless there has been an intervening TP transaction.

Action: Application dependent - this error indicates a discontinuity in the database state that may cause inconsistent application data.

# **DBROOTBURN**

**DBROOTBURN**, xxxx Root block has data level

DSE/Run Time Information: This indicates that the specified block has a block certification error or a DSE integrity error.

V6.2-002 MR Manual

Action: Report this database structure error to the group responsible for database integrity at your operation.

## **DBRSIZMN**

**DBRSIZMN**, xxxx Physical record too small

Run Time Warning: This indicates that a DSE or MUPIP INTEG command failed because block xxxx contains a record that does not meet the minimum size requirement.

Action: Report this database structure error to the group responsible for database integrity at your operation.

# **DBRSIZMX**

**DBRSIZMX**, xxxx Physical record too large

Run Time Warning: This indicates that a DSE or MUPIP INTEG command failed because block xxxx contains a record that exceeds the maximum record size (1MB) for a GDS database.

Action: Report this database structure error to the group responsible for database integrity at your operation.

# **DBSHMNAMEDIFF**

**DBSHMNAMEDIFF**, Database file ffff points to shared memory mmmm which points to a different database file

Run Time Error: Database access gives this error, if the database is copied or moved without properly closing it. This error indicates that database ffff and shared memory mmmmm do not correspond to each other.

Action: Perform MUPIP RUNDOWN on the database.

### **DBSPANCHUNKORD**

**DBSPANCHUNKORD**, xxxx Chunk of yyyy blocks is out of order

MUPIP Error: This is a MUPIP INTEG error. Refer to the MUPIP INTEG Errors section.

Action: N/A

# **DBSPANGLOINCMP**

**DBSPANGLOINCMP**, xxxx Spanning node is missing. Block no yyyy of spanning node is missing

V6.2-002 GT.M Message and Recovery Procedures Manual DBSTARCMP Chapter 1. Error Messages

MUPIP Error: This is a MUPIP INTEG error. Refer to the MUPIP INTEG Errors section.

Action: N/A

# **DBSTARCMP**

**DBSTARCMP**, DBSTARCMP xxxx Star record has nonzero compression count

Run Time Warning: This indicates that a block certification or DSE integrity check failed on xxxx. Block xxxx contains a record at offset yvyy that should be a star key; however, it has a non-zero compression count.

Action: Report this database structure error to the group responsible for database integrity at your operation.

# **DBSTARSIZ**

**DBSTARSIZ**, xxxx Star record has wrong size

Run Time Warning: This indicates that a block certification or DSE integrity check failed on xxxx. Block xxxx contains a record at offset yyyy whose star key does not have the proper size.

Action: Report this database structure error to the group responsible for database integrity at your operation.

## **DBSVBNMIN**

**DBSVBNMIN**, xxxx Start VBN smaller than possible

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual

Action: -

# **DBSZGT64K**

**DBSZGT64K**, xxxx Block size is greater than 64k

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBTN**

**DBTN**, Block TN is xxxx

MR Manual V6.2-002 Chapter 1. Error Messages DBTNLTCTN

MUPIP Information: This is an auxiliary message and is preceded by a primary message.

Action: Follow the primary message description and action as specified in this manual.

### **DBTNLTCTN**

**DBTNLTCTN**, Transaction numbers greater than the current transaction were found

MUPIP Information: This is an auxiliary message and is preceded by a primary message. It accompanies DBTNTOOLG.

Action: Follow the primary message description and action as specified in this manual.

# **DBTNNEQ**

**DBTNNEQ**, xxxx Current tn and early tn are not equal

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

# **DBTNRESET**

DBTNRESET, Cannot reset transaction number for this region

Run Time Error: This message is an auxiliary message to the DBRDONLY message.

Action: Follow the primary message description and action as specified in this manual.

# **DBTNRESETINC**

**DBTNRESETINC**, WARNING: tn\_reset for database is incomplete due to integrity errors

Run Time Warning: Automatic resetting of transaction number has not been done due to other errors.

Action: Clean up the other errors and then run integ again.

### **DBTNTOOLG**

**DBTNTOOLG**, xxxx Block transaction number too large

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBTOTBLK**

**DBTOTBLK**, Total blocks should be xxxx, is yyyy

MUPIP Information: This is an auxiliary message, and is preceded by a primary message.

Action: Follow the primary message description and action as specified in this manual.

#### **DBTTLBLK0**

DBTTLBLKO, xxxx Total blocks equal zero

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: -

### **DBUNDACCMT**

**DBUNDACCMT**, xxxx Cannot determine access method; trying with BG

MUPIP Error: This is a MUPIP INTEG error. Refer to the topic MUPIP INTEG Errors in About This Manual section of this manual.

Action: N/A

# **DBVERPERFWARN1**

DBVERPERFWARN1, Performance warning: Database aaaa is running in compatibility mode which degrades performance. Run MUPIP REORG UPGRADE for best overall performance.

Run Time Warning: This is a warning that the database is currently in compatibility (downgrade) mode. This mode causes all modified GDS blocks to be reformatted (to the downgraded database format) before they are flushed to the database file on disk. This is a very large performance hit.

Action: As the message indicates, run MUPIP REORG UPGRADE as soon as possible to move away from compatibility mode. This command can be run without taking the database offline. Once that completes successfully, the database is fully upgraded and there is no reformatting overhead anymore while flushing modified blocks to disk.

# **DBVERPERFWARN2**

**DBVERPERFWARN2**, Peformance warning: Database aaaa is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 67 Run Time Warning: This is a performance warning message that indicates the database is not yet fully upgraded i.e. there are still blocks in the database file that need to be upgraded. Staying in this mode causes some inefficiencies which include (but are not limited to) reading blocks from disk.

Action: As the message indicates, run MUPIP REORG UPGRADE at the earliest. This command can be run without taking the database offline. Once that completes successfully, the database file is fully upgraded.

# **DBWCVERIFYEND**

**DBWCVERIFYEND**, Database file xxxx, write cache verification finished by pid pppp [aaaa] at transaction number yyyy

Run Time Information: This indicates that process-id pppp (aaaa in hexadecimal) has completed verification of the database cache for the database file xxxx.

Action: -

### **DBWCVERIFYSTART**

**DBWCVERIFYSTART**, Database file xxxx, write cache verification started by pid pppp [aaaa] at transaction number bbbb

Run Time Information: This indicates that process-id pppp (aaaa in hexadecimal), has started a verification of the database cache for the database file xxxx.

Action: -

# **DCNINPROG**

**DCNINPROG**, Attempt to initiate operation while disconnect was in progress

GT.CM Error: This indicates that the GT.CM tried to link while disconnecting or experiencing network problems.

Action: Review network error logs.

# **DELIMSIZNA**

**DELIMSIZNA**, Delimiter size is not appropriate

Compile Time/Run Time Error: A socket related IO command (OPEN or USE) triggers this error if the delimiter string exceeds its maximum length.

Action: Use a delimiter string with an appropriate length.

# **DELIMWIDTH**

**DELIMWIDTH**, Delimiter length xxxx exceeds device width vvvv

Run Time Information: This indicates that the length of the first delimiter string specified in the DELIMITER deviceparameter exceeds the WIDTH of the socket device being OPENd (or USEd).

Action: Modify the first delimiter string to have a length of at most the WIDTH of the socket device.

# **DEVICEREADONLY**

**DEVICEREADONLY**, Cannot write to a read-only device

Run Time Error: The application made an attempt to WRITE to a read-only device.

Action: Review code and context to see if the WRITE was intended for another device, and if so add the appropriate USE. If the WRITE is intended for this device, change the device OPEN to permit the WRITE.

### DEVICEWRITEONLY

**DEVICEWRITEONLY**, Cannot read from a write-only device

Run Time Error: The application made an attempt to READ from a device in a WRITEONLY state, typically due to the OPEN command specifications.

Action: Check for logic errors and revise the code.

### **DEVNOTIMP**

**DEVNOTIMP**, XXXX device not implemented on in this environment

Run Time Error: This indicates that the device support is not available in the currently running version of GT.M.

Action: Refer to the GT.M documentation. Contact your GT.M support channel for information about the support available for this type of device on your platform.

#### **DEVOPENFAIL**

**DEVOPENFAIL**, Error opening xxxx

Run Time Error: This indicates that a GT.M process encountered an error while opening the device xxxx. A supplementary TEXT message and a system message provide more details about the cause of the error.

Action: Verify the device exists on the system where the OPEN is being attempted.

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 69

# **DEVPARINAP**

**DEVPARINAP**, Device parameter inappropriate to this command

Compile Time Error: This indicates that an OPEN, USE, or CLOSE command specifies a deviceparameter that does not apply to the command.

Action: Look for deviceparameters that should be on other I/O commands. For example, the deviceparameter "DELETE" is valid on CLOSE but produces this error if it is applied to the USE command.

### **DEVPARMNEG**

**DEVPARMNEG**, Deviceparameter must be a positive value

Run Time Error: This indicates that the argument to the deviceparameter had a negative value where only positive values are appropriate.

Action: Modify the argument to provide a positive value.

### **DEVPARMTOOSMALL**

**DEVPARMTOOSMALL**, Deviceparameter must be greater than zero (0)

Compile Time/Run Time Error: This error occurs when the TIMEOUT=<seconds> deviceparameter of a CLOSE command specifies a value less than one second. For PIPE devices that are not OPEN'd with the INDEPENDENT deviceparameter, the CLOSE command waits for a maximum of TIMEOUT=<seconds> before checking the termination status of the PIPE co-process.

Action: Specify an integer value greater than 0 as the TIMEOUT.

#### DEVPARPROT

**DEVPARPROT**, The protection specification is invalid

Compile Time Error: This indicates that an OPEN, USE, or CLOSE command specified a protection deviceparameter with an improperly formatted argument.

Action: Modify the protection mask.

# **DEVPARTOOBIG**

**DEVPARTOOBIG**, String deviceparameter exceeds 255 character limit

Compile Time/Run Time Error: This indicates that an OPEN, USE, or CLOSE command specified a deviceparameter that equated to a string expression whose evaluated length exceeds 255 characters. **DEVPARUNK** Chapter 1. Error Messages

Action: Verify the program logic and modify it to use shorter deviceparameter strings.

# **DEVPARUNK**

**DEVPARUNK**, Deviceparameter unknown

Compile Time Error: This indicates that an OPEN, USE, or CLOSE command specified an unrecognized keyword instead of an expected deviceparameter.

Action: Modify the deviceparameter in question.

# **DEVPARVALREQ**

**DEVPARVALREQ**, A value is required for this device parameter

Compile Time Error: This indicates that an OPEN, USE, or CLOSE command specified a valid deviceparameter that requires a value; however, one was not provided.

Action: Ensure that deviceparameters have values where required. For example, the deviceparameter WRAP is valid but must include a value for the wrap length.

#### **DIRONLY**

**DIRONLY**, Directories only are allowed in file specs: xxxx

Run Time Error: This indicates that a SET of \$ZROUTINES specified a SRC qualifier with an argument element xxxx that was not a valid directory specification.

Action: Look for missing parenthesis or brackets.

### **DISTPATHMAX**

**DISTPATHMAX**, \$gtm\_dist path is greater than maximum (xxxx)

Run Time Error: This indicates that the path specified by the gtm dist environment variable has exceeded the indicated maximum limit of 1024 bytes.

Action: Move the directory or use a link to shorten the path.

# **DIVZERO**

**DIVZERO**, Attempt to divide by zero

Run Time Error: This indicates that a divide or module operator had a zero for its divisor operand.

Action: Modify the routine to protect against zero division.

V6.2-002 MR Manual

# **DLCKAVOIDANCE**

**DLCKAVOIDANCE**, Possible deadlock detected: Database pppp: Dbtn qqqq: t\_tries rrrr: dollar\_trestart ssss: now\_crit tttt: TP transaction restarted

Run Time Error: This indicates that GT.Ms deadlock avoidance algorithm got triggered and aborted a possible deadlock.

Action: Report the error to your GT.M support channel with complete operator log information.

# **DLLCHSETM**

**DLLCHSETM**, Routine XXX in library YYY was compiled with CHSET=M which is different from \$ZCHSET. Recompile with CHSET=UTF-8 and re-link.

Run Time Error: This error is triggered when a UTF-8 mode process attempts to execute a shared library's routine that was complied in M-mode.

Action: Recompile and relink the routine using UTF-8-mode settings or switch to M mode.

### **DLLCHSETUTF8**

**DLLCHSETUTF8**, Routine XXX in library YYY was compiled with CHSET=UTF-8 which is different from \$ZCHSET. Recompile with CHSET=M and re-link.

Run Time Error: This error is triggered when an M mode process attempts to execute a shared library's routine that was complied in UTF-8 mode.

Action: Recompile and relink the routine using M-mode settings or switch to UTF-8 mode.

# **DLLNOCLOSE**

**DLLNOCLOSE**, Failed to unload external dynamic library

Run Time Error: This indicates that the process encountered a problem attempting to unload a dynamically linked library.

Action: Refer to the associated messages for more information.

# **DLLNOOPEN**

**DLLNOOPEN**, Failed to load external dynamic library xxxx

Run Time Error: This indicates that the process encountered a problem attempting to load a dynamically linked library.

Action: Refer to the associated messages for more information.

# **DLLNORTN**

**DLLNORTN**, Failed to look up the location of the symbol xxxx

Run Time Error: This indicates that the process was unable to find the routine it needed in the dynamically linked library.

Action: Ensure that the environment variable for dynamic library path is defined and correctly locates the shared library file, as well as any other dependent shared libraries. Also ensure that the sumbol xxxx is defined in one of the libraries.

### **DLLVERSION**

**DLLVERSION**, Routine aaaa in library bbbb was compiled with an incompatible version of GT.M. Recompile with the current version and re-link.

Run Time Error: This indicates that the routine aaaa that was loaded out of the shared library bbbb was compiled with a version of GT.M that is not compatible with the current version of GT.M.

Action: Recompile the M routine aaaa and re-link (recreate) the shared library. The linker options for creating a shared library are platform dependant. Refer to GT.M Programmer's Manual for details.

### **DLRCILLEGAL**

DLRCILLEGAL, Illegal \$CHAR() value xxxx

MUPIP Error: This indicates that MUPIP LOAD with the qualifier FORMAT=GO or ZWR encountered an invalid Unicode code point xxxx for \$CHAR() in its input stream.

Action: Edit or recreate the input file so the value falls within the valid range of Unicode code points.

# **DLRCTOOBIG**

**DLRCTOOBIG**, xxxx value cannot be greater than 255

MUPIP Error: This indicates that MUPIP LOAD with the qualifier FORMAT=GO encountered xxxx in its input stream. xxxx was in the \$CHAR() format used for non-graphic characters but it exceeded the maximum acceptable value of 255.

Action: Refer to the topic MUPIP LOAD Errors in About This Manual section of this manual. Edit the input file so the value falls within the range of 0-255.

# **DLRCUNXEOR**

**DLRCUNXEOR**, xxxx unexpected end of record in \$CHAR()/\$ZCHAR() subscript

MR Manual V6.2-002 June 09, 2015, Page 73 MUPIP Error: This indicates that MUPIP LOAD with the qualifier FORMAT=GO encountered xxxx in its input stream. xxxx was in the \$CHAR() format used for non-graphic characters but the \$C() format did not complete properly.

Action: Refer to the topic MUPIP LOAD Errors in About This Manual section of this manual. Edit the input file to remove a spurious "\$" or fix a \$CHAR() representation.

### **DSEBLKRDFAIL**

**DSEBLKRDFAIL**, Failed attempt to read block

DSE Error: This indicates that DSE could not read the block from the database file. This error may also be caused by attempts to reference blocks outside of the database. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Make sure that the referenced block is less than the total blocks. If not, report this database cache error to the group responsible for database integrity at your operation.

# **DSEFAIL**

**DSEFAIL**, DSE failed. Failure code: xxxx.

DSE Error: This indicates that DSE could not complete a database operation. xxxx contains failure codes for the four attempts. It is very likely that the database may have integrity errors or that the processprivate data structures are corrupted.

Action: Report this database structure error to the group responsible for database integrity at your operation.

## **DSEINVLCLUSFN**

**DSEINVLCLUSFN**, Specified function is invalid for clustered databases

DSE Error: This indicates that the DSE command (WCINIT or ALL used with the qualifiers RENEW or WCINIT) requested a cache reinitialization on a clustered database.

Action: This operation is managed automatically by the Cluster Control Program (CCP) on the first node to open the database file. Once the database is in use, all nodes must drop access in order to reinitialize the database cache.

## **DSEMAXBLKSAV**

DSEMAXBLKSAV, DSE cannot SAVE another block as it already has the maximum of mmmm

DSE Error: The current SAVE -BLOCK operation exceeds DSE's capacity to hold more than mmmm saved blocks

FIS V6.2-002 GT.M Message and Recovery Procedures Manual Action: Delete some saved blocks, possibly after RESTORE'ng them to free blocks, or restart DSE if none of the currently saved blocks have value.

## **DSENOFINISH**

**DSENOFINISH**, DSE unable to finish all requested actions

DSE Error: This indicates that DSE was not able to complete the actions it was directed to perform.

Action: Refer to the associated message(s) for more information.

# **DSENOTOPEN**

**DSENOTOPEN**, DSE could not open region rrrr - see DSE startup error message for cause

DSE Error: DSE could not operate on region rrrr because it was not able to open it when DSE started.

Action: Review the error messages issued when DSE started and address the issue(s) they describe.

### **DSEONLYBGMM**

**DSEONLYBGMM**, xxxx is supported only for BG/MM access methods

DSE Warning: This indicates that the current region has an access method that is neither Buffered Globals nor Memory Mapped. DSE can not flush such a region.

Action: Before starting DSE, make sure that the Global Directory contains regions that have an access method of Buffered Globals or Memory Mapped.

### **DSEWCINITCON**

**DSEWCINITCON**, No action taken, enter YES at CONFIRMATION prompt to initialize global buffers

DSE Warning: This indicates that DSE did not yet perform the operation that was initiated by the WCINIT command or the ALL command with either the WCINIT or RENEW qualifier because the operator did not confirm it.

Action: To perform these operations, enter YES at the CONFIRMATION prompt to verify your intention to perform this potentially disruptive operation. The DSE WCINIT command reinitializes shared memory structures for the current region.

### **DSEWCREINIT**

**DSEWCREINIT**, Database cache reinitialized by DSE for region rrrr

DSE Information: This indicates a DSE operator action to rebuild the database cache for region rrrr.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 75 Action: None required.

# **DSKNOSPCAVAIL**

**DSKNOSPCAVAIL**, Attempted write to file FFFF failed due to lack of disk space. Retrying indefinitely.

Run Time Error: This error indicates that GT.M could not update file FFFF due to lack of disk space in the file system. If -INST\_FREEZE\_ON\_ERROR is enabled, GT.M automatically disables it (sending a DSKSPCAVAILABLE message to the operator log) when adequate disk space becomes available again.

Action: Make disk space available in the file system to allow updates to file FFFF.

# **DSKNOSPCBLOCKED**

**DSKNOSPCBLOCKED**, Retry of write to file FFFF suspended due to new instance freeze. Waiting for instance to be unfrozen.

Run Time Error: This error indicates that a process waiting for space to write to file FFFF determined that another process froze the replication instance. The process will not make more attempts to write to the file until the replication instance is unfrozen.

Action: Check the system log for the most recent REPLINSTFROZEN message to determine the cause of the current freeze and resolve it.

### **DSKSPACEFLOW**

**DSKSPACEFLOW**, Disk space for file xxxx nearing maximum size. YYYY blocks available.

Run Time Warning: This indicates that disk space for the specified file system, on which the database / journal files are located, is almost full.

Action: Review and make disk space.

# **DSKSPCAVAILABLE**

**DSKSPCAVAILABLE**, Write to file FFFF succeeded after out-of-space condition cleared.

Success Information: This indicates that the file system of file FFFF has enough space to allow further updates (previously not possible as indicated by a DSKNOSPCAVAIL error message).

Action: None Required.

#### **DUPTN**

**DUPTN**, Duplicate transaction found [TN = xxxx] at offset aaaa in journal file yyyy

MUPIP Warning: This indicates that two different transactions have the same transaction number.

Action: Report the entire incident context to your GT.M support channel.

# **DUPTOKEN**

**DUPTOKEN**, Token xxxx is duplicate in the journal file yyyy for database zzzz

MUPIP Error: This indicates that two transactions (TP or ZTP) have the same token (xxxx), in the specified journal file yyyy, violating the uniqueness of the ID that distinguishes transactions from one another. The result is that both transactions are considered broken and reported in the broken transactions extract file.

Action: Report the entire incident context to your GT.M support channel.

# **DVIKEYBAD**

**DVIKEYBAD**, \$ZGETDVI("xxxx","yyyy") contains an illegal keyword

Run Time Error: This indicates that a \$ZGETDVI function encountered an invalid keyword. xxxx is the device. yyyy is the keyword.

Action: Verify the spelling of the keyword.

### **DYNUPGRDFAIL**

DYNUPGRDFAIL, Unable to dynamically upgrade block 0xaaa in database yyy due to lack of free space in block

DBCERTIFY/Run Time Error: There was not enough free space in the block to convert it in place to the current format during normal database access. This indicates that the DBCERTIFY database certification procedure was not properly carried out.

Action: Either mark the block free (making appropriate index changes) or downgrade the database and re-run DBCERTIFY (both phases).

### **DZTRIGINTRIG**

**DZTRIGINTRIG**, \$ZTRIGGER() is not allowed inside trigger context. Trigger name: nnnn

Run Time Error: This message indicates an attempt to use the \$ZTRIGGER() function, which potentially modifies triggers, while executing code within the context of some trigger.

Action: Rework the code to modify or examine triggers so that it falls outside of trigger execution.

# **DZWRNOALIAS**

**DZWRNOALIAS.** \$ZWRTAC cannot be aliased.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 77 Compile Time Error: This indicates the argument for a SET \* command attempted to assign a \$ZWRTAC\* pseudo-variable as a alias.

Action: Correct the code in question - the \$ZWRTAC\* is only useful in restoring context from ZSHOW or ZWRITE output and has very narrow capabilities.

### **DZWRNOPAREN**

DZWRNOPAREN, \$ZWRTACxxx is not allowed inside a parenthesized SET target

Compile Time Error: This indicates the argument for a SET command attempted to assign a \$ZWRTAC\* pseudo-variable within a parenthesized list of left-hand arguments.

Action: Correct the code in question - the \$ZWRTAC\* is only useful in restoring context from ZSHOW or ZWRITE output and has very narrow capabilities.

# **ECLOSTMID**

**ECLOSTMID**, \$ECODE overflow, the first and last ecodes are retained, but some intervening ecodes have been lost

Run Time Warning: If the \$ECODE exceeds the maximum string length, references to it return only the codes for the earliest and latest errors separated by the code for ECLOSTMID, which indicates that suppression of intervening error codes has occurred to accommodate string length restrictions.

Action: Consider whether it would be appropriate to introduce code to SET \$ECODE= . This error is encountered either when the \$ETRAP error handling is recursing (and probably defective), or while using \$ZTRAP error handling that was coded prior to the introduction of \$ECODE.

# **ENDIANCVT**

ENDIANCVT, Converted database file xxxx from yyyy endian to zzzz endian on a wwww endian system

MUPIP Information: When MUPIP ENDIANCVT has successfully completed, it displays the conversion information. This information includes the database file, its previous endian format, the new endian format, and the endian format that is native to the current system.

Action: N/A

# **ENOSPCQIODEFER**

**ENOSPCQIODEFER**, Write to file FFFF deferred due to lack of disk space

Information: This indicates GT.M chose to defer updating the file FFFF to avoid a possible deadlock. GT.M uses this message only if the environment is configured for Instance Freeze.

FIS V6.2-002 GT.M Message and Recovery Procedures Manual Action: None.

# **EORNOTFND**

EORNOTFND, xxxx End of record not found

MUPIP Error: This indicates that LOAD encountered a database reference record containing an open parenthesis without a close parenthesis. xxxx is the record.

Action: Refer to the topic MUPIP LOAD Errors in About This Manual section of this manual.

# **EPOCHTNHI**

**EPOCHTNHI**, At the EPOCH record at offset xxxx of yyyy transaction number [0xaaaa] is higher than database transaction number [0xbbbb]

MUPIP Error: This indicates that during turnaround point from where mupip applies logical records, backward recover found that epoch's transaction number is greater than the current database transaction number.

Action: Contact your system administrator and if necessary report the entire incident context to your GT.M support channel.

# **EQUAL**

EQUAL, Equal sign expected but not found

Compile Time Error: This indicates that a SET or FOR specified the left side of an assignment statement but not the expected equal (=) sign.

Action: Look for a missing equal sign.

### **ERRCALL**

**ERRCALL**, Error called from xxxx line yyyy

Run Time Error: This message provides additional diagnostic information related to accompanying messages.

Action: Review accompanying messages for additional information about the cause of this error. If necessary, report the entire incident context to your GT.M support channel.

# **ERRORSUMMARY**

**ERRORSUMMARY**, Errors occurred during compilation

Compile Time Error: This indicates that GT.M encountered one or more errors during compilation.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual

Action: Review the individual error messages for further information. The compilation may have produced code that is usable as long as the execution path does not encounter the error(s).

## **FRRWFTRAP**

**ERRWETRAP**, Error while processing \$ETRAP

Run Time Error: This indicates that \$ETRAP contained invalid M code or caused a run time error.

Action: Check the \$ETRAP variable. To get more information about the errors- SET \$ZTRAP to empty string, and a temporary variable to the contents of \$ETRAP. Then, SET \$ETRAP to "BREAK" and XECUTE the temporary variable. It is best to keep the source code in \$ETRAP simple if \$ZTRAP is an empty string, since ETRAP specifies a string that GT.M invokes upon encountering an exception condition.

### **ERRWEXC**

**ERRWEXC**, Error while processing exception string

Run Time Error: This indicates that an exception string contained invalid M code or caused a run-time error.

Action: Review the exception string and \$ZTRAP. To get more information about the errors, SET a temporary variable to the contents of the exception string. Then, SET the exception string to "BREAK" and XECUTE the temporary variable.

### **ERRWIOEXC**

**ERRWIOEXC**, Error while processing I/O exception string

Run Time Error: This indicates that a device EXCEPTION string contained invalid M code or caused a run-time error.

Action: Review the exception string. To get more information about the errors, SET a temporary variable to the contents of the exception string and XECUTE the temporary variable. The EXCEPTION deviceparameter on an OPEN, USE, or CLOSE command defines an error handler for an I/O device.

### **ERRWZBRK**

ERRWZBRK, Error while processing ZBREAK action string

Run Time Error: This indicates that a ZBREAK action contained invalid M code or caused a run-time error.

Action: Review the ZBREAK action string. To get more information about the errors, SET a temporary variable to the contents of the ZBREAK action string and XECUTE the variable. ZBREAK sets temporary break and trace points.

# **ERRWZINTR**

**ERRWZINTR**, Error while processing \$ZINTERRUPT

Run Time Error: This indicates that a job interrupt had been signaled but that there was an error compiling the \$ZINTERRUPT string. This message is sent to the operator log facility and if at the direct mode prompt or executing a direct mode command to the user console.

Action: Correct the \$ZINTERRUPT to contain valid GT.M commands.

### **ERRWZTRAP**

**ERRWZTRAP**, Error while processing \$ZTRAP

Run Time Error: This indicates that \$ZTRAP contained invalid M code or caused a run-time error.

Action: Verify the \$ZTRAP variable. To get more information about the errors, SET a temporary variable to the contents of \$ZTRAP. Then, SET \$ZTRAP to "BREAK" and XECUTE the variable. Make sure the source code in \$ZTRAP is simple because ZTRAP specifies a string that GT.M invokes when it encounters an exception condition.

### **EVENTLOGERR**

**EVENTLOGERR**, Error in event logging subsystem

Run Time Error: This indicates that the user is unable to access the event logging shared library or an event logging routine within the shared library.

Action: Review accompanying messages for additional information.

# **EXCLUDEREORG**

EXCLUDEREORG, Global: xxxx is present in the EXCLUDE option. REORG will skip the global.

MUPIP Warning: This indicates that MUPIP did not reorg the specified global because it was also mentioned in the EXCLUDE qualifier.

Action: Take out the global name from the EXCLUDE option and do not specify a global name in both the SELECT and EXCLUDE options.

# **EXECOM**

EXECOM, Executing command file xxxx

GDE/DSE Information: This indicates that an @ command activated command file xxxx.

Action: -

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual

## **EXPR**

**EXPR**, Expression expected but not found

Compile Time Error: This indicates that GT.M did not encounter a valid expression when it expected one.

Action: Look for missing expressions or extra delimiters, such as a space, comma, or colon.

### **EXTGBLDEL**

**EXTGBLDEL**, Invalid delimiter for extended global syntax

Run Time Error: This indicates that the global reference started with a vertical bar (|) or left-bracket ([), indicating that it includes an environment specification (Global Directory). However, the environment specification did not terminate with either a vertical bar (|) or right-bracket (]), respectively.

Action: Insert the appropriate trailing delimiter for the environment specification or remove the environment specification.

#### **EXTRACTCTRLY**

**EXTRACTCTRLY**, User interrupt encountered during extract, halting

MUPIP Warning: This indicates that EXTRACT encountered either a <CTRL>-Y or two <CTRL>-C in quick succession during the course of its operation and aborted prior to normal completion.

Action: If the results of the EXTRACT are needed, reactivate it.

### **EXTRACTFILERR**

Last used version: V4.4-000

**EXTRACTFILERR**, Error with extract file xxxx

MUPIP Error: This indicates that EXTRACT encountered an error when opening its output file: xxxx.

Action: Review the accompanying message(s) for additional information.

# **EXTRCLOSEERR**

EXTRCLOSEERR, Error closing extract file xxxx

MUPIP Error: OpenVMS or RMS error closing the specified xtract output file, during the MUPIP EXTRACT.

**EXTRFAIL** Chapter 1. Error Messages

Action: Refer to the accompanying message(s) for details and take appropriate action.

# **EXTRFAIL**

EXTRFAIL, Extract failed for the global gggg. MUPIP INTEG should be run.

MUPIP Error: A MUPIP EXTRACT operation on the global gggg failed because of database consistency issues.

Action: Run the MUPIP INTEG command to identify the database consistency issues. See verfiy database integrity 11.html for more information.

### **EXTRFILEXISTS**

**EXTRFILEXISTS**, Error opening output file: ffff -- File exists

Run Time Error: This message indicates that the specified output file already exists.

Action: Specify another file name and/or directory.

# **EXTRFMT**

**EXTRFMT**, Extract error: bad format type. Must be ZWR, GO, or BINARY.

MUPIP Error: This indicates that EXTRACT could not create the sequential output file because of an invalid format specified.

Action: Change the format to one of the three supported formats.

### **EXTRIOERR**

**EXTRIOERR**, Error writing extract file xxxx

MUPIP Error: OpenVMS or RMS errors writing to the specified extract output file, during the MUPIP EXTRACT.

Action: Refer to the accompanying message(s) for details and take appropriate action.

# **EXTSRCLIN**

**EXTSRCLIN**, xxxx yyyy

Run Time Error: This indicates that there is an error in the external call table. The message indicates the line where GT.M found the error.

Action: Review the line listed in the message and correct the error.

V6.2-002 MR Manual

## **EXTSRCLOC**

EXTSRCLOC, At column xxxx, line yyyy, source module zzzz

Run Time Error: This indicates that there is an error in the external call table. The message indicates the line and the location within that line where the error is located.

Action: Review the listed line and location and correct the error.

## **FALLINTOFLST**

**FALLINTOFLST**, Fall-through to a label with formallist is not allowed

Run Time Error: This error indicates that M code reached a label with a formallist by falling through from the previous label.

Action: Revisit your code to ensure that all invocations of labels with a formallist occur using a DO command or extrinsic function (\$\$).

# **FCHARMAXARGS**

FCHARMAXARGS, Argument count of \$CHAR() function exceeded the maximum of 255

Compile Time Error: This indicates that a \$CHAR() function specified an argument that was not in the range of 0 to 255. This error is also reported by services that attempt to format data using \$CHAR() format.

Action: Look for large or negative \$CHAR() arguments and ensure that all the arguments contain valid ASCII codes.

# **FCNSVNEXPECTED**

FCNSVNEXPECTED, Function or special variable expected in this context

Compile Time Error: This indicates that GT.M encountered a dollar sign in an expression that was not followed by a valid function or special variable name.

Action: Look for misspelled function and special variable names or a missing \$ in an extrinsic.

# **FILECREATE**

FILECREATE, AAAA file xxxx created

MUPIP Information: This indicates that a file xxxx was created due to AAAA, where AAAA is lost transaction, broken transaction, or Journal Extract file.

Action: Look for the xxxx file for further relevant data.

# **FILEDEL**

FILEDEL, File xxxx successfully deleted

Run Time/MUPIP Information: This indicates that GT.M or MUPIP has successfully deleted a file. This message is issued when a journal file in an inconsistent state found and deleted by the run-time system or MUPIP SET. This message is also issued by MUPIP JOURNAL RECOVER/ROLLBACK command when it deletes journal files that were created by a previously interrupted RECOVER/ROLLBACK command and are no longer necessary.

Action: -

# **FILEDELFAIL**

**FILEDELFAIL**. Deletion of file xxxx failed

Run Time/MUPIP Warning: This indicates that GT.M or MUPIP failed to remove the specified journal file xxxx.

Action: Review the accompanying message(s) for additional information.

# **FILEEXISTS**

**FILEEXISTS**, File xxxx already exists

MUPIP Error: This indicates that MUPIP discovered a file with the filename xxxx already existing and did not overwrite it while executing the specified command(s).

Action: Rename the already existing file xxxx and reissue the MUPIP command(s), or modify the MUPIP command to name (explicitly/implicitly) a file different from xxxx.

# **FILEIDGBLSEC**

FILEIDGBLSEC, File ID in global section does not match with the database file

Run Time Error: When a GT.M process attaches to a database and finds the corresponding shared memory structures initialized already, it performs integrity checks on the shared memory contents to ensure that they correspond back to the database file. When the shared memory copy of the database file ID does not match with the actual file ID of the database, this error is issued.

Action: Perform a MUPIP RUNDOWN on that region. If it fails with the same FILEIDGBLSEC error, then the shared memory contents are corrupt. Consult your GT.M support channel before proceeding further.

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 85

# **FILEIDMATCH**

**FILEIDMATCH**, Saved File ID does not match the current ID - the file appears to have been moved

Run Time Error: This indicates that the journal file identified by a database in turn identifies itself as belonging to another database. Since a journal file must have a one-to-one relationship with a database, the process cannot do updates on this region until the problem is resolved.

Action: Create a new journal file, make a backup if appropriate and resume work.

# **FILENAMETOOLONG**

FILENAMETOOLONG, File name too long

Run Time/MUPIP Information: This indicates that GT.M or MUPIP has encountered a file name exceeding the maximum permissible length. In OpenVMS all logical names are expanded and the expanded name must be within the maximum file name length permitted by GT.M.

Action: -

### **FILENOTCREATE**

FILENOTCREATE, AAAA file xxxx not created

MUPIP Information: This indicates that the file xxxx was not created due to AAAA; where AAAA is lost transaction, or broken transaction, or Journal Extract file.

Action: Review accompanying messages for any further information. If there are no accompanying messages, it indicates that MUPIP did not find any lost or broken transactions for the corresponding extract file to be created.

# **FILENOTFND**

**FILENOTFND**, File xxxx not found

Compile Time/Run Time Error: This indicates that GT.M could not locate the specified source file xxxx.

Action: Look for a misspelling of the file-specification or improper preparation of the environment. If xxxx is a source file, it could have been moved or modified since the object in the image was compiled. Use ZLINK to make the object match the source.

## **FILEOPENFAIL**

**FILEOPENFAIL**, Failed to open file ffff.

MUPIP Error: This message indicates that the MUPIP LOAD failed to open input file ffff.

Action: Please verify path and permission of input file ffff.

## **FILEPARSE**

**FILEPARSE**, Error parsing file specification: xxxx

Run Time Error: This indicates a problem with the specification of file xxxx, or the path to it. If the file is a source or object file, a ZLINK command or \$ZROUTINES-related action encountered the error.

Action: Look for, and correct any typographical errors in the file-specification.

### **FILERENAME**

**FILERENAME**, File xxxx is renamed to yyyy

Run Time Information: This indicates that an existing file xxxx has been renamed to yyyy so that a new file created with the original name does not overwrite the existing one. GT.M renames files during an automatic journal switch in case no explicit journal file name is specified, in which case the message is sent to the operator log. The utilities (MUPIP, GT.CM) rename files while opening log files or journal extract files and they send the message to the terminal. GT.M or utilities rename files only if the new file name specified already exists.

Action: -

### **FILTERBADCONV**

FILTERBADCONV, Bad conversion of transaction xxxx by filter

Run Time Error: This error is logged to the replication server log file. This indicates that the output of the user-supplied external replication filter for the transaction with journal sequence number xxxx is incorrect.

Action: Fix the filter. Restart the replication server with the fixed filter.

#### **FILTERCOMM**

FILTERCOMM, Error communicating transaction xxxx with the filter

Run Time Error: This error is logged to the replication server log file. This indicates that the replication server encountered an error writing transaction with journal sequence number xxxx to the user supplied external filter's input. The accompanying system error message gives more details.

Action: Stop the filter and restart the replication server with the filter. Report the entire incident context to your GT.M support channel.

### **FILTERNOTALIVE**

**FILTERNOTALIVE**, Replication server detected that the filter is not alive while attempting to send transaction xxxx

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 87 Run Time Error: This error is logged to the replication server log file. This indicates that the replication server detected abnormal termination of the user supplied external filter while attempting to write transaction with journal sequence number xxxx to the filter's input.

Action: Determine the cause of the filter's abnormal termination. Fix the filter and restart the replication server with the fixed filter.

## **FILTERTIMEDOUT**

FILTERTIMEDOUT, Replication server timed out attempting to read sequo ssss from external filter

MUPIP Error: This indicates that either a Source or Receiver Replication Server using an external filter took more than 30 sec to read a transaction with journal sequence number ssss from the user supplied external filter's output. The replication server reports this error in its log, stops the filter and terminates.

Action: Determine the cause for the filter's write delay. Fix the filter and restart the replication server with the fixed filter. If you cannot determine reason for delay, report the entire incident context to your GT.M support channel.

### **FMLLSTMISSING**

FMLLSTMISSING, The formal list is absent from a label called with an actual list: xxxx

Compile Time/Run Time Error: This indicates that a DO attempted to transfer control with an actuallist to a label xxxx that has no formallist.

Action: Look at the interface between the DO and the subroutine. Modify the actuallist, formallist, and/ or label as appropriate.

### **FMLLSTPRESENT**

Last used version: V5.4-002B

**FMLLSTPRESENT**, The actual list is absent from a call to a label with a formal list: xxxx

Compile Time/Run Time Error: This indicates that a DO attempted to transfer control with no actuallist to a label xxxx that has a formallist.

Action: Look at the interface between the DO and the subroutine. Modify the actuallist, formallist, and/ or label as appropriate.

### **FNARGINC**

**FNARGINC**, Format specifiers to \$FNUMBER are incompatible: "xxxx"

Run Time Error: This indicates that a \$FNUMBER function specified a format containing codes xxxx, which is incompatible code.

V6.2-002 GT.M Message and Recovery Procedures Manual Action: Look for the character code "P" or "p" with any character other than the code ",".

### **FNNAMENEG**

**FNNAMENEG**, Depth argument to \$NAME cannot be negative

Run Time Error: This indicates that GT.M encountered a \$NAME() reference with the optional integer expression that is set to a negative number.

Action: Modify the routine to ensure that \$NAME() arguments are never negative.

### **FNOTONSYS**

**FNOTONSYS**, Function or special variable is not supported by this operating system

Compile Time Error: This indicates that GT.M encountered a function or special variable it cannot process on the current operating system.

Action: Some functions are not appropriate to all operating environments. Contact your GT.M support channel if you have questions about how to accomplish a particular task.

## **FNUMARG**

FNUMARG, \$FNUMBER format specifier xxxx contains an illegal character: yyyy

Run Time Error: This indicates that an \$FNUMBER function specified a format xxxx that contains invalid codes.

Action: Ensure that the format specifier in a \$FNUMBER function is a sequence of the code characters "P", "p", "T", "t", "+", "-", and ",".

## **FORCEDHALT**

FORCEDHALT, Image HALTed by MUPIP STOP

Run Time Warning: This indicates that a GT.M process recognized the receipt of a MUPIP STOP command and is terminating. This command stops GT.M processes in an orderly fashion.

Action: Determine who initiated the MUPIP STOP and why they did so. Restart the process, if appropriate.

### **FORCTRLINDX**

Last used version: V5.4-002A

FORCTRLINDX, Using a FOR with an indexed control variable that's assigned values calculated in extrinsics is not currently safe

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual

Compile Time/Run Time Error: GT.M currently has trouble managing the interaction between a subscripted FOR control variable and expressions for its maintenance that have side effects that might change the array holding the control variable. Such elements include extrinsics (\$\$), external calls (\$&) and \$INCREMENT(). To avoid possible process context corruption, the compiler issues this error when it encounters the threatening circumstances. Note that the error can also appear at run-time without the accompanying indications of line and column if the construct appears in an XECUTE, the control variable is specified with indirection or the compiler warning is ignored.

Action: Chose an unsubscripted FOR control variable and / or evaluate the side-effect element(s) before setting up the FOR.

## **FOROFLOW**

FOROFLOW, FOR commands nested too deeply

Compile Time Error: This indicates that a single line contained more than 32 FOR statements.

Action: Rework the routine so FORs are not so deeply nested in a single line.

### **FREEBLKSLOW**

**FREEBLKSLOW**, Only bbbb free blocks left out of tttt total blocks for ffff

Run Time Warning: This message warns that database file ffff with automatic file extensions disabled has only bbbb blocks left out of a total allocation of tttt.

Action: Use MUPIP EXTEND to extend the file, or MUPIP SET to enable automatic extensions, or reduce the amount of data in the file.

### **FREEMEMORY**

**FREEMEMORY**, Error occurred freeing memory

Run Time Error: Indicates an internal problem with storage management. The error is usually accompanied by a secondary message, which lists the reason towards the request failure.

Action: Report the entire incident context to your GT.M support channel.

#### **FREEZE**

**FREEZE**, Region: xxxx is already frozen

DSE/MUPIP Information: MUPIP FREEZE or DSE CHANGE commands generate this error if the region is already frozen.

Action: If the existing FREEZE is appropriate, no further action is necessary. If you decide to remove the prior FREEZE, issue a FREEZE command with the OFF qualifier.

### **FREEZECTRL**

**FREEZECTRL**, Control Y or control C encountered during attempt to freeze the database. Aborting freeze.

MUPIP Information: This indicates that the user aborted the MUPIP FREEZE or MUPIP BACKUP/ NOONLINE command; while the command was attempting to freeze the already frozen database.

Action: -

### **FREEZEERR**

FREEZEERR, Error while trying to ffff region rrrr

MUPIP Error: This indicates an unsuccessful database freeze or unfreeze (ffff) operation on region rrrr.

Action: Look for accompanying text that explains the cause of the error and take appropriate action.

## **FSEXP**

**FSEXP**, File specification expected but not found

Run Time Error: This indicates that a \$ZROUTINES-related action did not specify a valid filespecification.

Action: Look for missing brackets.

### **FSYNCTIMOUT**

**FSYNCTIMOUT**, Timed out on fsync for journal file xxxx

Run Time Error: This indicates that the process has been unable to get the journal flush lock on the journal file for nearly two minutes and has timed out. It is very likely that another process is holding the journal flush lock, wanting to do an fsync() on the journal file and has not released it so long, which would suggest an issue with disk subsystem response times.

Action: Check the disk subsystem for a software or hardware problem.

### **FTOKERR**

FTOKERR, Error getting ftok of the file xxxx

Run Time Error: This indicates that GT.M failed to take ftok of the database.

Action: Review the accompanying message(s) to identify the cause of the failure.

## **FTOKKEY**

### FTOKKEY, FTOK key 0xnnnn

MUPIP Information: This message reports additional information for an associated error which had trouble with the FTOK key 0xnnnn.

Action: Check "ipcs -s" for the given key, and see the associated error.

### **GBLEXPECTED**

GBLEXPECTED, Global variable reference expected in this context

Run Time/MUPIP Error: This message indicates an attempt to apply a trigger definition to something other than a global variable.

Action: Review and correct the trigger definition.

## **GBLMODFAIL**

GBLMODFAIL, Global variable Conflict Test failed. Failure code: xxxx.

Run Time Error: This indicates that a \$ZQGBLMOD function encountered an integrity error while restoring from a failover. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Report this error to the group responsible for database integrity at your operation.

### **GBLNAMCOLLRANGE**

GBLNAMCOLLRANGE, Collation sequence #nnnn is out of range (0 thru 255)

GDE Error: This indicates that the collation sequence nnnn is out of the supported range of 0 thru 255.

Action: Specify a collation sequence number inside the supported range.

### **GBLNAMCOLLUNDEF**

GBLNAMCOLLUNDEF, Error opening shared library of collation sequence #nnnn for GBLNAME gggg

GDE Error: This indicates that there was an error opening the shared library for collation sequence nnnn.

Action: Define the environment variable gtm\_collate\_<nnnn> to point to the shared library for collation sequence nnnn. Also ensure the path to the library is readable and the library is usable on that platform.

### **GBLNAMCOLLVER**

GBLNAMCOLLVER, Global directory indicates GBLNAME gggg has collation sequence #nnnn with a version #vvvv but shared library reports different version #llll

GDE Error: This indicates that the shared library for collation sequence nnnn reported the version as vvvv when collation properties for global name gggg were first added by GDE into the global directory and that this invocation of GDE noticed the shared library reporting an incompatible version llll.

Action: See Action section for COLLTYPVERSION error in the GT.M Message and Recovery Procedures Manual.

### **GBLNAME**

**GBLNAME**, Either an identifier or a left parenthesis is expected after a ^ in this context

Compile Time Error: This indicates that GT.M encountered a circumflex in a valid location for a global variable name; however, the circumflex was not followed by a variable name or a left parenthesis.

Action: Look for unwanted circumflexes in expressions. Ensure that global variable names are valid.

## **GBLNAMEIS**

GBLNAMEIS, in gblname gggg

GDE Information: This indicates the gblname where an out-of-range value was specified. This is usually a secondary message and is preceded by a VALTOOSMALL or VALTOOBIG error.

Action: Fixing the preceding error would automatically address this accompanying informational message.

### **GBLNOEXIST**

**GBLNOEXIST**, Global xxxx no longer exists

MUPIP Information: The specified global variable does not exist in the database. This indicates that the global variable xxxx was present when MUPIP reorg started, but was killed when reorg was working on it.

Action: -

### **GBLNOMAPTOREG**

Last used version: V6.1-BL03

GBLNOMAPTOREG, Global gggg does not map to region rrrr in current global directory

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 93 Run Time Error: Run Time Error: This indicates that a VIEW "YDIRTREE" or \$VIEW("YDIRTREE") was done with global gggg and region rrrr as parameters but the global does not map to that region in the current global directory.

Action: VIEW "YDIRTREE" or \$VIEW("YDIRTREE") is an undocumented feature and so should NOT be used directly. \$\$get^%GBLDEF is the only tool that uses this but internally catches the GBLNOMAPTOREG error. This means the GBLNOMAPTOREG error message will never be visible to the end-user.

### **GBLOFLOW**

**GBLOFLOW**, Database segment is full

Run Time Error: This indicates that an error was encountered while extending the database file.

Action: Examine the accompanying message(s) for the cause of the error. If the error is due to lack of enough free space on the disk to fit the size of a database file, try performing a KILL of some nodes in the database to get free blocks in the existing allocated space (you may need to KILL several subscripted nodes before you can KILL a name node).

### **GBLSECNOTGDS**

**GBLSECNOTGDS**, Global section xxxx is not a GT.M global section

Run Time Error: This indicates that when attempting to startup a database file, GT.M encountered an existing global section whose contents it did not recognize.

Action: Investigate whether you have a global section name conflict between GT.M and some other application. GT.M uses GT\$ as a prefix for all global section names that it creates. Make sure no other application in the system is using the same naming convention; it is very likely the global section contents are damaged. If necessary, report the entire incident context to your GT.M support channel.

### **GDCREATE**

**GDCREATE**, Creating global directory File xxxx

GDE Information: This indicates that an EXIT command caused GDE to write a new Global Directory into file xxxx.

Action: N/A

### **GDECHECK**

**GDECHECK**, Internal GDE consistency check

GDE Fatal: This indicates that an internal consistency check failed.

**GDINVALID** Chapter 1. Error Messages

Action: Look in the user's current working directory for a GDEDUMP.DMP context file that your GT.M support channel can examine to help determine the cause of the error. If necessary, report the entire incident context to your GT.M support channel.

#### **GDINVALID**

GDINVALID, Unrecognized Global Directory file format: xxx, expected label: yyy, found: zzz

Run Time Error: This indicates that a version of the global directory file xxx does not match with the version expected by GT.M. The file might have been created by an incompatible GT.M version..

Action: Compare the labels yyy and zzz. If the global directory was created by an earlier GT.M version, upgrade the file by loading and then saving the file using the GDE of the new GT.M version.

### **GDNOTSET**

**GDNOTSET**, Global Directory not changed because the current GD cannot be written

GDE Information: This indicates that GDE could not complete a SETGD command because it could not verify the current Global Directory. This prevented a write of the current information.

Action: Either modify the current Global Directory or abandon it by adding the OUIT qualifier to the SETGD command.

### **GDREADERR**

GDREADERR, Error reading Global Directory: xxxx

GDE Information: This indicates that GDE encountered an error when it attempted to read the existing Global Directory in file xxxx.

Action: Review the accompanying message(s) for additional information.

### **GDUNKNFMT**

**GDUNKNFMT**, xxxx is not formatted as a global directory

GDE Information: This indicates that GDE could not load the specified file xxxx because it is not a valid Global Directory file. GDE aborts the load after it issues this message.

Action: Verify that the file is valid and look for typographical errors. Something other than GT.M or its utilities may have written to the Global Directory file or created a file with a name that coincides with the one specified by GTM\$GBLDIR / gtmgbldir.

## **GDUPDATE**

**GDUPDATE**, Updating Global Directory File xxxx

GDE Information: This indicates that an EXIT or SETGD command caused GDE to write a new version of the existing Global Directory in file xxxx.

Action: -

### **GDUSEDEFS**

GDUSEDEFS, Using defaults for Global Directory xxxx

GDE Information: This indicates that GDE did not find an existing Global Directory using the logical name GTM\$GBLDIR / gtmgbldir. As a result, it is starting the session with default values.

Action: -

### **GETADDRINFO**

**GETADDRINFO**, Error in getting address info

Run Time Error: This message indicates a problem converting a host name to an IP address.

Action: See associated TEXT message for more details. Check host names used for replication, backup, SOCKET devices, or GT.CM.

### **GETCWD**

Last used version: V4.0-001E

**GETCWD**, Error getting current working directory for file xxxx

Run Time/MUPIP Error: This indicates that GT.M could not get the full path of current working directory.

Action: Review up the accompanying message(s) for additional information.

### **GETNAMEINFO**

**GETNAMEINFO**, Error in getting name info

Run Time Error: This message indicates a problem converting an IP address to a readable format.

Action: See associated TEXT message for more details. Report the error to your GT.M support channel.

### **GETSOCKNAMERR**

**GETSOCKNAMERR**, Getting the socket name failed from getsockname(): (errno==aaaa) xxxx

Run Time Error: This indicates getsockname() system call, which retrieves the locally bound address of the specified socket, failed.

Action: Review the accompanying messages and error code.

### **GETSOCKOPTERR**

**GETSOCKOPTERR**, Getting the socket attribute xxxx failed: (errno == yyyy) zzzz

Run Time Error: This indicates that an attempt to determine a socket's attributes failed.

Action: Consider the OPEN or USE deviceparameters, and the error code.

## **GOQPREC**

GOOPREC, Numeric precision in key error: Blk #xxxx, Key #yyyy. Record not loaded.

MUPIP Information: This indicates that GT.M was unable to precisely represent a key in the GOQ input file to a MUPIP LOAD.

Action: Examine the key on the source system, modify it, and repeat the process, or manually enter the modified record into GT.M.

## **GTMASSERT**

GTMASSERT, xxxx - assert failed yyyy line zzzz

Compile Time/Run Time Fatal: This indicates that a design assumption failed at the location specified.

Action: Preserve the core (dump) files and report the entire incident context to your GT.M support channel for further analysis. If appropriate, verify database integrity by using the -FAST qualifier.

### **GTMASSERT2**

GTMASSERT2, GT.M eeee - Assert failed LLLL for expression (eeee)

Compile Time/Run Time Fatal: This indicates a design assumption failed at the location LLLL because the expression eeee was FALSE.

Action: Preserve the core (dump) files and report the entire incident context to your GT.M support channel for further analysis. If appropriate, verify database integrity by using the -FAST qualifier.

### **GTMCHECK**

**GTMCHECK**, Internal GT.M error. Report to GT.M Support.

Compile Time/Run Time Fatal: This indicates that a design assumption failed at the location specified.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 97 Action: Preserve the core (dump) files and report the entire incident context to your GT.M support channel for further analysis. If appropriate, verify database integrity by using the -FAST qualifier.

## **GTMDISTUNDEF**

GTMDISTUNDEF, Environmental variable \$gtm dist is not defined

DSE/Run Time/MUPIP/LKE Error: This indicates that the environment variable gtm dist, is not defined for all processes attempting to use (a particular version of) GT.M.

Action: Define the environment variable.

## **GTMDISTUNVERIF**

GTMDISTUNVERIF, Environment variable \$gtm\_dist (dddd) could not be verified against the executables path (pppp)

MUPIP/LKE/GT.CM/DSE/Run Time Error: This indicates that the executable pppp does not resides in the path pointed to by environment variable gtm dist, dddd.

Action: Ensure that the setting for \$gtm\_dist matches that of the executable.

## **GTMDUMPFAIL**

**GTMDUMPFAIL**, Could not create DUMP FILE

Run Time Error: This indicates that an unanticipated error caused GT.M to attempt to create a context file GTMDUMP.DMP in the SYS\$LOGIN directory of the process. GT.M could not create the file.

Action: Verify that privileges are appropriately assigned and that adequate disk space exists (usually less than 100 host blocks).

### **GTMEISDIR**

**GTMEISDIR**, dddd : Is a directory

Run Time Error: The file dddd opened for reading is a directory. Directories cannot be opened for reading.

Action: Check the argument to the OPEN for the appropriate file and its path.

### **GTMERREXIT**

**GTMERREXIT**, GTM image has exited with errors

Run Time Error: Seen when GT.M on VMS is exiting due to a FATAL error (previously displayed) but wishes to exit with error status and not generate a dump file (if SET PROC/DUMP were in effect).

Action: See previous FATAL error.

## **GTMSECSHR**

GTMSECSHR, xxxx Error during GTMSECSHR operation

Run Time Error: This indicates that user privileges do not allow access to GTMSECSHR; or GTMSECSHR was not properly installed.

Action: Verify that SECSHR is properly installed and review user privileges in the SECSHR log file.

### **GTMSECSHRBADDIR**

GTMSECSHRBADDIR, gtmsecshr is not running from \$gtm dist/gtmsecshrdir or \$gtm dist cannot be determined

Run Time Error: This message indicates an inappropriate gtmsecshr invocation. Either gtmsecshr is improperly installed or an inappropriate access attempt is underway.

Action: Verify that GT.M (and gtmsecshr) are correctly installed following FIS documented procedures and that filesystem mount points have not changed. If GT.M is correctly installed and filesystem mount points have not changed, investigate this as an attempt to break system security.

## **GTMSECSHRCHDIRF**

GTMSECSHRCHDIRF, gtmsecshr unable to chdir to its temporary directory (dddd). GTMSECSHR process error: GTMSECSHR is not able to change directory to its temporary directory, dddd.

GTMSECSHR Error: The UNIX gtmsecshr process, which assists other process with cross-user signaling and similar things, uses a temporary directory determined by the operating system defined temporary directory (typically /tmp or /var/tmp) when it needs to save a core file, but it was unable to find that directory.

Action: Verify that the environment provides the desired dddd, that dddd exists and that it is a directory.



the permissions on dddd should not matter (as long as it is a directory) since GTMSECSHR runs as root.

## **GTMSECSHRDEFLOG**

Last used version: V5.5-000

GTMSECSHRDEFLOG, \$gtm\_log is either undefined or not defined to an absolute path, so gtm\_log is set the default xxxx

MR Manual V6.2-002 Run Time Information: This indicates that GTMSECSHR has selected the default log file described in the message because the environment variable was not defined or had an unsuitable definition.

Action: When specifying the log file, be sure to select a full path and define the environment variable gtm\_log properly.

## **GTMSECSHRDMNSTARTED**

GTMSECSHRDMNSTARTED, [client pid pppp] File (ffff) removed

GTMSECSHR Information: This message indicates that GTMSECSHR removed file ffff on behalf of process pppp.

Action: N/A

### **GTMSECSHRFORKF**

GTMSECSHRFORKF, GTMSECSHR server unable to fork off a child process

Run Time Error: This indicates that a GTMSECSHR was unsuccessful in starting because it was unable to create an independent process to run as a daemon.

Action: Refer to the associated message(s) for more information.

## **GTMSECSHRGETSEMFAIL**

**GTMSECSHRGETSEMFAIL**, error getting semaphore errno = xxxx

GTMSECSHR Error: This error indicates that GTMSECSHR failed to obtain a semaphore set identifier for a specific IPC key during process termination, and that the error code returned by semget() is xxxx.

Action: The IPC resources that GTMSECSHR uses should be unique to GT.M, and this message indicates an unexpected condition. Investigate whether other software is using IPC resources in a way that conflicts with GT.M. If you can't find an explanation, report the entire incident context to your GT.M support channel.

### **GTMSECSHRISNOT**

**GTMSECSHRISNOT**, GTMSECSHRISNOTgtmsecshr is not running as gtmsecshr but xxxxx - must be gtmsecshr

Run Time Error: gtmsecshr is running with a name other than the one it is allowed to run by design.

Action: Verify that GT.M (and gtmsecshr) are correctly installed following FIS documented procedures and that filesystem mount points have not changed. If GT.M is correctly installed and filesystem mount points have not changed, investigate this as an attempt to break system security.

FIS V6.2-002

## **GTMSECSHRLOGF**

Last used version: V5.5-000

GTMSECSHRLOGF, XXXX - YYYY; Error while creating GTMSECSHR log file

Run Time Warning: This indicates that the [UNIX] GTMSECSHR daemon was not able to create its log file.

Action: Check the accompanying message(s) for additional information. Check gtm log environment variable.

## **GTMSECSHRLOGSWH**

Last used version: V5.5-000

GTMSECSHRLOGSWH, Error switching GTMSECSHR log file

Run Time Error: This indicates that an operator attempt to start a new log file failed.

Action: Refer to the associated message(s) for more information.

### **GTMSECSHRNOARG0**

**GTMSECSHRNOARG0**, GTMSECSHRNOARG0gtmsecshr cannot identify its origin - argv[0] is null

Run Time Error: This message occurs when gtmsecshr is called in an inappropriate manner by facilities other those allowed by design (like the gtmsecshr wrapper).

Action: Investigate this as an attempt to break system security.

### **GTMSECSHROPCMP**

GTMSECSHROPCMP, GTMSECSHR operation may be compromised

Run Time Error: This indicates that GTMSECSHR could not acquire the privileges required to assist more than a restricted set of processes.

Action: If this is the proper mode of operation, ignore the warning. Normally GTMSECSHR should be a setuid executable owned by root.

## **GTMSECSHRPERM**

GTMSECSHRPERM, The GTMSECSHR module in \$gtm\_dist does not have the correct permission and UID

Run Time Warning: This indicates that a client did not start a GTMSECSHR because the executable was not owned by root and did not have setuid permission.

Action: Arrange to provide the GTMSECSHR executable with the proper characteristics.

### **GTMSECSHRRECVF**

GTMSECSHRRECVF, GTMSECSHR receive on server socket failed

Run Time Error: This indicates that a receive operation failed in GTMSECSHR.

Action: Refer to the associated message(s) for more information.

## **GTMSECSHRREMFILE**

GTMSECSHRREMFILE, [client pid pppp] File (ffff) removed

GTMSECSHR/Operator log Information: This message indicates that GTMSECSHR removed file ffff on behalf of process pppp.

Action: -

### **GTMSECSHRREMSEM**

GTMSECSHRREMSEM, [client pid pppp] Semaphore (ssss) removed

GTMSECSHR Error: This message indicates that GTMSECSHR removed a semaphore identified by the key ssss on behalf of process pppp.

Action: This is benign. No action necessary.

### **GTMSECSHRREMSEMFAIL**

**GTMSECSHRREMSEMFAIL**, error removing semaphore errno = xxxx

GTMSECSHR Error: This error indicates that GTMSECSHR failed to remove a semaphore set identified by a specific IPC key during process termination, and that the error code returned by semctl() is xxxx.

Action: The IPC resources that GTMSECSHR uses should be unique to GT.M, and this message indicates an unexpected condition. Investigate whether other software is using IPC resources in a way that conflicts with GT.M. If you can't find an explanation, report the entire incident context to your GT.M support channel.

### **GTMSECSHRREMSHM**

GTMSECSHRREMSHM, [client pid pppp] Shared memory segment (ssss) removed, nattch = nnnn

GTMSECSHR Information: This message indicates that GTMSECSHR removed a shared memory segment identified by the key ssss on behalf of process pppp, and that there were nnnn processes attached to that segment.

V6.2-002 GT.M Message and Recovery Procedures Manual Action: N/A

## **GTMSECSHRSCKSEL**

GTMSECSHRSCKSEL, GTMSECSHR select on socket failed

Run Time Error: This indicates that a select operation failed in GTMSECSHR.

Action: Refer to the associated message(s) for more information.

## **GTMSECSHRSEMGET**

**GTMSECSHRSEMGET**, semget error errno = xxxx

GTMSECSHR Error: This error indicates that GTMSECSHR process failed to obtain a semaphore set identifier for a specific IPC key, and that the error code returned by semget() is xxxx.

Action: Consult your system administrator to ensure semaphores are appropriately configured.

## **GTMSECSHRSENDF**

GTMSECSHRSENDF, GTMSECSHR send on server socket failed

Run Time Error: This indicates that a socket operation failed in a GTMSECSHR.

Action: Refer to the associated message(s) for more information.

## **GTMSECSHRSGIDE**

GTMSECSHRSGIDF, GTMSECSHR server setGID to root failed

Run Time Error: This indicates that the setgid operation failed during GTMSECSHR startup.

Action: Refer to the associated message(s) for more information.

### **GTMSECSHRSHMCONCPROC**

GTMSECSHRSHMCONCPROC, More than one process attached to Shared memory segment (ssss) not removed (nnnn)

GTMSECSHR Error: This error indicates that the shared memory segment identified by the key ssss has not been removed because nnnn processes are currently attached to it.

Action: The IPC resources that GTMSECSHR uses should be unique to GT.M, and this message indicates an unexpected condition. Investigate whether other software is using IPC resources in a way that conflicts with GT.M. If you can't find an explanation, report the entire incident context to your GT.M support channel.

## **GTMSECSHRSHUTDN**

GTMSECSHRSHUTDN, GTMSECSHR process has received a shutdown request. Shutting down.

Run Time Information: This indicates that the GTMSECSHR daemon has shutdown.

Action: -

### **GTMSECSHRSOCKET**

GTMSECSHRSOCKET, xxxx - yyyy; Error initializing GTMSECSHR socket

Run Time Error: This indicates that a GT.M process or GTMSECSHR with PID yyyy was unable to open a socket for communication with either the server or client.

Action: Refer to the associated message(s) for more information.

## **GTMSECSHRSRVF**

**GTMSECSHRSRVF**, Client - yyyy; Attempt to service request failed (retry = zzzz)

Run Time Error: This indicates that a GT.M process with PID yyyy was unable to communicate with gtmsecshr after zzzz attempts (a maximum of four retries).

Action: This message is displayed when a process that needs service from gtmsecshr, cannot communicate with gtmsechsr, or cannot start one. While the most likely cause is a mismatch in the value of the gtm\_tmp environment variable between the GT.M process and the gtmsecshr process, examples of other causes include removal of socket files used for communication between GT.M and gtmsecshr processes. Check for a following associated message in syslog or in the stderr of the GT.M process.

### **GTMSECSHRSRVFID**

**GTMSECSHRSRVFID**, xxxx: yyyy - Attempt to service request failed. Client ID: zzzz, mesg ID: aaaa, mesg code: bbbb

Run Time Warning: This indicates that the GTMSECSHR was unable to complete the request of GT.M client.

Action: Examine the information in the message to see whether the message is appropriate to the environment; examine the environment and correct any inappropriate set up (such as the privileges available for GTMSECSHR).

### **GTMSECSHRSRVFIL**

**GTMSECSHRSRVFIL**, xxxx: yyyy; Attempt to service request failed. Client ID: zzzz, mesg type: aaaa, file: bbbb

FIS V6.2-002

GTMSECSHR Warning: This indicates that the GTMSECSHR was unable to complete the request of GT.M client.

Action: Review accompanying message(s) for information on why GTMSECSHR could not delete the file.

## **GTMSECSHRSSIDF**

GTMSECSHRSSIDF, GTMSECSHR server setSID failed

Run Time Error: This indicates that the setsid operation failed during GTMSECSHR startup.

Action: Refer to the associated message(s) for more information.

## **GTMSECSHRSTART**

GTMSECSHRSTART, xxxx - yyyy; GTMSECSHR failed to startup

Run Time Warning: This indicates that GTMSECSHR startup failed.

Action: Refer to the associated message(s) for more information.

### **GTMSECSHRSUIDF**

GTMSECSHRSUIDF, GTMSECSHR server setUID to root failed

Run Time Error: This indicates that the setuid operation failed during GTMSECSHR startup.

Action: Refer to the associated message(s) for more information.

### **GTMSECSHRTMOUT**

GTMSECSHRTMOUT, GTMSECSHR exiting due to idle timeout

Run Time Information: This indicates that the GTMSECSHR had been idle long enough to time out and terminate.

Action: No action is required, another GTMSECSHR is started when it is needed.

### **GTMSECSHRTMPPATH**

### GTMSECSHRTMPPATH, gtmsecshr path is pppp

Information: GT.M displays this message when different users of an instance of GT.M connect using a socket or a semaphore and when gtmsecshr is started and it detects an existing gtmsecshr. pppp indicates the gtm tmp path set in the clients. Gtmsecshr inherits the path from the first GT.M process that uses its services.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 105 Action: If different clients of the same instance of GT.M are using different gtmsecshr paths, then set a common value for the environment variable gtm tmp for all users of an instance of GT.M, then stop and restart the processes that were using incorrect paths. If gtmsecshr itself has the incorrect path, all processes that are using that incorrect path must be stopped first - then stop gtmsecshr with a kill command.

## **GTMSECSHRUPDDBHDR**

GTMSECSHRUPDDBHDR, [client pid pppp] database fileheader (dddd) updated iiii

GTMSECSHR Information: This message indicates that GTMSECSHR updated database fileheader dddd on behalf of process pppp for the purpose of iiii.

Action: N/A

## **GVDATAFAIL**

**GVDATAFAIL**, Global variable \$DATA function failed. Failure code: xxxx

Run Time Error: This indicates that a \$DATA function encountered a database problem. xxxx contains the failure codes for the four attempts. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Report this database error to the group responsible for database integrity at your operation.

### **GVDATAGETFAIL**

GVDATAGETFAIL, Global variable DATAGET sub-operation (in KILL function) failed. Failure code:

Trigger/Run Time Error: The target node for a KILL operation could not present its state to the trigger logic due to a database problem, cccc contains the failure codes for the failed attempts. The database may have integrity errors or the process-private data structures may be corrupted.

Action: Report this database error to the group responsible for database integrity at your operation.

### **GVFAILCORE**

**GVFAILCORE**, A core file is being generated for later analysis if necessary

Run Time Error: This is an operator log-only message, which indicates that a core (dump) is being generated for the immediately preceding xxxxFAIL error message.

Action: Report this database error to the group responsible for database integrity at your operation. If the cause of the xxxxFAIL message is not otherwise known (for example, database damage due to recent system crash), the produced core will contain information that your GT.M support channel can use to determine the source of failure (UNIX only).

V6.2-002 GT.M Message and Recovery Procedures Manual

## **GVGETFAIL**

GVGETFAIL, Global variable retrieval failed. Failure code: xxxx.

Run Time Error: This indicates that a database lookup of a global variable encountered an error. xxxx contains the failure codes for the four attempts. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Report this database error to the group responsible for database integrity at your operation.

### **GVINCRFAIL**

GVINCRFAIL, <Global variable \$INCR failed. Failure code: xxxx>

Run Time Error: This indicates that a \$INCREMENT command encountered a database problem when it attempted to update a global variable. xxxx contains the failure codes for the four attempts. It is very likely that the database may have structural damage or that the process-private data structures are corrupted.

Action: Report this database error to the group responsible for database integrity at your operation.

## **GVINCRISOLATION**

GVINCRISOLATION, <\$INCREMENT cannot be performed on global xxxx as it has NOISOLATION turned ON>

Run Time Error: Global xxxx has NOISOLATION turned ON (through a VIEW "NOISOLATION" command). \$INCREMENT is currently not supported for such globals.

Action: Change the application either to turn OFF NOISOLATION on the global or not use \$INCREMENT on it.

### **GVINVALID**

GVINVALID, xxxx Invalid global name

MUPIP Error: This indicates that LOAD encountered invalid global name xxxx in the input stream.

Action: Refer to the topic MUPIP LOAD Errors in About This Manual section of this manual.

### **GVIS**

GVIS, Global variable: xxxx

Run Time Information: This message identifies a global variable.

Action: Refer to the accompanying message(s) for more information.

## **GVKILLFAIL**

GVKILLFAIL, Global variable kill failed. Failure code: xxxx.

Run Time Error: This indicates that a KILL of a global variable encountered a database problem. xxxx contains the failure codes for the four attempts. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Report this database error to the group responsible for database integrity at your operation.

### **GVNAKED**

**GVNAKED**, Illegal naked global reference

Run Time Error: This indicates that the naked indicator was referenced before any named global reference or after an event that left it undefined.

Action: Review naked indicator references and correct them, if necessary. For example, the naked indicator cannot be the first global symbol referenced.

### **GVNAKEDEXTNM**

**GVNAKEDEXTNM**, Cannot reference different Global Directory in a naked reference

Compile Time Error: This indicates that a global variable reference used the environment syntax but did not specify a name.

Action: Verify that the environment specifies a full global name.

### **GVNEXTARG**

GVNEXTARG, Argument to global variable \$NEXT must be subscripted

Compile Time Error: This indicates that an attempt was made to use an un-subscripted global or local variable as the argument for a \$NEXT() function. In contrast to \$ORDER(), which can operate on unsubscripted names, \$NEXT() requires subscripted names.

Action: Use \$ORDER() or revise the code.

## **GVORDERFAIL**

GVORDERFAIL, Global variable \$ORDER or \$NEXT function failed. Failure code: xxxx.

Run Time Error: This indicates that a \$ORDER or \$NEXT function encountered a database problem. xxxx contains the failure codes for the four attempts. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Report this database error to the group responsible for database integrity at your operation.

## **GVPUTFAIL**

**GVPUTFAIL**, Global variable put failed. Failure code: xxxx.

Run Time Error: This indicates that a SET command encountered a database problem when it attempted to update a global variable. xxxx contains the failure codes for the four attempts. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Report this database error to the group responsible for database integrity at your operation.

## **GVQUERYFAIL**

**GVQUERYFAIL**, Global variable \$QUERY function failed. Failure code: xxxx.

Run Time Error: This indicates that a \$QUERY function failed. xxxx contains the failure codes for the four attempts. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Report this database error to the group responsible for database integrity at your operation.

## **GVQUERYGETFAIL**

**GVQUERYGETFAIL**, Global variable QUERY and GET failed. Failure code: xxxx.

Run Time Error: This indicates that database query and Lookup in the same atomic transaction encountered a problem. xxxx contains the failure codes for the four attempts.

Action: Contact the system administrator and if needed report to your GT.M support channel.

### **GVREPLERR**

**GVREPLERR**, Error replicating global in region xxxx

Run Time Error: This indicates that the database system successfully updated a global node on the primary copy of the database but it encountered an error making the same update in a replicated copy.

Action: Examine any secondary error. Investigate whether the problem is with the disk where the copy is located or with the communications system to the secondary copy, if it is remote. Correct the problem and resynchronize the copies.

### **GVRUNDOWN**

GVRUNDOWN, Error during global database rundown

Run Time Error: This indicates that the process encountered an error when it attempted to RUNDOWN all database files as part of image termination.

Action: Report this database error to the group responsible for database integrity at your operation.

### **GVSUBOFLOW**

GVSUBOFLOW, Maximum combined length of global subscripts exceeded

Run Time Error: This indicates that a global variable reference specified a total subscript length that exceeds the maximum length specified in the Global Directory for the current region.

Action: Ensure that the subscript is correct. Then, use DSE DUMP and the FILEHEADER qualifier to examine the key size for the region.

### **GVSUBSERR**

GVSUBSERR, GVSUBSERR, Invalid subscripted global name specification in \$VIEW() function

Run Time Error: This indicates that an invalid subscripted global name was specified as the second parameter in a \$VIEW("REGION",namevalue) function call.

Action: Fix the syntax error in the subscripted global name. The subscripted global variable name must be in the form returned by \$NAME(). For example, use \$VIEW("REGION","^abcd(1,20000)") instead of \$VIEW("REGION","^abcd(1,2E4)")

## **GVUNDEF**

**GVUNDEF**, Global variable undefined: xxxx

Run Time Error: This indicates that the program attempted to evaluate an undefined global variable.

Action: Review the program flow and the preparation of the environment.

### **GVZPREVFAIL**

GVZPREVFAIL, Global variable \$ZPREVIOUS function failed. Failure code: xxxx

Run Time Error: This indicates that a \$ZPREVIOUS function encountered a database problem. xxxx contains the failure codes for the four attempts. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Report this database error to the group responsible for database integrity at your operation.

## **GVZTRIGFAIL**

GVZTRIGFAIL, ZTRIGGER of a global variable failed. Failure code: cccc.

HLPPROC Chapter 1. Error Messages

Run Time Error: A ZTRIGGER command failed because of problems in the database. cccc is a list of four codes indicating the reason for the failure on each of the attempts to commit the ZTRIGGER action.

Action: Report this database error to the group responsible for database integrity at your operation.

## **HLPPROC**

**HLPPROC**, Helper Process error

MUPIP Error: GT.M replication was not able to start a helper process.

Action: Ensure that the gtm dist environment variable points to a valid GT.M distribution that is executable by the user.

## **HOSTCONFLICT**

**HOSTCONFLICT**, Host hhhh could not open database file dddd because it is marked as already open on node nnnn

Run Time Error: The database file (dddd) has already been opened by a host (nnnn) other than the local host (hhhh).

Action: Ensure that host nnnn has closed dddd. Make sure both host names are correct. Changing host names in the middle of a database access can cause this error.

### HTFXPFAII

Last used version: V5.3-001A

**HTEXPFAIL**, Hash table expansion failed for lack of memory

Run Time/MUPIP Error: The hash table, an internally expanding data structure maintained by GT.M. has exceeded its maximum capacity. In GT.M, each unique local variable name uses up some hash table space. In MUPIP, it is backward recovery (or rollback) that might encounter this error. Here each TP transaction that is encountered in the backward processing phase of recovery uses up some hash table space. In either case, it is more likely that a process will run out of virtual memory much before it reaches the maximum hashtable capacity.

Action: Increase process memory quotas to increase available process virtual memory. Reduce the number of unique local variable names referenced by the GT.M process. For MUPIP backward recovery/ rollback, reduce the number of TP transactions encountered in the backward processing phase by using a later timestamp in the SINCE\_TIME qualifier or higher RESYNC\_SEQNO for rollback.

### **HTOFLOW**

HTOFLOW, Hash table overflow, local or region name space exceeded

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 111 Run Time/MUPIP Error: This indicates that the hash table contains too many local names or region names.

Action: Reduce the number of local and region name entries in the table.

### **HTSHRINKFAIL**

HTSHRINKFAIL, Hash table compaction failed to allocate new smaller table due to lack of memory

Run Time Error: GT.M found an internal hash table over-allocated but was unable to reduce its size because the process memory was too large to allocate a new smaller table; GT.M must allocated the new table before it can release the old table because it must copy the contents out of the "too-large" table into the smaller one. After this warning, the process continues running with the larger table.

Action: Investigate whether the process size can be reduced, or the available memory increased.

### **ICUERROR**

**ICUERROR**, ICU returned status ssss which is either unrecognized or inconsistent with the operating context

Run Time Error: The open-source ICU module which GT.M uses for some Unicode processing return an error code ssss that GT.M did not recognize as valid for the current context.

Action: Consult the ICU documentation and / or refresh the ICU library with a known correct version.

### **ICUSYMNOTFOUND**

ICUSYMNOTFOUND, Symbol xxxxx not found in ICU libraries. ICU needs to be built with symbolrenaming disabled or gtm icu version environment variable needs to be specified

Run Time Error: ICU version installed on the machine is built with symbol renaming and gtm icu version has not been defined

Action: Build ICU without symbol renaming or set gtm\_icu\_version environment variable to point to an appropriate ICU version.

### **ICUVERLT36**

ICUVERLT36, Type 1 - \$gtm\_icu\_version is aaa.bbb. ICU version greater than or equal to 3.6 should be used. Type 2 - libicuio has version aaa.bbb. ICU version greater than or equal to 3.6 should be used.

Run Time Error: This message indicates an attempt to use an ICU version less than 3.6 with GT.M or utilities like MUPIP or DSE.

Action: Upgrade ICU version to at least 3.6.

## **IFBADPARM**

#### IFBADPARM. External Interface Bad Parameter

Run Time Error: This indicates that an external routine could not access a GT.M database library routine because it had an invalid parameter in its call argument list. The GT.M database library routines allow an external routine to access a GT.M database.

Action: Look for and correct any typographical errors in the call format for the GT.M library routine.

## **IFNOTINIT**

IFNOTINIT, External Interface must first call GTM\$INIT or M routine

Run Time Error: This indicates that an external routine could not access a GT.M database library routine because it did not call the GTM\$INIT library routine first. The GTM\$INIT library routine initializes the GT.M run-time environment.

Action: Call GTM\$INIT or a GT.M M routine before calling any other database access library routine.

### **IGNBMPMRKFREE**

**IGNBMPMRKFREE**, Ignoring bitmap free-up operation for region rrrr (dddd) due to concurrent ONLINE ROLLBACK

Run Time Information: A multi-node KILL bit map cleanup operation detected a concurrent online rollback in region rrrr mapped to database file dddd, and abandoned the cleanup, possibly leaving incorrectly marked busy errors.

Action: If there are incorrectly marked busy errors, match them with this cause and clean them up using DSE.

## **ILLCHAR**

ILLCHAR, xxxx is not a legal character in this context

GDE Information: This indicates that GDE encountered the invalid character xxxx in its command input stream. This character should never appear in the context in which it was found.

Action: Review and re-enter a valid command sequence.

### **ILLESOCKBFSIZE**

**ILLESOCKBFSIZE**, The specified socket buffer size is xxxx, which is either 0 or too big

Run Time Error: This indicates that the OPEN command specified an inappropriate buffer size.

Action: Revise the command.

## **IMAGENAME**

**IMAGENAME**, The executing module name should be xxxx instead of yyyy

Run Time Error: This indicates that the executable invoked should have been named xxxx instead of its current name yyyy.

Action: Revisit the GT.M installation.

### **INDEXTRACHARS**

**INDEXTRACHARS**, Indirection string contains extra trailing characters

Compile Time Error: This indicates that an indirection string ends with a syntactically incorrect sequence.

Action: Look for extra trailing characters in the indirection string.

### **INDMAXNEST**

Last used version: V6.0-000

**INDMAXNEST**, Maximum nesting of indirection expressions exceeded

Run Time Error: This indicates that indirection nesting required more space than GT.M provides. The space needed by GT.M is a function of the number, type and complexity of the indirect expressions being nested.

Action: Review the program logic and reduce the amount of nested indirection in the routine.

### **INDRCOMPFAIL**

**INDRCOMPFAIL**, Compilation of indirection failed

Run Time Error: This indicates that an indirection or XECUTE command failed due to syntax errors.

Action: Review the the code and make sure the indirection or XECUTE string has valid syntax and contains no non-graphic characters. Consider using \$ZWRITE to identify any such characters.

### **INDRMAXLEN**

INDRMAXLEN, Maximum length xxxxx of an indirection argument was exceeded

Run Time Error: This indicates that an indirection or XECUTE used a value that exceeded the maximum length for a source code element.

V6.2-002 GT.M Message and Recovery Procedures Manual Action: Review the the code to shorten the length of the XECUTE or indirection string.

### **INITORRESUME**

**INITORRESUME**, UPDATERESYNC on a Supplementary Instance must additionally specify INITIALIZE or RESUME

Receiver Server log/MUPIP Error: Issued by a Receiver Server when started with -UPDATERESYNC on a Supplementary Instance which allows local updates, but started without specifying either -INITIALIZE or -RESUME.

Action: Additionally specify -INITIALIZE if this is the first time this supplementary instance is connecting to the source side OR if the receiver side databases have been refreshed from a backup of the source side. If on the other hand, the receiving instance had already been replicating from the source before and only had its instance file recreated in between, -RESUME might be appropriate with the -UPDATERESYNC. Check -RESUME documentation for more details.

## **INPINTEG**

**INPINTEG**, Input integrity error -- aborting load

GDE Fatal: This indicates that GDE is aborting the session because integrity errors prevented it from loading the specified Global Directory. GDE usually displays this message with other error messages. GDE aborts the load after issuing this message.

Action: Review the accompanying message(s) for additional information. Verify whether the command specified the intended file. Something other than GT.M and its utilities probably wrote to a Global Directory file or created a file with a name identical to the one specified by GTM\$GBLDIR / gtmgbldir.

## **INSFFBCNT**

**INSFFBCNT**, Insufficient byte count quota left for requested operation

Run Time Error: This indicates that an OPEN or JOB command could not establish a mailbox because it would exceed the process OpenVMS BYTLM.

Action: Review the I/O flow of the program and make adjustments to minimize concurrently open buffered I/O devices, or talk to your system manager about increasing the user BYTLM.

# **INSNOTJOINED**

**INSNOTJOINED**, Replicating Instance RRRR is not a member of the same Group as Instance IIII

Receiver Server log/MUPIP Error: A Receiver Server or a MUPIP JOURNAL -ROLLBACK -FETCHRESYNC on instance RRRR produces this error when it attempts to establish a replication

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 115 connection with an instance that belongs to a different replication configuration or Group. MUPIP performs this safety check at the time it establishes a replication connection between two instances.

Action: Use the Remote IP Address in the Receiver / Source Server log files or the primary instance name field from MUPIP REPLICATE - INLPOOL -SHOW command to identify the Source Server that may have inadvertently attempted to establish a replication connection with your Source Server. Shut down the Source Server if the Source Server does not belong to your replication configuration. If you are attempting to move a Source Server from a different Group, reinitialize the Source Server. Note that only supplementary instances started with -UPDOK can accept updates from a different Group.

### **INSROLECHANGE**

INSROLECHANGE, Supplementary Instance SSSS and non-Supplementary Instance IIII belong to the same Group

Receiver Server log/MUPIP Error: Issued by a Receiver Server or a MUPIP JOURNAL -ROLLBACK -FETCHRESYNC on Supplementary Instance SSSS attempted to connect to non-Supplementary Instance IIII, but found they have the same Group identification. Because supplementary and non-Supplementary Instances cannot belong to the same Group, one of these instances must have changed roles without appropriate re-initialization.

Action: Either reinitialize the instance that is changing roles or revert the inappropriate role change.

### **INSTFRZDEFER**

**INSTFRZDEFER**, Instance Freeze initiated by eeee error on region rrrrr deferred due to critical resource conflict.

Run Time Information: eeee error encountered on region rrrrr triggered the Instance Freeze mechanism in an attempt to set the freeze, but couldn't do complete the freeze due to a critical resource conflict. Any process subsequently attempting an update will reattempt the freeze later until one succeeds or the error subsides.

Action: None necessary.

## **INSUNKNOWN**

**INSUNKNOWN**, Supplementary Instance SSSS has no instance definition for non-Supplementary Instance IIII

Receiver Server log/MUPIP Error: Issued by a Receiver Server or a MUPIP JOURNAL -ROLLBACK -FETCHRESYNC on Supplementary Instance SSSS, started with -UPDOK, attempted to connect to non-Supplementary Instance IIII, but found it has no matching instance information.

Action: Take a backup of the database and replication instance file from a current instance on the non-Supplementary Group, load the backup data on the Supplementary Instance and start the Receiver

**INTEGERRS** Chapter 1. Error Messages

Server on the supplementary instance using -UPDATERESYNC=<instbak.repl> where instbak.repl is the backup of the replication instance file taken along with the database backup.

## **INTEGERRS**

**INTEGERRS**, Database integrity errors

MUPIP Error: This indicates that INTEG encountered one or more errors in the database file.

Action: Review the accompanying errors for more information, and report this database error to the group responsible for database integrity at your operation.

### **INVACCMETHOD**

**INVACCMETHOD**. Invalid access method

MUPIP Error: This indicates that the user specified an invalid access method in a MUPIP SET command.

Action: This command can only use Memory Map (MM) or Buffered Globals (BG) access methods.

## **INVADDRSPEC**

INVADDRSPEC, Invlaid IP address specification

Run Time Error: This indicates that there is no valid response at the IP address specified.

Action: Verify the IP address.

### **INVALIDRIP**

INVALIDRIP, Invalid read-in-progress field in Cache Record. Resetting and continuing. Region: xxxx.

Run Time Error: This indicates that the read-in-progress field corresponding to a particular global buffer had an invalid value. The read-in-progress field usually indicates whether this global buffer is currently being read into from disk or not, and hence takes on two values only. Whenever the field takes on any value outside of these two, GT.M detects the situation and corrects it in addition to logging this incident in the operator log.

Action: Report the operator log message with any other relevant information to your GT.M support channel.

### **INVBITLEN**

**INVBITLEN**, Invalid size of the bit string

Run Time Error: This indicates that an attempt was made to create a bit string of size less than 1 or more than 253,952 bits.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 117 Action: Modify the code so it adheres to the permitted range.

## **INVBITPOS**

**INVBITPOS**, Invalid position in the bit string

Compile Time/Run Time Error: This indicates that GT.M encountered a bit position argument to a \$ZBITGET or \$ZBITSET function that exceeded the length of the bit string, or was less than one (1).

Action: Use \$ZBITLEN() to modify the code so the bit reference falls within the allocated length of the bit string.

### **INVBITSTR**

### **INVBITSTR**, Invalid bit string

Run Time Error: This indicates that an attempt was made to use a bit string with a leading character that was not within the permitted range of values.

Action: Determine the source for the first character of the bit string and modify the method of its creation to limit possible values to the valid range of 0 to 7.

### **INVCMD**

INVCMD, Invalid command keyword encountered

Compile Time Warning: This indicates that the program attempted to use an invalid keyword where a command was expected.

Action: Look for typographical errors or improper command abbreviations.

### **INVCTLMNE**

**INVCTLMNE**, Invalid control mnemonics

Run Time Error: The current device does not support the specified controlmnemonic.

Action: Check the spelling of the controlmnemonic, and be sure the mnemonicspace (if any) for the current device supports the requested usage of the controlmnemonic.

### **INVDLRCVAL**

INVDLRCVAL, Invalid \$CHAR() value.

Run Time Error: The \$CHAR() function triggers this error if its arguments contains an invalid codepoint. According to the Unicode Standard version 5.0, invalid code-points include the following sets:

V6.2-002 GT.M Message and Recovery Procedures Manual INVECODEVAL Chapter 1. Error Messages

1. The "too big" code-points (those greater than the maximum U+10FFFF).

2. The "surrogate" code-points (in the range [U+D800, U+DFFF]) which are reserved for UTF-16 encoding.

3. The "non-character" code-points that are always guaranteed to be not assigned to any valid characters. This set consists of [U+FDD0, U+FDEF] and all U+nFFFE and U+nFFFF (for each n from 0x0 to 0x10).

Action: Specify argument in the range of valid Unicode code-points.

### INVECODEVAL

**INVECODEVAL**, Invalid value for \$ECODE (xxxx).

Run Time Error: This indicates that an attempt was made to assign \$ECODE an invalid value. Such an action modifies \$ECODE to have a valid value indicating this error, which triggers an error trap.

Action: Revise the SET \$ECODE value complies with the required specification of the error codes of the format ,Mnnn,Zxxx,Uxxx,. The error codes in the form of ,Mnnn,, ,Zxxx, and ,Uxxx, represent ANSI standard codes, implementation-specific codes and end-user defined codes respectively.

### **INVERRORLIM**

INVERRORLIM, Invalid ERROR LIMIT qualifier value. Must be at least zero

MUPIP Error: This indicates that the value assigned to the ERROR LIMIT qualifier is negative (less than zero).

Action: Assign a value greater than zero (0) for ERROR LIMIT qualifier.

### **INVFCN**

**INVFCN**. Invalid function name

Compile Time Error: This indicates that an expression contained a string of the form "\$name(...)", but "name" was not a valid function name.

Action: Look for typographical errors, improper function name abbreviation, or a missing \$ in an extrinsic.

### **INVGBLDIR**

**INVGBLDIR**, Invalid Global Directory spec: xxxx. Continuing with yyyy.

GDE Information: This indicates that the Global Directory xxxx specified by GTM\$GBLDIR / gtmgbldir or by SETGD and the qualifier FILE= is not a valid file-specification.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 119 Action: When this error occurs, GDE uses the default specification of the current process default directory. Continue with the default and rename the result after leaving GDE, or change the specification with a SETGD command and the FILE= qualifier.

## **INVGLOBALQUAL**

INVGLOBALQUAL, Error in GLOBAL qualifier: Parse error at offset xxxx in yyyy

MUPIP Error: This indicates a syntax error in GLOBAL qualifier value yyyy at offset xxxx.

Action: Specify correct value for GLOBAL.

### **INVGTMEXIT**

**INVGTMEXIT**, Inappropriate invocation of gtm\_exit. gtm\_exit cannot be invoked from external calls.

Call in/Run Time Error: This indicates that the call-in shut-down function gtm exit() has been called from an external call C function. Since the GT.M run-time system must be operational even after the external call function returns, gtm exit() is meant to be called only once during a process lifetime, and only from the base C/C++ program when GT.M functions are no longer required by the program.

Action: Remove all invocations of gtm\_exit() from external call functions.

## **INVICUVER**

Last used version: V5.3-004

**INVICUVER**, xxx not found in the ICU libraries. ICU version 3.6.x must be used.

Run Time Error: GT.M triggers this error when it encounters an incompatible ICU version.

Action: Install ICU version 3.6.x. See "V5.2-000 Release Notes" for instructions on installing ICU Version 3.6.x on a supported platform.

### **INVIDQUAL**

**INVIDOUAL**, Invalid ID qualifier value xxxx

MUPIP Error: This indicates that an invalid value xxxx was assigned to the ID qualifier.

Action: Assign a valid value for ID qualifier.

### **INVINTMSG**

**INVINTMSG**, Invalid interrupt message received



GT.CM Error: An invalid interrupt request was received. This may indicate a network problem.

Action: Check the DECnet error logs and other network components.

### INVLINKTMPDIR A

INVLINKTMPDIR, Value for \$gtm linktmpdir is either not found or not a directory: dddd

Run Time Error: Indicates the process cannot access directory dddd, which it needs in order to do autorelink as specified by its \$ZROUTINES; the directory may not exist as a directory or the process lacks authorization to the directory.

Action: The directory specification comes from \$gtm\_linktmpdir if it is defined, otherwise from \$gtm tmp if that is defined; otherwise it defaults to the system temporary directory, typically /var/tmp on Solaris and /tmp in other environments. Either correct the environment variable definition or ensure directory dddd is appropriately set up. Note that all users of auto-relink for a directory normally need to use the same temporary directory for their relink control files.

## **INVMEMRESRV**

**INVMEMRESRV**, Could not allocate GT.M memory reserve (xxxx)

Images Warning: The memory reserver requested by the xxxx UNIX environment variable (\$gtm\_memory\_cache) or the VMS logical name (GTM\_MEMORY\_CACHE) could not be allocated. The following system message indicates why why the allocation could not be made.

Action: If value is to high, lower and retry. If value is reasonable determine what else would be preventing the allocation (process or system limits or usage by other system components).

### **INVMNEMCSPC**

**INVMNEMCSPC**, Unsupported mnemonicspace xxxx

Run Time Error: The mnemonicspace xxxx specified in an OPEN command is not supported by GT.M.

Action: Replace the mnemonicspace with a supported one.

### **INVMVXSZ**

INVMVXSZ, Invalid block size for GOQ load format

MUPIP Error: This indicates that the LOAD command with the qualifier FORMAT=GOO determined that the input file did not have the proper block size for that format.

Action: Determine how the file was created and use the proper specification for the FORMAT= qualifier.

## **INVNETFILNM**

**INVNETFILNM**, Invalid file name following node designation in global directory

GT.CM Error: This indicates that the GT.CM Server received a node name that does not exist on the network.

Action: Use GDE to check the Global Directory on the originating node for typographical errors in a remote node file-specification.

## **INVOBI**

INVOBJ, Cannot ZLINK object file due to unexpected format

Run Time Error: This indicates that ZLINK encountered invalid records in the object file it was trying to integrate into the image.

Action: Determine whether ZLINK has the intended argument. If the object file has been damaged, recreate it with a ZLINK that specifies the source file using an .M extension.

## **INVOBJFILE**

**INVOBIFILE**, Cannot ZLINK object file ffff due to unexpected format

Run Time Error: This indicates that ZLINK encountered invalid records in the object file ffff it was trying to integrate into the image.

Action: Determine whether ZLINK has the intended argument. If the object file has been damaged, recreate it with a ZLINK that specifies the source file using an .M extension, a ZCOMPILE or a mumps command at the shell.

#### INVPORTSPEC

**INVPORTSPEC**, Invalid port specification

Run Time Error: This indicates that the OPEN command socket parameter contained an invalid port number.

Action: Redefine the socket parameter to a value between 0 and 65535.

## **INVPROT**

**INVPROT**, Invalid protocol specified by remote partner

GT.CM Error: This indicates that the remote networked system used a protocol incompatible with the locally installed version of GT.CM.

**INVQUALTIME** Chapter 1. Error Messages

Action: Verify that both systems have compatible versions of GT.CM installed.

## **INVQUALTIME**

**INVQUALTIME**, Invalid time qualifier value. Specify as xxxx=delta\_or\_absolute\_time.

MUPIP Error: This indicates that time qualifier value specified for xxxx is invalid.

Action: Reissue the command with correct syntax.

### **INVREDIRQUAL**

INVREDIRQUAL, Invalid REDIRECT qualifier value. xxxx

MUPIP Error: This indicates a syntax error in REDIRECT qualifier value.

Action: Reissue the command with correct syntax for REDIRECT.

### **INVROLLBKLVL**

INVROLLBKLVL, Rollback level (xxxx) not less than the current \$tlevel (yyyy). Cannot rollback.

Run Time Error: This indicates that the application is attempting to ROLLBACK to a transaction level that is zero (0) or negative. The minimum transaction level that an application can be rolled back to is one (1).

Action: Review the logic and code path that led to the error and modify the code appropriately.

#### **INVSPECREC**

INVSPECREC, Invalid global modifier record

Run Time Error: This indicates that GT.M could not access the header information for a global; therefore, it could not determine the collation characteristics of the global.

Action: Use the %gbldef utility routine to investigate the current state of the global header and correct it.

### **INVSTACODE**

**INVSTACODE**, Invalid value for second parameter of \$STACK (xxxx).

Run Time Error: This indicates that the intrinsic function \$STACK received an unrecognized string xxxx for the info (second) parameter.

Action: Make sure the second argument is "MCODE", "ECODE" or "PLACE".

### **INVSTRLEN**

**INVSTRLEN**, Invalid string length xxxx: max yyyy

Run Time Error: This indicates that GT.M encountered a string with a length of xxxx that exceeds the maximum acceptable length yyyy in this context.

Action: Modify the string to an acceptable length.

#### **INVSVN**

**INVSVN**, Invalid special variable name

Compile Time Error: This indicates that a variable of the form "\$name" did not match any valid special variable name.

Action: Look for typographical errors, an improper special variable name abbreviation, or a missing \$ in an extrinsic.

### INVTMPDIR O

**INVTMPDIR**, Value for \$gtm\_tmpdir is either not found or not a directory: dddd - Reverting to default value

Error: Indicates the process cannot access directory dddd, which it may need for a number of actions; the directory may not exist as a directory or the process lacks authorization to locate the directory.

Action: The directory specification comes from \$gtm\_tmp if it is defined, otherwise it defaults to the system temporary directory, typically /var/tmp on Solaris and /tmp in other environments. Either correct the environment variable definition or ensure directory dddd is appropriately set up. Note that all users of a particular GT.M instance normally need to use the same temporary directory to ensure proper interprocess communication.

#### **INVTRCGRP**

INVTRCGRP, Invalid trace group specified in \$gtm trace groups: gggg

Run Time Error: The process startup environment attempted to activate a diagnostic tracing facility but specified a group name of gggg and there is currently no such group.

Action: Check with your GT.M support channel for the currently available group names.

### **INVTRNSQUAL**

INVTRNSQUAL, Invalid TRANSACTION qualifier. Specify only one of TRANSACTION=[NO]SET or TRANSACTION=[NO]KILL.

MUPIP Error: This indicates that an invalid value was assigned to the -TRANSACTION qualifier.



Action: Specify appropriate value to the -TRANSACTION qualifier.

### INVZBREAK O

**INVZBREAK**, Cannot set ZBREAK in direct mode routine (GTM\$DMOD)

Run Time Error: GTM\$DMOD is an embedded routine that provides direct mode and it does not permit insertion of a ZBREAK.

Action: Issue ZBREAK only for application code

#### **INVZDIRFORM**

INVZDIRFORM, Illegal value (xxxx) specified for ZDIR FORM

Run Time Error: This indicates that the value specified for ZDIR\_FORM in the VIEW command is not recognized by GT.M.

Action: Specify a valid value for ZDIR FORM.

### **INVZROENT**

**INVZROENT**, xxxx is neither a directory nor an object library(DLL)

Run Time Error: This indicates that an invalid entry (xxxx), neither an object directory, nor a shared library, has been specified in \$ZROUTINES.

Action: Remove xxxx or replace it with a valid directory or a shared library.

### **INVZSTEP**

**INVZSTEP**, Invalid ZSTEP qualifier

Run Time Error: This indicates that ZSTEP had an argument other than OVER, INTO, or OUTOF.

Action: ZSTEP only accepts these three keyword arguments. It does not accept variables or indirection. Use one of the valid arguments. If you need additional control, consider using ZBREAK.

#### **IOEOF**

**IOEOF**, Attempt to read past an end-of-file

Run Time/MUPIP Error: This indicates that a READ command for a run-time system or a MUPIP command attempted to move past an end-of-file.

Action: Verify that the \$ZEOF special variable is tested by the function before each read or that an EXCEPTION code string is assigned to handle EOFs. The USE command has a REWIND

V6.2-002 MR Manual June 09, 2015, Page 125 Chapter 1. Error Messages **IOERROR** 

deviceparameter that allows you to read from the beginning of the file without having to CLOSE and OPEN again, which may facilitate recovery from this error. In the event of a MUPIP error, make sure the file being read is not corrupted.

#### **IOERROR**

**IOERROR**, Error occurred while doing aaaa in oooo operation -- called from module mmmm at line LLLL

Run Time Error: On UNIX this indicates a system call used to manage the underlying O/S device for a FIFO, PIPE or Sequential Disk failed in a way that GT.M did not anticipate.

Action: Use the OS documentation to investigate the failure.

### **IONOTOPEN**

IONOTOPEN, Attempt to USE an I/O device which has not been opened

Run Time Error: This indicates that a USE command attempted to make the current device one that had not been OPENed. The current device remains unchanged when this error occurs.

Action: Look for a missing OPEN or an extra CLOSE command.

#### **IORUNDOWN**

IORUNDOWN, Error during image rundown

Run Time Error: This indicates that as part of image termination, the process attempted to deallocate all devices and files allocated in GT.M but encountered an error.

Action: Use the appropriate host shell commands to display the statuses of the devices being used by the process, and deallocate any device that is still allocated.

#### **IOWRITERR**

**IOWRITERR**, IO write by PID xxxx to block yyyy of database zzzz failed. PID aaaa retrying the IO.

Run Time Error: This error message is sent to operator log when a queued write fails and is about to be retried. If an error status is available, it follows this message.

Action: Appearance of this message usually indicates disk subsystem error condition. Check disk error logs, in addition to operator logs for accompanying messages.

### **IPADDRREQ**

Last used version: V6.1-000

**IPCNOTDEL** Chapter 1. Error Messages

**IPADDRREQ**, Active connection requires IP address

Run Time Error: This indicates that an OPEN command specified a TCP mnemonicspace; however, it did not have a socket for an active connection or a LISTEN deviceparameter to designate a passive connection.

Action: Determine the type of connection desired and add a SOCKET=socket-id and/or a LISTEN deviceparameter.

#### **IPCNOTDEL**

**IPCNOTDEL**, xxxx : yyyy did not delete IPC resources for region zzzz

MUPIP Information: This indicates that MUPIP did not delete the shared system resources of the region. The shared system resources may still be being in use by some other processes.

Action: Find out if some other process was attached to the shared system resource. If appropriate, issue MUPIP RUNDOWN REG \* to remove the shared resource.

### **ISOLATIONSTSCHN**

ISOLATIONSTSCHN, Error changing NOISOLATION status for global xxxx within a TP transaction from aaaa to bbbb

Run Time Error: In GT.M, the VIEW "NOISOLATION" command changes the isolation-status of the global variable(s) specified. If a process attempts to change the global variable's isolation-status within a TP transaction after it has referenced the global variable in the same TP transaction, the ISOLATIONSTSCHN error gets triggered.

Action: Change the application to issue the VIEW "NOISOLATION" command in conformance with the allowed usage.

#### **ISSPANGBL**

ISSPANGBL, Operation cannot be performed on global ^gggg as it spans multiple regions in current global directory

Run Time Error: This indicates that a \$\$set^%GBLDEF or \$\$kill^%GBLDEF was attempted on a global that spans multiple regions.

Action: Only \$\$get^%GBLDEF is supported for spanning globals. Specify a non-spanning global or change the set/kill to a get. For spanning globals, use the GDE ADD -GBLNAME command to set collation characteristics.

#### **IVTIME**

IVTIME, Invalid time specification: xxxx

V6.2-002 MR Manual

Run Time Error: This indicates that a JOB command specified a SCHEDULE jobparameter with an invalid time xxxx

Action: Specify the time for the jobparameter according to the OpenVMS time format. GT.M requires a space between the date and time; DCL commands require a colon (:). For more information about the OpenVMS time format, refer to the OpenVMS DCL Dictionary.

## JIUNHNDINT

**JIUNHNDINT**, An error during \$ZINTERRUPT processing was not handled: eeee;

Run Time Error: When returning from code invoked by MUPIP INTRPT (clearing \$ZININTERRPT), GT.M implicitly clears any error(s) detected while 1=\$ZININTERRUPT, sends this error notification to the operator log and continues processing; eeee is the mnemonic for the unhandled error.

Action: Fix \$ZINTERRUPT handler to either not generate the error or to correctly handle it before returning to interrupted code

### INI

JNI, xxxx

Run Time Error: GT.M uses this message with appropriate accompanying text, xxxx, to indicate an error condition with a Java call-out invocation.

Action: Examine the text and address the described error condition.

# **INLACCESS**

**INLACCESS**, Error accessing journal file xxxx

Run Time Error: GT.M sends this message to the system log or the OpenVMS Operator Communications facility (OPCOM) followed by other messages detailing the failure. xxxx is the filespecification for the inaccessible journal. In most situations, this error occurs when the journal file storage runs out of disk space or there are permission issues.

Action: Review the accompanying message(s) for additional information. This usually means an error while trying to write to the journal file.

# **JNLACTINCMPLT**

JNLACTINCMPLT, Mupip journal action might be incomplete

MUPIP Warning: This indicates that MUPIP did not finish to completion successfully.

Action: Review and analyze the accompanying message(s).

**JNLALIGNSZCHG** Chapter 1. Error Messages

# **JNLALIGNSZCHG**

**INLALIGNSZCHG**, Journal ALIGNSIZE is rounded up to xxxx blocks (closest next higher power of two)

Run Time Information: This indicatest that the ALIGNSIZE specified in the MUPIP SET JOURNAL command was not a perfect power of two. It has been rounded up to the closest next higher power of two and the new journal file created (if any) will use this value for ALIGNSIZE.

Action: -

# **JNLALIGNTOOSM**

JNLALIGNTOOSM, Alignsize xxxx (bytes) is smaller than block size yyyy (bytes) for aaaa bbbb. Using alignsize of cccc (bytes) instead.

MUPIP Warning: This indicates that the specified alignsize xxxx is smaller than the specified block size yyyy for the mentioned region/database (aaaa) file bbbb. MUPIP will use the default cccc bytes instead of the specified xxxx.

Action: If the alignsize cccc used is not acceptable, choose some other legal value for alignsize and reissue the command.

### **JNLALLOCGROW**

JNLALLOCGROW, Increased Journal ALLOCATION from [ssss blocks] to [aaaa blocks] to match AUTOSWITCHLIMIT for ffff nnnn

GDE/MUPIP Information: The utility increased the journal allocation value from ssss to aaaa for the journal files associated with ffff nnnn, which is either "database file" followed by a database file name or "region" followed by a region name. This indicates that the specified journal allocation and journal extension values combined exceed the specified journal autoswitchlimit and the utility has adjusted the journal allocation value accordingly.

Action: None required.

# **INLBADLABEL**

JNLBADLABEL, Specified File xxxx fdoes not have a GT.M Journal File Label

MUPIP Error: This indicates that the journal file indicated in the accompanying previous message does not match the expected format.

Action: If a command specification caused this error, determine whether the command has the proper file-specification. Make sure the journal file was created by the current GT.M version. Also ensure that a process is not using a journal file-specification for some other purpose.

MR Manual V6.2-002 Chapter 1. Error Messages JNLBADRECFMT

## **JNLBADRECFMT**

JNLBADRECFMT, Journal Record Format Error encountered for file xxxx at disk address yyyy

MUPIP Error: This indicates that MUPIP has found an error in the journal file.

Action: Report the entire incident context to your GT.M support channel.

### **JNLBUFFDBUPD**

JNLBUFFDBUPD, Journal file buffer size for database file dddd has been adjusted from xxxx to yyyy

MUPIP Warning: The journal buffer size specified by the user for the database file dddd or previously stored in the database file header fell outside the permissible range, and was automatically adjusted, up or down, from xxxx to a legitimate value of yyyy.

Action: None Required.

## **JNLBUFFREGUPD**

JNLBUFFREGUPD, Journal file buffer size for region rrrr has been adjusted from xxxx to yyyy

MUPIP Warning: The journal buffer size specified by the user for the region rrrr or previously stored in the corresponding database file header fell outside the permissible range, and was automatically adjusted, up or down, from xxxx to a legitimate value of yyyy.

Action: None Required.

# **JNLBUFFTOOLG**

Last used version: V5.5-000

**JNLBUFFTOOLG**, Journal file buffer xxxx is greater than the maximum allowed size of yyyy. Journal file not created.

MUPIP Warning: This indicates that a MUPIP SET command with the JOURNAL qualifier failed because BUFFER\_SIZE=xxxx exceeded the maximum number of pages allowed. yyyy is the maximum buffer size permitted.

Action: Reduce the BUFFER\_SIZE= definition.

### **JNLBUFFTOOSM**

Last used version: V5.5-000

**INLBUFINFO** Chapter 1. Error Messages

JNLBUFFTOOSM, Journal file buffer xxxx is less than minimum of database block size in 512 byte pages + 1 (yyyy)

MUPIP Warning: This indicates that a SET command with the JOURNAL qualifier failed because the BUFFER SIZE=xxxx was inadequate to handle a database block, yyyy is the minimum buffer size permitted for the existing block size.

Action: Increase the BUFFER SIZE so it contains at least one more page than the database block, that is, bytes divided by 512.

# **JNLBUFINFO**

JNLBUFINFO, Pid aaaa dsk bbbb free cccc bytcnt dddd io in prog eeee fsync in prog ffff dskaddr gggg freeaddr hhhh qiocnt iiii now\_writer xxxx fsync\_pid yyyy filesize zzzz cycle oooo errcnt pppp wrtsize gggg fsync dskaddr rrrr

Run Time Information: This message always accompanies some other GT.M journaling error message. This gives detailed information on the state of the journal buffers at the time of the accompanying error.

Action: For information purposes only. Review the accompanying message(s) for additional information.

# **INLCLOSE**

**JNLCLOSE**, Error closing journal file: xxxx

Run Time Error: This indicates that GT.M could not properly close journal file xxxx.

Action: Review the accompanying message(s) for additional information.

### **JNLCLOSED**

**JNLCLOSED**, Journaling closed for database file dddd at transaction number xxx

Run Time Warning: This message indicates GT.M had to turn journaling OFF on the specified database. Other preceding messages identify the cause (e.g. lack of disk space while writing to journal file, permissions issue while auto-switching to new journal files etc.). The message also displays the database transaction number.

Action: Fix the issue that caused journaling to get turned OFF in the first place (disk space, permissions etc.).

Turn journaling back ON by issuing a MUPIP SET JOURNAL=ON or MUPIP BACKUP NEWJNL command. This command can work while processes are concurrently updating the database and causes GTM to journal subsequent updates in the journal file.

Chapter 1. Error Messages **INLCNTRL** 

### **JNLCNTRL**

**JNLCNTRL**, Journal control unsynchronized for ffff.

Run Time Error: This indicates that there is a discrepancy between the journal file updates and the database updates. The system is not updating journal files.

Action: Review the accompanying message(s) and take appropriate action. After the cause is resolved, to reestablish durability, perform a MUPIP BACKUP that turns journaling back on. Once the system is backup and running, contact your GT.M support channel with operator log information and any additional information that you feel is relevant for further diagnosis.

## **JNLCREATE**

JNLCREATE, Journal file xxxx created for <database/region> yyyy with aaaa

MUPIP Information: This indicates that a journal file xxxx is created for database/region yyyy with NOBEFORE IMAGES or BEFORE IMAGES journaling option (aaaa).

Action: -

### **JNLCREATERR**

Last used version: V5.4-001

**JNLCREATERR**, Error creating journal file xxxx

Run Time Error: This indicates that there was an error while trying to create journal file xxxx.

Action: Review the accompanying message(s) for additional information.

### **INLCRESTATUS**

**INLCRESTATUS**, xxxx at line aaaa for journal file yyyy, database file zzzz encountered error

Run Time/MUPIP Warning: This indicates the creation of journal file yyyy for database file zzzz failed.

Action: Review the accompanying messages and take appropriate action.

### **INLCYCLE**

JNLCYCLE, Journal file xxxx causes cycle in the journal file generations of database file yyyy

MUPIP Error: This indicates that MUPIP encountered journal file xxxx causing cycle in the journal file generations of database file yyyy. (this is not explanatory, at least to me.)

V6.2-002 GT.M Message and Recovery Procedures Manual INLDBERR Chapter 1. Error Messages

Action: Contact your GT.M support channel with appropriate log messages.

# **JNLDBERR**

**JNLDBERR**, Journal file xxxx does not correspond to database yyyy

Run Time Error: This indicates that GT.M could not open journal file xxxx for database file yyyy because the journal file header identifies itself as belonging to a different database file that does not exist in the system.

Action: Use a MUPIP SET command with the qualifier JOURNAL to create a journal file that matches the database.

## **JNLDBTNNOMATCH**

JNLDBTNNOMATCH, Journal file xxxx has beginning transaction number aaaa but database yyyv has current transaction number bbbb

MUPIP Error: MUPIP JOURNAL FORWARD has found that journal file xxxx has beginning transaction number aaaa, but the corresponding database file yyyy has current transaction number bbbb. This condition may arise due to missing or duplicate transactions.

Action: Verify that the correct journal file names were specified. If appropriate, force forward recovery using the NOTNCHECK qualifier.

# **JNLDISABLE**

**INLDISABLE**, Specified journal option(s) cannot take effect as journaling is DISABLED on database file xxxx

MUPIP Warning: This indicates that none of the specified journal option(s) in MUPIP SET -JOURNAL or MUPIP BACKUP command took effect, because journaling was found DISABLED on database file XXXX.

Action: -

# **JNLDSKALIGN**

Last used version: V4.3-000

JNLDSKALIGN, Journal Record Alignment xxxx is not a multiple of 512

MUPIP Warning: This indicates that the system is not updating the journal file correctly.

Action: Close the journal file and begin journaling with a new journal file. If the error continues, check the disk subsystem.

### **JNLENDIANBIG**

JNLENDIANBIG, Journal file jjjj is BIG endian on a LITTLE endian system

MUPIP Error: The MUPIP command on a little endian system specified journal file jjjj which was created on a big endian system. GT.M does not convert journal files with incompatible byte ordering.

Action: Set up operational procedures that ensure journal files are used on systems with the same byte ordering as where they are created. If necessary, extract journal file data on the source system and use an M program on the opposite endian system to restore it.

### **INLENDIANLITTLE**

JNLENDIANLITTLE, Journal file jijj is LITTLE endian on a BIG endian system

MUPIP Error: The MUPIP command on a big endian system specified journal file jjjj which was created on a little endian system. GT.M does not convert journal files with incompatible byte ordering.

Action: Set up operational procedures that ensure journal files are used on systems with the same byte ordering as where they are created. If necessary, extract journal file data on the source system and use an M program on the opposite endian system to restore it.

### **JNLEOFPREZERO**

Last used version: V4.4-000

**JNLEOFPREZERO**, Error while zeroing journal file xxxx

Run Time Error: Write operation fails. When the last process with write access to a journaled database leaves, the system closes the journal file by writing an end-of-file (EOF) record at a 512-byte boundary. To do this, the system zeroes the journal file from the current offset until the next aligned 512-byte boundary. It is this write operation whose failure causes this error.

Action: Check the integrity of the journal file by doing a MUPIP JOURNAL -FORWARD -VERIFY jnl-file.

# **INLEXTEND**

**JNLEXTEND**, Journal file extension error for file xxxx.

Run Time Error: Journal file xxxx failed to extend. If the environment is not configured for instance freeze, this causes journaling to be turned off for the region.

Action: Review the accompanying message(s) and take appropriate action. If the environment is not configured for instance freeze, perfrom a MUPIP BACKUP, that turns journaling on again, to reestablish durability.

FIS V6.2-002

## **JNLEXTR**

**JNLEXTR**, Error writing journal extract file: xxxx

MUPIP Error: This indicates that an error was encountered while trying to write to either the JNL EXTRACT file or lost-transaction file or broken-transaction file as part of a MUPIP JOURNAL command.

Action: Review the accompanying message(s) for additional information.

## **JNLFILECLOSERR**

**JNLFILECLOSERR**, Error closing journal file xxxx

MUPIP Error: This indicates that MUPIP JOURNAL command failed to close the specified journal file XXXX.

Action: Review the accompanying message(s) for additional information.

### **JNLFILEDUP**

**INLFILEDUP**, Journal files xxxx and yyyy are the same

MUPIP Information: MUPIP JOURNAL -RECOVER -FORWARD does not allow duplicated journal files in forward recovery.

Action: Remove any duplicated journal file(s) and re-issue the forward recovery command.

# **JNLFILEOPNERR**

**JNLFILEOPNERR**, Error opening journal file xxxx

MUPIP Error: This indicates that MUPIP JOURNAL command failed to open the specified journal file xxxx.

Action: Ensure the journal file name specified is correct. Review the accompanying message(s) for additional information.

# **JNLFILEXTERR**

**INLFILEXTERR**, Error during extension of journal file xxxx

Run Time Error: This indicates that an error was encountered during the course of journal file extension, while trying to determine the available space on the file system housing the journal file xxxx. This causes the journaling to be turned off.

Action: Locate appropriate disk space and adjust the journal file path. To reestablish durability, perform a MUPIP BACKUP that turns back journaling on again.

V6.2-002 MR Manual June 09, 2015, Page 135 Chapter 1. Error Messages INLFILNOTCHG

# **JNLFILNOTCHG**

JNLFILNOTCHG, Journal file not changed

MUPIP Error: This indicates that the MUPIP SET-JNLFILE command was unable to change the journal file as specified.

Action: Review accompanying message(s) for additional information.

## **JNLFILOPN**

**JNLFILOPN**, Error opening journal file xxxx for database file yyyy

Run Time Error: This indicates that GT.M was unable to open journal file xxxx for the specified database file. The Source Server exits with a JNLFILOPN message after six failed attempts to open journal files.

Action: Review the accompanying message(s) for additional information.

## **INLFILRDOPN**

JNLFILRDOPN, Error opening journal file xxxx for read for database file yyyy

Source Server log/MUPIP Error: This indicates that GT.M was unable to open journal file xxxx in readonly mode for the specified database file. The Source Server exits with a JNLFILRDOPN message after six failed attempts to open journal files.

Action: Review the accompanying message(s) for additional information.

### **INLFLUSH**

**JNLFLUSH**, Error flushing journal buffers to journal file xxxx

Run Time Error: This indicates that an attempt to write existing journal records to the journal file failed.

Action: Review the accompanying message(s) for additional information.

# **INLFLUSHNOPROG**

**JNLFLUSHNOPROG**, No progress while attempting to flush journal file xxxx

Run Time Warning: This warning message is logged to the operator facility. This indicates that a GT.M process waited for about 2 minutes for journal file xxxx to be flushed to disk from database shared memory. The accompanying TEXT message gives more details. The JNLFLUSHNOPROG message is preceded by JNLFLUSH messages.

V6.2-002 GT.M Message and Recovery Procedures Manual INLFNF Chapter 1. Error Messages

Action: Indicative of a clogged disk subsystem on which journal file xxxx resides. Consider balancing disk subsystem load.

## **INLFNF**

**JNLFNF**, Journal file xxxx not found

MUPIP Information: This indicates that MUPIP did not find the specified journal file xxxx while executing the command.

Action: -

### **JNLFSYNCERR**

JNLFSYNCERR, Error synchronizing journal file xxxx to disk

Run Time Error: This indicates that the fsync() function on the journal file xxxx failed. This is likely a disk subsystem related problem.

Action: Review the accompanying messages for cause of the failure.

## **JNLFSYNCLSTCK**

#### JNLFSYNCLSTCK,

Run Time Error:

Action: -

# **JNLINVALID**

**JNLINVALID**, xxxx is not a valid journal file Region: yyyy

Run Time Error: This indicates that GT.M could not open journal file xxxx, due to an error that is detailed in the accompanying previous message(s). While trying to create a new journal file for the same region it encountered errors. yyyy is the region name associated with the journal.

Action: Review the accompanying error message(s) to determine the cause of the failure of the new journal file creation. After the cause is resolved, to reestablish durability perform a MUPIP BACKUP that turns journaling back on.

# **JNLINVALLOC**

**JNLINVALLOC**, Journal file allocation xxxx is not within the valid range of yvyy to zzzz. Journal file not created.

V6.2-002 MR Manual June 09, 2015, Page 137 MUPIP Warning: This indicates that a SET command modified with the JOURNAL qualifier failed because ALLOCATION=xxxx was less than the minimum or greater than the maximum number of blocks. yyyy is the minimum allocation permitted. zzzz is the maximum allocation permitted.

Action: Adjust the ALLOCATION= to adhere to the valid range.

## **JNLINVEXT**

**JNLINVEXT**, Journal file extension xxxx is greater than the maximum allowed size of yyyy. Journal file not created.

MUPIP Warning: This indicates that a SET command modified with the JOURNAL qualifier failed because the EXTENSION=xxxx argument exceeded the maximum number of pages. yyyy is the maximum extension permitted.

Action: Reduce the EXTENSION= qualifier definition.

## **JNLINVSWITCHLMT**

JNLINVSWITCHLMT, Specified AUTOSWITCHLIMIT xxxx falls outside of allowed limits aaaa and bbbb

MUPIP Error: This indicates that the specified autoswitchlimit for the journal file is outside of the allowed range [that is indicated in the error message].

Action: Specify an autoswitchlimit within the specified allowed range.

### **INLMEMDSK**

Last used version: V5.3-001A

JNLMEMDSK, Journal file unsynchronized with the journal buffer. Journaling closed for xxxx.

Run Time Error: This indicates that the structures in the journal buffer reflect an out-of-design situation. As a result, GT.M has shut down journaling for the xxxx region.

Action: Review the accompanying message(s) and take appropriate action. After the cause is resolved, to reestablish durability, perform a MUPIP BACKUP that turns journaling back on. Once the system is backup and running, contact your GT.M support channel with operator log information and any additional information that you feel is relevant for further diagnosis.

# JNLMINALIGN

JNLMINALIGN, Journal Record Alignment xxxx is less than the minimum value of yyyy

MUPIP Warning: This indicates that a MUPIP SET JOURNAL command specified an alignsize for the new journal file, which is less than the minimum allowed yyyy.

FIS V6.2-002

**INLMOVED** Chapter 1. Error Messages

Action: Specify an alignsize that is greater than the allowed minimum.

## **INLMOVED**

**INLMOVED**, Journal file appears to have been moved. Journaling activity will not be done.

Run Time Error: This indicates that while opening a journal file the system encountered the journal file name in the database header file, pointing to a different location than the journal file ID.

Action: Use MUPIP SET to specify the correct journal file location.

### **INLNAMLEN**

**JNLNAMLEN**, Journal file xxxx: for database file yyyy exceeds maximum of zzzz

MUPIP Error: This indicates that the file-specification xxxx of the journal for database file yyyy exceeds the maximum supported length of zzzz.

Action: Modify the journal file-specification to adhere to the file length restrictions.

### **JNLNEWREC**

**INLNEWREC**, Target system cannot recognize journal record of type xxxx. Last recognized type is уууу.

MUPIP Error: This error is logged to the replication server log file. This indicates that the GT.M application on the replication primary generated a newly introduced journal record (of type xxxx) that is not recognized by the secondary system. The highest numbered journal record type on the secondary is yyyy. A new type that can be transformed to an older type internally by the source server on the primary side will be automatically done. This error occurs when the primary source server cannot transform the new type to an older type due to impact on the application logic.

Action: The application either should not generate a journal record that is not recognized by the secondary, or, write a filter that transforms the unknown type to a known type on the target system. The replication source server on the primary should be restarted with the filter.

# **JNLNMBKNOTPRCD**

JNLNMBKNOTPRCD, Journal file xxxx does not match the current journal file yyyy of database file ZZZZ

MUPIP Error: This indicates that MUPIP JOURNAL BACKWARD cannot proceed because the journal file name xxxx is not same as the journal file name yyyy in the database file header of zzzz.

Action: Specify the correct journal file name for the database zzzz. If the database file header is not pointing to the correct journal file, fix it using MUPIP SET JOURNAL.

# **JNLNOBIJBACK**

JNLNOBIJBACK, MUPIP JOURNAL BACKWARD cannot continue as journal file xxxx does not have before image journaling

MUPIP Error: This indicates that an attempt to use BACKWARD qualifier on xxxx journal file was made without enabling before image journaling on the file.

Action: Ensure before image journaling is enabled prior to the usage of BACKWARD qualifier, alternatively use FORWARD qualifier for nobefore image journaling enabled files.

## **JNLNOCREATE**

**INLNOCREATE**, Journal file xxxx not created

MUPIP Error: This indicates that MUPIP could not create journal file xxxx.

Action: Review the accompanying message(s) for additional information.

## **INLNOREPL**

**JNLNOREPL**, Replication not enabled for journal file jjjj (database file dddd)

Source Server log/MUPIP Error: Replication Source Server startup encountered a database dddd with journal file jijj for which replication was turned off because of a journaling issue and has not since been re-enabled.

Action: Use MUPIP SET to re-enable replication. Take steps to ensure that there is sufficient management of journal file space to prevent a reoccurrence of this issue.

### **JNLNOTFOUND**

Last used version: V4.4-000

**JNLNOTFOUND**, File xxxx does not exist -- possibly moved or deleted

MUPIP Information: This indicates that MUPIP has encountered a journal file link name xxxx, which does not exist in the system anymore.

Action: This message is usually accompanied by a NORECOVERR error message. Either a closer turnaround-point mapping to an existing prior journal file generation needs to be specified, or the missing journal file needs to be restored from the backup.

### **INLOPNERR**

**JNLOPNERR**, Error opening journal file xxxx for region yyyy

**INLORDBFLU** Chapter 1. Error Messages

Run Time/MUPIP Error: This indicates that GT.M could not open the journal file xxxx.

Action: Review and trouble shoot accompanying messages.

## **JNLORDBFLU**

**INLORDBFLU**, Error flushing database blocks to dddd. See related messages in the operator log

Run Time Error: This message indicates that hardening journal or database records could not be completed due to an error. The operator log should contain one or more accompanying messages indicating the cause of the error.

Action: Verify the normal state of the file system and appropriate permissions of the database and journal files. Report the entire incident context to your GT.M support channel along with any GT.M operator log messages within the same time frame.

### **INLPOOLBADSLOT**

**INLPOOLBADSLOT**, Source server slot for secondary instance xxxx is in an inconsistent state. Pid = pppp, State = ssss, SlotIndex = iiii

Source Server log/MUPIP Warning: This is a debugging message sent to the syslog (operator log) whenever a source server startup or showbacklog command finds a structure in the journal pool holding inconsistent information.

Action: Forward the information to your GT.M support channel. No action otherwise necessary. The source server command will automatically fix the inconsistency of that structure

# **JNLPOOLSETUP**

**JNLPOOLSETUP**, Journal Pool setup error

Run Time/MUPIP Error: This indicates that an error occurred in the replication subsystem while opening the journal pool.

Action: Verify that the source server has been configured correctly. Review accompanying messages for more information about the cause of this error.

# **INLPREVRECOV**

JNLPREVRECOV, Journal file has nonzero value in prev recov end of data field

Run Time Error: This indicates that GT.M encountered a non-zero value for the journal file header prev recov end of data field. MUPIP JOURNAL RECOVER/ROLLBACK can cause the field to be nonzero but it cannot become a current generation journal file for GT.M run-time. Run-time considers the journal file as bad and switches to a new journal file cutting the back-link.

Action: Report the complete error to GT.M support along with appropriate log messages within the same time frame.

# **JNLPROCSTUCK**

JNLPROCSTUCK, Journal file writes blocked by process xxxx

Run Time Warning: This indicates that a GT.M process waited for nearly one minute and is not able to flush the journal as the journal write mechanism seems to be blocked by process xxxx.

Action: If the situation does not improve, kill the offending process xxxx. This may indicate an overloaded disk subsystem on which journal file xxxx resides. Consider balancing disk subsystem load. If necessary, report the entire incident context with operator log information to your GT.M support channel.

# **INLPVTINFO**

JNLPVTINFO, Pid aaaa cycle mmmm fd\_mismatch nnnn channel rrrr sync\_io ssss pini\_addr xxxx qio\_active yyyy old\_channel zzzz

Run Time Information: This message always accompanies some other GT.M journaling error message. This gives detailed information on the state of the journal buffers at the time of the accompanying

Action: For information purposes only. Review the accompanying message(s) for additional information.

# **JNLQIOLOCKED**

Last used version: V4.4-000

**JNLQIOLOCKED**, Error obtaining io in prog lock on journal file xxxx

Run Time Error: When the last process with write access to a journaled database exits, it does a cleanup of the journal file by attempting to get an exclusive write lock on the journal file. If that fails after waiting for nearly one minute, it issues this error.

Action: Attempt MUPIP RUNDOWN on the region making sure to run down all processes actively attached to this database. If the error persists even after no one is attached, contact your GT.M support channel before proceeding.

# **INLQIOSALVAGE**

JNLQIOSALVAGE, Journal IO lock salvaged

Run Time Information: An active process salvaged a critical resource marked as belonging to a no longer active (terminated) process during a journal flush.

FIS V6.2-002 GT.M Message and Recovery Procedures Manual **INLRDERR** Chapter 1. Error Messages

Action: The system automatically returns the critical resource to normal operation and continues execution. If this message continues to occur, please investigate why the process holding the crit abnormally exited.

### **INLRDERR**

**JNLRDERR**, Error reading journal file xxxx: unable to initialize.

Run Time Error: This indicates that GT.M encountered an error while trying to read from the journal file xxxx. This can happen if the journal file size is less than the minimum size of the journal file header, or if the journal-file-specification does not match the intended file, or if the intended file is not accessible by the processes that update the database. GT.M automatically attempts to create a new journal file. If the attempt to create a new journal file fails, GT.M issues another error and the intended update is lost and does not get registered in the database and journal.

Action: To reestablish durability, perform a MUPIP BACKUP that switches to a new set of journal files.

### **JNLRDONLY**

**JNLRDONLY**, Journal file xxxx read only

MUPIP Error: This indicates that the process in use does not have journal file write privileges or the journal file has been set to read-only.

Action: You may be performing an invalid operation. Contact your Systems Administrator.

# **INLREAD**

JNLREAD, Error reading from journal file xxxx at offset yyyy

MUPIP Error: This indicates that MUPIP failed to read from journal file xxxx at offset yyyy.

Action: Review the accompanying message(s) for additional information.

## **INLREADBOF**

JNLREADBOF, Beginning of journal file encountered for xxxx

MUPIP Error: This indicates that MUPIP JOURNAL command reached the beginning of journal file xxxx, while processing backward, and is not able to process backward anymore. This maybe due to the time qualifiers used to control the length of the backward processing.

Action: Verify that the time qualifiers specified are as intended.

# **INLREADEOF**

**INLREADEOF**, End of journal file encountered for xxxx

V6.2-002 MR Manual June 09, 2015, Page 143 MUPIP Error: This indicates that MUPIP JOURNAL encountered the end-of-file for the journal file xxxx, before it completed processing.

Action: This error indicates an improperly closed journal file.

## **INLRECFMT**

**INLRECFMT**, Journal file record format error encountered

Run Time/MUPIP Error: This indicates that MUPIP JOURNAL encountered an invalid record in the journal file.

Action: In the event of GT.M issuing this error message, use MUPIP BACKUP to ensure durability by creating a fresh set of journals consistent with the database. Else, to resume operation, restore the database from the last backup and play forward the updates using the appropriate MUPIP JOURNAL command. As soon as possible, report the entire incident context with information from the operator log and any other relevant information to your GT.M support channel.

# **JNLRECINCMPL**

JNLRECINCMPL, Incomplete journal record at disk address agaa for file jijj while attempting to read seqno ssss

Source Server log/MUPIP Error: The replication Source Server had a problem with journal file jijj at disk offset aaaa attempting to read the record with sequence number ssss.

Action: Report the entire incident context to your GT.M support channel for further analysis. Use MUPIP SET JOURNAL -EXTRACT to investigate the issue.

## **INLRECTYPE**

**JNLRECTYPE**, Journal record type does not match expected type

Run Time Error: This indicates that when GT.M tried to open the journal file as part of an M update, the end of the journal file as indicated by the journal-file-header did not contain an EOF journal record implying that the journal file is either damaged or corrupted. This message follows a JNLOPNERR message, which indicates the journal file name and the corresponding region. GT.M automatically attempts to create a new journal file and errors out if the attempt does not succeed, in which case the intended update is not reflected in the database and journal.

Action: To reestablish durability, perform a MUPIP BACKUP that switches to a new set of journal files consistent with the database.

# **INLSENDOPER**

JNLSENDOPER, pid = aaaa : status = bbbb : jpc\_status = ccc : jpc\_status2 = dddd : iosb.cond = eeee

**INLSETDATA2LONG** Chapter 1. Error Messages

Run Time Information: This message gives information on the process that encountered an error in GT.M journaling and the error code encountered. This message is always followed by a GT.M journaling error message that gives the error detail.

Action: Review the accompanying message(s) for additional information.

# **INLSETDATA2LONG**

JNLSETDATA2LONG, SET journal record has data of length xxxx. Target system cannot handle more than yyyy bytes.

MUPIP Error: This error message is logged to the replication server log file. The version of GT.M running on the replication primary system supports longer data lengths for globals than the GT.M version running on the secondary system.

Action: Until the secondary is upgraded to the newer version of GT.M, the application should not use the new feature of longer data lengths.

### **INLSPACELOW**

JNLSPACELOW, Journal file xxxx nearing maximum size, aaaa blocks to go

Run Time Information: This indicates that the journal file xxxx is approaching the maximum size specified for it. The system creates a new journal file when the limit is reached. Typically none, unless operational practice uses this as a trigger to intervene in journal file management.

Action: -

## **JNLSTATE**

**JNLSTATE**, Journaling state for <database/region> xxxx is now yyyy

MUPIP Information: This indicates that journal state for the database/region xxxx is now yyyy.

Action: -

# **JNLSTATEOFF**

**JNLSTATEOFF**, ROLLBACK or RECOVER BACKWARD cannot proceed as database file xxxx does not have journaling ENABLED and ON

MUPIP Error: This indicates that ROLLBACK or RECOVER cannot proceed because MUPIP encountered a database file xxxx, which does not have journaling ENABLED and ON.

Action: Verify that the file(s) specified is correct. Ensure that Journaling is ENABLED and ON for RECOVER BACKWARD to work.

## **INLSUCCESS**

JNLSUCCESS, xxxx successful

MUPIP Success: This indicates that xxxx command has finished successfully.

Action: -

## **INLSWITCHSZCHG**

JNLSWITCHSZCHG, Journal AUTOSWITCHLIMIT [aaaa blocks] is rounded down to [bbbb blocks] to equal the sum of journal ALLOCATION

Run Time Information: This indicates that the specified AUTOSWITCHLIMIT value was rounded down as little as possible to make it aligned to the ALLOCATION + a multiple of EXTENSION. The new journal file created (if any) will use this value for AUTOSWITCHLIMIT.

Action: -

### **JNLSWITCHTOOSM**

JNLSWITCHTOOSM, Journal AUTOSWITCHLIMIT [aaaa blocks] is less than journal ALLOCATION [bbbb blocks] for database file xxxx

Run Time Error: This indicates that the value of AUTOSWITCHLIMIT specified in a MUPIP SET JOURNAL command is less than the default or specified value of ALLOCATION. This error also indicates that the AUTOSWITCHLIMIT value specified was greater or equal to the ALLOCATION but in turn got rounded down, and this rounded down value is lesser than the ALLOCATION.

Action: Specify a higher value of AUTOSWITCHLIMIT.

# **INLTMQUAL1**

JNLTMQUAL1, Time qualifier BEFORE TIME=xxxx is less than SINCE TIME=yyyy

MUPIP Error: This indicates that the specified before time xxxx is earlier than the since time yyyy.

Action: Specify correct values for time qualifiers and make sure that BEFORE\_TIME is specified to be later than the SINCE TIME.

### **INLTMQUAL2**

JNLTMQUAL2, Time qualifier LOOKBACK\_TIME=xxxx is later than SINCE\_TIME=yyyy

MUPIP Error: This indicates that the specified lookback time xxxx is later than the since time yyyy.

Action: Specify correct values for time qualifiers and make sure that the LOOKBACK TIME qualifier is set to an earlier time value than the SINCE\_TIME qualifier.

FIS V6.2-002 GT.M Message and Recovery Procedures Manual

# **INLTMQUAL3**

**INLTMOUAL3**, Time qualifier BEFORE TIME=xxxx is less than the journal file(s) minimum timestamp=yyyy

MUPIP Error: This error indicates that the -BEFORE TIME xxxx is earlier than the earliest timestamp yyyy found in the journal file(s).

Action: Issue the MUPIP command again with an appropriate value for -BEFORE TIME. Note that journal files record time based on a UTC clock, which is time zone independent, while MUPIP interprets time-based input based your local clock and adjusts its actions accordingly. If you use a local clock (in UNIX, set by the TZ environment variable) that is subject to significant shifts, such as between standard time and daylight savings, when the time shifts back (for example, from daylight to standard), the time change may cause this error. One way to address this is to, possibly temporarily, switch your local time setting to UTC.

# **JNLTMQUAL4**

JNLTMQUAL4, Time qualifier BEFORE TIME="xxxx is less than AFTER TIME="yyyy"

MUPIP Error: This indicates that the specified BEFORE TIME xxxx is earlier than the AFTER TIME yyyy specified

Action: Specify correct values for the time qualifiers and make sure that AFTER\_TIME is earlier than BEFORE TIME qualifier.

## **INLTNOUTOFSEQ**

**INLTNOUTOFSEO**, End transaction aaaa of journal xxxx different from Begin transaction bbbb of next generation journal yyyy

MUPIP Error: MUPIP JOURNAL FORWARD command has found that the transaction numbers (aaaa and bbbb) of two consecutive generation journal files (xxxx and yyyy) are not in sequence. It is expected that the end transaction of a journal file is the same as the begin transaction of the immediately succeeding generation.

Action: Ensure the specification of journal file names is as intended. Verify if the journal file xxxx and yyyy are really in sequence. Find out if any of the transactions are missing or duplicate using MUPIP JOURNAL SHOW=HEAD FORWARD NOVERIFY. If appropriate, force forward recovery using the NOTNCHECK qualifier.

# **JNLTPNEST**

JNLTPNEST, Mupip journal command found nested TP transactions for journal file jijj at offset oooo at transaction number nnnn

V6.2-002 MR Manual June 09, 2015, Page 147 MUPIP Warning: MUPIP JOURNAL -RECOVER or ROLLBACK encountered a TSTART record for transaction nnnn at offset oooo in journal file jijj while already processing an uncommitted transaction. Since the run-time system should never produce this situation, the journal file is suspect. MUPIP discards the in-progress transaction and proceeds.

Action: Extract the journal file(s) and use the context from the message to find the transactions in question and adjust for any lost or tangled transaction(s).

## **JNLTRANS2BIG**

**INLTRANS2BIG**, Transaction needs an estimated [aaaa blocks] in journal file xxxx which exceeds the AUTOSWITCHLIMIT of bbbb

Run Time Error: This indicates that a database update transaction needs agaa blocks of space in the journal file for its corresponding journal records and this exceeds the AUTOSWITCHLIMIT value of the current journal file.

Action: Increase the AUTOSWITCHLIMIT, or if the transaction is a TP transaction decrease the number of updates done within one transaction thereby decreasing its journal file space requirement.

## **JNLTRANSGTR**

**JNLTRANSGTR**, Transaction number in journal is greater than in database

Run Time Warning: This indicates that GT.M was unable to open the journal file because its transaction number does not match the database files transaction number

Action: GT.M automatically closes the current journal file and creates a new one. To reestablish durability, perform MUPIP BACKUP to create a fresh set of journals consistent with the database. Review the accompanying message(s) for information on the journal file name.

## **JNLTRANSLSS**

JNLTRANSLSS, Transaction number in journal is less than in database

Run Time Warning: This indicates that GT.M was unable to open the journal file because its transaction number does not match the database files transaction number.

Action: GT.M automatically closes the current journal file and creates a new one. To reestablish durability, perform MUPIP BACKUP to create a fresh set of journals consistent with the database. Review the accompanying message(s) for information on the journal file name.

## **JNLUNXPCTERR**

**INLUNXPCTERR**, Unexpected error encountered for Journal aaaa at disk address 0xbbbb

**INLVSIZE** Chapter 1. Error Messages

MUPIP Error: This indicates that MUPIP JOURNAL has detected an unexpected error in the journal file that prevents the command from proceeding. A recovery or rollback that uses this journal file cannot successfully complete.

Action: Report the entire incident context to your GT.M support channel.

## **JNLVSIZE**

JNLVSIZE, Journal File xxxx has incorrect virtual filesize aaaa Allocation is bbbb extension is cccc filesize is dddd file system block size is eeee

Run Time Error: This indicates that journal file xxxx has incorrect value in the Virtual file size file header field. Either it is less than the actual filesize or it is not the same as allocation + n \* extension.

Action: Run time system creates and switches to a new journal file and continues to run. Report to your GT.M support channel with any accompanying message(s).

## **JNLWRERR**

JNLWRERR, Error writing journal file xxxx. Undable to update header Region: yyyy

Run Time Error: This indicates that GT.M encountered an error while updating the journal file header as part of trying to open the journal file.

Action: Review the accompanying message(s) for detail on the cause of the error. GT.M automatically closes the current journal file and creates a new one. To reestablish durability, perform MUPIP BACKUP to create a fresh set of journals consistent with the database.

## **INLWRTDEFER**

**JNLWRTDEFER**, Journal write start deferred

Run Time Information: This message always accompanies some other GT.M journaling message. This indicates that a flush of the journal buffer to the disk system was deferred since some other process is currently busy flushing the journal buffer.

Action: Review the accompanying message(s) for additional information.

## **JOBACTREF**

**JOBACTREF**, Actual parameter in job command passed by reference

Compile Time Error: This indicates that arguments to JOB cannot be passed by reference.

Action: Arguments to JOB must be passed by value.

### **JOBARGMISSING**

JOBARGMISSING, Missing job argument nnnn - can't skip non-trailing arguments to a JOB command in OpenVMS editions

Run Time Error: Indicates a JOB command parameter list contains two adjacent commas (,,), which should show an intention to not supply an actuallist value for the corresponding formallist parameter. nnnn is the ordinal number of the first argument with this issue.

Action: If the parameter was not intentionally skipped, correct the JOB command. If the parameter should be optional, reorder the lists so the parameter in question is at the end of the list where it can be omitted or establish a distinguished value, such as an empty string, to serve in place of an omitted value.

## **JOBEXAMDONE**

**JOBEXAMDONE**, GT.M process aaaa completed job examine to xxxx

Run Time/Operator log Information: This informational message reports that a \$ZJOBEXAM was performed and gives a complete file specification. The message is sent to the operator log.

Action: -

## **JOBEXAMFAIL**

JOBEXAMFAIL, GT.M process agaa executing \$ZJOBEXAM function failed with the preceding error message

Run Time/Operator log Error: This is a secondary message that accompanies a \$ZJOBEXAM function error. This error message is sent to the operator log.

Action: Review the accompanying message(s) and take appropriate action.

# **IOBFAIL**

JOBFAIL, JOB command failure

Run Time Error: This indicates that a JOB command did not complete successfully.

Action: Review the accompanying message(s) for additional information. If a STARTUP jobparameter is specified, make sure that the file is accessible and has the desired content.

On OpenVMS systems: Verify the logical names and the LOGIN.COM file of the process that is issuing the IOB command because differences in the environment are the most common reason for failure.

# **JOBLABOFF**

**JOBLABOFF**, Label and offset not found in created process

**IOBLVN2LONG** Chapter 1. Error Messages

Run Time Error: This indicates that a JOB command specified an entry reference that could not be located in the image used by the new job.

Action: Verify that the image being JOBbed is properly linked. If the image has been changed since it was last LINKed, determine whether the new job has access to the files necessary to ZLINK the changes. You can also LINK the image to include the changes.

## JOBLVN2LONG

JOBLVN2LONG, The zwrite representation of a local variable transferred to a JOB'd process can not exceed MMMM. Encountered size: LLLL

Run Time Error: This error indicates that the total length LLLL (in bytes) of the ZWRITE representation of the variable name, subscripts, and value exceeds the maximum MMMM supported by the PASSCURLVN facility. Note that the ZWRITE representation contains the appropriate punctuation for any subscripts, the equal-sign and replaces any non-graphic characters with their \$[Z]CHAR() representations.

Action: Look at the error output of the JOB'd process for the length and maximum values as they are not available to the process issuing the JOB command and appear in its message as zeros (0). Consider whether the JOB'd process needs the variable(s) that exceed the maximum for PASSCURLVN - if not they can be taken out of scope before the JOB command. Alternatively, pass them using global variables or a local SOCKET device.

# **JOBLVNDETAIL**

JOBLVNDETAIL, The zwrite representation of a local variable transferred to a JOB'd process is too long. The zwrite representation cannot exceed XXXX. Encountered size: YYYY

Run Time Error: The length of the zwrite representation of a local, (including the quotes, the '=', concatenate operator "\_", and "\$[Z]C()") has the length of YYYY which exceeds the maximum limit of XXXX.

Action: Please check the sizes of locals that needs to be sent and make sure their lengths are less than XXXX. For those big locals, consider using another mechanism such as sockets.

# **IOBPARM**

Last used version: V5.4-000A

**JOBPARM**, Error accessing job parameters

Run Time Error: GT.M could not retrieve the job information piped from the originating job.

Action: Check for appropriate permissions for the parent and child job environments, also for operational actions that might delete temporary pipes; if necessary, report the entire incident context to your GT.M support channel for additional diagnostic assistance.

### **JOBPARNOVAL**

JOBPARNOVAL, This job parameter cannot take a value

Compile Time Error: This indicates that a JOB command specified a value for a jobparameter that does not accept a value.

Action: Modify the jobparameter or remove its argument.

### **JOBPARNUM**

JOBPARNUM, The value of this job parameter must be an integer

Compile Time Error: This indicates that a JOB command specified a valid jobparameter but it did not assign an integer value, which is required.

Action: Verify that the jobparameter has an integer literal argument and not a string or variable argument.

### **JOBPARSTR**

**JOBPARSTR**, The value of this job parameter must be a string

Compile Time Error: This indicates that a JOB command specified a valid jobparameter but did not assign the jobparameter a string value as expected.

Action: Ensure that the jobparameter has a string literal argument and not a variable or keyword argument.

# **JOBPARTOOLONG**

JOBPARTOOLONG, JOBPARTOOLONG Total parameter length is too long for job command

Run Time Error: This indicates that the total length of jobparameters that must be passed to the created job exceeded the size of the buffer that was available to handle them.

Action: Use fewer and/or shorter items in parameter passing; consider passing information in a global.

## **JOBPARUNK**

JOBPARUNK, Job parameter unknown

Compile Time Error: This indicates that a JOB command specified an invalid jobparameter keyword.

Action: Specify a valid jobparameter keyword. Refer to the Programmer's Guide for a valid keyword.

**JOBPARVALREQ** Chapter 1. Error Messages

# **JOBPARVALREQ**

**JOBPARVALREQ**, A value is required for this job parameter

Compile Time Error: This indicates that a JOB command specified a valid jobparameter but did not assign the jobparameter a value, which is required.

Action: Review the jobparameters for proper assignments.

## **JOBSETUP**

**JOBSETUP**, Error receiving aaaa from parent process

Run Time Error: This message indicates that a process created by the JOB command was unable to receive setup information aaaa from the process which issued the JOB command.

Action: Report this and the associated SYSTEM-E-ENO## message to your GT.M support channel.

### **JOBSTARTCMDFAIL**

**JOBSTARTCMDFAIL**, JOB command STARTUP script invocation failed.

Run Time Error: This message indicates STARTUP script specified as JOB command process parameter failed.

Action: Verify the STARTUP script is present, and check it has appropriate permissions to execute.

# **JRTNULLFAIL**

**JRTNULLFAIL**, Applying NULL journal record failed. Failure code: xxxx.

Update Process log/MUPIP Error: Issued by an Update Process, MUPIP JOURNAL -ROLLBACK or MUPIP JOURNAL -RECOVER indicating it encountered a database problem when it attempted to play a NULL journal record into the database. xxxx contains the failure codes for the four attempts. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Report the entire incident context to your GT.M support channel for further analysis.

### **JUSTFRACT**

**JUSTFRACT**, Fraction specifier to \$JUSTIFY cannot be negative

Run Time Error: This indicates that a \$JUSTIFY or \$FNUMBER function specified a negative value as its third argument.

Action: Modify the third argument of the function so that it specifies the positive number of fractional digits to which the function rounds its result.

### **KEY2BIG**

**KEY2BIG**, Key size (xxxx) is greater than maximum (yyyy) for region zzzz

Run Time Error: This indicates that a SET command attempted to establish a global variable with a total subscript length xxxx, which exceeds the maximum length yyyy specified in the file header for the current region zzzz.

Action: Verify that the subscripts are as intended. Use the DSE DUMP command and qualifier FILEHEADER to examine the key size for the region. Modify KEYSIZE if required by the application.

### **KEYFORBLK**

**KEYFORBLK**, But block size bbbb and reserved bytes rrrr limit key size to kkkk.

GDE Error: The maximum key for a region must fit in the block size less record overhead and any reserved bytes for that region; kkkk is the maximum key size for block size bbbb.

Action: Reduce the key size or reserved bytes or increase the block size.

#### **KEYSIZIS**

**KEYSIZIS**, Key size is xxxx

GDE/DSE Information: This message displays the maximum key size xxxx of the REGION with which you are working.

Action: -

### **KEYTOOBIG**

KEYTOOBIG, But record size xxxx can only support key size yyyy

GDE Warning: This indicates that an ADD, CHANGE, or TEMPLATE command specified a value for the KEYSIZE qualifier that is incompatible with the value xxxx assigned to RECORDSIZE. yyyy is the maximum value of KEYSIZE that this RECORDSIZE value can support.

Action: Review the accompanying message for the key size. Modify the key size and/or record size so that they are compatible.

### **KEYWRDAMB**

KEYWRDAMB, xxxx is ambiguous for yyyy

GDE Error: This indicates that the keyword xxxx is ambiguous for the command or local qualifier yyyy.

Action: Ensure that the command or qualifier has enough characters to differentiate it from similar command elements.

### **KEYWRDBAD**

**KEYWRDBAD**, xxxx is not a valid yyyy in this context

GDE Error: This indicates that GDE did not encounter a valid syntax element. xxxx is the invalid element. yyyy designates whether the element in context is a verb (command), object, or qualifier.

Action: Look for and correct typographical errors.

### **KILLABANDONED**

KILLABANDONED, Abandoned kills counter is greater than zero for file ffff, tttt

Run Time Error: This indicates a process terminated during KILL cleanup in database file ffff; tttt is text waring of the implications. Generally, this leaves a database with block incorrectly marked busy errors. Such errors are benign in that they only cause blocks to be inappropriately unavailable. Nonetheless they should be addressed promptly to avoid operators becoming desensitized to errors in INTEGs.

Action: Use DSE MAP to carefully FREE individual incorrectly marked busy block. If there are many blocks, you can edit the output of the integ (run with NOMAP) to create a script for driving repeated DSE MAP FREE. Alternatively, if you can get standalone access, to the database you may use DSE MAP RESTORE - never use MAP RESTORE on an active database.

## **KILLBYSIG**

**KILLBYSIG**, Process xxxx has been killed by a signal yvyy

Run Time Error: This indicates that the xxxx process failed due to signal yvyy.

Action: Preserve the core (dump) files and report the entire incident context to your GT.M support channel for further analysis.

#### KILLBYSIGSINFO1

**KILLBYSIGSINFO1**, iiii process xxxx has been killed by a signal yyyy at address aaaa (vaddr bbbb)

Run Time Error: This indicates that the process failed due to the yyyy signal, which occurred at the code address aaaa. bbbb is the virtual address attempting to be accessed from code address aaaa.

Action: Preserve the core (dump) files and report the entire incident context to your GT.M support channel for further analysis.

### **KILLBYSIGSINFO2**

KILLBYSIGSINFO2, iiii process xxxx has been killed by a signal yyyy at address aaaa

Run Time Error: This indicates that the process iiii failed due to a signal, which occurred while attempting a memory access with an instruction at location aaaa.

Action: Preserve the core (dump) files and report the entire incident context to your GT.M support channel for further analysis.

### **KILLBYSIGSINFO3**

KILLBYSIGSINFO3, iiii process xxxx has been killed by a signal yyyy accessing vaddress aaaa

Run Time Error: This indicates that the iiii (GTM, MUPIP, DSE, and so on) process failed due to the yyyy signal, which occurred while attempting to access virtual address aaaa.

Action: Preserve the core (dump) files and report the entire incident context to your GT.M support channel for further analysis.

### **KILLBYSIGUINFO**

**KILLBYSIGUINFO**, Process xxxx has been killed by a signal yyyy from process zzzz with userid number aaaa

Run Time Error: This indicates that the process failed due to a signal, sent by another process zzzz, owned by user ID aaaa.

Action: Preserve the core (dump) files and report the entire incident context to your GT.M support channel for further analysis.

#### KRNLKILL

**KRNLKILL**, Process was terminated by SIGDANGER signal from the system --System swap space is too low --Report to System Administrator

Run Time Error: This indicates that a GT.M process received the SIGDANGER signal from AIX, which means that virtual memory is critically low. This message is sent to the user and the system log, notifying that the GT.M process is terminating.

Action: Report this condition to the system administrator as soon as possible. Check the system configuration to ensure sufficient swap space for the expected workload. Investigate whether the paging space is adequate.

### **LABELEXPECTED**

LABELEXPECTED, Label expected in this context

LABELMISSING Chapter 1. Error Messages

Compile Time Error: This indicates that GT.M did not find a valid line reference where expected.

Action: Look for a missing label in an extrinsic or in a command such as DO, GOTO, or JOB.

#### LABELMISSING

**LABELMISSING**, Label referenced but not defined: xxxx

Compile Time Error: This indicates that a transfer of control command specified a label xxxx that does not exist in the routine.

Action: Look for a missing or misspelled label.

### **LABELNOTEND**

**LABELNOTFND**. GOTO referenced a label that does not exist

Run Time Error: A GOTO referenced a label with neither a routine nor an offset but that label does not currently exist in the current routine. The location that accompanies this message is the last line in the routine.

Action: Check the errors from the compilation, as they provide the name of the missing label. As appropriate add the label or a routine, or better yet refactor to remove the GOTO.

### **LABELONLY**

**LABELONLY**, Routine xxxx was compiled for label-only entry.

Run Time Error: This indicates that a transfer of control command specified an offset in routine xxxx that was compiled with the NOLINE ENTRY qualifier; therefore, it can be invoked only at a label.

Action: Modify the invocation or recompile the routine without the NOLINE ENTRY qualifier.

### **LABELUNKNOWN**

LABELUNKNOWN, Label referenced but not defined

Compile Time Error: This indicates that a transfer of control command specified a label that is not defined in the image.

Action: Look for an unresolved reference in the last LINK caused by a missing or misspelled label.

### **LASTFILCMPLD**

**LASTFILCMPLD**, The file currently being compiled is xxxx

MR Manual V6.2-002 June 09, 2015, Page 157 Compile Time Information: This indicates that the GT.M compiler encountered a <CTRL>-C in the input stream and issued this status. xxxx is the name of the routine the compiler is currently processing.

Action: Use <CTRL>-Y to abort the process.

### LASTWRITERBYPAS O

LASTWRITERBYPAS, The last writer for database file xxxx bypassed the rundown

All GT.M Components Warning: This indicates that the last process which had the xxxx database file open for writing bypassed the rundown while disconnecting.

Action: This may occur due to an instance freeze. If so, first ensure that the Instance Freeze is resolved, manually clearing the Instance Freeze if necessary. If there is a source server still running, a normal shutdown of the source server will perform the rundown. Otherwise, the DSE ALL -B[UFFER\_FLUSH] command may be used to ensure that any changes remaining in shared memory are written to disk.

### **LCKGONE**

LCKGONE, Lock removed: xxxx

LKE Success: This indicates that CLEAR removed an M LOCK. xxxx is the resource name.

Action: -

#### **LCKSCANCELLED**

**LCKSCANCELLED**, Error on remote node holding locks or zallocates. All locks and zallocates cancelled.

Run Time Error: This indicates that when a GT.M process encounters a network error that involves a node holding LOCKs and/or ZALLOCATEs, the process attempts to cancel all LOCKs and ZALLOCATEs regardless of their node.

Action: If GT.M determines that communication with any part of its lock database is suspect, it releases all locks to establish a known state and minimize the impact of the failure on remaining network processes. After this error occurs, ensure that any restart reinstates ALL locks.

#### **LCKSGONE**

LCKSGONE, Locks selected for deletion removed

LKE Success: This indicates that CLEAR removed an M LOCK on a remote database.

Action: -

# **LCKSTIMOUT**

LCKSTIMOUT, DAL timed lock request expired

Run Time Warning: This indicates that a call to seize a named M resource specified a timeout, and the resource was not available within the timeout.

Action: This is a normal signal to the calling process. If it occurs at an inappropriate time, use LKE to examine the lock environment.

#### **LDBINFMT**

LDBINFMT, Unrecognized header for load file

MUPIP Error: This message identifies a MUPIP load file that is not having the correct header format in either BINARY, ZWR or GO format.

Action: Examine the file with a text editor for possible correction to format header. If fixing the header does not resolve the error, attempt MUPIP EXTRACT with a different file format.

# **LDGOOFMT**

LDGOQFMT, Corrupt GOQ format header information

MUPIP Error: This indicates that MUPIP terminated the loading of a GOQ format file because of a corrupt file header.

Action: Ensure that the proper tape is mounted and review how it was created. Use the host shell DUMP command to examine the first few blocks of the tape.

# **LDSPANGLOINCMP**

**LDSPANGLOINCMP**, Incomplete spanning node found during load!/!! at File offset: oooo

MUPIP Error: This error indicates that MUPIP LOAD encountered an issue with a spanning node in the input file at offset oooo. MUPIP LOAD produces the following LDSPANGLOINCMP errors:

- Expected chunk number: ccccc but found a non-spanning node
- Expected chunk number : ccccc but found chunk number : ddddd
- Not expecting a spanning node chunk but found chunk: ccccc
- Global value too large: expected size: sssss actual size: tttttt chunk number: ccccc
- Expected size : sssss actual size : ttttt

Action: Refer to the LDSPANGLOINCMP Errors section in the Maintaining Database Integrity chapter of the Administration and Operations Guide

## **LINKVERSION**

**LINKVERSION**, This image must be relinked with the current version of GT.M

Run Time Fatal: This indicates that GT.M attempted to access an image that was created with a previous version of GT.M.

Action: Relink the image using the current version of GT.M. If the previous version of GT.M is still available, adjust the logical names to activate the appropriate old version of GT.M.

## **LISTENPASSBND**

**LISTENPASSBND**, Controlmnemonic LISTEN can be applied to PASSIVE socket which is in the state **BOUND ONLY** 

Run Time Error: This indicates that the LISTEN controlmnemonic can only be applied to passive sockets in a bound state.

Action: Use ZSHOW to verify that the command syntax is correct. Use the USE command to bind the socket.

## **LITNONGRAPH**

LITNONGRAPH, standard requires graphics in string literals; found non-printable: \$ZCHAR(cccc)

Compile Time Warning: flags a standard violation. The generated code will accept the string, even though it contains cccc, which is not a visible character.

Action: Consider revising the literal to use \$\[ Z\]CHAR() and possibly concatenation to make the code more maintainable.

#### **LKENOFINISH**

**LKENOFINISH**, LKE unable to finish all requested actions

LKE Error: This indicates that the previously reported error(s) prevented LKE from completing the requested action.

Action: Review the accompanying error message(s).

# **LKNAMEXPECTED**

**LKNAMEXPECTED**, An identifier is expected after a ^ in this context

Compile Time Error: This indicates that the LOCK command specified an argument that started with ^, but does not contain a valid global name.

LKRUNDOWN Chapter 1. Error Messages

Action: Look for and correct any typographical errors or attempted naked references in LOCK names.

## **LKRUNDOWN**

**LKRUNDOWN**, Error during lock database rundown

Run Time Error: This indicates that the process encountered an error when it attempted to release its LOCKs as part of image termination.

Action: Report this error to the group responsible for database integrity within your organization. Although this is not strictly a database error, other processes can be affected if LOCKs were left behind.

## **LKSECINIT**

**LKSECINIT**, Error creating lock section for database xxxx

Run Time Error: This indicates that GT.M encountered a problem initializing the lock database associated with the database file (xxxx) it was trying to open.

Action: Review the accompanying message(s) for additional information.

## **LNKNOTIDLE**

LNKNOTIDLE, Attempt to initiate operation before previous operation completed

GT.CM Error: This indicates that the networking protocol failed by trying to open an already accessed connection.

Action: Review DECnet error logs to determine the cause and location of the failure. Report the entire incident context to your GT.M support channel.

## **LOADABORT**

LOADABORT, Aborting load at record xxxx

MUPIP Error: This indicates that LOAD encountered an error while processing input record number XXXX.

Action: Refer to the topic MUPIP LOAD Errors in About This Manual section in this manual.

# **LOADBGSZ**

**LOADBGSZ**, Load error: BEGIN too small. No records loaded.

MUPIP Error: This indicates that an operation initiated by MUPIP LOAD with the qualifier FORMAT=GO did not take place because the record specified for the qualifier BEGIN= is negative or zero.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 161 Action: Specify a record that is within the actual file.

## LOADBGSZ2

LOADBGSZ2, Load error: BEGIN too large. No records loaded

MUPIP Error: This error is returned when the BEGIN qualifier's value exceeds the maximum (4GB - 1) value.

Action: Reduce the size of the parameter value and retry.

## LOADCTRLY

LOADCTRLY, Control Y encountered during load. Load halting.

MUPIP Warning: This indicates that LOAD encountered a <CTRL>-Y in its input stream and terminated.

Action: The result of the LOAD is incomplete. If the LOAD was with FORMAT=GO, the database is usable. If the LOAD was with FORMAT=BIN, the database may be corrupt.

## **LOADEDBG**

LOADEDBG. Load error: END smaller than BEGIN. No records loaded.

MUPIP Error: This indicates that a MUPIP LOAD operation did not occur because the record specified for the qualifier END= is smaller than the record specified for the qualifier BEGIN=.

Action: Specify a record for the qualifier END= that is greater than or equal to the record for the qualifier BEGIN=.

## **LOADEDSZ**

LOADEDSZ, Load error: END too small. No records loaded.

MUPIP Error: This indicates that a MUPIP LOAD operation did not occur because the record specified for the qualifier END= is smaller than 2.

Action: Modify the qualifier END= value.

## LOADEDSZ2

LOADEDSZ2, Load error: END too large. No records loaded.

MUPIP Error: This error is produced when the END qualifier's value exceeds the maximum (4GB - 1) value.

V6.2-002 GT.M Message and Recovery Procedures Manual LOADEOF Chapter 1. Error Messages

Action: Reduce the size of the parameter value and retry.

## **LOADEOF**

LOADEOF, Load error: EOF reached prior to BEGIN record xxxx No records loaded

MUPIP Error: This indicates that LOAD did not transfer any records to the database because its input steam reached the end-of-file before the record specified by the qualifier BEGIN=xxxx.

Action: Specify a record for the qualifier BEGIN= that does not exceed the number of records in the file.

## **LOADFILERR**

LOADFILERR, Error with load file xxxx

MUPIP Error: This indicates that LOAD encountered an error when opening its input file xxxx.

Action: Make sure correct load file has been specified. Review the accompanying message(s) for additional information.

# **LOADFMT**

**LOADFMT**, Load error: bad format type. Must be GO, BINARY, or GOO.

MUPIP Error: This indicates that a MUPIP LOAD operation did not take place because the qualifier FORMAT= specified an unsupported format.

Action: Look for and correct any typographical errors in the qualifier FORMAT= value.

#### **LOADGD**

LOADGD, Loading Global Directory xxxx

GDE Information: GDE displays this message at the beginning of a GDE session when Global Directory xxxx already exists.

Action: -

#### LOADINVCHSET

**LOADINVCHSET**, Extract file CHSET xxx is incompatible with gtm chset.

MUPIP Information: This indicates that a MUPIP LOAD operation did not take place because the value of the environment variable gtm chset at the time of creating the extract file was not the same as the current value of gtm chset.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 163 Action: Determine whether to change the current character set or redo the EXTRACT with a different character set. Alternatively, you can edit the extract file so the EXTRACT file header matches the gtm chset environment variable. This enables an M mode MUPIP LOAD to treat the input as a byte stream or a UTF-8 mode MUPIP LOAD, which either detects BADCHAR errors or not, depending on the setting of the gtm badchar environment variable..

#### LOADRUNNING

LOADRUNNING, Cannot ZLINK an active routine xxxx

Run Time Error: This indicates that a ZLINK specified a routine xxxx, that is currently on the M invocation stack. A routine cannot be altered in the image if its current form may be required for continued processing.

Action: ZLINK the routine prior to or after running it. Use QUIT or ZGOTO to remove the routine from the M stack.

## LOCALSOCKREQ

LOCALSOCKREQ, LOCAL socket required

Run Time Error: The operation attempted requires a LOCAL socket, and a non-LOCAL (TCP) socket was specified.

Action: Make sure the correct socket is being used and that the socket is OPENed with the ":LOCAL" suffix. ZSHOW "D"may provide useful details on the current socket state.

# **LOCKINCR2HIGH**

LOCKINCR2HIGH, Attempt to increment a LOCK more than LLLL times

Run Time Error: This message indicates that a LOCK + command attempted to increase a LOCK increment higher than LLLL (the maximum level). The following associated message gives the resource name for the LOCK that failed.

Action: Examine the application for pathological use of incremental LOCKs (LOCK +) and ensure that no process LOCKs a single resource more than 511 increments with no intervening decrements (LOCK -) for that resource or lock releases (LOCK with no + or - in its argument).

## **LOCKIS**

LOCKIS, Resource name: RRRR

Run Time Information: This message identifies a lock resource.

Action: Refer to the accompanying message(s) for more information.

#### LOCKSPACEFULL

LOCKSPACEFULL, No more room for LOCK slots on database file ffff

Run Time Error: This indicates that the environment attempted more concurrent M LOCKs than the configured LOCK SPACE for file ffff can support.

Action: Analyze the LOCK protocol for efficiency. Use mupip set -file -lock space=size ffff to increase the lock space for region xxx. To avoid the same problem the next time you recreate the database, use GDE to make the analogous change to lock space for the segment mapped to the ffff file in the global directory used to MUPIP CREATE this region

## **LOCKSPACEINFO**

LOCKSPACEINFO, Region: rrrr: processes on queue: pppp/qqqq; LOCK slots in use: llll/kkkk; name space not full

Run Time Error: This indicates that the environment attempted more concurrent M LOCKs than the configured LOCK SPACE for region rrrr can support, pppp processes are waiting on a lock, llll locks are in use, qqqq and kkkk indicate maximum number of process queue entries, and maximum number of locks respectively.

Action: Analyze the LOCK protocol for efficiency. Use mupip set -region -lock space=size "rrrr" to increase the lock space for region rrrr. To avoid the same problem the next time you recreate the database, use GDE to make the analogous change to lock space for the segment mapped to the ffff file in the global directory used to MUPIP CREATE this region.

#### **LOCKSPACEUSE**

**LOCKSPACEUSE**, Estimated free lock space: xxx% of pppp pages.

LKE Information: SHOW command displays the amount of free space along with the number of pages configured for lock space.

Action: If the free lock space report does not show a comfortable amount of free space, use MUPIP SET -LOCK SPACE to increase the space; remember to also use GDE to revise the LOCK SPACE in the global directory used to create the region in question so the change remains when the database is recreated.

## **LOCKSUB2LONG**

LOCKSUB2LONG, Following subscript is xxxx bytes long which exceeds 255 byte limit.

Run Time Error: This indicates that one of the substrings of a lock is taking more than 255 bytes. Check the following message to see which substring caused this error.

Action: Make sure none of the substrings are larger than 255 bytes. If UTF-8 is enabled, use the encoded byte length rather the character length for the key size.

#### LOGOFF

LOGOFF, No longer logging to file xxxx

GDE Information: This indicates that a LOG command with the qualifier OFF terminated logging of GDE commands to log file xxxx.

Action: When appropriate, resume logging with LOG and the qualifier ON[=]. GDE closes the log file(s) at the end of the GDE session.

## **LOGON**

LOGON, Logging to file xxxx

GDE Information: This indicates that a LOG command with the qualifier ON[=] initiated the logging of GDE commands to log file xxxx.

Action: You can suspend logging with LOG and the qualifier OFF.

#### LOGTOOLONG

**LOGTOOLONG**, Environment variable eeee is too long. Maximum length allowed is llll bytes.

Information: This error is triggered whenever the length of an environment variable that GT.M cares about exceeds the maximum allowed limit.

Action: The maximum allowed limit is indicated in the message. Specify a value for the environment variable within this length.

#### LOWSPACECRE

**LOWSPACECRE**, Disk space for database file xxxx is not enough for yyyy future extension. aaaa blocks are needed, only bbbb available.

MUPIP Warning: This indicates that the database file xxxx was created but it was found that the file system/volume does not have enough space for even vyvy future extensions.

Action: Check the allocations and extension sizes specified in the Global Directory. If no extensions are anticipated, no action is required. Otherwise, consider moving some files to another file system/volume, or reconfiguring the file system/volume housing the database file.

#### **LPARENMISSING**

LPARENMISSING, Left parenthesis expected

LPARENREOD Chapter 1. Error Messages

Compile Time Error: This indicates that GT.M did not find a left parenthesis in the next source position.

Action: Look for invalid subscripts in indirection operations and errors in SET \$PIECE commands.

# **LPARENREQD**

**LPARENREQD**, xxxx Left parenthesis expected

MUPIP Error: This indicates that LOAD failed because it found xxxx in the input stream where it expected to find a left parenthesis.

Action: Refer to the topic MUPIP LOAD Errors in About This Manual section of this manual.

# **LQLENGTHNA**

LOLENGTHNA, Listening queue length xxxx not appropriate, it should be between 1 and 5

Run Time Error: This indicates that the GT.M listening queue restricts the number of pending connections between one (1) and five (5).

Action: Specify the number of pending connections in the queue as a number between one and five.

#### **LSEXPECTED**

**LSEXPECTED**, A line separator is expected here

Compile Time Error: This indicates that a source line did not specify a space or tab before the first command.

Action: Look for and correct typographical errors. If missing, put a tab or space at the beginning of the line.

## **LVNULLSUBS**

LVNULLSUBS, LVNULLSUBS Null subscripts not allowed in local variables

Run Time Error: This indicates that an attempt was made to set a local variable with null subscript.

Action: Modify the subscript generation to avoid the null subscript or change the LVNULLSUBS parameter for this job or process. For information on changing LVNULLSUBS, refer to documentation on GTM\$DEFAULTS and the VIEW command in the Programmer's Guide.

## **LVORDERARG**

LVORDERARG, Argument to local variable \$NEXT must be subscripted

Compile Time Error: This indicates that a \$NEXT function specified an unsubscripted local variable as an argument.

Action: Use the \$ORDER function or ZWRITE command to display local variables.

# **LVSTARALON**

LVSTARALON, The \* name cannot be deleted or renamed

GDE Error: This indicates that a DELETE or RENAME command attempted to delete or rename the \* namespace. The \* namespace is protected because it is associated with namespaces that are not explicitly mapped.

Action: None.

#### **MALLOCMAXUNIX**

MALLOCMAXUNIX, Exceeded maximum allocation defined by \$gtm\_max\_storalloc.

Run Time Error: This error accompanies a MEMORY error as a secondary error to indicate that the limit the process hit was not an OS limit but one artificially defined by the \$gtm\_max\_storalloc environment variable.

Action: Increase the value of, or unset, \$gtm\_max\_storalloc, or identify the source of the memory consumption (for example, creating and keeping lots of local variables) and reduce it.

## **MALLOCMAXVMS**

MALLOCMAXVMS, Exceeded maximum allocation defined by GTM MAX STORALLOC.

Run Time Error: This error accompanies a MEMORY error as a secondary error to indicate that the limit the process hit was not an OS limit but one artificially defined by the GTM\_MAX\_STORALLOC logical.

Action: Increase the value of or unset the GTM\_MAX\_STORALLOC logical or identify the source of the memory consumption (for example, creating and keeping lots of local variables) and reduce it.

# **MAPBAD**

MAPBAD, xxxx for yyyy does not exist

GDE Information: This indicates that a NAME points to a REGION or a REGION points to a SEGMENT that does not exist. xxxx is the missing object. yyyy describes the type of the object. When you enter the VERIFY or EXIT command, GDE displays this message after it verifies the global directory.

Action: Use the ADD command to add the REGION or SEGMENT.

## **MAPDUP**

MAPDUP, xxxx and yyyy both map to zzzz

GDE Information: This indicates that GDE encountered two REGIONs mapped to the same SEGMENT or two SEGMENTS mapped to the same FILE. xxxx and yyyy are the REGIONS or SEGMENTS with the same mapping. zzzz is the SEGMENT or FILE with more than one mapping. When you enter the VERIFY or EXIT command, GDE displays this message after it verifies the global directory.

Action: Delete mappings to eliminate duplication.

# **MAXACTARG**

MAXACTARG, Maximum number of actual arguments exceeded

Compile Time Error: This indicates that a DO or extrinsic function supplied an actuallist with more than 32 elements.

Action: Modify the routine so that it passes fewer parameters explicitly.

## **MAXARGCNT**

Last used version: V4.4-000

MAXARGCNT, Maximum number of arguments xxxx exceeded

Compile Time/Run Time Error: If this error occurs during compilation, it indicates that a command or function specified more than xxxx arguments. If this error occurs during run-time execution, it indicates that a SET of a \$ZROUTINES has more than the allowed number of elements in an array. The maximum number of arguments is xxxx.

Action: If this error occurs during compilation, it indicates that a command or function specified more than xxxx arguments. If this error occurs during run-time execution, it indicates that a SET of a \$ZROUTINES has more than the allowed number of elements in an array. The maximum number of arguments is xxxx.

#### **MAXBTLEVEL**

MAXBTLEVEL, Global ^gggg in region rrrr reached maximum level

Run Time/MUPIP Error: This indicates that the global-variable-tree for global xxxx reached the maximum level permissible. Very likely, MUPIP REORG was specified with a fill-factor much less than 100. Small fill-factors can cause REORG to revise existing GDS-blocks (in order to accommodate the fill-factor requirement), in turn causing block-splits, which might lead to an increase of the tree height. Alternatively a SET or MERGE has made the global really too large for the current block size, which is most likely to happen with large (spanning) database nodes. Note that if this message does not specify the global name, it means the directory tree for the region hit the limit - FIS believes the directory tree full condition is almost impossible to create in practice.

Action: If MUPIP reorg was specified with a small fill-factor, try higher number (close to 100) to reduce tree-height. Other techniques include increasing GDS-block-size, reducing reserved bytes, killing unwanted portions of the tree or moving some nodes in the global to a different database region.

#### MAXFORARGS

MAXFORARGS, Maximum number of arguments to a single FOR command exceeded

Compile Time Error: This indicates that a FOR statement specified more than 127 arguments.

Action: Modify the routine so that it uses fewer arguments in one FOR command.

# **MAXGTMPATH**

MAXGTMPATH, The executing module path is greater than the maximum xxxx

Run Time Error: This indicates that the path specified for the mumps executable environment variable has a length limitation of xxxx.

Action: Move the directory or use a link to shorten the path.

#### **MAXNRSUBSCRIPTS**

MAXNRSUBSCRIPTS, Maximum number of subscripts exceeded

Compile Time Error: This indicates that a subscripted variable exceeded the maximum limit of 31 subscripts.

Action: Modify the routine to observe this limit on subscripts in a single variable.

## **MAXSEMGETRETRY**

MAXSEMGETRETRY, Failed to get flok semaphore after tttt tries because it is being continually deleted

Run Time Error: A process was unable to open a database file because on every one of tttt tries it found something kept deleting the IPC semaphore that gates access to the file.

Action: Check for one or more rogue processes disrupting IPC semaphore, or for damage to the Operating System semaphore services.

#### **MAXSSREACHED**

MAXSSREACHED, Maximum snapshots - mmmm - for region rrrr reached. Please wait for the existing snapshots to complete before starting a new one.

V6.2-002 GT.M Message and Recovery Procedures Manual MAXSTRLEN Chapter 1. Error Messages

MUPIP Error: Starting this snapshot would exceed the maximum number of snapshots.

Action: Wait for a currently active process using snapshots to complete or terminate an existing snapshot activity.

#### **MAXSTRLEN**

MAXSTRLEN, Maximum string length exceeded

Run Time Error: This indicates that a string exceeded the maximum limit of 1,048,576 bytes. In M mode, each byte holds a character, but in UTF-8 mode, a character may take between one and four bytes.

Action: Modify the routine so it uses shorter strings.

# **MAXTRACEHEIGHT**

Last used version: V5.4-002B

MAXTRACEHEIGHT, <The maximum trace tree height (xxxx) has been exceeded. The trace information will be incomplete>

Run Time Information: The internal GT.M data structure used to gather information during M Profiling can not hold all the information.

Action: Not all lines executed will be reported in the global specified by VIEW "TRACE". There is no impact on the actual execution of the user program. Report the entire incident context with all information necessary to reproduce this error to your GT.M support channel.

#### **MAXTRACELEVEL**

Last used version: V5.4-002B

MAXTRACELEVEL. The maximum traceable level of xxxx has been exceeded. The frame information will not be maintained.

Run Time Information: This indicates that M profiling reached the maximum level (\$ZLEVEL) it can manage. The information for frames will not be maintained from this point on. Line information is maintained and reported correctly and information gathered about frames upto this point will be reported. Further MAXTRACELEVEL errors will not be reported to the users.

Action: Determine if the number of levels of execution is as intended, if not, correct the application.

# **MAXTRIGNEST**

MAXTRIGNEST, Maximum trigger nesting level LLLL exceeded

Trigger/Run Time Error: GT.M limits trigger invocation depth to LLLL.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 171 Action: If you are sure that you do not have an application code bug or misfeature, reduce the depth of trigger invocation, possibly by consolidating triggers.

#### **MBXRDONLY**

**MBXRDONLY**, Mailbox is read only, cannot write to it

Run Time Error: This indicates that a WRITE command attempted to access a mailbox that was opened read-only.

Action: Verify that the routine is using the right mailbox and that the mailbox was opened with the appropriate deviceparameter.

#### **MBXWRTONLY**

MBXWRTONLY, Mailbox is write only, cannot read from it

Run Time Error: This indicates that a READ command attempted to access a mailbox that was opened write-only.

Action: Verify that the routine is using the correct mailbox and that the mailbox was opened with the appropriate deviceparameter.

# **MEMORY**

**MEMORY**, Central memory exhausted during request for xxxx bytes

Compile Time/Run Time Error: This indicates that the compiler or the run-time system could not allocate sufficient storage.

Action: Look for very large variables. This error can also be caused by problems in the GT.M environment, such as using components of different versions or different platforms. Verify that there is no such problem in the environment.

#### **MEMORYRECURSIVE**

**MEMORYRECURSIVE**, Memory Subsystem called recursively

Run Time Error: This indicates that GT.M made an error calling the memory subsystem.

Action: Report the entire incident context to your GT.M support channel.

#### **MERGEDESC**

**MERGEDESC**, Merge operation not possible. xxxx is descendent of yyyy.

MERGEINCOMPL Chapter 1. Error Messages

Run Time Error: This indicates that GT.M was not able to MERGE xxxx into yyyy or vice versa, because xxxx is a descendent of yyyy. When merging global variables specifications included extended references, the MERGE command issues a MERGDESC error if any part of the source or target tree, as mapped, is a descendant of the other. In MERGE  $^{\prime}$  "**x.gld**" | **a**(1)= $^{\prime}$  "**mumps.gld**" |  $^{\prime}$  **a** there is no error if mumps.gld maps ^a to different database files than those to which x.gld maps ^a(1). A MERGDESC error occurs if any part of ^a as mapped by mumps.gld overlaps any part of ^a(1) as mapped by x.gld.

Action: Modify the routine to avoid MERGE operation between two variables where one is the descendant of the other.

# **MERGEINCOMPL**

MERGEINCOMPL, Error encountered during MERGE; operation may be incomplete

Run Time Error: This indicates that GT.M was not able to complete MERGE operation.

Action: Review the accompanying message(s) for additional information.

# **MISSINGDELIM**

MISSINGDELIM, Delimiter dddd expected before gggg vvvv

GDE Error: This indicates that the delimiter dddd (usually dash character in Unix, slash character in VMS) is expected just before vvvv is specified. vvvv is a GDE object or qualifier indicated by ggqq.

Action: Specify the delimiter as indicated.

# **MMBEFOREINL**

MMBEFORE JNL, BEFORE image journaling cannot be set with MM access method in database file ffff

MUPIP Error: MM access method is incompatible with BEFORE IMAGE journaling.

Action: If you require BEFORE IMAGE journaling, use the BG access method. If you wish to use MM, turn off BEFORE IMAGE journaling before selection MM as the access method.

# **MMFILETOOLARGE**

**MMFILETOOLARGE**, Size of rrrr region (ffff) is larger than maximum size supported for memory mapped I/O on this platform.

Run Time Error: GT.M and its Utility programs issue this to indicate an attempt to open the database ffff corresponding to region rrrr when the size of the database file is greater than the maximum size supported for memory mapped I/O.

Action: Consider as appropriate: migrating to a platform not having this limitation, using more, but smaller, regions, or using the BG access method.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 173

## MMNOBEFORIMG

MMNOBEFORIMG, MM segments do not support before image journaling

GDE Information: This indicates that a JOURNAL=BEFORE IMAGE region qualifier appeared on a segment that has segment qualifier ACCESS METHOD=MM.

Action: Change the segment qualifier to ACCESS METHOD=BG or use NOBEFORE IMAGE for the region.

## **MMNOBFORRPL**

MMNOBFORRPL, Replication cannot be used in database file ffff which uses MM access method and NOBEFORE image journaling

MUPIP Error: You can't turn on replcation for MM access method database file ffff.

Action: Forgo replication for the file or change the access method to BG.

# **MMNODYNDWNGRD**

**MMNODYNDWNGRD**, Unable to use dynamic downgrade with MM access method for region xxx. Use BG access method for downgrade

Run Time/MUPIP Error: An attempt was made to use MM mode on a database that has not completed being downgraded. MM mode is only supported on fully downgraded or fully upgraded databases.

Action: Use MUPIP SET FILE or MUPIP SET REGION with the ACCESS METHOD parameter to set the access mode to BG. Then complete the file downgrade using MUPIP REORG DOWNGRADE or file upgrade using MUPIP REORG UPGRADE. And finally set the access mode back to MM using the MUPIP SET FILE or MUPIP SET REGION command again.

#### **MMNODYNUPGRD**

MMNODYNUPGRD, Unable to use MM access method for region yyy until all database blocks are upgraded

Run Time/MUPIP Error: An attempt was made to use MM mode on a database that has not completed being upgraded. MM mode is only supported on fully upgraded databases.

Action: Use MUPIP SET FILE or MUPIP SET REGION with the ACCESS\_METHOD parameter to set the access mode to BG. Then complete the file upgrade using MUPIP REORG UPGRADE. And finally set the access mode back to MM using the MUPIP SET FILE or MUPIP SET REGION command again.

## **MMREGNOACCESS**

**MMREGNOACCESS**, Region rrrr (ffff) is no longer accessible. See prior error messages in the operator and application error logs

**MPROFRUNDOWN** Chapter 1. Error Messages

Run Time Error: Issued when a process attempts to access region rrrr corresponding to database file ffff (opened with the MM access method) which previously became inaccessible to this process due to failure during file extension.

Action: Review the operator log for DBFILERR messages and application error logs for GBLOFLOW status to diagnose the circumstances for the earlier failure of memory mapped I/O operations and take corrective action.

# **MPROFRUNDOWN**

MPROFRUNDOWN, Error during M-profiling rundown

Run Time Error: During process exit, GT.M attempted to store the results of an M-profiling trace but encountered an error.

Action: Report this database error to the group responsible for database integrity at your operation.

## **MRTMAXEXCEEDED**

MRTMAXEXCEEDED, Maximum value of xxxx for SOCKET deviceparameter MOREREADTIME exceeded.

Compile Time/Run Time Error: GT.M triggers this error when MOREREADTIME exceeds its maximum value of 999ms.

Action: Specify a value between 1 and 999, Never set MOREREADTIME to 0 as it may cause a CPU to "spin". See "Input/Output Processing" Chapter of the Programmer's Guide for more information.

## **MTANSIFOR**

MTANSIFOR, Use of ANSI labels does not allow stream format

Run Time Error: This indicates that the LABEL="ANSI" device parameter appeared in a device command for a tape with STREAM format.

Action: Modify the format to FIXED or VARIABLE, delete the LABEL device parameter, or use LABEL="DOS11" for STREAM format.

# **MTANSILAB**

MTANSILAB, Tape label is not in valid ANSI format

Run Time Error: This indicates that the magnetic tape device driver expected an ANSI label but did not find one.

Action: Verify that the tape was properly made and that current processing device parameters match.

# **MTBLKTOOBIG**

MTBLKTOOBIG, Magtape BLOCK\_SIZE exceeds maximum size allowed

Run Time Error: This indicates that an OPEN command specified a BLOCK\_SIZE deviceparameter that is larger than this type of tape can accommodate.

Action: Review the routine to ensure that block sizes do not exceed host I/O driver limitations.

## **MTBLKTOOSM**

MTBLKTOOSM, Magtape BLOCK\_SIZE is less than xxxx bytes

Run Time Error: This indicates that an OPEN command specified a BLOCK\_SIZE device parameter that is smaller than this type of tape can handle.

Action: Review the program to ensure that block sizes do not fall below host driver limitations. For example, the industry standard for 9-track tapes is to treat blocks smaller than 14 bytes as noise in an inter-record gap.

#### **MTDOSFOR**

MTDOSFOR, Use of DOS-11 labels requires stream format

Run Time Error: This indicates that the LABEL="DOS11" deviceparameter appeared in a device command for a tape with FIXED or VARIABLE format.

Action: Modify the format to STREAM, delete the LABEL deviceparameter, or use LABEL="ANSI" for FIXED or VARIABLE format.

## **MTDOSLAB**

MTDOSLAB, Tape label is not in valid DOS-11 format

Run Time Error: This indicates that the magnetic tape device driver did not find the expected DOS11.

Action: Verify that the tape was properly made and that the current processing deviceparameters match.

## **MTFIXRECSZ**

MTFIXRECSZ, BLOCK\_SIZE xxxx must be a multiple of fixed record size yyyy

Run Time Error: This indicates that an OPEN command specified a BLOCK\_SIZE that is not a multiple of its FIXED RECORDSIZE.

Action: Ensure that the block size is evenly divisible by the record size.

# **MTINVLAB**

MTINVLAB, Invalid label type specified in magtape OPEN

Run Time Error: This indicates that the LABEL= deviceparameter appeared in a device command for a tape with an argument evaluating to arguments other than "DOS11" or "ANSI", which are the only valid ones.

Action: Remove or modify the LABEL=.

#### **MTIOERR**

MTIOERR, I/O Error with magnetic tape device xxxx

Run Time Error: This indicates that an attempt to access a magnetic tape encountered a hardware error on tape drive xxxx.

Action: Review accompanying system error messages. If appropriate, try another tape or another drive. Initiate diagnostics on the tape drive in question.

#### **MTIS**

**MTIS**, Magnetic tape: xxxx

Run Time Information: This message identifies magnetic tape xxxx as the current device at the time of an error.

Action: Review the accompanying message(s) for additional information.

#### **MTNOSKIP**

MTNOSKIP, SKIP operation not supported on this device

Run Time Error: This indicates that the program attempted to use the SKIP deviceparameter for a type of tape that is not able to SKIP.

Action: Remove the SKIP deviceparameter or select a type of tape that supports SKIP.

#### **MTRDBADBLK**

MTRDBADBLK, Block read too small, contained only xxxx bytes, block size = yyyy

Run Time Error: This indicates that a READ command encountered a block on the tape that contained xxxx bytes, which is less than the BLOCKSIZE=yyyy deviceparameter specified.

Action: Verify that the proper tape is mounted and that the appropriate BLOCKSIZE is used when OPENing the magtape.

## **MTRDONLY**

MTRDONLY, Cannot write to a READONLY magtape

Run Time Error: This indicates that a WRITE command attempted to access a read-only tape.

Action: Verify that the proper tape is mounted. If the tape is to be written, insert the write ring and remount. If the tape is properly mounted, ensure that the tape was OPENed NOREADONLY.

#### **MTRDTHENWRT**

MTRDTHENWRT, Attempt to read after a write to a magtape

Run Time Error: This indicates that a READ command followed a WRITE command to a magnetic tape with no intervening positioning toward the beginning of the tape.

Action: Look for a logic problem or a missing USE command. If previously written data is to be read, the tape must first be repositioned by a REWIND, a SKIP, or a SPACE with negative arguments.

#### MTRECGTRBLK

MTRECGTRBLK, Magtape record size cannot exceed block size

Run Time Error: This indicates that an OPEN command attempted to initialize a magnetic tape with a RECORDSIZE that exceeds the BLOCKSIZE.

Action: Review the program and modify the value for BLOCKSIZE or RECORDSIZE.

## **MTRECTOOBIG**

MTRECTOOBIG, Magtape record size exceeds maximum allowed

Run Time Error: This indicates that an OPEN command attempted to initialize a magnetic tape with a RECORDSIZE larger than this type of tape can accommodate. Note that the maximum size allowed may depend on whether the records are FIXED or VARIABLE.

Action: Modify the routine to use smaller record sizes.

## **MTRECTOOSM**

MTRECTOOSM, Magtape record size is too small for record type

Run Time Error: This indicates that an OPEN command attempted to initialize a magnetic tape with a variable length record size that is smaller than this type of tape can accommodate.

Action: Modify the routine to use a larger record size or use FIXED length records. For example, in OpenVMS the minimum variable RECORDSIZE requires a single byte of data and 4 bytes of overhead in every variable-length record.

# **MUBCKNODIR**

MUBCKNODIR, MUPIP backup aborted due to error in output directory

MUPIP Error: This indicates that the output directory specified in a BACKUP command could not receive the output file.

Action: Use the host shell commands to verify that the output directory exists, that it is properly protected, and has enough space.

## **MUDWNGRDNOTPOS**

**MUDWNGRDNOTPOS**, Start VBN value is [xxx] while downgraded GT.M version can support only [yyy]. Downgrade not possible

MUPIP Error: Older versions of GT.M require the first GDS block be at Virtual Block Number yyy but it is at VBN xxx. This is likely due to the file initially being created using a newer version of GT.M and thus cannot be downgraded.

Action: To use the database with an older version of GT.M, it must be extracted with the current version and loaded into the older version both in ZWR format.

## MUDWNGRDNRDY

MUDWNGRDNRDY, Database xxx is not ready to downgrade - still yyy database blocks to downgrade

MUPIP Error: A MUPIP DOWNGRADE was attempted when the file-header blks to upgrd counter was not equal to the database used block count. This means that not all database blocks have been converted to V4 format.

Action: Before the database file-header can be downgraded, all of the blocks in the database must be downgraded to V4 format. This is normally accomplished with MUPIP REORG DOWNGRADE. If this fails to set the counter correctly, run MUPIP INTEG (not FAST) on the region which will compute and set the correct counter.

## MUDWNGRDTN

MUDWNGRDTN, Transaction number 0xaaa in database xxx is too big for MUPIP [REORG] DOWNGRADE. Renew database with MUPIP INTEG TN RESET

MUPIP Error: A MUPIP DOWNGRADE or MUPIP REORG DOWNGRADE was attempted when the database transaction number was greater than 4,026,531,839 (the TN RESET warning limit for V4 databases).

Action: Before the database can be downgraded, the transaction number must be reset with the MUPIP INTEG TN RESET command. This requires standalone access to the database and may take a significant amount of time.

## **MUFILRNDWNFL**

MUFILRNDWNFL, File: xxxx rundown failed

MUPIP Error: This indicates that the RUNDOWN command could not close a database.

Action: This message indicates that information in memory may need to be transferred to disk. Review the accompanying message(s) for additional information.

#### **MUFILRNDWNFL2**

MUFILRNDWNFL2, Database section (id = dddd) belonging to database file ffff rundown failed

MUPIP Error: This error indicates that an argumentless MUPIP RUNDOWN failed for database ffff and could not safely remove the shared memory with ID dddd from the system.

Action: Refer to accompanying for more detail on why the argumentless MUPIP RUNDOWN failed.

## **MUFILRNDWNSUC**

MUFILRNDWNSUC, File successfully rundown

MUPIP Success: This indicates that RUNDOWN ensured that the disk file is current.

Action: -

## **MUINFOSTR**

MUINFOSTR, xxxx: aaaa

MUPIP Information: MUINFOSTR message is issued by a variety of MUPIP commands to inform the user of the command's progress. This indicates the string xxxx has the value aaaa.

Action: None necessary.

## **MUINFOUINT4**

MUINFOUINT4, xxxx : aaaa [0xbbbb]

MUPIP Information: MUINFOUINT4 message is issued by a variety of MUPIP commands to inform the user of the command's progress. This indicates the string xxxx has the decimal value aaaa and hexadecimal value bbbb.

Action: None necessary.

# **MUINFOUINT6**

MUINFOUINT6, <tttt: vvvv [0x!hhhh]; \$H=dddddd,tttttt

MUPIP Information: This is secondary information message that provides additional context for some other MUPIP message; tttt is explanatory text, vvvv is a numeric value, hhhh is the hexadecimal equivalent of vvvv, dddddd and tttttt are a date and time in \$HOROLOG format.

Action: Refer to the preceding message.

## **MUINFOUINT8**

MUINFOUINT8, xxxx: aaaa [0xbbbb]

MUPIP Information: MUINFOUINT4 message is issued by a variety of MUPIP commands to inform the user of the command's progress. This indicates the string xxxx has the decimal 8-byte value aaaa and hexadecimal 8-byte value bbbb.

Action: None necessary.

#### **MUINSTFROZEN**

MUINSTFROZEN, tttt: Instance iiii is frozen. Waiting for instance to be unfrozen before proceeding with writes to database file ffff

Run Time/MUPIP Information: This indicates the process attempting a write to database file ffff finds the instance iiii frozen (due to either a manual or an anticipatory freeze action). All writes suspend until the instance is unfrozen.

Action: Examine the cause of the Instance Freeze and take necessary actions to unfreeze the instance.

## **MUINSTUNFROZEN**

MUINSTUNFROZEN, tttt: Instance iiii is now unfrozen. Continuing with writes to database file ffff

Run Time/MUPIP Information: This indicates that the instance iiii (that was previously frozen) is now unfrozen and the MUPIP operation can continue with writes to database file ffff that were previously suspended. Additionally, tttt provides the time stamp at which the MUPIP operation noticed the unfrozen instance.

Action: None needed.

# **MUJNLDBMISSING**

Last used version: V5.4-000

MUJNLDBMISSING, Journal files for required database dddd missing in the MUPIP JOURNAL command

MUPIP Error: MUPIP JOURNAL processing requires journal files for database dddd in order to perform the requested recovery, but the invoking command did not supply a path for those files.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 181 Chapter 1. Error Messages MUJNLPREVGEN

Action: Revise the command to include the appropriate journal specification(s) and reissue it.

# **MUJNLPREVGEN**

MUJNLPREVGEN, Previous generation journal file xxxx included for database file yyyy

MUPIP Information: This indicates that MUPIP included journal file xxxx for database file yyyy for recovery.

Action: -

# **MUINLSTAT**

MUJNLSTAT, xxxx at yyyy

MUPIP Information: This displays the system time yyyy, when the step xxxx was executed.

Action: -

# **MUJPOOLRNDWNFL**

MUJPOOLRNDWNFL, Julpool section (id = xxxx) belonging to the replication instance yyyy rundown failed

MUPIP Error: This indicates that an attempt to run-down the shared memory for a journal pool failed; xxxx is the resource ID of the memory and yyyy is the instance designation.

Action: Analyze the preceding messages for additional information on the failure before attempting the run-down again.

# **MUJPOOLRNDWNSUC**

MUJPOOLRNDWNSUC, Jnlpool section (id = xxxx) belonging to the replication instance yyyy successfully rundown

MUPIP Information: This indicates that the journal pool for instance yyyy was successfully closed and removed; xxxx is the shared memory resource id for the pool and yyyy is the instance designation.

Action: -

## **MUKILLIP**

MUKILLIP, Kill in progress indicator is set for file xxxx, incorrectly marked busy errors should follow

MUPIP Warning: This indicates that the kill-in-progress flag (shows up as KILLs in progress in DSE DUMP file) is set to a non zero value for database file xxxx.

V6.2-002 GT.M Message and Recovery Procedures Manual MULOGNAMEDEF Chapter 1. Error Messages

Action: If there are no accompanying integrity errors, no action is required. Else fix those integrity errors and then perform a MUPIP INTEG -F[AST] -FILE on the database which will then reset the killin-progress flag to zero.

#### **MULOGNAMEDEF**

MULOGNAMEDEF, logical name xxxx, needed to start replication server is already defined for this job. Check for an existing or improperly terminated server.

MUPIP Error: This indicates that the logical name xxxx is already defined, which prevents MUPIP from starting the replication server. Either there is an already running server, or a previous server was not properly terminated.

Action: Check for an existing or improperly terminated server, use MUPIP RUNDOWN to clean up.

# **MULTFORMPARM**

MULTFORMPARM, This formal parameter is multiply defined

Compile Time Error: This indicates that an element appears more than once in a formallist.

Action: Modify the formallist.

#### **MULTLAB**

MULTLAB, This label has been previously defined

Compile Time Error: This indicates that a label is defined more than once in the routine.

Action: Rework the labels so that each one is unique. If labels contain more than eight characters, they are truncated to eight characters, which can cause conflicts.

#### MUNOACTION

MUNOACTION, MUPIP unable to perform requested action

MUPIP Error: This indicates that MUPIP encountered an error, which prevented the requested action.

Action: Review the accompanying message(s) for additional information to identify the cause.

#### **MUNODBNAME**

MUNODBNAME, A database name or the region qualifier must be specified

MUPIP Error: This indicates that a MUPIP command did not have a FILE or REGION or JNLFILE qualifier.

Action: Add one of the required qualifiers to the command.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual

#### **MUNODWNGRD**

MUNODWNGRD, MUPIP downgrade did not occur because of preceding errors

MUPIP Error: This indicates that MUPIP failed to downgrade a database.

Action: Review the accompanying message(s) for additional information.

## **MUNOFINISH**

MUNOFINISH, MUPIP unable to finish all requested actions

MUPIP Error: This indicates that MUPIP encountered an error, which prevented the requested action from completing. The action has partially completed.

Action: Review the accompanying message(s) for additional information to identify the cause.

#### **MUNOSTRMBKUP**

**MUNOSTRMBKUP**, Database xxxx has a block size larger than yyyy and thus cannot use stream (incremental) backup

MUPIP Warning: GT.M does not support bytestream (a.k.a incremental) backup of a database file that is created with a GDS block size larger than xxxx. As of GT.M version V5.0-000, this limit is 32256 bytes. MUPIP CREATE issues MUNOSTRMBKUP warning when creating a database file with a block size that exceeds the limit. MUPIP BACKUP -BYTESTREAM issues MUNOSTRMBKUP error and skips backing up a file that has block size that exceeds the limit. NOTE: Comprehensive BACKUP does not impose any limit on the GDS block size of the database file being backed up.

Action: Create the database file with a block size that does not exceed the limit.

#### MUNOTALLINTEG

**MUNOTALLINTEG**, At least one region skipped. See the earlier messages

MUPIP Warning: The INTEG report is incomplete because MUPIP could not access all of the selected regions.

Action: If appropriate, correct the issue(s) that caused INTEG to skip one or more regions

# **MUNOTALLSEC**

MUNOTALLSEC, WARNING: not all global sections accessed were successfully rundown

MUPIP Warning: This indicates that RUNDOWN encountered at least one database that appeared to be in use and therefore could not be processed.

IS V6.2-002

MUNOUPGRD Chapter 1. Error Messages

Action: If appropriate, initiate actions to cause all GT.M users to exit from GT.M and repeat the MUPIP RUNDOWN.

# MUNOUPGRD

MUNOUPGRD, MUPIP upgrade did not occur because of preceding errors

MUPIP Error: This indicates that MUPIP could not upgrade a database from one version to another.

Action: Review the preceding error messages. Review all the release notes for the new version and for all versions between it and the existing version.

#### **MUPCLIERR**

**MUPCLIERR**. Action not taken due to CLI errors

MUPIP Error: This indicates that a MUPIP command did not process because of invalid syntax.

Action: Review the command documentation for correct syntax. Review the accompanying message(s) if any, for more information about the cause of this error.

#### **MUPGDERR**

MUPGDERR, Command aborted due to global directory errors

MUPIP Error: This indicates that a MUPIP command failed because it required a Global Directory and that file was inaccessible or damaged.

Action: Verify that GTM\$GBLDIR / \$gtmgbldir identifies the proper file and that the file is accessible to the process. Use GDE to recreate the Global Directory, if necessary.

## **MUPGRDSUCC**

MUPGRDSUCC, Database file xxx successfully yyy to zzz

MUPIP Information: The database file header for xxx has been upgraded or downgraded to the version zzz format.

Action: -

## **MUPIPINFO**

#### **MUPIPINFO**, xxxx

MUPIP Information: The LOAD command with the FORMAT qualifier defined to GO or GOQ uses this message to display the input file label xxxx.

Action: -

## **MUPIPSIG**

MUPIPSIG, STOP (signal xxxx) issued from process yyyy to process zzzz

MUPIP Information: This message indicates that process yyyy issued a MUPIP STOP to process zzzz, and xxxx signal is sent to process zzzz. Note that the message is logged at the time the signal is sent, regardless of when or if it is processed by process zzzz.

Action: -

# **MUPJNLINTERRUPT**

**MUPJNLINTERRUPT**, Database file xxxx indicates interrupted MUPIP JOURNAL command. Restore from backup for forward recovery.

MUPIP Information: This indicates that MUPIP Journal command did not proceed because a previous MUPIP JOURNAL command was terminated abnormally.

Action: The failed MUPIP command may be reissued if appropriate, else restore the database and journal files from backup to proceed with RECOVER FORWARD.

#### MUPRECFLLCK

MUPRECFLLCK, Database file xxxx is locked by MUPIP RECOVER. Could not secure access.

Run Time Error: This indicates that GT.M could not open a database file xxxx because MUPIP JOURNAL with the RECOVER qualifier was applying a journal to the file.

Action: Wait for RECOVER command to complete.

#### **MUPRESTERR**

**MUPRESTERR**, MUPIP RESTORE aborted due to preceding errors

MUPIP Error: This indicates that a RESTORE operation failed, which left the database in an indeterminate state.

Action: Review the preceding errors for additional information.

# **MUQUALINCOMP**

**MUQUALINCOMP**, Incompatible qualifiers - FILE and REGION

MUPIP Error: This indicates that the FILE and REGION qualifiers cannot be used in the same command.

Action: Choose one or the other.

# MURAIMGFAIL

MURAIMGFAIL, MUPIP RECOVER failed while processing after-image journal record. Failure code: XXXX.

MUPIP Error: This indicates that MUPIP RECOVER/ROLLBACK encountered an error when processing an after-image journal record written for each DSE database update. xxxx contains the failure codes for the four attempts. It is very likely that the database may have integrity errors or that the processprivate data structure are corrupted.

Action: Attempt the MUPIP RECOVER/ROLLBACK again. If the error persists, report the entire incident context with as much information about the system as possible to your GT.M support channel.

# MUREORGFAIL

MUREORGFAIL, MUPIP REORG failed. Failure code: xxxx.

MUPIP Error: This indicates that a REORG encountered a database error with failure code xxxx.

Action: Report this error to the group responsible for database integrity within your organization.

## **MUREPLPOOL**

MUREPLPOOL, Error with replpool section xxxx

MUPIP Error: This indicates that MUPIP RUNDOWN command found the specified replication pool shared memory section having a problem.

Action: Refer to the subsequent message text for details.

## **MUREPLSECDEL**

MUREPLSECDEL, Replication section xxxx deleted

MUPIP Information: This indicates that a replication pool was successfully closed and removed; xxxx is the shared memory resource ID for the pool.

Action: -

## **MUREPLSECNOTDEL**

MUREPLSECNOTDEL, Replication section xxxx not deleted

MUPIP Error: This indicates that an attempt to rundown the shared memory for a replication pool failed; xxxx is the resource ID of the memory.

Action: Review the preceding messages for additional information on the failure before attempting a rundown again.

V6.2-002 MR Manual

#### **MUREUPDWNGRDEND**

**MUREUPDWNGRDEND**, Region xxxx : MUPIP REORG UPGRADE/DOWNGRADE finished by pid aaaa [0xbbbb] at transaction number [0xcccc]

MUPIP Information: This is an informational message printed by MUPIP REORG UPGRADE or DOWNGRADE when the reorg has successfully completed its upgrade or downgrade respectively.

Action: None necessary.

## **MURNDWNOVRD**

MURNDWNOVRD, OVERRIDE qualifier used with MUPIP RUNDOWN on database file dddd

MUPIP Information: This message records use of the OVERRIDE qualifier with a MUPIP RUNDOWN command to bypass an an error, which would normally suggest a more appropriate action.

Action: No action required. This message serves primarily to facilitate analysis of database crashes and recovery procedures.

## MURPOOLRNDWNFL

**MURPOOLRNDWNFL**, Recvpool section (id = xxxx) belonging to the replication instance yyyy rundown failed

MUPIP Error: This indicates that an attempt to rundown the shared memory for a receive pool failed; xxxx is the resource ID of the memory and yyyy is the instance designation.

Action: Review the preceding messages for additional information on the failure before attempting a rundown again.

## **MURPOOLRNDWNSUC**

**MURPOOLRNDWNSUC**, Recvpool section (id = xxxx) belonging to the replication instance yyyy successfully rundown

MUPIP Information: This indicates that the receive pool for the specified instance was successfully closed and removed; xxxx is the shared memory resource ID for the pool and yyyy is the instance designation.

Action: -

## **MUSECDEL**

MUSECDEL, Section xxxx deleted

FIS V6.2-002

MUSECNOTDEL Chapter 1. Error Messages

MUPIP Information: This indicates that RUNDOWN removed the global memory section xxxx that is associated with an inactive database.

Action: -

## **MUSECNOTDEL**

MUSECNOTDEL, Section xxxx not deleted

MUPIP Information: This indicates that RUNDOWN could not eliminate the global memory section xxxx that is associated with an apparently inactive database.

Action: -

#### **MUSELFBKUP**

MUSELFBKUP, Database file xxxx can not be backed upon itself

MUPIP Error: This indicates that GT.M attempted to perform a backup that would have overlaid the database being backed up.

Action: Modify the name of the output file and reissue the command.

## MUSIZEFAIL

MUSIZEFAIL. MUPIP SIZE: failed. Failure code: xxxx.

MUPIP Error: This error indicates that MUPIP SIZE command encountered a database error with failure code xxxx.

Action: Report this error to the group responsible for database integrity within your organization.

## **MUSIZEINVARG**

MUSIZEINVARG, MUPIP SIZE: Invalid parameter value for: xxxx

MUPIP Error: This indicates that MUPIP SIZE encountered a qualifier or parameter xxxx with an invalid value

Action: Review the proper syntax for MUPIP SIZE. Refer to the Administration and Operations Guide or the online help for the MUPIP SIZE command.

## **MUSTANDALONE**

MUSTANDALONE, Could not get exclusive access to xxxx

MR Manual V6.2-002 June 09, 2015, Page 189 MUPIP Information: This indicates that the process required but could not get exclusive access to the listed resource.

Action: Retry the process at a time when there are no other users accessing the resource or log off the resource users.

#### **MUTEXERR**

MUTEXERR, Mutual Exclusion subsystem failure

Run Time Error: This indicates that GT.M encountered a system error while intializing mutual exclusion resource(s).

Action: Review the accompanying message(s) for more information about the cause of the error.

## **MUTEXFRCDTERM**

MUTEXFRCDTERM, Mutual Exclusion subsystem detected forced termination of process xxxx. Crit salvaged from region yyyy.

Run Time Warning: This indicates that GT.M confirmed inappropriate termination of the process xxxx, while holding crit on region yyyy.

Action: Determine the cause of the termination and take appropriate action.

#### **MUTEXLCKALERT**

MUTEXLCKALERT, Mutual Exclusion subsystem ALERT - Lock attempt threshold crossed for region rrrr. Process pppp is in crit cycle cccc.

Run Time Error: This warning indicates that a process could not obtain a critical section lock for region rrrr even after waiting longer than the GT.M determined threshold (approximately 45 seconds) because the critical section lock was held that entire time by another process pppp, cccc is the crit cycle count which GT.M increases by one every time it successfully grants the mutual exclusion (mutex) lock to a process, cccc provides a measure of the frequency of mutex lock use. MUTEXLCKALERT messages indicate that process pppp is blocking access to region rrrr for inappropriately long periods of time and thereby impacting performance for other processes needing access that region.

GT.M produces this warning when:

- A process owning a critical section dies (most likely because of a kill -9) and the OS gives its PID to another process. To reclaim the inappropriately held critical section, GT.M first checks whether the process is alive and whether it holds hold the critical section. On finding that the process is alive but does not hold the critical section, GT.M concludes that it is not safe to free the critical section and alerts the operator with this message.
- The process holding the critical section is using a non-Isolated command such as ZSYSTEM, BREAK or a timed command in a way that creates a deadlock or a live-lock. GT.M attempts to limit this by

limiting the time a process using one of these commands can hold a critical section, but your use of non-Isolated commands and your settings for \$ZMAXTPTIM and / or the environment variable \$gtm tpnotacidtime may be such that you set get MUTEXLCKALERT messages. Revise your settings for \$gtm\_tpnotacidtime and \$ZMAXTPTIM appropriately.

• There is an IO bottleneck that caused GT.M to slow down: GT.M detects that process pppp is currently using the critical section lock.

Action: Monitor the system to determine whether there is a process with process id pppp and whether that process is a GT.M process.

Implement a script to get a stack trace for process pppp or take other appropriate action and use the \$gtm procstuckexec environment variable to activate it before the block process sends the MUTEXLCKALERT message.

Identify and terminate process pppp to release control of that resource. If the process is a GT.M process, use a MUPIP STOP to terminate it. If a process of another application, use an appropriate mechanism to stop it.

If this message is due to an IO bottleneck, adopt a strategy that reduces IO. Some of the IO reducing strategies are:

- Revisit your database configuration parameters (especially block size, number of global buffers, journal buffers, and so on) to see if you can make improvements.
- Create separate region (database) for temporary globals and do not replicate them.
- Consider whether a different database access method and journaling strategy could improve throughput while satisfying your operational needs.
- For application configurations with large numbers of concurrent processes and/or large process memory footprints, consider placing object code in shared libraries on GT.M editions that support it. This may free system memory which the OS can use for its file system cache, or which you can use to increase the number of global buffers.



Do not apply IO reduction strategies all at once. Try them one at a time and always verify/measure the results of each strategy.

## **MUTEXRELEASED**

MUTEXRELEASED, Process xxxx [aaaa] has released the critical section for database yyyy to avoid deadlock. \$TLEVEL: pppp t\_tries: qqqq

Run Time Information: This indicates an out-of-design state within GT.M that was recoverable.

Action: If this message is frequent, report the entire incident context to your GT.M support channel.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 191

# **MUTEXRSRCCLNUP**

MUTEXRSRCCLNUP, Mutex subsystem leftover resource xxxx removed.

Run Time Information: This indicates that GT.M removed leftover system resource xxxx, used by the mutual exclusion subsystem. The resource was leftover due to abnormal termination of a GT.M component.

Action: -

#### **MUTNWARN**

**MUTNWARN**, Database file xxxx has 0xaaa more transactions to go before reaching the transaction number limit (0xbbbb). Renew database with MUPIP INTEG TN\_RESET.

MUPIP Warning: This indicates that MUPIP INTEG detected that the transaction numbers in the named database are approaching the maximum number as specified by the Maximum TN Warn field in the database file header. The actual maximum TN is less than this theoretical limit. DSE DUMP FILEHEADER shows what the limit is. The actual limit reflects some overhead used, for example, during a TN\_RESET operation.

Action: Use MUPIP INTEG with the qualifier TN\_RESET to reset the transaction numbers in the database. If the database is in the V4 format, consider converting it to the V5 format.

#### **MUTRUNC1ATIME**

MUTRUNC1ATIME, Process with PID iiii already performing truncate in region rrrr

MUPIP Information: Issued when a REORG -TRUNCATE on a region rrrr detects some other active REORG process concurrently processing a truncation.

Action: No action required. The other process will complete the truncate.

#### MUTRUNCBACKINPROG

MUTRUNCBACKINPROG, Truncate detected concurrent backup in progress for region rrrr

MUPIP Information: REORG truncate process detected concurrent backup. Database file not truncated.

Action: Ensure the backup has completed and rerun MUPIP REORG -TRUNCATE command.

#### **MUTRUNCERROR**

**MUTRUNCERROR**, Truncate of region rrrr encountered service error eeee

MUPIP Error: This indicates that a system call failed during REORG truncate.

Action: Use the OS documentation to investigate the failure.

## **MUTRUNCFAIL**

MUTRUNCFAIL, Truncate failed after reorg

MUPIP Error: This indicates that REORG encountered an unexpected error. Truncate may be partially complete.

Action: Review accompanying message(s) for more information.

## **MUTRUNCNOSPACE**

MUTRUNCNOSPACE, Region rrrr has insufficient space to meet truncate target percentage of yyyy

MUPIP Information: Issued when REORG truncate determines that there is not enough free space at the end of the file; database file not truncated.

Action: If appropriate specify a larger threshold.

# **MUTRUNCNOTBG**

MUTRUNCNOTBG, Region rrrr does not have access method BG

MUPIP Error: The truncate feature is only supported with the BG access method.

Action: Use the BG access method for files you wish to truncate.

## **MUTRUNCNOV4**

MUTRUNCNOV4, Region rrrr is not fully upgraded from V4 format.

MUPIP Error: The truncate feature is only available for fully upgraded database files.

Action: In order to use truncate, first upgrade the database file to the current major version.

## **MUTRUNCPERCENT**

MUTRUNCPERCENT, Truncate threshold percentage should be from 0 to 99

MUPIP Error: This indicates the the value entered for MUPIP REORG -TRUNCATE is invalid.

Action: Specify a valid threshold percentage.

## **MUTRUNCSSINPROG**

MUTRUNCSSINPROG, Truncate detected concurrent snapshot in progress for region rrrr

MUPIP Information: REORG truncate process detected concurrent snapshot; database file not truncated.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 193 Action: Ensure snapshot, for example a MUPIP INTEG, has completed and rerun the MUPIP REORG -TRUNCATE command.

## **MUTRUNCSUCCESS**

MUTRUNCSUCCESS, Database file dddd truncated from oooo blocks to nnnn at transaction tttt

MUPIP Information: This operator log message indicates that the specified database file was truncated by MUPIP REORG as described by the message.

Action: -

## MUUPGRDNRDY

MUUPGRDNRDY, Database xxx has not been certified as being ready to upgrade to yyy format

MUPIP Error: The named database file is in an older format than is in use by this GT.M version and has not been certified as ready for use by this GT.M version.

Action: Run DBCERTIFY to certify the database as being ready for upgrade.

#### **MUUSERECOV**

MUUSERECOV, Abnormal shutdown of journaled database dddd detected

Run Time Error: This error is issued when attempting a MUPIP RUNDOWN on a previously crashed journaling-enabled database dddd.

Action: Use MUPIP RECOVER to restore the normal state of the database.

## **MUUSERLBK**

MUUSERLBK, Abnormal shutdown of replication-enabled database dddd detected

Run Time Error: This error is issued when attempting a MUPIP RUNDOWN on a previously crashed replication-enabled (with BEFORE IMAGE journaling) database dddd.

Action: Use MUPIP ROLLBACK to restore the normal state of the database.

#### **NAMEEXPECTED**

**NAMEEXPECTED**, A local variable name is expected in this context

Compile Time Error: This indicates that an actual name or a formallist item did not specify a local variable name.

Action: Look for and correct typographical errors. Verify that actualnames and formallist items are local variable names.

V6.2-002 GT.M Message and Recovery Procedures Manual

### **NAMENDBAD**

**NAMENDBAD**, Subscripted name ssss must end with right parenthesis

GDE Error: This indicates that a subscripted name ssss (global name immediately followed by a left parenthesis) was specified without a balancing right parenthesis at the end of the subscripts.

Action: Specify the subscripted name with the appropriate right parenthesis.

### NAMGVSUBOFLOW

NAMGVSUBOFLOW, Subscripted name hhhh...tttt is too long to be represented in the database using collation value #nnnn

GDE Error: This indicates that the subscripted name is too big to be represented in the database (exceeds the maximum limits of GT.M for the key size). The message also reports the alternative collation nnnn which was used to arrive at the subscript/key representation inside the database. The head (hhhh) and tail (tttt) of the long subscript is displayed with a ... in the middle.

Action: Specify a shorter subscripted name.

## **NAMGVSUBSMAX**

NAMGVSUBSMAX, Subscripted Name specification nnnn has more than the maximum # of subscripts (mmmm)

GDE Error: This indicates that a name nnnn was specified with more than the maximum allowed number mmmm.

Action: Specify a name within the maximum allowed number of subscripts.

# NAMLPARENNOTBEG

NAMLPARENNOTBEG, Subscripted Name specification nnnn needs to have a left parenthesis at the beginning of subscripts

GDE Error: This indicates that a name was specified using : or , or ), which indicates a subscripted name, but the left parenthesis was missing.

Action: Specify a name with the appropriate left parenthesis.

#### **NAMNOTSTRSUBS**

**NAMNOTSTRSUBS**, Subscript #nnnn with value vvvv in name specification is not a properly formatted string subscript

V6.2-002 MR Manual June 09, 2015, Page 195 GDE Error: This indicates that the nnnn'th subscript in a name did not have a valid string subscript. For example usages like GBL("AB" ) where the syntax is used to do concatenation of string subscripts but the right side of the operator is missing the string specification.

Action: Specify the name with a properly formatted string subscript.

## NAMNUMSUBSOFLOW

NAMNUMSUBSOFLOW, Subscript #nnnn with value vvvv in name specification has a numeric overflow

GDE Error: This indicates that the nnnn'th subscript in a name specification includes a number that is too big to be represented in GT.M.

Action: Specify a subscript with a number that is inside the numeric range supported by GT.M.

#### NAMONECOLON

NAMONECOLON, Subscripted Name specification nnnn must have at most one colon (range) specification

GDE Error: This indicates that a subscripted name was specified with a range specification using: in the last subscript but more than one colon character was used.

Action: Specify a range with only one colon.

### NAMRANGELASTSUB

NAMRANGELASTSUB, Ranges in name specification nnnn are allowed only in the last subscript

GDE Error: This indicates that one or more ranges (using: syntax) were specified in a name somewhere other than the last subscript.

Action: Specify any ranges only in the last subscript of a name.

## **NAMRANGEORDER**

NAMRANGEORDER, Range in name specification nnnn specifies out-of-order subscripts using collation sequence #cccc

GDE Error: This indicates that the range in the name specification is out-of-order. For example yy(10:1) specifies numeric subscripts that are not in order (10 is greater than 1 and so it should have been 1:10 instead). In case of string subscripts, the collation sequence cccc is used to arrive at the subscript representation in the database and this is what gets compared for the left and right ends of the range to determine if they are in order or not. For example yy("a":"g") is in order in case of collation sequence 0 (ascii ordering) but might not be in order if the name yy has a non-zero collation defined and that collation sorts strings in reverse ascii order.

V6.2-002 GT.M Message and Recovery Procedures Manual NAMRANGEOVERLAP Chapter 1. Error Messages

Action: Specify ranges in order i.e. lower end of the range on the left hand side and the higher end of the range on the right hand side.

# **NAMRANGEOVERLAP**

NAMRANGEOVERLAP, Range in name specifications mmmm and nnnn overlap using collation sequence #cccc

GDE Error: This indicates that the subscripted name specifications mmmm and nnnn belong to the same unsubscripted global name and map to different regions but define ranges that overlap.

Action: Ranges that overlap cannot map to different regions. The only exception is sub-ranges where one range lies completely inside of another. Fix the range specifications to either map to the same region or split the ranges further to avoid overlap.

# **NAMRPARENNOTEND**

**NAMRPARENNOTEND**, Subscripted Name specification nnnn cannot have anything following the right parenthesis at the end of subscripts

GDE Error: This indicates that a subscripted name was specified where the right parenthesis denoting the end of the subscripts was followed by more characters.

Action: Specify all subscripts of a name inside the left and right parenthesis that immediately follow the unsubscripted name.

# NAMSTARSUBSMIX

NAMSTARSUBSMIX, Name specification nnnn cannot contain \* and subscripts at the same time

GDE Error: This indicates that the name nnnn contains both \* and subscripts which is not allowed.

Action: Specify a wildcard (\*) or subscripts, but not both.

### **NAMSTARTBAD**

NAMSTARTBAD, xxxx must start with '%' or an alphabetic character

GDE Error: This indicates that an ADD or CHANGE command specified a name xxxx that does not begin with a '%' sign or an alphabetic character.

Action: Add a '%' sign or an alphabetic character to the beginning of the name.

### NAMSTRSUBSCHARG

NAMSTRSUBSCHARG, Subscript #nnnn with value vvvv in name specification specifies a \$C/\$ZCH with number cccc that is invalid in the current \$zchset

GDE Error: This indicates that the nnnn'th subscript in a name specifies a string subscript using \$CHAR/\$ZCHAR but one of the arguments to this function (potentially in a comma-separated list) is invalid.

Action: An invalid integer argument is one which returns a null string when passed to \$CHAR/\$ZCHAR with the current \$zchset setting. Specify the string subscript with a valid argument to \$CHAR/\$ZCHAR.

## **NAMSTRSUBSCHINT**

**NAMSTRSUBSCHINT**, Subscript #nnnn with value vvvv in name specification does not have a positive integer inside \$C/\$CHAR/\$ZCH/\$ZCHAR

GDE Error: This indicates that the nnnn'th subscript in a name specifies a string subscript using \$CHAR/\$ZCHAR but one of the arguments to this function (potentially in a comma-separated list) is not a positive integer.

Action: Specify the string subscript with a positive integer argument to \$CHAR/\$ZCHAR.

### **NAMSTRSUBSFUN**

**NAMSTRSUBSFUN**, Subscript #nnnn with value vvvv in name specification uses function other than \$C/\$CHAR/\$ZCH/\$ZCHAR

GDE Error: This indicates that the nnnn'th subscript in a name specifies a string subscript using an unsupported function. The only two supported functions are \$CHAR or \$ZCHAR (long form and short forms).

Action: Specify the string subscript using only the supported functions.

### **NAMSUBSBAD**

NAMSUBSBAD, Subscript #nnnn with value vvvv in name specification is an invalid number or string

GDE Error: This indicates that the nnnn'th subscript in a name specification is neither a valid number or a string.

Action: Specify a valid subscript.

## **NAMSUBSEMPTY**

NAMSUBSEMPTY, Subscript #nnnn is empty in name specification

GDE Error: This indicates that the nnnn'th subscript in a name specification is empty. For example the 2nd subscript in a(1,,3) is empty.

Action: Specify the subscripted name with a non-empty subscript.

FIS

V6.2-002

# **NCTCOLLDIFF**

NCTCOLLDIFF, Source and destination for MERGE cannot have different numerical collation type

Run Time Error: This indicates that two arguments of the MERGE command have different numerical collation type.

Action: Use the %GBLDEF utility to set the same numerical collation type for both the arguments or use another method, such as a \$ORDER() loop or MUPIP EXTRACT and LOAD to move the data.

## **NCTCOLLSPGBL**

NCTCOLLSPGBL, Database region rrrr contains portion of spanning global 'gggg and so cannot support non-zero numeric collation type

Run Time Error: This indicates that region rrrr contains parts of a global gggg that spans multiple regions according to the current global directory but the directory tree in rrrr indicates gggg has a nonzero numeric collation type.

Action: Spanning globals only support a value of zero for numeric collation (i.e. numbers collate as numbers, not as strings). Access region rrrr using a temporary global directory that maps all names (including gggg) to rrrr, extract the gggg global, KILL it, use \$\$set^%^GBLDEF to fix the numeric collation to 0, reload the global from the extract, switch back to the regular global directory. An alternative recovery action that does not require extract/load is to change the global directory so gggg is no longer a spanning global or has no mappings into any region that collates numbers using their string value.

## **NEEDTRIGUPGRD**

**NEEDTRIGUPGRD**, Cannot do trigger operation on database file ffff until it is upgraded; Run MUPIP TRIGGER -UPGRADE first

Run Time Error: Upgrades from some versions to some more recent versions change aspects of the trigger definitions. This message indicates GT.M encountered a trigger definition in an old format.

Action: Run MUPIP TRIGGER -UPGRADE. Alternatively, revert to the older version, use MUPIP TRIGGER or \$ZTRIGGER() to select all triggers and save the result, delete all the triggers, return to the newer version and reinstall the triggers.

### **NEGFRACPWR**

NEGFRACPWR, Invalid operation: fractional power of negative number

Run Time Error: This indicates that the power of an exponentiation operation is negative and contains a fractional portion. This type of operation produces an imaginary component in its result, and M does not specify such operations.

Action: Modify the code to prevent negative powers with fractional parts in exponentiation operations or trap the resulting errors.

### **NESTFORMP**

**NESTFORMP**, Formal parameter list cannot be combined with nested line

Compile Time Error: This indicates that a line included both a formallist and a nesting level-indicator (.).

Action: Parameter passing is incompatible with argumentless DO commands. Remove the formallist or the level-indicator and reorganize the routine, if appropriate.

### **NETDBOPNERR**

**NETDBOPNERR**, Error while attempting to open database across net

Run Time Error: This indicates that the GT.M encountered an error when it attempted to open a database that is on a remote node served by a GT.CM server.

Action: Review subsequent message(s) to determine the nature of the problem.

### **NETFAIL**

NETFAIL, Failure of Net operation

Run Time Error: This indicates that a network failure occurred but it could not be traced to any current activity.

Action: If the problem persists, contact the group responsible for database operations on your network.

### **NETLCKFAIL**

**NETLCKFAIL**, Lock operation across Net failed

Run Time Error: This indicates that a LOCK, ZALLOCATE, or ZDEALLOCATE that involved a remote database failed.

Action: This network failure involves M LOCKs. Retry the operation from a point that establishes all necessary LOCKs. If the problem persists, contact the group responsible for database operations on your network.

# **NEWJNLFILECREAT**

**NEWJNLFILECREAT**, Journal file xxxx nearing maximum size. New journal file created.

**NLMISMATCHCALC** Chapter 1. Error Messages

Run Time/MUPIP Information: This indicates that GT.M created a new journal file as it reached the maximum allowed journal size.

Action: Refer to the documentation on maximum allowed journal file size.

# **NLMISMATCHCALC**

NLMISMATCHCALC, Location of xxxx expected at yyyy, but found at zzzz

Run Time Error: This indicates that the shared memory location of xxxx shows a layout problem. Typically, this is caused by attempting to use databases opened by a GT.M version, different from the currently running version.

Action: Rundown the database and ensure a stable and consistent database configuration before attempting to use it again.

## **NOACTION**

**NOACTION**, Not updating Global Directory xxxx

GDE Information: This indicates that GDE did not write a new version of existing Global Directory xxxx due to a QUIT or an EXIT when no changes had been made.

Action: GDE displays this message when you EXIT GDE without making any changes to the Global Directory. It also displays this message when you terminate a GDE session with the QUIT command. If you made changes you want to save, you must restart GDE, perform your work and save the changes before exiting GDE.

## **NOALIASLIST**

**NOALIASLIST**, Parenthetical lists of multiple arguments cannot have a preceding alias introducer or include alias (\*) forms

Run Time Error: This indicates the argument for a SET command attempted to assign an alias using a parenthesized list as a left-hand argument, which is unsupported syntax.

Action: Correct the code in question to avoid the parenthesized list.

# **NOCANONICNAME**

**NOCANONICNAME**, Value is not a canonic name (xxxx).

Run Time Error: This indicates that the argument supplied to \$QLENGTH, or the first argument to \$QSUBSCRIPT is not a valid glvn.

Action: Pass valid argument to \$QLENGHT/\$QSUBSCRIPT

V6.2-002 MR Manual

## **NOCCPPID**

**NOCCPPID**, Cannot find CCP process ID

CCE Error: This indicates that a CCE DUMP did not complete because it could not find a process with the name for the CCP.

Action: The CCP is not running properly on your node. Report this error to the group responsible for clustered databases at your site.

### **NOCHLEFT**

**NOCHLEFT**, Unhandled condition exception (all handlers exhausted) process terminating

Run Time Fatal: This indicates an internal error in handling of error conditions in GT.M.

Action: Report the entire incident context with the complete operator log generated to your GT.M support channel.

# NODFRALLOCSUPP O

**NODFRALLOCSUPP**, The NODEFER\_ALLOCATE qualifier is not allowed on this operating system. Not changing the defer allocation flag

MUPIP Error: Indicates the disk space preallocation is not supported on the current operating system.

Action: Consider using an external utility, such as FALLOCATE, to fulfill the need. Currently, Linux and AIX are the supported operating systems for the NODEFER ALLOCATE feature.

#### **NOEDITOR**

NOEDITOR, Can't find an executable editor: eeee

Run Time Error: The ZEDIT command cannot find an executable editor.

Action: Ensure that the EDITOR environment variable points to an editor that is executable by the user..

### **NOENDIANCYT**

NOENDIANCVT, Unable to convert the endian format of file dddd due to eeee

MUPIP Error: One of the requirements for the MUPIP ENDIANCYT command was not met. The problems include: "database format is not the current version", "minor database format is not the current version", "some blocks are not upgraded to the current version", "kills in progress", "the database is frozen", "a GT.CM server accessing the database", "recovery was interrupted", "database creation in progress", "wc\_blocked is set-rundown needed", "the database is corrupted".

Action: Resolve the reported conditions and repeat the command or use the -OVERRIDE qualifier if it is appropriate to bypass the error condition.

### **NOEXCLUDE**

NOEXCLUDE, None of the excluded variables exist

MUPIP Information: This indicates that MUPIP REORG did not find any of the variables specified in the EXCLUDE qualifier to be present in the database.

Action: Verify the names specified in the EXCLUDE qualifier in case you expected them to be present in the database file and not be reorged.

## **NOEXCNOZTRAP**

**NOEXCNOZTRAP**, Neither an exception nor a Ztrap is specified

Run Time Warning: This indicates that a \$CTRAP character arrived but no EXCEPTION or \$ZTRAP existed to handle it.

Action: Determine why these circumstances coincide. This error never appears on a device; in this particular case, it is assigned to the image termination status as a warning.

# **NOEXIT**

**NOEXIT.** Cannot exit because of verification failure

GDE Information: This indicates that GDE encountered errors in the REGION-SEGMENT or SEGMENT-FILE mappings and cannot exit.

Action: Review the accompanying message(s) for additional information. Verify the mappings and modify them as appropriate.

### **NOFORKCORE**

**NOFORKCORE**, Unable to fork off process to create core. Core creation postponed.

Run Time Warning: This indicates that the process, which failed was unable to create a memory dump file, possibly due to lack of system resources.

Action: Reduce the number of users and stop any unnecessary processes.

## **NOGTCMDB**

NOGTCMDB, ffff does not support operation on GT.CM database region: rrrr

Chapter 1. Error Messages NOINL

Utility Error: Facility ffff cannot perform the requested operation on a GT.CM database such as rrrr.

Action: Use the utility on the remote GT.CM server system or move the database so it is local rather than remote.

# **NOINL**

NOJNL, ssss segments do not support journaling.

MUPIP Error: This error indicates that the segment type ssss does not support journaling.

Action: For more information on Journaling, refer to the GT.M Journaling chapter in the Administration and Operations Guide.

# **NOJNLPOOL**

**NOJNLPOOL**, No journal pool info found in the replication instance of xxxx

Run Time/MUPIP Error: This indicates that GT.M / MUPIP did not get replication information from the instance file specified. Replication instance file was not initialized because replication did not start, or some other process reset the replication instance file.

Action: Start the source server if it was not started. If the source server was running, stop the server and perform MUPIP RUNDOWN (if MUPIP RUNDOWN fails, try MUPIP RUNDOWN region \*).

#### **NOLBRSRC**

**NOLBRSRC**, Object libraries cannot have SRC paths associated

Run Time Error: This indicates that GTM\$ROUTINES / gtmroutines or a SET \$ZROUTINES attempted to place a source specification (SRC qualifier / source directory path) on an object library.

Action: Remove the source specification. GT.M does not use the qualifier SRC= or source directories on object libraries. On OpenVMS, if you must provide access to source corresponding to objects in an object library, move the objects to a directory. If the objects exist only in the library, use LIBRARY with the qualifier EXTRACT to recreate them. On UNIX, if you must provide access to sources corresponding to objects in the shared library, attach the source directory to an existing object directory entry. Since GT.M does not support automatic recompilations into libraries, care must be taken when providing access to sources of library routines.

## **NOLOCKMATCH**

**NOLOCKMATCH**, No matching locks were found in rrrr

LKE Information: SHOW or CLEAR, found that no LOCKs match the specified criteria in region rrrr; note that specifying no search criteria acts like a wildcard, checking all LOCKs in the region.

NOLOG Chapter 1. Error Messages

Action: If this is not the expected result, check the search criteria and / or research the LOCK protocol to validate its correct operation.

### **NOLOG**

**NOLOG**, Logging is currently disabled. Log file is xxxx.

GDE Error: This indicates that GDE is not logging user activities.

Action: Use the LOG -ON command to turn on GDE logging.

## **NONASCII**

**NONASCII**, ssss is illegal for a oooo as it contains non-ASCII characters

GDE Error: The specification ssss contains non-ASCII characters which are required for an object of type oooo.

Action: Chose an object name or value containing only ASCII characters.

### **NONEGATE**

NONEGATE, Qualifier xxxx cannot be negated

GDE Error: This indicates that the qualifier does not support this usage.

Action: Review the Administration and Operations Guide or the Programmer's Guide for the correct usage.

### **NONUTF8LOCALE**

NONUTF8LOCALE, Locale has character encoding (cccc) which is not compatible with UTF-8 character set

Run Time Error: This error is reported by GT.M when it recognizes that the LC CTYPE locale category cccc (as shown by the UNIX locale command) does not use UTF-8 character encoding when gtm chset is "UTF-8".

Action: Set the environment variable LC\_CTYPE to a Unicode locale name with UTF-8 character encoding. Note that LC\_ALL, if defined, overrides LC\_CTYPE. The name of the locale varies between different UNIX platforms, but mostly in the form of <lang>\_<country>.<charset>, where each element (without the angular brackets) has the form shown below:

- <lang> is the language code in lower case (such as en, or de).
- <country> is the country name in upper case (such as US, GB)

• <charset> is the character set encoding (such as UTF-8, ISO8859-1)

Refer to the operating system manuals for the specific details of available locale names on the system.

### **NOPINI**

**NOPINI**, PINI journal record expected but not found in journal file xxxx at offset yyyy

MUPIP Error: This indicates that MUPIP did not encounter a valid and expected Process Initialization Record (PINI), at offset yyyy of the journal file xxxx.

Action: Run MUPIP JOURNAL EXTRACT -FULL DETAIL FORWARD FENCE=NONE NOERROR LIMIT xxxx. Report the entire incident context with the appropriate extract file and error message(s) to your GT.M support channel.

## **NOPLACE**

NOPLACE, Line specified in a ZBREAK cannot be found

Run Time Warning: This indicates that the ZBREAK was ignored because it specified a line that could not be found in the image.

Action: Modify the ZBREAK or ZLINK the routine that has the missing label.

#### NOPREVLINK

**NOPREVLINK**, Journal file xxxx has a null previous link

MUPIP Error: This indicates that MUPIP found the previous link of journal file xxxx to be null, when it needed to process backward beyond the journal files first record.

Action: Verify the specified resync or time qualifiers are as intended. If correct values were specified, and null link was due to operator action, restore the journal generation link and reissue the command.

# NOPRINCIO A

**NOPRINCIO**, NOPRINCIO Unable to write to principal device

Run Time Fatal: This indicates that GT.M attempted to but could not read from or write to the principal device.

Action: The NOPRINCIO error message works differently from other messages. The first occurrence results in an error that can be caught by device and trap handlers. The second occurrence is FATAL which does not drive device or trap handlers and terminates the process. The most common causes for the principal device to cease to exist involve terminal sessions or socket connections (including

those from processes started by inetd/xinetd). When the remote client terminates the connection, the underlying principal device is closed and becomes inaccessible when the process attempts to READ from, or WRITE to, it. In the case of terminals, a typical cause is users closing the window of a terminal session without cleanly exiting from the GT.M process.

### NORECVPOOL

NORECVPOOL, No receiver pool info found in the replication instance of xxxx

Run Time/MUPIP Error: This indicates that GT.M / MUPIP did not get replication information from the instance file specified. Replication instance file was not initialized because receiver server did not start or, some other process reset the replication instance file.

Action: Start the receiver server if the server was not started. If the receiver server was running, stop the server and perform MUPIP RUNDOWN (if MUPIP RUNDOWN fails, try MUPIP RUNDOWN region \*).

# **NOREGION**

NOREGION, REGION not found: xxxx

LKE Error: This indicates that a SHOW or CLEAR command with the qualifier REGION=xxxx could not locate region xxxx in the current Global Directory.

Action: Look for and correct any typographical errors in the region name. Use GDE to look in the Global Directory for names of defined regions.

#### NOREPLCTDREG

**NOREPLCTDREG**, Replication subsystem found no region replicated for dddd ffff

MUPIP Warning: This indicates that the replication system is present, but no globals are configured for replication in ffff where dddd is "instance file" for UNIX and "global directory" for OpenVMS.

Action: Use MUPIP SET to specify which database regions to replicate.

# NORESYNCSUPPLONLY

NORESYNCSUPPLONLY, NORESYNC only supported for Supplementary Instances

Receiver Server log/MUPIP Error: Issued by a Receiver Server on a non-Supplementary Instance when it is started with a -NORESYNC; -NORESYNC only applies to Supplementary Instances started with -UPDOK, not to non-Supplementary Instances.

Action: Use this qualifier only in a valid context.

# NORESYNCUPDATERONLY

**NORESYNCUPDATERONLY**, NORESYNC qualifier only allowed on a Supplementary Instance which allows local updates

Receiver Server log/MUPIP Error: Issued by a Receiver Server when started with -NORESYNC on a Supplementary Instance but started without -UPDOK; -NORESYNC applies only to Supplementary Instances started with -UPDOK.

Action: Use this qualifier only in a valid context.

### **NOSELECT**

NOSELECT, None of the selected variables exist, halting

MUPIP Information: This indicates that a MUPIP EXTRACT or REORG operation did not occur because the global variables specified by the SELECT= qualifier do not exist.

Action: Look for an inappropriate definition for GTM\$GBLDIR / gtmgbldir or typographical errors in the specified variables.

### NOSOCKETINDEV

**NOSOCKETINDEV**, There is no socket in the current socket device

Run Time Error: This indicates that either no sockets have been established for the device or that all the sockets attached to the device have been closed prior to the current command.

Action: Review the logic managing the sockets and correct it.

## **NOSOCKHANDLE**

NOSOCKHANDLE, No socket handle specified in WRITE /PASS

Run Time Error: WRITE /PASS was called without specifying at least one socket handle to pass.

Action: Make sure the code is specifying at least one socket handle.

#### NOSPACECRE

**NOSPACECRE**, Not enough space to create database file xxxx. aaaa blocks are needed, only bbbb available.

MUPIP Error: This indicates that the requested file was not created because the file system (in UNIX) or volume (in OpenVMS) did not have sufficient space.

Action: Check the allocation size specified in the global directory. Choose another location or reconfigure the file system or volume.

Page 208, June 09, 2015

# **NOSPACEEXT**

NOSPACEEXT, Not enough disk space for file xxxx to extend. aaaa blocks needed. bbbb blocks available.

Run Time Error: This indicates that there is not adequate space to do a needed journal file extension of the currently specified extension size of aaaa. If the Instance Freeze mechanism is active, GT.M modifies the NOSPACEEXT message from error (-E-) to warning (-W-) to indicate it is performing the extension even though the available space is less than the specified extension amount. In OpenVMS, this causes journaling to be turned off for the region.

Action: Locate appropriate disk space and adjust the journal file path. To reestablish durability, perform a MUPIP BACKUP that turns journaling on again.

#### **NOSTARFILE**

**NOSTARFILE**, Only star(\*) argument can be specified with xxxx

MUPIP Error: This indicates that the qualifier xxxx, specified with the MUPIP JOURNAL command allows only star (\*) as an argument.

Action: Specify star (\*) as an argument instead of explicit journal file names.

## **NOSUBSCRIPT**

**NOSUBSCRIPT**, No such subscript found (xxxx)

Run Time Error: This indicates that the second argument to \$QSUBSCRIPT is less than -1.

Action: Pass a value greater than -1 as the second argument to \$QS.

### **NOSUCHPROC**

NOSUCHPROC, Process xxxx does not exist no need to yyyy it

Run Time Information: This indicates the specified process xxxx does not exist, to which an attempt to signal yyyy was made. This may occur in normal operation, but is reported to the operator logging facility in case an abnormal situation needs to be studied.

Action: -

### **NOSUPPLSUPPL**

NOSUPPLSUPPL, Instance ssss is configured to perform local updates, so it cannot receive from Supplementary Instance iiii

Receiver Server log/MUPIP Error: Issued by a Receiver Server or a MUPIP JOURNAL -ROLLBACK -FETCHRESYNC on a Supplementary Instance ssss started with -UPDOK attempted to connect to

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 209 instance iiii, but found IIII is also a Supplementary Instance. A Supplementary Instance that permits local updates can only replicate updates that originate on a non-Supplementary Instance.

Action: Reconfigure the instances to a supported configuration.

#### NOTALLDBOPN

**NOTALLDBOPN**, Not all required database files were opened

MUPIP Fatal: This indicates that all databases needed for replication could not be opened; the server will not start.

Action: Refer to the accompanying message(s) to determine why all required files would not open. Fix the problem and retry.

### **NOTALLDBRNDWN**

NOTALLDBRNDWN, Not all regions were successfully rundown

Run Time Error: This message indicates an error while running down the database. It could be caused by various conditions such as running out of disk space or IO error.

Action: Look at the previous error messages to identify the cause of this error

# **NOTALLINLEN**

**NOTALLINLEN**, Journaling not enabled and on for all regions

MUPIP Warning: This indicates that MUPIP found that not all regions had journaling enabled.

Action: -

### **NOTALLREPLON**

**NOTALLREPLON**, Replication state is not on for all regions

MUPIP Warning: This indicates that not all the database of the current global directory has replication state ON.

Action: -

# NOTERMENTRY

**NOTERMENTRY**, TERM = "xxxx" has no "terminfo" entry. Possible terminal handling problems.

Run Time Information: This indicates that while opening a terminal device, the value of the environment variable TERM was xxxx for which no matching entry was found in the terminfo

V6.2-002 GT.M Message and Recovery Procedures Manual database. GT.M uses this information in the terminfo entry to perform terminal specific functions such as cursor movement on screen clearing. With an incorrect entry, such functions are not performed properly.

Action: Exit GT.M and set the TERM environment variable to a value which exists in the terminfo database and which matches the terminal or terminal emulator being used. See the UNIX user documentation for more information about terminfo.

# **NOTERMENV**

NOTERMENV, Environment variable TERM not set. Assuming "unknown."

Run Time Information: This indicates that the TERM environmental variable indicating the terminal type in use does not have a value specified.

Action: Find the correct value for the TERM environmental variable for the terminal in use and specify that terminal type.

## **NOTERMINFODB**

**NOTERMINFODB**, No "terminfo" database. Possible terminal handling problems.

Run Time Information: This indicates that the operating system could not find the terminfo database. The database may be deleted or moved to different location. GT.M needs this database to display information and accept user input correctly.

Action: This message reflects an operating system problem. Refer to the operating system troubleshooting.

### **NOTEXTRINSIC**

NOTEXTRINSIC, Quit does not return to an extrinsic function, argument not allowed

Run Time Error: This indicates that a QUIT command specified an argument but did not match to an extrinsic function or special variable.

Action: Look for a missing double space after a QUIT, a faulty logic path, or a routine that should be invoked as an extrinsic but was invoked with a DO.

# **NOTGBL**

**NOTGBL**, Expected a global variable name starting with an up-arrow (^): xxxx

Run Time/MUPIP Error: This indicates that the VIEW argument expression for tracing specifies xxxx which is not a valid global name. In case of MUPIP error, it indicates that LOAD aborted because it encountered xxxx in its input stream, which is not a valid global name.

Action: Correct the argument of the VIEW command to point to a valid global name. For MUPIP error, refer to the topic MUPIP LOAD Errors in About This Manual section of this manual.

# NOTPOSITIVE

**NOTPOSITIVE**, xxxx qualifier must be given a value greater than zero

MUPIP Error: This indicates that the value assigned to the xxxx qualifier value is negative (less than zero).

Action: Assign a value greater than zero (0) for qualifier xxxx.

# **NOTPRINCIO**

**NOTPRINCIO**, Output currently directed to device xxxx

Run Time Warning: This message displays the current device xxxx when it is not the principal device and the process enters Direct Mode.

Action: To redirect all I/O to the terminal, note the current device or save it in a temporary variable and USE \$P. If you decide to resume program execution, remember to restore the current device with a USE command.

### **NOTREPLICATED**

**NOTREPLICATED**, Transaction number xxxx generated by the yyyy process (PID = zzzz) is not replicated to the secondary

DSE Information: This indicates that a transaction generated by DSE update was not replicated to secondary side. This is an expected behaviour. Inappropriate DSE updates while running replication can cause primary and secondary to be out of sync.

Action: -

## **NOTRNDMACC**

NOTRNDMACC, Only random access files are supported as backup files for non-incremental backup

MUPIP Error: This indicates that for comprehensive BACKUP, only random access files are supported, other types of devices, for example, TCP devices and pipes, are not supported.

Action: Perform the BACKUP to a random access file.

## **NOTTOEOFONPUT**

NOTTOEOFONPUT, Not positioned to EOF on write (sequential organization only)

**NOUSERDB** Chapter 1. Error Messages

Run Time Error: This indicates that a WRITE command attempted to update a sequential disk file that was not positioned to end-of-file (EOF).

Action: Read to end-of-file or OPEN the file with the APPEND deviceparameter if you want to add to the file. If you need a fresh copy of the file, OPEN it with the NEWVERSION deviceparameter.

## **NOUSERDB**

**NOUSERDB**, ffff does not support operation on non-GDS format region: rrrr

Utility Error: Facility ffff cannot perform the requested operation on a user-defined database such as rrrr.

Action: Convert the database to a GDS format or use the utilities appropriate to the user-defined format.

# **NOVALUE**

**NOVALUE**, Qualifier xxxx does not take a value

GDE Error: This indicates that GDE encountered a value for a qualifier that does not accept a value. xxxx is the name of the qualifier.

Action: Specify the qualifier without a value.

### **NOZBRK**

**NOZBRK**. No zbreak at that location

Run Time Information: This indicates that a ZBREAK command attempted to remove a ZBREAK from a line that did not specify one. Therefore, no action occurred.

Action: Review the current ZBREAKs using ZSHOW "B". All breaks can be removed using ZBREAK -\*.

### NOZTRAPINTRIG

NOZTRAPINTRIG, Use of \$ZTRAP in a database trigger environment (\$ZTLEVEL greater than 0) is not supported.

Trigger/Run Time Error: GT.M requires the use of \$ETRAP for error handling within trigger logic.

Action: Modify the application code to use \$ETRAP to handle errors in trigger logic.

# **NULLCOLLDIFF**

**NULLCOLLDIFF**, Null collation order cannot be different for all regions

Run Time Error: Standard null collation setting is not same for all regions.

Action: Using GDE show or DSE dump fileheader, check standard null collation field for all regions and make sure they are same.

### NULLENTRYREE

NULLENTRYREF, JOB command did not specify entryref

Run Time Error: This error is issued when mandatory entryref is not specified with JOB command.

Action: Specify the entryref for JOB command.

## **NULSUBSC**

NULSUBSC, Null subscripts are not allowed for region: xxxx

Run Time Error: This indicates that a global variable specified a null subscript in a database reference that mapped to region xxxx, which does not accept null subscripts.

Action: Look for the source of the null subscript(s). You can use GDE and/or DSE to remove the prohibition.

### **NUMOFLOW**

**NUMOFLOW**. Numeric overflow

Compile Time/Run Time Error: This indicates that a numeric literal or a string evaluated to a numeric that exceeds the numeric range of GT.M.

Action: Look for the source of the large number.

# **NUMPROCESSORS**

**NUMPROCESSORS**, Could not determine number of processors

Run Time Warning: This indicates that the process was unable to determine the number of CPUs in the machine. (The subsequent message(s) give more detailed information.) This causes the number to default to one (1), which if incorrect may cause sub-optimal tuning.

Action: Analyze the accompanying message(s). If you require assistance, report the entire incident context to your GT.M support channel.

## **NUMUNXEOR**

NUMUNXEOR, xxxx unexpected end of record in numeric subscript

MUPIP Error: This indicates that LOAD aborted because it encountered an improperly formatted numeric subscript xxxx in its input stream.

**OBIDUP** Chapter 1. Error Messages

Action: Refer to the topic MUPIP LOAD Errors in About This Manual section in this manual.

# **OBIDUP**

**OBJDUP**, xxxx yyyy already exists

GDE Error: This indicates that an ADD command attempted to add a NAME, REGION, or SEGMENT xxxx, that already exists. yyyy is the NAME, REGION, or SEGMENT.

Action: Use the CHANGE command or specify a different object name.

# **OBJFILERR**

**OBJFILERR**, Error with object file I/O on file xxxx

Run Time Error: This indicates that [auto]ZLINK processing encountered an error when it attempted to access object file-specification xxxx.

Action: Use host shell commands to examine the file and its protection.

# **OBJNOTADD**

**OBJNOTADD**, Not adding xxxx

GDE Error: This indicates that GDE did not add the specified NAME, REGION, or SEGMENT. xxxx is the NAME, REGION, or SEGMENT specified with the ADD command.

Action: Review the accompanying message(s) for additional information.

# **OBINOTCHG**

**OBJNOTCHG**, OBJNOTCHG Not changing xxxx

GDE Error: This indicates that GDE has not changed the specified NAME, REGION, or SEGMENT. xxxx is the NAME, REGION, or SEGMENT specified with the CHANGE command.

Action: Review the accompanying message(s) for additional information.

# **OBJNOTFND**

**OBJNOTFND**, xxxx does not exist

GDE Error: This indicates that a CHANGE or DELETE command specified a NAME, REGION, or SEGMENT that does not exist. xxxx is the NAME, REGION, or SEGMENT.

Action: Use the ADD command or look for and correct any typographical errors.

Chapter 1. Error Messages **OBJREOD** 

# **OBJREQD**

### OBJREOD, xxxx required

GDE Error: This indicates that an ADD, CHANGE, DELETE, RENAME, or TEMPLATE command does not specify a NAME, REGION, or SEGMENT. xxxx is the required object-type.

Action: Look for a missing space or supply the NAME, REGION, or SEGMENT.

## **OFFSETINV**

OFFSETINV, Entry point xxxx+yyyy not valid

Compile Time/Run Time Error: This indicates that GT.M encountered a label xxxx and an offset yyyy that did not fall within the actual lines of the routine.

Action: Modify the routine so the entry point is a valid entryref.

### **OLDBINEXTRACT**

**OLDBINEXTRACT**, Loading an older version (xxxx) of binary extract

Run Time Error: This indicates that a MUPIP LOAD input file is of an older type that may not properly deal with collations other than the default (standard M) collation.

Action: No action is required if collation is not an issue. If collation is an issue, the source of the EXTRACT should be upgraded and the MUPIP EXTRACT re-run before the LOAD.

## **OMISERVHANG**

### **OMISERVHANG**, GTCM OMI server is hung

GT.CM Error: The GT.CM OMI server has gone a long time, exceeding the design expectation without acknowledged activity. At the point of this error, GT.M creates a core image of the GT.CM OMI server.

Action: Investigate the state of the server and its clients. Restart processes including the server as appropriate; refer diagnostic information to the group responsible for database integrity at your operation.

### **OPCOMMISSED**

**OPCOMMISSED**, n errors and m MBFULLs sending prior operator messages

Information: GT.M issues this message to the operator log if any operator messages prior to the immediately preceding one had not been sent due to errors from \$SNDOPR. m is the number of time a persistent MBFULL error prevented a messages from being sent and n is the number of other errors whose reports were bypassed.

Action: None.

# **OPENCONN**

**OPENCONN**, Error opening socket connection

Run Time Error: This indicates that the process of opening a socket resulted in a device error.

Action: Review the accompanying message(s) for additional information.

## **OPRCCPSTOP**

**OPRCCPSTOP**, The Cluster Control Program has been halted by an operator stop request

CCE Error: This indicates that a CCE STOP command halted access to clustered databases from this node.

Action: Contact the group responsible for databases at your site for information about when clustered operation will resume.

## **ORDER2**

ORDER2, Invalid second argument to \$ORDER. Must be -1 or 1

Run Time Error: This indicates that the second argument to a \$ORDER function was not a 1 or -1, which are the values the standard permits.

Action: Modify the argument.

## **ORLBKCMPLT**

ORLBKCMPLT, ONLINE ROLLBACK completed successfully on instance iiii corresponding to dddd

MUPIP Information: Issued by MUPIP ROLLBACK -ONLINE when it successfully completes work on database file dddd on instance iiii.

Action: None required.

# **ORLBKFRZOVER**

ORLBKFRZOVER, tttt: FREEZE on region rrrr (ddd) cleared

MUPIP Information: Issued by MUPIP ROLLBACK -ONLINE when it clears a FREEZE on region rrrr mapped to database file dddd; tttt is the time it cleared the FREEZE.

Action: None required.

MR Manual V6.2-002

# **ORLBKFRZPROG**

**ORLBKFRZPROG**, tttt: waiting for FREEZE on region rrrr (dddd) to clear

MUPIP Information: Issued by MUPIP ROLLBACK -ONLINE when it encounters a region rrrr mapped to dabase file dddd which is frozen; tttt is the time it encountered the condition.

Action: ROLLBACK waits for a period determined the the gtm db startup max wait environment variable, after which it clears the FREEZE and proceeds. The ROLLBACK is inappropriate due to the conditions that lead to the FREEZE, cancel the ROLLBACK, otherwise cancel the FREEZE or wait for ROLLBACK to clear it automatically.

# **ORLBKINPROG**

**ORLBKINPROG**, Online ROLLBACK in progress by PID pppp in region rrrr

Run Time Information: This message in the operator log indicates an online rollback has been in progress by process pppp on region rrrr for more than 30 seconds.

Action: None Required.

## **ORLBKNOSTP**

ORLBKNOSTP, ONLINE ROLLBACK proceeding with database updates. MUPIP STOP will no longer be allowed

MUPIP Information: Issued by MUPIP ROLLBACK -ONLINE when it starts processing that cannot be interrupted without jeopardizing database integrity.

Action: Wait for the ROLLBACK to complete.

### **ORLBKNOV4BLK**

ORLBKNOV4BLK, Region rrrr (dddd) has V4 format blocks. Database upgrade required. ONLINE ROLLBACK cannot continue

MUPIP Error: Issued by MUPIP ROLLBACK -ONLINE when it finds the region rrrr mapped to database file dddd contains V4 format blocks - online rollback does not support old format blocks.

Action: Upgrade the database to the current major version before attempting to use online rollback.

# **ORLBKSTART**

ORLBKSTART, ONLINE ROLLBACK started on instance iiii corresponding to dddd

MUPIP Information: Issued by MUPIP ROLLBACK -ONLINE when it starts work on database file dddd on instance iiii.

Action: None required.

## **ORLBKTERMNTD**

ORLBKTERMNTD, ONLINE ROLLBACK terminated on instance iiii corresponding to dddd with the above errors

MUPIP Error: Issued by MUPIP ROLLBACK -ONLINE when it encounters issues that prevent it from operating on database file dddd on instance iiii.

Action: Analyze and address the errors in the output preceding this message.

### **OUTOFSPACE**

OUTOFSPACE, Database file xxxx ran out of disk space. Detected by process aaaa. Exit without clearing shared memory due to the disk space constraints. Make space and then perform mupip rundown to ensure database integrity.

Run Time Fatal: This indicates that the specified database is full and cannot extend due to lack of disk space. The database could not properly run down.

Action: Examine the space management procedures and take actions to prevent any reoccurrence of this error. The database might get damaged if you do not make enough space for MUPIP RUNDOWN to succeed.

## **PADCHARINVALID**

**PADCHARINVALID**, PAD deviceparameter cannot be greater than 127.

Run Time Error: The PAD deviceparameter (valid only for Sequential Disk files) specified in the open command can be between 0 and 127 (both inclusive).

Action: Specify a value within the allowed range.

## **PARBUFSM**

PARBUFSM, Parse buffer too small

Run Time Error: This indicates that an attempt to parse a file-specification exceeded the maximum length for file-specifications.

Action: Review the file-specification for valid syntax; if it is a logical name / environment variable, confirm its definition.

# **PARFILSPC**

PARFILSPC, Parameter: xxxx file specification: yyyy

MR Manual V6.2-002 June 09, 2015, Page 219 Run Time Error: This indicates that a JOB command jobparameter xxxx specified an invalid filespecification vyvy. For file specifications of the form "SOCKET:<handle>", this message indicates that "<handle>" is not a valid socket handle in the socket pool.

Action: Review the file-specification for valid syntax based on the operating system. For sockets, verify that the socket handle is in the socket pool.

### **PARNORMAL**

#### PARNORMAL, Parse successful

Run Time Information: This indicates that the parse was completed successfully.

Action: -

# **PATCLASS**

**PATCLASS**, Illegal character class for pattern code

Compile Time Error: This indicates that a pattern match specified an invalid pattern class code.

Action: Look for a code that is not supported by the current code definitions or for a literal match that is not enclosed in quotes.

## **PATCODE**

PATCODE, Illegal syntax for pattern

Compile Time Error: This indicates that a pattern match specified an invalid syntax.

Action: Look for a missing repeat count.

# **PATLIT**

**PATLIT**, Illegal character or unbalanced quotes for pattern literal

Compile Time Error: This indicates that a pattern match included the start of a string literal that did not finish properly.

Action: Look for unbalanced quotes in the string literal.

## **PATLOAD**

**PATLOAD**, Error loading pattern file xxxx

Compile Time Error: This indicates that GT.M failed to load the pattern file.

**PATMAXLEN** Chapter 1. Error Messages

Action: Review accompanying messages for additional information about the cause of this error.

### **PATMAXLEN**

PATMAXLEN, Pattern code exceeds maximum length

Compile Time Error: This indicates that a pattern match specification required more temporary storage than is available.

Action: Modify the routine so it uses shorter pattern specifications.

## **PATNOTFOUND**

**PATNOTFOUND**, Current pattern table has no characters with pattern code xxxx

Run Time Error: This indicates that the specified pattern code does not exist in the pattern table.

Action: Update the pattern table with the code, or change the program to make sure the specified pattern code is not referenced in the table.

## **PATTABNOTEND**

PATTABNOTFND, Pattern table xxxx not found

Run Time Error: This indicates that an attempt to load a pattern table failed because it was not found in the file described by the logical name / environment variable gtm pattern file or loaded by the VIEW "PATLOAD" command.

Action: Use host shell commands to examine the file and modify either the file or the VIEW command that performs the load.

## **PATTABSYNTAX**

PATTABSYNTAX, Error in xxxx at line yyyy

Compile Time/Run Time Error: This indicates that GT.M found an error on line yyyy of the file xxxx that defines the patterns to be used by the pattern match operator.

Action: Modify the pattern match file and reload it. For more information, refer to the "Internationalization" chapter in the Programmer's Guide.

## **PATUPPERLIM**

PATUPPERLIM, Pattern code upper limit is less than lower limit

Compile Time Error: This indicates that a pattern match specified a repeat count range with an upper limit that is below the lower limit.

Action: Look for improperly ordered repeat count ranges.

## **PCONDEXPECTED**

Last used version: V4.4-000

**PCONDEXPECTED**, Post-conditional expression expected but not found

Compile Time Error: This indicates that a colon (:) appeared to start a postconditional but it was not followed by a valid postconditional expression.

Action: Look for unwanted colons or missing post-conditional expressions.

### **PEERPIDMISMATCH**

**PEERPIDMISMATCH**, Local socket peer with PID=pppp does not match specified PID=qqqq

Run Time Error: WRITE /PASS or WRITE /ACCEPT was given a process id qqqq to verify, but the connection peer process id is pppp.

Action: Make sure that only the specified process has opened the socket connection.

### **PERMGENDIAG**

PERMGENDIAG, Permissions: Proc(uid:uuuu,gid:gggg), DB File(uid:vvvv,gid:hhhh,perm:pppp), Lib File(gid:iiii,perm:qqqq), Group Mem(opener:jjjj,owner:kkkk)

Run Time Information: This shows the permissions involved in a resource creation for the process, the associated database file, the libgtmshr and the process group membership.

Action: Typically none, but if you have a permission issue use this key information for diagnosis.

# **PERMGENFAIL**

**PERMGENFAIL**, Failed to determine access permissions to use for creation of xxxx for file yyyy

Run Time/MUPIP Error: This message indicates that GT.M was unable to determine the permissions to use when creating a file or resource associated with database file yyyy. xxxx may be "ipc resources", "journal file", "backup file", or "snapshot file".

Action: Note the user and group ownership of the database file and \$gtm\_exe/libgtmshr.\*, and the user and group permissions of the GT.M process, and report them to your GT.M support channel.

### **PRCNAMLEN**

**PRCNAMLEN**, Process name xxxx length is greater than yyyy

V6.2-002 GT.M Message and Recovery Procedures Manual



Run Time Error: This indicates that a JOB command PROCESS\_NAME=xxxx jobparameter specified a value that exceeds the maximum acceptable length yyyy.

Action: Modify the process name so that it does not exceed yyyy characters.

# PREALLOCATEFAIL •

PREALLOCATEFAIL, Disk space reservation for SSSS segment has failed

MUPIP/Run Time Error: Indicates the disk space preallocation has failed due to a system call error.

Action: Please read the accompanying system message to find out why the system call error occurred and resolve that problem.

### **PREFIXBAD**

**PREFIXBAD**, xxxx must start with an alphabetic character to be a yyyy

GDE Error: This indicates that an ADD, CHANGE, DELETE, RENAME, or TEMPLATE command specified a REGION or SEGMENT name that does not begin with an alphabetical character. xxxx is the REGION or SEGMENT name. yyyy is the object-type.

Action: Look for and correct typographical errors.

## **PREMATEOF**

PREMATEOF, Premature end of file detected

MUPIP Error: LOAD detected an end-of-file when it was expecting additional records.

Action: Refer to the About this Manual section on MUPIP LOAD errors earlier in this manual.

# **PREVJNLLINKCUT**

**PREVJNLLINKCUT**, Previous journal file name link set to NULL in new journal file xxxx created for database file yyyy

Run Time/MUPIP Error: This indicates that GT.M or MUPIP has removed the link of previous journal file name and set it to NULL in the new xxxx journal files header. This could possibly be because journal state was ON for the database file yyyy and its corresponding journal file was inaccessible, this triggered MUPIP or GT.M to create new journal file xxxx clearing the previous generation journal file name(s).

Action: If the error is issued by GT.M review the accompanying message(s) in the operator log.

If a MUPIP SET -JOUNAL=ON command produces this message for the region in the operator log, it may indicate that one or more of the current generation journal files are damaged/missing and new

MR Manual V6.2-002
GT.M Message and Recovery Procedures Manual June 09, 2015, Page 223

journal files were created with no back pointers to the previous journal files. FIS recommends taking a database backup at the earliest convenience because a MUPIP RECOVER/ROLLBACK will not be able to go back past xxxx. If this message is for a specified region(s), consider switching the journal files for all regions (with REGION "\*") that the process has opened (all journaled/replicated regions in the instance if replication is in use) to ensure that the RECOVER/ROLLBACK for other regions remains unaffected.

PREVINLLINKSET

No action is required if the MUPIP BACKUP -NEWJNLFILES=NOPREVLINK issues the error.

# **PREVINLLINKSET**

**PREVINLLINKSET**, Previous generation journal file name is changed from xxxx to yyyy

MUPIP Information: This indicates that MUPIP SET -JNLFILE command has changed previous generation journal file name from xxxx to yyyy.

Action: -

# **PREVINLNOEOF**

**PREVINLNOEOF**, A previous generation journal file xxxx does not have valid EOF

MUPIP Error: This indicates that while opening the previous generation journal file xxxx MUPIP encountered the journal file in an inconsistent state; it had not been terminated properly.

Action: Report the entire incident context to your GT.M support channel.

## **PRIMARYISROOT**

**PRIMARYISROOT**, Attempted operation not valid on root primary instance xxxx

MUPIP Error: If a replication instance has local updates enabled, that is: the Source Server that created the journal pool was started with -UPDOK, issuing any Source Server command with the start, activate or deactivate qualifiers where the command explicitly specifies the propagateprimary qualifier or that qualifier is implicitly assumed by default, or, if this is a not a supplementary instance, attempting to start a Receiver Server causes MUPIP to issue this error.

Action: Do not start a Receiver Server on a root primary non-supplementary instance. Use rootprimary qualifier instead of propagateprimary in the source server command.

### **PRIMARYNOTROOT**

**PRIMARYNOTROOT**, Attempted operation not valid on non-root primary instance xxxx

MUPIP Error: If a replication instance is not a root primary (the journal pool already exists and was created by a source server command that specified propagateprimary), issuing a source server command with the start or deactivate qualifiers that has the rootprimary qualifier explicitly specified

V6.2-002 GT.M Message and Recovery Procedures Manual (or implicitly assumed) on this instance will cause this error to be issued. This error can also be issued by the receiver server or mupip rollback if the instance that the source server is running on is not a root primary and it connects to a receiver server or a mupip journal -rollback -fetchresync running on an instance that was formerly a root primary and has not yet had a mupip replic -source -losttncomplete command run either explicitly or implicitly on it.

Action: Use propagate primary qualifier instead of rootprimary in the source server command. If this error is issued by the receiver server or fetchresync rollback, the secondary instance has to be brought up as the secondary of a root primary since it was a root primary immediately before this. The rule is that any instance that was previously a root primary should be brought up as a secondary of the new root primary. This will create a lost transaction file that needs to be applied on the new root primary. Once that is done, a mupip replic -source -losttncomplete command should be run either explicitly or implicitly on this instance before trying to bring this up as a secondary of a propagating primary.

### **PROCTERM**

PROCTERM, uuuu process termination due to cccc from eeee

Utility Warning: A utility uuuu, typically MUPIP, executing application code, possibly from a trigger, encountered a command cccc to terminate at \$zposition location pppp.

Action: It is not typically wholesome for MUPIP to terminate this way - review your error handling and trigger definitions for a possible bug or misfeature.

### **PROTNOTSUP**

**PROTNOTSUP**, Protocol xxxx not supported

Run Time Error: This indicates that the protocol specified on the CONNECT or LISTEN deviceparameters is not currently supported.

Action: Use TCP/IP domain sockets by specifying TCP for the protocol string or LOCAL (aka UNIX) domain sockets by specifying LOCAL.

### **QUALBAD**

**OUALBAD**, xxxx is not a valid qualifier

GDE Error: This indicates that GDE encountered a command with an invalid qualifier xxxx.

Action: Look for and correct typographical errors in the qualifier.

## **OUALDUP**

**QUALDUP**, xxxx qualifier appears more than once in the list

GDE Error: This indicates that GDE encountered the qualifier xxxx more than once in the command.

V6.2-002 MR Manual June 09, 2015, Page 225 Chapter 1. Error Messages **QUALEXP** 

Action: Specify the qualifier only once in the list.

# **QUALEXP**

QUALEXP, Qualifier expected but not found

Run Time Error: This indicates that a \$ZROUTINES function did not encounter a qualifier, which is the next valid syntax element.

Action: In OpenVMS, look for a missing / (slash) preceding SRC or NOSRC. In UNIX, look for a missing right parenthesis or extra left parenthesis in a source directory specification.

# **QUALREQD**

**QUALREQD**, xxxx required

GDE Error: This indicates that a command was missing the required xxxx qualifier.

Action: Enter the missing qualifier.

# **QUALVAL**

QUALVAL, Qualifier value required but not found

Run Time Error: This indicates that a \$ZROUTINES function did not specify a value for the SRC qualifier.

Action: The SRC qualifier requires a value.

### **QUITALSINV**

**QUITALSINV**, QUIT \* return when the extrinsic was not invoked with SET \*

Run Time Error: A [sub-]routine tried to pass an alias back to the caller, but the routine was not invoked to accept an alias return.

Action: Rework either the invocation or the return, or troubleshoot why the inappropriate invocation occurred. If the routine should conditionally return an alias, use \$QUIT to select the proper type of return.

## **QUITARGLST**

**QUITARGLST**, Quit cannot take a list of arguments

Compile Time Error: This indicates that a QUIT specified multiple arguments; M accepts only one argument.

V6.2-002 GT.M Message and Recovery Procedures Manual **QUITARGREQD** Chapter 1. Error Messages

Action: Look for a missing space after the QUIT or a typographical error. Modify the QUIT argument so that it consists of a single expression.

# **QUITARGREQD**

**QUITARGREOD**, Quit from an extrinsic must have an argument

Run Time Error: This indicates that a QUIT did not specify an argument but it corresponded to an invocation by an extrinsic function or special variable.

Action: Review the interface between the extrinsic and the invoked routine. Modify the QUIT or the invocation.

# **QUITARGUSE**

**QUITARGUSE**, Quit cannot take an argument in this context

Compile Time Error: This indicates that a QUIT in the scope of a FOR command specified an argument.

Action: Look for a missing space after the QUIT.

# RANDARGNEG

RANDARGNEG, Random number generator argument must be greater than or equal to one

Run Time Error: This indicates that a \$RANDOM function specified a zero or a negative argument.

Action: Look for the source of the argument. If you want to generate a 0 or 1 result, the argument should be 2 because a seed of 1 always produces the less-than-random result of 0.

### RBWRNNOTCHG

RBWRNNOTCHG, Not all specified databases were changed

MUPIP Warning: This indicates that the MUPIP SET command did not include a value for the RESERVED BYTES qualifier, or, the value specified was out of permissible range. Therefore, it did not modify the specified database.

Action: Verify the RESERVED BYTES qualifier specification.

### **RCVR2MANY**

Last used version: V5.5-000

RCVR2MANY, The instance already has the maximum supportable number of receiver servers nnnn active

V6.2-002 MR Manual June 09, 2015, Page 227 MUPIP Error: Issued by a Receiver Server on a Supplementary Instance (started with -UPDOK) which found it exceeds nnnn, the currently permitted number of Receiver Servers.

Action: Reconfigure the instances to a supported configuration.

#### RCVRMANYSTRMS

**RCVRMANYSTRMS**, Receiver server now connecting to source stream NNNN but had previously connected to a different stream nnnn

Receiver Server log/MUPIP Error: Issued by a Receiver Server on a Supplementary Instance (started with -UPDOK) which had formerly connected to a source server corresponding to non-Supplementary stream nnnn, later disconnected and on reconnection found the Source Server corresponds to a different non-Supplementary stream NNNN.

Action: Mixing of non-Supplementary streams are not allowed in the same Receiver Server process. Restart the Receiver Server.

# **RDFLTOOLONG**

RDFLTOOLONG, Length specified for fixed length read exceeds the maximum string size

Run Time Error: The size specified in the fixed length READ is too large. It should not exceed 1048576, which is the maximum string size supported by GT.M.

Action: Modify the READ to specify a length less than or equal to 1048576.

## **RDFLTOOSHORT**

RDFLTOOSHORT, Length specified for fixed length read less than or equal to zero

Run Time Error: This indicates that a READ fixed length (#) specified a value of less than one.

Action: Change the length (i.e., the portion of the READ argument that appears after the delimiter (#)) to a valid value, or add a postconditional to the READ command to suppress the length when it is less than or equal to zero.

## **REC2BIG**

**REC2BIG**, Record size (xxxx) is greater than maximum (yyyy) for region: zzzz

Run Time Error: This indicates that a SET attempted to create a database node with a combined length of keys and data (xxxx) that exceeds the maximum length yyyy permitted for region zzzz.

Action: Use smaller data records or keys in the program. If you want to enlarge the record size for the region, use GDE to change the Global Directory and recreate the database with MUPIP CREATE. If it is necessary to permit the data without allowing time to rebuild the database, use DSE CHANGE with the

V6.2-002 GT.M Message and Recovery Procedures Manual FILEHEADER and RECORD-MAX-SIZE qualifiers. Be careful when you increase the size for existing databases; use GDE to ensure that they have proper characteristics the next time they are CREATEd.

### **RECCNT**

**RECCNT.** Last LOAD record number: xxxx

MUPIP Information: EXTRACT and LOAD use this message to display xxxx, the total number of records processed.

Action: -

## RECLOAD A

RECLOAD, Error loading record number: nnnn

MUPIP Error: This message identifies a record that MUPIP could not LOAD and follows a message about the cause. If this message is Fatal, which it can be for BIN format, it produces a core file for diagnostic analysis.

Action: Address the cause or, for GO and ZWR format input files, examine the record with a text editor for possible correction or alternate action and for BIN format if fixing the cause does not resolve the error switch to ZWR format EXTRACT.

# RECNOCREJNL

Last used version: V4.3-001F

**RECNOCREJNL**, Recover could not create new journal file xxxx.

Run Time Error: This message is generated when recover/rollback fails to create the temporary forw phase journal file. The database is restored to a consistent state with some earlier time, but recovery to the specific time could not be performed.

Action: Review the accompanying messages for additional information. Refer to the *Maintaining* Database Integrity chapter in the Administration and Operations Guide.

#### RECORDSTAT

RECORDSTAT, gggg: Key cnt: kkkk max subsc len: ssss max rec len: dddd max node len: rrrr

MUPIP Information: LOAD and EXTRACT use this to report on some characteristics of the global variables they processed, where gggg is an unsubscripted global name (region name appears in parentheses if gggg spans multiple regions), kkkk is the number of unique data cells in the array, ssss is the maximum subscripted key length, dddd is the maximum data length and rrrr is the maximum combined length of keys and subscripts.

Action: Actions: Use the information as appropriate.

## RECSIZENOTEVEN

**RECSIZENOTEVEN**, RECORDSIZE [xxxx] needs to be a multiple of 2 if ICHSET or OCHSET is UTF-16, UTF-16LE or UTF-16BE

Run Time Error: This error is issued when the OPEN command specifies an ICHSET or OCHSET or CHSET of UTF-16 or UTF-16E and the RECORDSIZE specified (xxxx) is not a multiple of 2.

Action: Specify a RECORDSIZE that is a multiple of 2.

## **RECSIZIS**

**RECSIZIS**, Record size is xxxx

GDE Information: This message displays the record size of the REGION with which you are working.

Action: Review the accompanying message(s) for additional information.

# **RECTOOBIG**

**RECTOOBIG**, Block size xxxx and yyyy reserved bytes limit record size to zzzz

GDE Warning: This indicates that an ADD, CHANGE, or TEMPLATE command specified a value for the qualifier RECORDSIZE that is incompatible with the value of xxxx specified for BLOCKSIZE. zzzz is the maximum RECORDSIZE supported by this BLOCKSIZE, and yyyy RESERVED\_BYTES for the block. GDE displays this message with other error messages, including one that reports the specified record size.

Action: Modify the RECORDSIZE, BLOCKSIZE and/or RESERVED BYTES, so they are compatible.

## **RECVPOOLSETUP**

**RECVPOOLSETUP**, Receive Pool setup error

Run Time Error: This indicates that an error occurred in the replication subsystem while initializing the receive pool.

Action: Verify that the receiver server has been configured correctly. See accompanying messages for more information about the cause of this error.

# **REGIS**

**REGIS**, in region xxxx

FIS V6.2-002

REGNTFND Chapter 1. Error Messages

GDE Information: This message displays the name of the REGION with which you are working.

Action: Review the accompanying message(s) for additional information.

#### **REGNTFND**

**REGNTFND**, Region referenced not initialized

GT.CM Error: This indicates that there has been a region management error. The region may not be present, or there may have been an error during initialization.

Action: Record any accompanying messages and if necessary report the entire incident context to your GT.M support channel.

#### REGOPENFAIL

**REGOPENFAIL**, Failed to open region rrrr (dddd) due to conflicting database shutdown activity

DSE/LKE Error: Another process or processes repeatedly removed shared memory right after each one of the interlocking bypass. As a result of this, LKE/DSE failed to initialize region rrrr (database for dddd)

Action: Identify the process or processes that causes LKE/DSE to bypass interlocking mechanism by holding semaphore(s). To do that, follow RESRCINTRLCKBYPAS messages. They should tell you the PID of the process currently holding the semaphore. Check that process to see if it is stuck. If it is not stuck or has already terminated, it is likely that the database is being closed and opened abnormally fast. You may try running LKE/DSE again to achieve successful initialization.

## REGOPENRETRY

**REGOPENRETRY**, Attempt to open region rrrr (dddd) using startup shortcut failed due to conflicting database shutdown. Retrying...

DSE/LKE Information: Another process removed shared memory right after the interlocking bypass, so LKE/DSE could not attach to the shared memory of region rrrr (database dddd). LKE/DSE is repeating database initialization for database file dddd.

Action: None necessary.

#### REGSSFAIL

**REGSSFAIL**, Process pppp encountered error contributing to the snapshot for region rrrr - the snapshot is no longer valid.

MUPIP Error: A GT.M process encountered failure while opening snapshot file or attaching to shared memory or writing a block to the snapshot file, any of which invalidate the snapshot file. The original error should be in the operator log.

V6.2-002 MR Manual

Action: Examine the operator log for messages issued by process pppp to obtain details of the failure and take action, possibly by modifying file access characteristics or user roles, to address the problem.

#### RELINKCTLERR

**RELINKCTLERR**, Error with relink control structure for \$ZROUTINES directory dddd

Run Time Error: Indicates a problem accessing a relink control file in the temporary directory typically specified by the gtm linktmpdir environment variable.

Action: Use the accompanying message(s) for a detailed error status to diagnose and address the access issue.

#### RELINKCTLFULL

**RELINKCTLFULL**, Relinkctl file for directory dddd is full (maximum entries mmmm)

Run Time Error: A process using directory dddd for initiated an auto-relink action with ZLINK or ZRUPDATE, or an autolink check with DO, GOTO, ZBREAK, ZGOTO, ZPRINT or \$TEXT() which required adding information for the routine in question to the relinketl file for directory dddd, but that relinkctl file was full with mmmm entries.

Action: Shut down all processes accessing the relinkctl file and issue MUPIP RUNDOWN -RELINKCTL dddd to cleanup the relinkctl file of potentially unused entries. Additionally, reduce the number of objects in the directory, typically by adding an additional object directory.

#### REMOTEDBNOSPGBL

**REMOTEDBNOSPGBL**, Database region rrrr contains portion of a spanning global and so cannot point to a remote file

Run Time Error: This indicates that region rrrr of the current global directory contains parts of a spanning global and therefore cannot point to a remote database file.

Action: Fix the global directory file so region rrrr points to a local file or remove the global nodes that span into this region.

## REMOTEDBNOTRIG

**REMOTEDBNOTRIG**, Trigger operations on global gggg not supported as it maps to database region rrrr that points to a remote file

MUPIP/Run Time Error: \$ZTRIGGER() or MUPIP TRIGGER attempted to add, delete or modify a trigger in global gggg mapped to database region rrrr, which is defined as a GT.CM remote region, but GT.CM does not support trigger update actions.

Action: If you have a need for triggers on that globals in that region, log on to the remote instance in order to perform trigger maintenance.

### RENAMEFAIL

**RENAMEFAIL**, Rename of file xxxx to yyyy failed

MUPIP Warning: This indicates that MUPIP failed in its attempt to rename the existing file xxxx to yyyy, before creating the new xxxx file.

Action: Check the accompanying message(s) for additional information.

### REORGCTRLY

**REORGCTRLY**, User interrupt encountered during database reorg -- halting

MUPIP Information: This indicates that a REORG was interrupted. The reorganization is incomplete but the database is intact with no loss of data.

Action: Initiate REORG with RESUME qualifier, if appropriate.

## **REORGINC**

**REORGINC**, Reorg was incomplete. Not all globals were reorged.

MUPIP Warning: This indicates that MUPIP did not reorg all the globals because of some resource constraint errors.

Action: Review the accompanying message(s) for more information.

## **REPL2OLD**

**REPL2OLD**, Instance IIII uses a GT.M version that does not support connection with the current version on iiii.

MUPIP Error: Issued by a Source Server, Receiver Server or MUPIP JOURNAL -ROLLBACK -FETCHRESYNC on Instance iiii attempted to connect to instance IIII, but found IIII is running an earlier version that does not support the current replication protocol. This can indicate either that the older version is just too old for any connection with the newer version (in case the older version is less than V5.1-000) or that the older version doesn't have the logic required to support a Supplementary Instance (in case the older version is less than V5.5-000). Note that IIII may not be available if the older instance uses a version of GT.M less than V5.1-000.

Action: Upgrade the GT.M version on IIII to a version that can support communication with the current version or, if this is a Supplementary Instance, that can deal with a Supplementary Instance or choose another appropriate instance for the connection.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 233

## **REPLACCSEM**

**REPLACCSEM**, Error with replication access semaphore (id = xxxx) for instance file aaaa

MUPIP Error: This indicates problem with the semaphore xxxx associated with the instance designated by aaaa.

Action: Review the accompanying message(s) for details.

#### REPLBRKNTRANS

**REPLBRKNTRANS**, Replication subsystem found transaction xxxx broken or missing in the journal files

MUPIP Error: This indicates that while attempting to read the transaction with journal sequence number xxxx from journal files, the source server could not find all (or any) journal records belonging to that transaction.

Action: Restore the journal generation links, and/or the journal files. Deactivate and activate the source server (or shutdown and restart the source server). If the journal files that are needed are no longer available, follow the procedure Restoring secondary from backup of Primary detailed in the Replication chapter of Administration and Operations Guide.

#### **REPLCOMM**

**REPLCOMM**, Replication subsystem communication failure

MUPIP Error: This is a generic error indicating that there has been a communication error between the two systems performing replication.

Action: Review the accompanying message(s) for more information about the cause of this error.

#### **REPLERR**

#### REPLERR, XXXX

MUPIP Warning: This indicates that GT.M is performing tasks that may result in an error.

Action: Review accompanying messages for more information about why GT.M generated this message.

## REPLEXITERR

**REPLEXITERR**, Replication process encountered an error while exiting

Run Time Error: This indicates that the source, receiver or update process encountered an error during exit processing.

Action: Review accompanying message(s) for more information.

## **REPLFILIOERR**

**REPLFILIOERR**, Replication subsystem file I/O error xxxx

MUPIP Error: This indicates that the system was unable to perform an I/O operation on a file on the replication primary server. The accompanying message also tells whether there was a read error or a write error and names the file on which the error occurred.

Action: Review the accompanying message(s) for more information about the cause of this error.

## REPLFILTER

**REPLFILTER**, Replication filter subsystem failure

MUPIP Error: This indicates that the replication filter subsystem failed to start the application filter.

Action: In order to restart the filter subsystem, it is necessary to shut down the replication server and restart. If this error continues to appear, report the entire incident context to your GT.M support channel.

## **REPLFTOKSEM**

**REPLFTOKSEM**, Error with replication semaphores for instance file xxxx

MUPIP Error: This indicates that MUPIP could not create semaphore for replication instance file.

Action: Review the accompanying message(s) for more information.

#### REPLGBL2LONG

**REPLGBL2LONG**, Global names longer than 8 characters cannot be handled at the secondary

Source Server log Error: A journal record contains a global variable name longer than 8 characters and the version running at the secondary does not support global variables longer than 8 characters.

Action: Upgrade the secondary to V5.0-FT01 or later. If upgrade is not possible, avoid replicating regions that contain globals longer than 8 characters.

#### **REPLINFO**

REPLINFO, xxxx

Run Time Information: The information is contained in the message.

Action: -

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual

#### REPLINSTACC

REPLINSTACC, Error accessing replication instance file xxxx

Run Time/MUPIP Error: This indicates that some internal GT.M errors were encountered while accessing the specified replication instance file defined by \$gtm\_repl\_instance.

Action: Refer to the accompanying message(s) for additional information.

## **REPLINSTCLOSE**

**REPLINSTCLOSE**, Error closing replication instance file xxxx

Run Time Error: There was an error when GT.M or MUPIP tried to close the replication instance file. The error detail accompanies this message.

Action: Look at the accompanying error detail. Possible causes are file permissions, system quotas, etc. Fix the cause if possible. If not, report the entire incident context to your GT.M support channel for further analysis.

#### REPLINSTCREATE

**REPLINSTCREATE**, Error creating replication instance file xxxx

Run Time Error: There was an error when GT.M or MUPIP tried to create the replication instance file. The error detail accompanies this message.

Action: Look at the accompanying message that gives error details. Possible causes are file permissions, system quotas, and so on. If possible, correct the cause and retry creating the replication instance file. If the error persists, report to your GT.M support channel along with the error details.

#### REPLINSTDBMATCH

**REPLINSTDBMATCH**, Replication instance file xxxx has seqno xxxx while database has a different seqno yyyy

MUPIP Error: This error is issued by the first source server that is started on a replication instance or a mupip journal -rollback command if the journal sequence numbers stored in the instance file does not match that stored in the database file header. This is possible if the database was recreated or refreshed from a backup on another instance without correspondingly recreating the instance file.

Action: If this instance is not the root primary, this error can be handled by restoring both the database and the instance file from a previous backup (consistent backup of the instance file AND database files taken together at the same time) and restarting the instance. Subsequent to such a restore, all transactions since the last backup will be sent across from this instance's primary. Alternatively, this can be handled by shipping a copy of the database from any other instance (either the primary or any

other secondary/tertiary), recreating the instance file and starting this instance as a secondary with the -updateresync qualifier. In either case, this procedure has to be repeated on all tertiary instances etc. that descend from this instance ensuring that for every primary-secondary instance pair, the secondary is not ahead of the primary in terms of journal sequence number. If this instance is the root primary, restoring from a prior backup may not be viable as it may mean loss of transactions that occurred after the backup. The alternative way to handle this error is to recreate the instance file on the root primary, ship a copy of the database from the primary and recreate instance files on ALL secondaries (tertiaries etc.) and restart the secondaries with the -updateresync qualifier. In addition, report the entire incident context to your GT.M support channel.

#### REPLINSTDBSTRM

REPLINSTDBSTRM, Replication instance file rrrr has seqno xxxx for Stream nnnn while database has a different segno XXXX

MUPIP Error: Issued by the first source server started on a supplementary instance if the journal stream sequence numbers (for any non-supplementary stream from 0 through 15) stored in the instance file do not match those stored in the database file headers. This is possible if a database was recreated or refreshed from a backup on another instance without correspondingly recreating the instance file.

Action: If the database file is known to be accurate, recreate the instance file. If not, reinitialize this instance from a backup of some other instance in the same LMS Group (see Action section of REPLINSTDBMATCH error for more details on this).

#### REPLINSTEMT

**REPLINSTFMT**, Format error encountered while reading replication instance file xxxx. Expected yyyy. Found zzzz.

Run Time/MUPIP Error: This error is issued by GT.M or MUPIP whenever it tries to open the replication instance file and finds that it was created with a format that the current version of GT.M cannot interpret. GT.M also produces this error when it encounters:

- 1. an instance file created on a different endian system or
- 2. an instance file created by a 32-bit (or 64-bit) version of GT.M that is different from the current 64bit (or 32-bit) version of GT.M.

Action: Recreate the instance file using the mupip replic -instance create command with the current version of GT.M.



The REPLINSTCORRV message that was displayed in V5.0-000 has now been replaced by REPLINSTFMT

Action: If the error is issued by GT.M review the accompanying message(s) in the operator log.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 237 If a MUPIP SET -JOUNAL=ON command produces this message for the region in the operator log, it may indicate that one or more of the current generation journal files are damaged/missing and new journal files were created with no back pointers to the previous journal files. FIS recommends taking a database backup at the earliest convenience because a MUPIP RECOVER/ROLLBACK will not be able to go back past xxxx. If this message is for a specified region(s), consider switching the journal files for all regions (with REGION "\*") that the process has opened (all journaled/replicated regions in the instance if replication is in use) to ensure that the RECOVER/ROLLBACK for other regions remains unaffected.

No action is required if the MUPIP BACKUP -NEWJNLFILES=NOPREVLINK issues the error.

## REPLINSTFREEZECOMMENT

#### REPLINSTFREEZECOMMENT. Freeze Comment: xxxx

Run Time Information: This message contains details about a freeze on a replication instance. The instance information is included in an associated REPLINSTFROZEN message. In the case of an automatic freeze, xxxx identifies an error that triggered the freeze. In the case of an administrative freeze, xxxx contains the text provided by MUPIP REPLICATE -SOURCE -FREEZE=ON -COMMENT="xxxx".

Action: Refer to REPLINSTFROZEN.

## **REPLINSTFROZEN**

#### REPLINSTFROZEN, Instance xxxx is now Frozen

Run Time Error: This indicates that the replication instance xxxx is frozen due to a custom error or an out-of-space condition on a region with INST\_FREEZE\_ON\_ERROR set, or by an administrator with the MUPIP REPLICATE -SOURCE -FREEZE=ON command. Updates to database files or shared memory for regions in the instance are blocked.

Action: Check the associated REPLINSTFREEZECOMMENT message for details on the cause of the freeze. For out-of-space conditions, make sufficient disk space available to remove the freeze. For custom errors or for administrative freezes, MUPIP REPLICATE -SOURCE -FREEZE=OFF or a system restart removes the freeze.

#### REPLINSTMISMTCH

**REPLINSTMISMTCH**, Process has replication instance file ffff (jnlpool shmid = ssss) open but database dddd is bound to instance file gggg (jnlpool shmid =tttt)

Run Time Error: The process attempted an update on the replicated database dddd associated with the replication instance file ffff and journal pool shared memory id ssss; however, the process has a different replication instance file gggg or journal pool shmid tttt open (On OpenVMS, replication instance file corresponds to active global directory).

FIS V6.2-002

Action: A replicated database can only accept updated by processes that have the same replication instance file (defined by the environment variable gtm repl instance) open. Ensure the environment variable gtm repl instance is defined to be the same for all processes that update the same replicated database file. This error can also occur if the replication instance file was recreated (while processes were still accessing the replication instance). In this case, the name ffff and gggg would be the same but the corresponding journal pool shared memory ids would be different. To recover from this situation, shut down all processes accessing the instance from before and after the instance file recreate. Run an argumentless MUPIP RUNDOWN to clean up the older journal pool tttt and restart the instance. The following applies to OpenVMS only: Verify this database file is in the global directory used by the Source Server and restart the instance. The Source Server (which is the first process to start on a replicated instance) only binds replicated databases from its global directory to the journal pool that it creates. No other replicated database file can be bound with this journal pool.

## **REPLINSTNMLEN**

**REPLINSTNMLEN**, Replication instance name xxxx should be 1 to 15 characters long

MUPIP Error: This error is issued by the mupip replic instance create command if the instance name was specified either through the name qualifier or through the environment variable gtm repl instname and if name was longer than 15 characters or was the empty string.

Action: Specify a valid instance name that is 1 to 15 characters long.

## **REPLINSTNMSAME**

**REPLINSTNMSAME**, Primary and Secondary instances have the same replication instance name xxxx

MUPIP Error: This error is issued by any source server command where the -instsecondary qualifier specifies a secondary instance name that matches the name of the primary instance the command is started from.

Action: Two instances should never have the same name. Recreate the instance file on the secondary with a different name and restart the receiver server with the updateresync qualifier.

## **REPLINSTNMUNDEF**

REPLINSTNMUNDEF, Replication instance name not defined

MUPIP Error: This error is issued by the mupip replic -instance create command if the -name qualifier was not specified and if the environment variable gtm repl instname is not defined either.

Action: Specify the instance name using the -name qualifier.

#### REPLINSTNOHIST

REPLINSTNOHIST, REPLINSTNOHIST History record for xxxx not found in replication instance file уууу

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 239 MUPIP Error: The source server or receiver server issue this message as an error while mupip rollback issues this message as a warning when they scan the replication instance file looking for a history record corresponding to a journal sequence number that is lesser than the earliest sequence number or greater than the latest sequence number stored in the instance file. This means that the replication instance files on the primary and secondary have differing level of history detail (possible if the instance file was later recreated in one instance) and that it is no longer possible to determine the sync point (resync segno) between the two instances.

Action: If mupip rollback issues this error, it truncates the replication instance file history. This means that if this instance is a secondary, it should be brought up with the -updateresync qualifier. If the source or receiver server issue this error, this error needs to be handled by ensuring the primary and secondary databases are in sync (by shipping a copy of the database from the primary to the secondary if not already done), recreating the instance file on the secondary (if not already done) and start the receiver server on the secondary with the -updateresync qualifier.

## **REPLINSTNOSHM**

**REPLINSTNOSHM**, Database dddd has no active connection to a replication journal pool

Run Time Error: The Source server was started with a repication instance that had this database file listed but later the source server and this particular database file were shut down while other database files in this instance file were still active.

Action: Restart the source server.

## **REPLINSTOPEN**

**REPLINSTOPEN**, Error opening replication instance file xxxx

Run Time Error: There was an error when GT.M or MUPIP tried to open the replication instance file. The error detail accompanies this message.

Action: Look at the accompanying error detail. Possible causes are file permissions, system quotas, and so on. Fix the cause if possible. If not, report the entire incident context to your GT.M support channel for further analysis.

### **REPLINSTREAD**

**REPLINSTREAD**, Error reading xxxx bytes at offset yyyy from replication instance file ffff

Run Time Error: There was an error when GT.M or MUPIP tried to read from the replication instance file. The error detail accompanies this message.

Action: Look at the accompanying error detail. Possible causes are file permissions, system quotas, etc. Fix the cause if possible. If not, report the entire incident context to your GT.M support channel for further analysis.

## **REPLINSTSECLEN**

REPLINSTSECLEN, REPLINSTSECLEN Secondary replication instance name xxxx should be 1 to 15 characters long

MUPIP Error: This error is issued by any mupip replic -source command that specifies a secondary instance name. This error is issued if the secondary instance name was specified either through the instsecondary qualifier or through the environment variable gtm repl instsecondary and if the name was longer than 15 characters or was the empty string.

Action: Specify a valid secondary instance name that is 1 to 15 characters long.

## REPLINSTSECMTCH

**REPLINSTSECMTCH**, REPLINSTSECMTCH Secondary replication instance name xxxx sent by receiver does not match vyvy specified at source server startup

Source Server log/MUPIP Error: This error is issued by a source server that connects to a receiver server on the secondary and finds that the secondary instance name sent by the receiver does not match the secondary instance name specified (INSTSECONDARY qualifier) when the source server was started. The source server terminates after issuing this error.

Action: Restart the source server with the correct -instsecondary qualifier value. Also make sure the instance name in the -instsecondary qualifier and the host/port information in the secondary qualifier of the source server startup command correspond to each other.

#### REPLINSTSECNONE

**REPLINSTSECNONE**, No information found for secondary instance xxxx in instance file yyyy

MUPIP Error: This error is issued by any mupip replic source command that specifies a replicating (secondary) instance name (except for the one which specifies -start) if no information on this name can be found in the instance file. This is possible if no Source Server was ever started since the initialization of this instance file for such a replicating instance.

Action: Make sure the replicating instance name is correct. If it is, make sure a Source Server for that replicating instance has been started at least once in the life of the instance file even if it is currently not up and running.

## REPLINSTSECUNDF

**REPLINSTSECUNDF**, REPLINSTSECUNDF Secondary replication instance name not defined

MUPIP Error: This error is issued by any mupip replic -source command that requires a secondary instance name to be specified. The source server commands that require this qualifier are those that have any of -activate, changelog, deactivate, needrestart, start, statslog or stopsourcefilter specified.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 241 The secondary name can be specified either through the INSTSECONDARY qualifier or through the environment variable gtm repl instsecondary. If neither of them is specified, this error is issued.

Action: Specify the secondary instance name using the INSTSECONDARY qualifier.

## **REPLINSTSEQORD**

**REPLINSTSEQORD**, REPLINSTSEQORD ssss has seqno xxxx which is less than last record seqno yyyy in replication instance file zzzz

MUPIP Error: This error is issued in one of two scenarios. The instance file consists of a sequence of history records that should correspond to an increasing range of sequence numbers. They need to hence have their starting sequence number in increasing order. If an attempt is made to append a history record with a starting sequence number that is lesser than the last history record currently existing in the instance file, the source or receiver server issues this error. In this case ssss would be the string New history record. This error is also issued if at journal pool creation time, the source server notices that the instance file header has a value of the current sequo that is lesser than the starting segno of the last history record in the instance file. In this case ssss would be the string Instance file header.

Action: If this instance is not the root primary, this error can be handled by restoring both the database and the instance file from a previous backup (consistent backup of the instance file AND database files taken together at the same time) and restarting the instance. Subsequent to such a restore, all transactions since the last backup will be sent across from this instance's primary. Alternatively, this can be handled by shipping a copy of the database from any other instance (either the primary or any other secondary/tertiary), recreating the instance file and starting this instance as a secondary with the UPDATERESYNC qualifier. In either case, this procedure has to be repeated on all tertiary instances etc. that descend from this instance ensuring that for every primary-secondary instance pair, the secondary is not ahead of the primary in terms of journal seqno. If this instance is the root primary, restoring from a prior backup may not be viable as it may mean loss of transactions that occurred after the backup. The alternative way to handle this error is to recreate the instance file on the root primary, ship a copy of the database from the primary and recreate instance files on ALL secondaries (tertiaries etc.) and restart the secondaries with the UPDATERESYNC qualifier. In addition, report the entire incident to your GT.M support channel.

#### **REPLINSTSTNDALN**

REPLINSTSTNDALN, REPLINSTSTNDALN Could not get exclusive access to replication instance file XXXX

MUPIP Error: This error is issued by MUPIP REPLIC INSTANCE CREATE if it finds that the replication instance file it is attempting to create already exists and is being used (the journal pool for that instance exists) by GTM and/or MUPIP process(es).

Action: Shutdown all GTM and/or MUPIP processes that are using the replication instance file and reissue the command. If it fails even though you know for sure there is no other GT.M or MUPIP process accessing the replication instance file, delete the instance file and reissue the command.

V6.2-002 GT.M Message and Recovery Procedures Manual

#### REPLINSTUNDEF

**REPLINSTUNDEF**, Replication instance environment variable \$gtm repl instance is undefined

Run Time/MUPIP Error: This indicates that the replication instance environment variable \$gtm repl instance is undefined.

Action: Define the environment variable to the appropriate instance file.

## **REPLINSTUNFROZEN**

**REPLINSTUNFROZEN.** Instance xxxx is now Unfrozen

Run Time Information: This indicates that a replication instance which had previously been frozen is no longer frozen and updates to regions in the instance will resume.

Action: None required.

## **REPLINSTWRITE**

REPLINSTWRITE, REPLINSTWRITE Error writing xxxx bytes at offset yyyy from replication instance file ffff

Run Time Error: There was an error when GT.M or MUPIP tried to write to the replication instance file. The error detail accompanies this message.

Action: Look at the accompanying error detail. Possible causes are file permissions, system quotas, etc. Fix the cause if possible. If not, report the entire incident context to your GT.M support channel.

# **REPLINLCLOSED**

**REPLINLCLOSED**, Replication in jeopardy as journaling for database file ddd. Current region segno is xxx[XXX] and system segno is yyy[YYY]

Run Time Warning: This message indicates that GT.M turned OFF journaling and switched replication from ON to WAS ON on the specified database. Other preceding messages identify the cause (for example, lack of disk space while writing to journal file, permissions issue while auto-switching to new journal files, and so on). The message also displays the region and journal sequence numbers. From this point, replicating updates on the primary to the secondary might or might not work depending on the backlog on the primary until replication/journaling gets turned back ON.

Action: First, correct the cause (lack of disk space, permission issues, and so on) that turned journaling OFF.

Execute the MUPIP SET REPLICATION=ON or MUPIP BACKUP REPLICATION=ON command to turn replication (and journaling) ON and switch to a new set of journal files. This command can work while

processes are concurrently updating the database and causes GTM to journal subsequent updates in both the journal file and journal pool (rather than only in the journal pool as it does when replication is in the WAS ON state).

Execute the MUPIP REPLIC -SOURCE -SHOWBACKLOG command. Note down the value of "sequence number of last transaction written to journal pool".

Execute the above command at regular intervals and note down the value of "sequence number of last transaction sent by source server."

If the "sequence number of last transaction sent by source server" is greater than "sequence number of last transaction written to journal pool", it means that the source server successfully sent all journal records during the time interval when journaling was turned OFF. In this case, no further action is required.

On the other hand, if the "sequence number of last transaction sent by source server" is less than "sequence number of last transaction written to journal pool" and reports the same value across repeated SHOWBACKLOG commands, then check the source server log file for any error messages most likely a NOPREVLINK error from the source server. This means the source server could not locate the corresponding journal records required from the journal files to replicate a particular sequence number and therefore, it failed to synchronize the primary and secondary. In this case, take an online backup of the primary, restore it on the secondary and start the secondary with the UPDATERESYNC qualifier to synchronize the secondary with the primary.

# **REPLINLCNFLCT**

**REPLJNLCNFLCT**, Journaling cannot be turned nnnn on database file ffff as the replication state is rrrr and must also be turned nnnn in the same command

MUPIP Warning: This message indicates that the requested journaling state (nnnn) and current replication state (rrrr) do not match and the command must explicitly specify an outcome such that they do match.

Action: Issue one or more commands that leave journaling and replication either both ON or both OFF.

## REPLLOGOPN A

**REPLLOGOPN**, Replication subsystem could not open log file xxxx: yyyy. Logging done to zzzz

MUPIP Error: This indicates that MUPIP could not find the log file or did not have access permission to open the log file. If there is another log file available (a previously opened file), MUPIP writes to the other log file. If there is no other log file available, MUPIP sends any remaining messages to /dev/null and terminates the replication server process.

Action: Check the log file permissions, and if permissions are correct, move the log file and specify that MUPIP should log to a log file which has appropriate access permissions.

### **REPLNOBEFORE**

**REPLNOBEFORE**, NOBEFORE option cannot be used when the current replication state is ON for a database file xxxx

MUPIP Warning: This indicates that GT.M could not use NOBEFORE journal option because replication is already turned ON for the database file xxxx.

Action: Use BEFORE option for the database file xxxx. NOBEFORE image journaling is not currently supported for replication. If NOBEFORE is necessary, use -replication=OFF option.

## **REPLNOHASHTREC**

**REPLNOHASHTREC**, Sequence number NNNN contains trigger definition updates. IIII side must be at least V6.2-000 for replication to continue

Receiver Server log/Source Server log Error: \$ZTRIGGER() or MUPIP TRIGGER updated a trigger definition in a replicated region, but the replicating instance is running a version that cannot process trigger definitions from this version. Prior to V6.2-000 trigger maintenance actions replicated as data, while V6.2-000 and and later, trigger maintenance actions replicate as logical actions. V6.2-000 can reformat maintenace actions as data for older versions, but the current version cannot.

Action: Use V6.2-000 as a step on an upgrade path from earlier to later versions. Alternatively, if you need to perform trigger maintenance on replicating instances that are on either side of V6.2-000, you must perform them independently on the two systems when replication is off, recording and manipulating the sequence numbers such that you can resume replication.

## REPLNOMULTILINETRG

**REPLNOMULTILINETRG**, Sequence number ssss contains a trigger definition too large for transmission to the current replicating instance, which does not support multi-line triggers - stopping replication.

Trigger/Source Server log/MUPIP Error: The source server logs this message whenever it detects replication to a V5.4-001 or V5.4-000A instance of a transaction that involves multi-line triggers spanning across multiple blocks in the database, which is possible if the multi-line trigger definition is large enough that it does not fit in a single database block.

Action: Upgrade the replicating instance to at least V5.4-002 or eliminate any usages of large multi-line triggers spanning across database blocks from the application logic.

#### REPLNOTLS

**REPLNOTLS**, xxxx requested TLS/SSL communication but the yyyy was either not started with TLSID qualifier or does not support TLS/SSL protocol

MUPIP Error: This indicates that xxxx (Source Side or Receiver Side) requested TLS/SSL communication but the other side was not started with a TLSID qualifier or was pre-V6.1-000 version that does not support TLS/SSL protocol.

Action: If both sides are running with GT.M version >= V6.1-000, then make sure the TLSID qualifier is specified for both the Source and Receiver Server startup commands. If one of the instances involved in the replication is a pre V6.1-000 GT.M version, upgrade it to V6.1-000 to support TLS.

## **REPLNOTON**

**REPLNOTON**, Replication is not on for journal file xxxx, rollback will not continue

MUPIP Error: This indicates that ROLLBACK cannot proceed because MUPIP encountered xxxx, a journal file for which replication is not turned ON.

Action: ROLLBACK cannot be used for a journal file if it does not have replication state ON, use MUPIP JOURNAL RECOVER instead.

#### REPLNOXENDIAN

**REPLNOXENDIAN**, SSSS side is running on a GT.M version that does not support cross-endian replication. Upgrade the SSSS side to at least V5.3-003 to support cross-endian replication. Cannot continue.

MUPIP Error: The originating or the replicating instance in a cross-endian replication environment issue this error when a replication startup detects that the other side is running on a GT.M version without needed cross-endian support.

Action: Upgrade the instance for which the error was reported to a version with support for crossendian replication.

# **REPLOFFINLON**

**REPLOFFJNLON**, Replication state for database file <xxx> is OFF but journaling state is enabled.

MUPIP Error: In a replicated environment, this indicates that the database file <xxx> cannot have journaling ENABLED or ON when the replication state is OFF. This is an out of design situation due to implications on recovery as journal files can't be a mix of SET/KILL records that were created when replication was ON and those created when replication was OFF.

Action: In order to prevent this situation, enable replication state for the database file <xxx> (using MUPIP SET -REPLICATION=ON or MUPIP BACKUP -REPLICATION=ON) or disable journaling using MUPIP SET -JOURNAL=DISABLE whichever is desirable.

#### **REPLPOOLINST**

**REPLPOOLINST**, Error with replication pool xxxx for instance file yyyy

MUPIP Error: This indicates that MUPIP encountered an error for the replication shared memory of shared memory xxxx.

Action: Refer to the accompanied message(s) for detailed information.

## **REPLRECFMT**

REPLRECFMT, Replication journal record format error encountered

Source Server log/MUPIP Fatal: This indicates that a formatting error has been encountered by the replication source server for a journal record.

Action: Report the entire incident context along with any GT.M logs, dump, and/or core files created within the same timeframe to your GT.M support channel.

## REPLREQROLLBACK

REPLREQROLLBACK, Replication instance file xxxx indicates abnormal shutdown. Run MUPIP JOURNAL ROLLBACK first.

MUPIP Error: This error is issued by MUPIP REPLIC SOURCE %C3%A2%E2%82%AC%E2%80%9CSTART if it is about to create the journal pool and finds that the replication instance file header indicates the journal pool was not cleanly shutdown previously. This may cause the instance file not to correspond to the database and/or journals.

Action: Run MUPIP JOURNAL ROLLBACK to cleanup the instance file, database and journal files before starting a source server on this instance.

## REPLREQRUNDOWN

REPLREQRUNDOWN, Error accessing replication instance xxxx. Must be rundown on cluster node уууу.

Run Time/MUPIP Error: This indicates that GT.M could not open the specified replication instance file because it was not properly closed on the cluster node yyyy.

Action: Issue MUPIP RUNDOWN command on the cluster node. A GT.M process or, replication server on that node may have been terminated by a method other than MUPIP STOP. If MUPIP RUNDOWN with no parameters fails, try MUPIP RUNDOWN region \* with an appropriate global directory.

## REPLSRCEXITERR O

**REPLSRCEXITERR**, Source server for secondary instance xxxx exited abnormally. See log file yyyy for details.

Operator log Warning: This indicates the the source server for instance xxxx exited abnormally.

Action: Check the end of the log file at yyyy for additional message(s).

## **REPLSTATE**

**REPLSTATE**, Replication state for region/database file xxxx is now yyyy

MUPIP Information: This indicates that replication state for region/database file xxxx, is now yyyy.

Action: -

## **REPLSTATEERR**

**REPLSTATEERR**, Replication state cannot be changed to the specified value for database file <xxx>.

MUPIP Error: This MUPIP BACKUP error indicates that the specified change in the replication state cannot be done due to the reason described in a following GTM-E-TEXT message.

Action: If the message indicates "Standalone access required", try to enable the replication in the standalone mode using MUPIP SET REPLICATION. If the message suggests switching journal file, specify the backup qualifier NEWJNL in the command line.

## **REPLSTATEOFF**

REPLSTATEOFF, ROLLBACK cannot proceed as database xxxx does not have replication ON

MUPIP Error: This indicates that ROLLBACK command cannot proceed because the specified database xxxx does not have replication state ON. In most situations, this error occurs when the journal file storage runs out of disk space.

Action: Ensure replication is turned ON for a database, before executing the ROLLBACK command. If the database is in the WAS\_ON state, refer to the "Recovering from the WAS\_ON state" section in the Database Replication chapter of the Administration and Operations Guide. Alternatively, if REPLICATION was not used on the database, use MUPIP JOURNAL RECOVER.

#### **REPLTRANS2BIG**

REPLTRANS2BIG, Transaction xxxx of size yyyy too large to be accommodated in the zzzz pool

MUPIP Error: This indicates that the size of the incoming transaction is larger than the specified receive pool.

Action: The receiver server must be shut down and restarted with a larger receive pool size or, if possible, break the file transmission into smaller files.

## **REPLUPGRADEPRI**

Last used version: V5.4-002B

REPLUPGRADEPRI, Attempted operation requires primary instance xxxx to support multi-site replication

MUPIP Error: This error is issued if an attempt is made to start an active source server or activate a passive source server on a propagating primary instance while the receiver server on that instance is connected to a primary that has not yet been upgraded to the multi-site version of GT.M. This error is also issued when the receiver server on a propagating primary finds that the primary it connects to does not support multi-site replication and that there is at least one active source server running on the instance at that time.

Action: An active source server cannot be running on a secondary instance at the same time that the receiver server on this instance is connected to a primary that does not support multi-site functionality. Upgrade the primary instance identified in the message to the version of GT.M that supports multi-site replication functionality and then start active source servers.

## **REPLUPGRADESEC**

Last used version: V5.4-002B

**REPLUPGRADESEC**, Attempted operation requires secondary instance xxxx to support multi-site replication

MUPIP Error: This error is issued in three cases. 1) If a source server is currently connected to a dual-site secondary (i.e. a secondary running on a version of GT.M that does not support multi-site functionality), starting additional source servers will issue this error. 2) If a source server finds more than one source server (active or passive) running on the same instance at the time it connects to a dual-site secondary it will issue this error. 3) On a propagating primary instance, a source server that connects to a dual-site tertiary instance will issue a this error at connection time.

Action: Upgrade the secondary instance identified in the message to the version of GT.M that supports multi-site replication functionality and then start multiple source servers.

#### **REPLWARN**

#### REPLWARN, XXXX

MUPIP Warning: This indicates that GT.M is performing tasks that may result in an error.

Action: Review accompanying messages for more information about why GT.M generated this message. The Source Server exits with a REPLWARN message for the first five failed attempts to open journal files.

## **REPLXENDIANFAIL**

**REPLXENDIANFAIL**, SSSS side encountered error while doing endian conversion at journal sequence number IIII

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 249 MUPIP Error: The originating or the replicating instance in a cross-endian replication environment report this error whenever they detect that the endian conversion failed.

Action: Restart replication - if the transmission caused the problem, it's probably intermittent. Perform a MUPIP JOURNAL -EXTRACT -DETAIL on the journal files and search for the sequence number JJJJ to look for anything different about that journal record. If the report is on the secondary, take a fresh backup on the originating instance requesting new journal files, refresh the replicating instance and restart replication.

## **REQ2RESUME**

**REQ2RESUME**, Request to resume suspended processing received from process xxxx owned by userid уууу

Run Time Information: The information is logged to the operator facility. This indicates that a suspended process received signal SIGCONT to resume processing. This happens when a process is suspended while holding a scarse resource in order to permit other processes to access the resource. On systems that do not support advanced signal information, xxxx and yyyy both are 0 (zero).

Action: -

## **REQDVIEWPARM**

**REQDVIEWPARM**, Required View parameter is missing

Run Time Error: This indicates that the failed program attempted to use the VIEW function without specifying a keyword argument or with an invalid keyword argument.

Action: Programmer's should consult the Programmer's Guide for the correct syntax.

## **REQRECOV**

**REORECOV**, Error accessing database dddd. Must be recovered on cluster node ccccc.

Run Time Error: This indicates that GT.M could not open a previously journaled database file dddd due to a prior improper shutdown on cluster node ccccc. A GT.M process on cluster node ccccc may have failed to attach a database memory segment or it was terminated by a method other than MUPIP STOP.

Action: Perform a MUPIP JOURNAL RECOVER operation to address this issue.

## REQRLNKCTLRNDWN

**REQRLNKCTLRNDWN**, Error accessing relinkctl file for \$ZROUTINES directory dddd. Must be rundown

Run Time Error: A process initiated an auto-relink action with ZLINK or ZRUPDATE, or an auto-relink check with DO, GOTO, ZBREAK, ZGOTO, ZPRINT or \$TEXT() which required adding information for

V6.2-002 GT.M Message and Recovery Procedures Manual REQROLLBACK Chapter 1. Error Messages

the routine in question to the Relinketl file for directory dddd, but the shared memory associated with that Relinketl file had been removed, presumably by an operator using a iperm.

Action: Run MUPIP RUNDOWN -RELINKCTL dddd to clear the state of the Relinkctl file. Determine the cause for the improper close and take action to prevent additional occurrences.

## REQROLLBACK

REOROLLBACK, Error accessing database dddd. Run MUPIP JOURNAL ROLLBACK on cluster node ccccc.

Run Time Error: This indicates that GT.M could not open a previously replicated database file dddd due to a prior improper shutdown on cluster node ccccc. A GT.M process on cluster node ccccc may have failed to attach a database memory segment or it was terminated by a method other than MUPIP STOP.

Action: Perform MUPIP JOURNAL ROLLBACK to cleanup the instance file, database, and journal files before starting a source server on this instance.

## **REQRUNDOWN**

**REQRUNDOWN**, Error accessing database dddd. Must be rundown on cluster node ccccc.

Run Time Error: This indicates that GT.M could not open database file dddd due to a prior improper shutdown on cluster node ccccc. A GT.M process on cluster node ccccc may have failed to attach a database memory segment or it was terminated by a method other than MUPIP STOP.

Action: Perform MUPIP RUNDOWN from cluster node ccccc. If MUPIP RUNDOWN with no parameters does not work, specify the region name or file-specification with -REGION or -FILE, respectively.

#### RESCRCWAIT

**RESCRCWAIT**, Waiting briefly for the ssss semaphore for region rrrr (ffff) currently held by PID pppp (Sem. ID: ssss).

Run Time Information: A process started a three (3) second wait for an FTOK or access control semaphore. If process with PID pppp does not release the semaphore before the timeout expires, the waiting process bypasses acquiring the semaphore. ssss identifies the semaphore type: "FTOK" or "access control"; rrrr is the region; ffff is the file corresponding to region rrrr; pppp is the PID of the hanging process; ssss is the semaphore ID.

Action: None required.

## **RESOLVESEQNO**

**RESOLVESEQNO**, Resolving until sequence number dddd [0xxxxx]

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 251 MUPIP Information: This indicates MUPIP JOURNAL ROLLBACK expects to do backward processing until it reaches sequence number with hexadecimal value xxxx (decimal value dddd). This is usually the common sequence number agreed upon between the primary and secondary by a -FETCHRESYNC rollback or the sequence number specified in a -RESYNC rollback.

Action: No action required.

## **RESOLVESEQSTRM**

RESOLVESEQSTRM, Resolving until stream sequence number Stream nnnn: Seqno dddd xxxx

MUPIP Information: This indicates MUPIP JOURNAL ROLLBACK expects to do backward processing until it reaches the stream sequence number whose hexadecimal value is xxxx (decimal value dddd). This is usually the common stream sequence number agreed upon between the primary and secondary by a -FETCHRESYNC rollback or the stream sequence number specified in a -RESYNC rollback where -RSYNC STRM is also specified.

Action: No action required.

#### RESRCINTRLCKBYPAS A

**RESRCINTRLCKBYPAS**, xxxx with PID qqqq bypassing the ssss semaphore for region rrrr (ffff) currently held by PID pppp.

Run Time Information: LKE or DSE automatically bypassed FTOK or access control semaphore. xxxx identifies the process type: "LKE", "DSE" or "GT.M"; qqqq is the bypassing process's PID; ssss identifies the semaphore type: "FTOK" or "access control"; rrrr is the region bypassed; ffff is the file corresponding to region rrrr; pppp is the PID of the process holding the semaphore. In normal operation these messages indicate incidental conflicts with no impact. If they occur when shutting the system downthey indicate the last process may have bypassed rundown actions that normally flush all information from memory to durable storage and release shared resources like semaphores and shared memory.

Action: These messages when shutting down GT.M activity may indicate a need to complete the process by invoking MUPIP RUNDOWN to get the database to a safe state; doing so as part of every shutdown is good practice.

#### RESUMESTRMNUM

RESUMESTRMNUM, Error with stream number specified in RESUME qualifier

MUPIP Error: Issued by a Receiver Server as an accompanying message to a UPDSYNCINSTFILE error. The stream number nnnn can be any integer value from -1 through 15.

Action: No action required for this message. Action is required for the preceding UPDSYNCINSTFILE error.

FIS V6.2-002 GT.M Message and Recovery Procedures Manual

#### REUSEINSTNAME

**REUSEINSTNAME**, Error with instance name specified in REUSE qualifier

MUPIP Error: Issued by a Receiver Server when started with the -REUSE qualifier in case of either inappropriate use of this qualifier or an inappropriate instance name specified as a value to this qualifier.

Action: An accompanying GTM-I-TEXT message describes the particular error situation. Take appropriate corrective action based on that.

#### **RHMISSING**

**RHMISSING**, Right-hand side of expression expected

Compile Time Error: This indicates that a binary operator did not specify a corresponding right-hand value.

Action: Look for missing or invalid expressions.

## RLBKCONFIGBNDRY

Last used version: V5.5-000

RLBKCONFIGBNDRY, Rollback encountered journal records indicating current source iiii replaced old source oooo; cannot rollback past sequence number ssss

MUPIP Error: Issued by MUPIP JOURNAL -ROLLBACK indicating it found a change in the source configuration from instance oooo to iiii for stream ssss within the range of its attempt to process. Since it cannot dynamically reconfigure the source connections to deal with this, it stops.

Action: Investigate whether a shorter rollback that won't encounter this configuration change would be useful. If not, refresh this instance from a backup or use the -RSYNC STRM qualifier if appropriate.

## **RLBKINLNOBIMG**

RLBKJNLNOBIMG, Journal file jiji has NOBEFORE IMAGE journaling.

MUPIP Information: MUPIP JOURNAL ROLLBACK displays this informational message whenever it finds journal file jjjj with NOBEFORE\_IMAGE journaling (DSE DUMP -FILE for the corresponding database reports "Journal Before imaging" as FALSE). As there are no before-image records in this journal file, MUPIP JOURNAL ROLLBACK does not roll back the database. Instead, it only generates a lost-transaction file.

Action: No user action required except to confirm that this type of rollback is appropriate and expected.

# **RLBKJNSEQ**

**RLBKJNSEQ**, Journal segno of the instance after rollback is xxxx[yyyy]

MUPIP Information: This indicates that the journal sequence number of the instance after MUPIP JOURNAL ROLLBACK command is xxxx.

Action: -

#### RLBKLOSTTNONLY

RLBKLOSTTNONLY, ROLLBACK will only create a lost transaction file (database and journal files will not be modified)

MUPIP Information: MUPIP JOURNAL -ROLLBACK displays this informational message at startup if it finds at least one database region with NOBEFORE IMAGE journaling. In such a case, MUPIP JOURNAL -ROLLBACK can only create broken and lost transaction files (if appropriate) but otherwise not modify the database, journal files, or replication instance files.

Action: No user action required except to confirm that this type of rollback is appropriate and expected.

## **RLBKNOBIMG**

**RLBKNOBIMG**, ROLLBACK cannot proceed as database dddd has NOBEFORE IMAGE journaling

MUPIP Error: Rollback relies on BEFORE IMAGE journaling and dddd did not have it turned on, so no rollback is currently possible.

Action: Restore the database from a backup and use forward recovery or a replication resynchronization to recover the database state. Use BEFORE IMAGE journaling for databases you wish to be able to rollback.

## **RLBKSTRMSEQ**

**RLBKSTRMSEQ**, Stream journal segno of the instance after rollback is Stream nnnn: Segno dddd xxxx

MUPIP Information: On a Supplementary Instance, MUPIP JOURNAL -ROLLBACK issues this message for each stream (from 0 through 15) that has at least one update. This message indicates how many updates in each stream this Supplementary Instance has processed.

Action: No action required.

#### RLNKCTLRNDWNFL

RLNKCTLRNDWNFL, Relinkctl file for \$ZROUTINES directory dddd failed to rundown as it is open by nnnn process(es)

RLNKCTLRNDWNSUC Chapter 1. Error Messages

MUPIP Error: MUPIP RUNDOWN -RELINKCTL attempted to rundown the Relinkctl file for directory dddd, but did not because there were nnnn processes still using it.

Action: This may be expected, particularly if the command has no directory argument specified. Target MUPIP RUNDOWN -RELINKCTL to directories that are not currently in use, which under some circumstances can require stopping processes.

## **RLNKCTLRNDWNSUC**

RLNKCTLRNDWNSUC, Relinketl file for \$ZROUTINES directory dddd successfully rundown

MUPIP Information: MUPIP RUNDOWN -RELINKCTL successfully ensured the auto-relink Relinkctl file for directory dddd had a guiescent state.

Action: None required

## RLNKRECLATCH

RLNKRECLATCH, Failed to get latch on relinked record for routine name rrrr in \$ZROUTINES directory dddd

Error: The process attempted to auto-relink or ZLINK routine rrrr from directory dddd but was unable to acquire the resource that ensures auto-relink state information for the routine is consistent.

Action: Report the entire incident context to your GT.M support channel.

## **RLNKSHMLATCH**

RLNKSHMLATCH, Failed to get latch on relinketl shared memory for \$ZROUTINES directory dddd

Run Time Error: The process attempted to access auto-relink information for directory dddd but an interlocked operation failed in the shared memory segment corresponding to the relinkctl file for directory dddd.

Action: Report the entire incident context to your GT.M support channel.

## RMBIGSHARE

RMBIGSHARE, File with BIGRECORD specified may only be SHARED if READONLY

Run Time Error: An OPEN command specified BIGRECORD and SHARED without also specifying READONLY. BIGRECORD files may only be shared if all uses are READONLY.

Action: If the file will only be read, add READONLY to the OPEN. If the file is to be written, remove the SHARED.

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 255

## **RMNOBIGRECORD**

RMNOBIGRECORD, RMNOBIGRECORD File record size requires BIGRECORD parameter

Run Time Error: The RECORDSIZE specified is larger than 32767. The BIGRECORD parameter must be specified before a RECORDSIZE larger than 32767.

Action: Modify the OPEN to specify BIGRECORD before RECORDSIZE.

### **RMSRDONLY**

Last used version: V5.4-002A

RMSRDONLY, Cannot write to a read-only sequential file

Run Time Error: This indicates that a WRITE command attempted to access a read-only file.

Action: Look for a missing USE or improper deviceparameters on the OPEN.

#### **RMWIDTHPOS**

**RMWIDTHPOS**, File record size or width must be greater than zero

Run Time Error: This indicates that the WIDTH deviceparameter specified a negative argument.

Action: Modify the routine to ensure a positive WIDTH.

## **RMWIDTHTOOBIG**

**RMWIDTHTOOBIG**, File record size too big

Run Time Error: The RECORDSIZE specified is too large. For disk files the maximum is one megabyte.

Action: Modify the OPEN to use a smaller RECORDSIZE.

## **RNDWNSEMFAIL**

RNDWNSEMFAIL, Attempting to acquire gds rundown semaphore when it is already owned

Run Time Error: This indicates a logic error in GT.M.

Action: Report the entire incident context to your GT.M support channel.

## RNDWNSKIPCNT

Last used version: V5.5-000

RNDWNSKIPCNT, A total of nnnn process(es) skipped database rundown due to a concurrent ONLINE ROLLBACK

Run Time Information: nnnn processes disconnected from a one or more databases while online rollback was running and therefore relied on online rollback or other remaining processes to complete any database shutdown.

Action: None required typically. If there's cleanup required, use MUPIP RUNDOWN.

#### ROLLBKINTERRUPT

**ROLLBKINTERRUPT**, Database file xxxx indicates interrupted ROLLBACK, Reissue the MUPIP JOURNAL ROLLBACK command.

MUPIP Error: This indicates that ROLLBACK has been interrupted on xxxx database file. Though MUPIP JOURNAL RECOVER command is issued instead of MUPIP JOURNAL ROLLBACK, but a previous MUPIP JOURNAL ROLLBACK command was terminated abnormally. Note that, when ROLLBACK is interrupted, only ROLLBACK can be used to fix the interrupted operation.

Action: Reissue the MUPIP JOURNAL ROLLBACK command.

#### ROUTINEUNKNOWN

ROUTINEUNKNOWN, Routine could not be found

Run Time Error: This indicates that a command (such as DO or JOB) or a \$TEXT function referred to a routine that is not in the running image.

Action: Look for unresolved reference warnings on the LINK that created the image. This error occurs on a JOB command when the routine is not in the image or available for ZLINKing, or when an auto-ZLINK finds that the routine reference has been damaged by an incomplete LINK.

## **RPAREN**

RPAREN, List must end with right parenthesis or continue with comma

GDE Error: This indicates that a qualifier that accepts a list of arguments had an improper list format.

Action: Modify the command so that the list is enclosed in parentheses () and separated by commas (,).

## **RPARENMISSING**

RPARENMISSING, Right parenthesis expected

Compile Time Error: This indicates that an expression, function, or subscripted variable contained a left parenthesis and no matching right parenthesis.

Action: Look for and correct any typographical errors.

## **RPARENREQD**

**RPARENREQD**, xxxx Right parenthesis expected

MUPIP Error: This indicates that LOAD failed because it encountered xxxx in its input stream when it expected to find a right parenthesis.

Action: Refer to the topic MUPIP LOAD Errors in About This Manual section in this manual.

#### RSVDBYTE2HIGH

RSVDBYTE2HIGH, Record size ssss is greater than the maximum allowed for region rrrr with Block size bbbb and Reserved bytes cccc

Run Time Error: The attempted database update would result in a record size that is greater than what is allowed by the current database block size and reserved byte setting.

Action: If the Reserved Bytes setting for the database region identified is non-zero, try reducing it to allow this update. Otherwise, modify the update to reduce the resulting record size.

## RSYNCSTRMSUPPLONLY

**RSYNCSTRMSUPPLONLY**, RSYNC STRM qualifier only supported for Supplementary Instances

MUPIP Error: Issued by MUPIP JOURNAL -ROLLBACK indicating the -RSYNC\_STRM qualifier only applies to Supplementary Instances - Business Continuity instances require comprehensive synchronization.

Action: Reissue the command without the -RSYNC\_STRM qualifier.

#### **RSYNCSTRMVAL**

RSYNCSTRMVAL, RSYNC STRM qualifier can only take on a value from 0 to 15

MUPIP Error: Issued by a MUPIP JOURNAL -ROLLBACK -RESYNC command which also specifies -RSYNC STRM with a stream number outside of the range of 0 through 15.

Action: Specify a stream number within the allowed range.

## **RTNNAME**

RTNNAME, Routine name expected here

Compile Time Error: This indicates that an entry reference specified a circumflex without a valid routine name.

Action: Look for a missing routine name in commands such as DO, GOTO, and JOB.

## **RTSLOC**

RTSLOC, At M source location xxxx

Run Time Information: GT.M uses this message to display the line, offset, and routine where it encountered a run-time error.

Action: Review the accompanying message(s) for additional information.

## RUNPARAMERR

RUNPARAMERR, Error accessing parameter for run command

Run Time Error: This indicates that a MUMPS -RUN command had a missing or invalid argument.

Action: Ensure that a MUMPS -RUN has an argument that specifies a valid entryref ([label] ^routinename).

## **RWARG**

RWARG, This is not a legal argument for a READ command

Compile Time Error: This indicates that a READ command specified an invalid argument.

Action: Look for a non-alphanumeric character in the READ argument.

#### **RWFORMAT**

RWFORMAT, A valid format expression (!!, #, or ?expr) expected here

Compile Time Error: This indicates that a READ or WRITE command specified a format with invalid trailing characters.

Action: Look for and correct any typographical errors.

## **SCNDDBNOUPD**

**SCNDDBNOUPD**, Database updates not allowed on the secondary

Run Time Error: This indicates that updates on secondary are currently not allowed as they may lead to inconsistency between primary and secondary.

Action: If you need to do an implicit database update on the secondary, contact the group responsible for maintaining database integrity at your operation.

### **SDSEEKERR**

SDSEEKERR, Sequential device seek error

Run Time Error: This indicates that a GT.M process encountered an error using the SEEK deviceparameter for an OPEN or USE on a sequential disk device. A supplementary TEXT message provides more details about the cause of the error.

Action: Analyze the accompanying message and appropriately adjust the SEEK deviceparameter or its value.

### **SECNODZTRIGINTP**

SECNODZTRIGINTP, Sequence number ssss contains \$ZTRIGGER() updates made inside a transaction which the current replicator does not support. The replicator must be upgraded to at least V5.4-002 to support this type of transaction. Cannot continue

MUPIP Error: The originating instance encountered a \$ZTRIGGER() function within a transaction with sequence number ssss. However, the replicating instance is running a pre-V5.4-002 version which cannot handle \$ZTRIGGER() within a transaction.

Action: Upgrade the replicating instance to V5.4-002 or later. Alternatively adjust the application code to avoid using \$ZTRIGGER() within a transaction.

## **SECNOTSUPPLEMENTARY**

SECNOTSUPPLEMENTARY, ssss is a Supplementary Instance and so cannot act as a source to non-Supplementary Instance iiii

Source Server log/MUPIP Error: Issued by a Source Server on a Supplementary Instance ssss attempted to connect to a Replicating Instance iiii, but found iiii is not configured as a Supplementary Instance.

Action: Reconfigure the instances to a supported configuration.

## **SECONDAHEAD**

**SECONDAHEAD**, Secondary ahead of Primary: Secondary db possibly updated by process other than Update process. Do rollback first.

Run Time Error: The update process issues this error on finding the Secondary database containing more updates than the Primary.

Action: If you allow database updates on Secondary, no action is needed. If not, investigate the cause. Make sure the database on secondary and primary are consistent.

## **SECSHRCHDIRFAILED**

**SECSHRCHDIRFAILED**, gtmsecshr unable to chdir to its temporary directory (dddd)

Run Time Error: This error indicates that GTMSECSHR process failed to change the current working directory to dddd.

Action: Verify that the environment provides the desired dddd, that dddd exists, and that it is a directory

## **SECSHRCLEARENVFAILED**

**SECSHRCLEARENVFAILED**, clearenv failed. gtmsecshr will not be started

Run Time Error: This error indicates that GTMSECSHR process failed to clear its environment of all name-value pairs.

Action: Verify that no other processes have corrupted the environment via non-standard means.

## **SECSHREXECLFAILED**

**SECSHREXECLFAILED**, execl of ffff failed

Run Time Error: This error indicates that GTMSECSHR process failed to update its process image with file ffff.

Action: Ensure that GTMSECSHR executables and their parent directories have correct permissions.

## SECSHRGTMDBGLVL2LONG

SECSHRGTMDBGLVL2LONG, gtmdbglvl env var too long, gtmsecshr will not be started

Run Time Error: This error indicates that the value of the gtmdbglvl environment variable is too long.

Action: Verify that gtmdbglvl contains a proper integer in the decimal or hexadecimal format.

## SECSHRGTMDIST2LONG

SECSHRGTMDIST2LONG, gtm dist env var too long. gtmsecshr will not be started

Run Time Error: This error indicates that the value of the gtm dist environment variable is too long.

Action: Verify that gtm dist contains a proper path to GT.M installation directory.

## SECSHRGTMTMP2LONG

SECSHRGTMTMP2LONG, gtm\_tmp env var too long. gtmsecshr will not be started

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 261 Chapter 1. Error Messages SECSHRNOGTMDIST

Run Time Error: This error indicates that the value of the gtm\_tmp environment variable is too long.

Action: Verify that gtm tmp contains a proper path to the directory for GT.M/GTMSECSHR socket communication.

## **SECSHRNOGTMDIST**

SECSHRNOGTMDIST, gtm dist env var does not exist. gtmsecshr will not be started

Run Time Error: This error indicates that the gtm dist environment variable is not set.

Action: Ensure that gtm\_dist is set and points to the GT.M installation directory.

## **SECSHRNOTOWNEDBYROOT**

SECSHRNOTOWNEDBYROOT, dddd not owned by root. gtmsecshr will not be started

Run Time Error: This error indicates that dddd is not owned by root.

Action: Ensure that GTMSECSHR executables and their parent directories have correct ownership and permissions.

## **SECSHRNOTSETUID**

SECSHRNOTSETUID, ffff not set-uid. gtmsecshr will not be started

Run Time Error: This error indicates that ffff does not have the set-uid bit set.

Action: Ensure that GTMSECSHR executables and their parent directories have correct permissions.

## **SECSHRPERMINCRCT**

**SECSHRPERMINCRCT**, dddd permissions incorrect (pppp). gtmsecshr will not be started

Run Time Error: This error indicates that pppp, the current permissions of dddd, are incorrect.

Action: Ensure that GTMSECSHR executables and their parent directories have correct permissions.

## **SECSHRSETGTMDISTFAILED**

SECSHRSETGTMDISTFAILED, seteny for gtm dist failed, gtmsecshr will not be started

Run Time Error: This error indicates that the GTMSECSHR process failed to adjust gtm\_dist environment variable.

Action: Ensure that the root user is configured with adequate space for environment variables.

V6.2-002 GT.M Message and Recovery Procedures Manual

## SECSHRSETGTMTMPFAILED

SECSHRSETGTMTMPFAILED, seteny for gtm tmp failed, gtmsecshr will not be started

Run Time Error: This error indicates that the GTMSECSHR process failed to adjust gtm tmp environment variable.

Action: Ensure that the root user is configured with adequate space for environment variables.

## **SECSHRSETUIDFAILED**

SECSHRSETUIDFAILED, setuid failed. gtmsecshr will not be started

Run Time Error: This error indicates that the GTMSECSHR process failed to set its effective user ID to root.

Action: Ensure that GTMSECSHR executables and their parent directories have correct permissions.

## **SECSHRSTATFAILED**

SECSHRSTATFAILED, stat failed on dddd, errno xxxx. gtmsecshr will not be started

Run Time Error: This error indicates that the GTMSECSHR process failed to obtain file information on dddd, and that the error code is xxxx.

Action: Ensure that GTMSECSHR executables and their parent directories have correct permissions.

## **SECSHRWRITABLE**

SECSHRWRITABLE, ffff writable. gtmsecshr will not be started

Run Time Error: This error indicates that ffff has 'write' permission.

Action: Ensure that GTMSECSHR executables and their parent directories have correct permissions.

#### **SEFCTNEEDSFULLB**

SEFCTNEEDSFULLB, Current side effect setting does not permit full Boolean to be turned off

Run Time Error: A VIEW "NOFULL BOOLEAN" cannot enable GT.M short-circuit Boolean compilation for a process running with a gtm\_side\_effects setting of 1 or 2.

Action: Keeping in mind that gtm boolean and gtm side effects affect compilation behavior, and that gtm boolean must be 1 or 2 (Standard Boolean mode) for gtm side effects setting 1 or 2 (Standard side effects), choose appropriate compilation modes. Note that once you choose the modes for your application you would typically not change them except to get warnings and modify the application to be somewhat more efficient.

#### **SEGIS**

**SEGIS**, in xxxx segment yyyy

GDE/DSE Information: This message displays the name xxxx of the SEGMENT with which you are working.

Action: Review the accompanying message(s) for additional information.

#### **SELECTFALSE**

**SELECTFALSE**, No argument to \$SELECT was true

Run Time Error: This indicates that a \$SELECT function did not specify any truth value expressions that evaluated to true.

Action: Modify the \$SELECT(). The common technique is to end the selection list with-1:expr)-where expr is some default value and the integer constant 1 is always true.

## **SELECTSYNTAX**

SELECTSYNTAX, Argument to xxxx clause is not valid

MUPIP Error: This indicates that EXTRACT encountered a qualifier with an invalid value and aborted.

Action: Review the proper syntax for EXTRACT with the qualifier SELECT. Refer to the Administration and Operations Guide or the online help for the MUPIP EXTRACT command.

#### **SEMID**

**SEMID**, Semaphore id nnnn

MUPIP Information: This message reports additional information for an associated error which had trouble with the semaphore with id nnnn.

Action: Check "ipcs -s" for the given id, and see the associated error.

## **SEMKEYINUSE**

**SEMKEYINUSE**, Semaphore key xxxx is already in use (possibly by an older version)

Run Time/MUPIP Error: This indicates that GT.M failed to create a semaphore. One possible cause is that a semaphore of ID xxxx already exists in the system and the number of semaphores in that semaphore set is different than the semget has attempted to create. If a new GT.M version increases the number of semaphores in the semaphore set, collision with an older GT.M version can cause this error.

Action: Check accompanying message(s) for additional information. Use the semstat2 tool to find detailed information about the existing semaphores in the system.

## **SEMREMOVED**

**SEMREMOVED**, Semaphore id xxxx removed from the system

MUPIP Information: This indicates that the orphaned semaphore with ID xxxx is removed; because it contained the signature of a GT.M semaphore, and no process was currently using it.

Action: -

## **SEMWT2LONG**

**SEMWT2LONG**, Process wwww waited ssss second(s) for the llll lock for region rrrr, lock held by pid pppp

Run Time Error: This indicates that the process pppp appears to be holding the llll control semaphore for region rrrr for longer than GT.M expects.

Action: Analyze the behavior of process pppp, and terminate it if appropriate. This error may indicate that the system is under-configured for the workload.

## **SEQNUMSEARCHTIMEOUT**

SEQNUMSEARCHTIMEOUT, Timed out trying to find sequence number ssss in Journal File(s). See above messages for details. Source server exiting

Source Server log/MUPIP Error: The Source Server was unable to access a journal record corresponding to sequence number ssss as requested by the Replicating instance.

Action: Check to see that the journal chain is intact and all the file in the Source Server has authorization to all the files in the chain. Review the accompanying message for more information.

## **SERVERERR**

**SERVERERR**, Severe error on server: xxxx

GT.CM Error: This indicates that the GT.CM Server encountered a fatal error and terminated.

Action: Review subsequent message(s) for more information. If necessary, report the entire incident context to your GT.M support channel.

## **SETECODE**

**SETECODE**, Non-empty value assigned to \$ECODE (user-defined error trap)

Run Time Error: This indicates that an error trap occured because \$ECODE got altered to a non-null string in an M routine.

Action: Make sure that either \$ETRAP or \$ZTRAP is set to the valid value, if the error needs to be handled by GT.M.

## **SETEXTRENV**

**SETEXTRENV**, Database files are missing or Instance is frozen; supply the database files, wait for the freeze to lift or define gtm extract nocol to extract possibly incorrect collation

MUPIP Error: It indicates that gtm extract nocol environment variable needs to be defined to run MUPIP JOURNAL EXTRACT completion if Instance is Frozen or Database files are missing.

Action: If the you know there are no variables with alternate collation or if the EXTRACT is for analysis rather than a LOAD, define gtm extract nocol to a positive value and reissue the command. Otherwise correct the condition before reissuing the EXTRACT.

## **SETINSETTRIGONLY**

SETINSETTRIGONLY, ISV iiii can only be modified in a 'SET' type trigger

Run Time Error: Code invoked for a trigger other than SET (such as KILL or ZTRIGGER) attempted to modify Intrinsic Special Variable iiii, which applies only to a SET trigger context.

Action: Review the trigger definition and correct the types or the code to avoid the issue.

## **SETINTRIGONLY**

**SETINTRIGONLY**, ISV iiii cannot be modified outside of the trigger environment

Trigger/Run Time Error: The Intrinsic Special variable iiii can only be SET within the context of trigger logic (\$ZTLEVEL > 0)

Action: Examine the application logic to determine whether code intended for use in a trigger context falls in an execution path outside of trigger logic. For code intended to execute both inside and outside triggers, use a postcondition that limits the SET to within a trigger.

## **SETITIMERFAILED**

**SETITIMERFAILED**, A setitimer() call returned an error status of ssss

Run Time Fatal: The above error is issued when GT.M fails to schedule or stop a system timer using the setitimer() system call.

Action: Verify the normal state of the OS kernel. Report the entire incident context to your GT.M support channel along with any GT.M operator log messages within the same time frame.

## **SETREG2RESYNC**

**SETREG2RESYNC**, Setting resync sequence number xxxx to region sequence number yyyy for database zzzz

MUPIP Information: This displays that resync sequence number xxxx is being set to region sequence number yyyy for database zzzz, because the journal file had crash field set and update was disabled.

Action: -

# **SETSOCKOPTERR**

**SETSOCKOPTERR**, Setting the socket attribute xxxx failed: (errno == aaaa) yyyy

Run Time Error: This indicates that an attempt to modify the xxxx socket attribute failed for the reason described by yyyy.

Action: Review the message(s) and take appropriate action.

# **SETZDIR**

**SETZDIR**, Cannot change working directory to xxxx.

Run Time Error: This indicates that there is an invalid directory specified in the SET \$ZDIR=<xxxx> command. The accompanying message indicates the exact cause of the failure.

Action: Make sure the specified argument confirms to the syntax of a directory specification on the host operating system. Check for the existence of the directory and access control permissions associated with the directory.

# **SHMPLRECOV**

SHMPLRECOV, Shared memory pool block recovery invoked for region xxxx

Run Time Information: GT.M carves out a portion of shared memory/global section allocated for each database region to use for ONLINE BACKUP - this portion is called "shared memory pool". This portion is also used by GT.M on OpenVMS while the region is being downgraded dynamically. In the unlikely event of corruption of shared memory pool, or if the blocks are "lost" due to stopped/killed or failed processes, GT.M detects the corruption or lost blocks and runs a recovery procedure to fix these errors. Such an occurrence is logged in the operator log (syslog on UNIX) with SHMLRECOV message.

Action: Report the occurrence to your GT.M support channel. No user action required. GT.M will continue to operate normally.

## **SHMREMOVED**

SHMREMOVED, Removed Shared Memory id mmmm corresponding to file ffff

V6.2-002 MR Manual June 09, 2015, Page 267 MUPIP Information: MUPIP RUNDOWN removed shared memory segment mmmm, corresponding to the file ffff, which could be a database file or a replication instance file with a GT.M signature because the resource was not actively in use.

Action: No action required.

#### **SHRMEMEXHAUSTED**

**SHRMEMEXHAUSTED**, Attempt by process to use more shared memory than currently permitted by OpenVMS

Run Time Error: A OpenVMS out-of-memory error was encountered while trying to open a shared global section for a database file.

Action: Reduce the shared global section usage by reducing the number of global buffers, or database block size, or the number of database files that the process tries to open.

# **SIDEEFFECTEVAL**

**SIDEEFFECTEVAL**, Extrinsic (\$\$), External call (\$&) or \$INCREMENT() with potential side effects in actuallist, function arguments, non-Boolean binary operands or subscripts

Compile Time Warning: A side effect expression appeared to the right of a global or local variable (glvn) in an order within an outer expression where the side effect might modify the glvn. Setting the gtm\_side\_effects environment variable in UNIX or logical name in OpenVMS to 2 (two) activates this check.

Action: Analyze the effect(s) of the side effect expressions, which are \$INCREMENT(). extrinsics (\$ \$), external calls (\$& or \$ZCALL()) as to whether they modify a glvn earlier in the expression. If they do, the setting of gtm\_side\_effects modifies the behavior and you either need to modify the code to eliminate the side effect interaction or be sure to select the behavior you desire.

## **SIGACCERR**

**SIGACCERR**, Signal was caused by invalid permissions for mapped object

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

#### **SIGADRALN**

SIGADRALN, Signal was caused by invalid address alignment

FIS V6.2-002

**SIGADRERR** Chapter 1. Error Messages

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

#### **SIGADRERR**

**SIGADRERR**, Signal was caused by non-existent physical address

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

#### **SIGBADSTK**

**SIGBADSTK**, Signal was caused by an internal stack error

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

#### **SIGCOPROC**

SIGCOPROC, Signal was caused by a coprocessor error

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

## **SIGFLTDIV**

**SIGFLTDIV**, Signal was caused by a floating point divided by zero

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

## **SIGFLTINV**

**SIGFLTINV**, Signal was caused by an invalid floating point operation

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

#### **SIGFLTOVE**

**SIGFLTOVF**, Signal was caused by a floating point overflow

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

#### **SIGFLTRES**

**SIGFLTRES**, Signal was caused by a floating point inexact result

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

#### **SIGFLTUND**

**SIGFLTUND**, Signal was caused by a floating point underflow

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

FIS V6.2-002 GT.M Message and Recovery Procedures Manual

# **SIGILLADR**

**SIGILLADR**, Signal was caused by illegal addressing mode

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

#### **SIGILLOPC**

**SIGILLOPC**, Signal was caused by an illegal opcode

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

# **SIGILLOPN**

SIGILLOPN, Signal was caused by an illegal operand

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

## **SIGILLTRP**

**SIGILLTRP**, Signal was caused by an illegal trap

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

# **SIGINTDIV**

SIGINTDIV, Signal was caused by an integer divided by zero

V6.2-002 MR Manual June 09, 2015, Page 271 Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

# **SIGINTOVF**

SIGINTOVF, Signal was caused by an integer overflow

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

#### **SIGMAPERR**

**SIGMAPERR**, Signal was caused by an address not mapped to an object

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

# **SIGOBJERR**

SIGOBJERR, Signal was caused by an object specific hardware error

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

## **SIGPRVOPC**

**SIGPRVOPC**, Signal was caused by a privileged opcode

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

V6.2-002 GT.M Message and Recovery Procedures Manual Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

## **SIGPRVREG**

**SIGPRVREG**, Signal was caused by a privileged register

Run Time Error: This message is an auxiliary message and is preceded with a primary KILLBYSIGxxx message.

Action: Refer to the accompanying message(s) and take appropriate action. Refer to the UNIX user documentation. If necessary, report the entire incident context to your GT.M support channel for further analysis.

# **SIZENOTVALID4**

**SIZENOTVALID4**, Size (in bytes) must be either 1, 2, or 4

Run Time Error: The DSE CACHE command triggers this error when the size operand is not 1, 2, or 4.

Action: Specify 1, 2, or 4 as size (in bytes).

#### SIZENOTVALID8

SIZENOTVALID8, Size (in bytes) must be either 1, 2, 4, or 8

Run Time Error: Both the DSE CHANGE -FILEHEADER command and MUPIP REPLICATE -SOURCE -JNLPOOL -CHANGE command triggers this error when the SIZE qualifier is not set to 1, 2, 4, or 8.

Action: Specify 1, 2, 4, or 8 as size (in bytes).

## **SNAPSHOTNOV4**

SNAPSHOTNOV4, Cannot downgrade (to V4) while snapshots are in progress. Currently ssss snapshots are in progress for region rrrr.

MUPIP Error: A request to downgrade a region to V4 occurred while a snapshot is in progress.

Action: Wait for a currently active process using snapshots to complete before running the downgrade. Since a downgrade to V4 would not normally be expected, check to verify that the downgrade invocation is appropriate.

# **SOCKACCEPT**

**SOCKACCEPT**, Socket accept failed

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 273 Chapter 1. Error Messages SOCKACPT

Run Time Error: WRITE /ACCEPT encountered an I/O error while attempting to accept the sockets. No sockets were added to the socket pool.

Action: See the accompanying ENO or TEXT message for details.

## **SOCKACPT**

**SOCKACPT**, Error accepting socket connection

Run Time Error: This indicates that the process of opening a socket resulted in a device error.

Action: Review the accompanying message(s) for additional information.

# **SOCKACTNA**

**SOCKACTNA**, Action not appropriate for current socket

Compile Time Error: This indicates that the socket state does not support the attempted action.

Action: Review the code for compatible socket actions.

## **SOCKBENOTEMPTY**

**SOCKBFNOTEMPTY**, Socket buffer size cannot be set to xxxx due to aaaa bytes of buffered data. Read first.

Run Time Error: This indicates that a USE command attempted to adjust the size of the socket buffer while it contained data.

Action: Make sure the buffer is empty when adjusting the size.

## **SOCKBIND**

**SOCKBIND**, Error in binding socket

Run Time Error: This message indicates a problem binding a socket to a port or file.

Action: Check the associated ENO message for more details.

## **SOCKETEXIST**

**SOCKETEXIST**, Socket xxxx already exists

Run Time Error: This error is issued:

• On OPEN: ATTACH=xxxx is used to name a newly created socket but the name already exists in the current Socket device's collection.

V6.2-002 GT.M Message and Recovery Procedures Manual **SOCKINIT** Chapter 1. Error Messages

• On USE: DETACH=xxxx is used to move a socket to the socketpool but the socketpool already has a socket with the specified name. ATTACH=xxxx is used to move a socket from the socketpool but the current Socket device already has a socket with the specified name.

Action: Review the names of the sockets already present on that device and specify a unique name.

# **SOCKINIT**

**SOCKINIT**, Error initializing socket: (errno == aaaa) xxxx

Run Time Error: This indicates that the process of opening a socket resulted in a device error. xxxx is the text description of the failure for the OS service.

Action: Review the accompanying message(s) for additional information.

# **SOCKLISTEN**

**SOCKLISTEN**, Error listening on a socket

Run Time Error: This indicates that GT.M was unable to listen in the specified socket.

Action: Review accompanying messages for more information on the cause of the failure.

#### **SOCKMAX**

SOCKMAX, Attempt to exceed maximum sockets xxx for the SOCKET device

Run Time Error: Attempting to connect more than the maximum number of sockets defined for the process triggers this error. xxx is the maximum for the current process.

Action: Reduce the number of connections or use a process that has a higher maximum number of sockets defined by the gtm max sockets environment variable.

# **SOCKNOTFND**

**SOCKNOTFND**, Socket xxxx not found

Run Time Error: This error is issued:

- On CLOSE when SOCKET=xxxx is used to specify which socket to close.
- On USE:
  - DETACH=xxxx when the specified socket in not in the current Socket device.

MR Manual V6.2-002

- ATTACH=xxxx when the specified socket is not in the socketpool.
- SOCKET=xxxx when the specified socket is not in the current Socket device.

Action: Make sure the socket is created before an I/O operation attempts using it.

## **SOCKNOTPASSED**

**SOCKNOTPASSED**, Socket message contained no passed socket descriptors

Run Time Error: WRITE /ACCEPT received no sockets over the LOCAL connection.

Action: Verify the connection and make sure the WRITE /PASS on the sender is correct.

# **SOCKPARMREQ**

Last used version: V6.1-000

SOCKPARMREQ, Socket device parameter is required for TCP open

Run Time Error: This indicates that a socket deviceparameter was not defined to OPEN a TCP connection.

Action: Establish a TCP connection by specifying the SOCKET deviceparameter for the OPEN command. For a more complete description of this deviceparameter refer to the Input/Output Processing chapter of the Programmer's Guide.

#### **SOCKPASS**

**SOCKPASS**, Socket pass failed

Run Time Error: WRITE /PASS encountered an I/O error while attempting to pass the sockets. No sockets were closed.

Action: See the accompanying ENO or TEXT message for details.

## **SOCKPASSDATAMIX**

SOCKPASSDATAMIX, Attempt to use a LOCAL socket for both READ/WRITE and PASS/ACCEPT

Run Time Error: The code attempted to use a LOCAL socket for both data communication, using READ and/or WRITE, and socket passing, using WRITE /PASS or WRITE /ACCEPT. Using both forms of communication on the same socket is not supported.

Action: Use separate sockets for data and socket passing.

SOCKNOTPASSED

## **SOCKWAIT**

**SOCKWAIT**, Error waiting for socket connection

Run Time Error: This indicates that the process of waiting for an event on a socket resulted in a device error.

Action: Review the accompanying message(s) for additional information.

# **SOCKWRITE**

**SOCKWRITE**, Write to a socket failed

Run Time Error: This indicates that GT.M was unable to write to a socket.

Action: Review the accompanying messages for more information on the cause of the failure.

# **SPCLZMSG**

**SPCLZMSG**, The following error message cannot be driven through ZMESSAGE

Run Time Error: The specified error code is not allowed to be driven through ZMESSAGE

Action: Make sure ZMESSAGE is not driving any prohibited error message.

## **SPOREOL**

**SPOREOL**, Either a space or an end-of-line was expected but not found

Compile Time Error: This indicates that a command that required an argument did not specify one or an ELSE attempted to specify an argument.

Action: Look for and correct any typographical errors.

#### **SRCFILERR**

**SRCFILERR**, Error with source file I/O on file xxxx

Compile Time Error: This indicates that a ZCOMPILE, ZLINK, or auto-ZLINK encountered an error when it attempted to access source file xxxx. An M command may also report this error at compiletime.

Action: Use host operating system commands to list the file and review accompanying messages for additional information.

## **SRCLIN**

SRCLIN, xxxx

MR Manual V6.2-002 June 09, 2015, Page 277 Compile Time Information: This message displays the source code line where an error occurred.

Action: -

## **SRCLNNTDSP**

**SRCLNNTDSP**, Source lines exceeding wwww character width are not displayed

Compile Time Error: Displayed instead of the source line when source line exceeds 1023 characters.

Action: Refer to the source code, the line number and column number in the associated messages identify the position of the problem .Consider shortening the line, at least until the error is found and corrected.

#### **SRCLOC**

**SRCLOC**, At column xxxx, line yyyy, source module zzzz

Compile Time Error: GT.M uses this message to display the line, offset, and routine where it encountered a compile-time error. xxxx is the column. yyyy is the line number. zzzz is the routine name.

Action: Review the accompanying message(s) for additional information.

#### **SRCLOCUNKNOWN**

SRCLOCUNKNOWN, M source location unknown

Run Time Warning: This indicates that GT.M could not locate the source line associated with the error.

Action: Find out if source code is available to you, if not this message is expected. Otherwise, check ZROUTINES and file permissions.

#### **SRCNAM**

**SRCNAM**. in source module xxxx

Compile Time Information: This message identifies the module xxxx, which contains some other error.

Action: Review the accompanying message(s) for additional information.

# **SRCSRVEXISTS**

**SRCSRVEXISTS**, Source server for secondary instance xxxx is already running with pid yvyy

Source Server log/MUPIP Error: This error is issued by a Source Server startup command if there is already a Source Server up and running for the secondary instance name specified in the command.

FIS V6.2-002 GT.M Message and Recovery Procedures Manual Action: Do not start multiple source servers for the same secondary instance.

## **SRCSRVNOTEXIST**

**SRCSRVNOTEXIST**, Source server for secondary instance xxxx is not alive

Source Server log/MUPIP Error: This error is issued by a mupip replic -source command that specifies any one of activate, changelog, checkhealth, deactivate, shutdown, showbacklog, statslog, stopsourcefilter if it finds no Source Server up and running for the replicating (secondary) instance name specified in the command.

Action: Make sure the Source Server for the specified replicating instance name is up and running to provide working replication.

## **SRCSRVTOOMANY**

**SRCSRVTOOMANY**, Cannot start more than xxxx source servers in primary instance file yyyy

MUPIP Error: A maximum of 16 active and/or passive source servers are allowed at any point in time per instance. If 16 source servers are already running and another source server startup is attempted, it will issue this error.

Action: Shutdown any active or passive source server to allow the new source server to start up.

## SRVLCKWT2LNG

**SRVLCKWT2LNG**, PID pppp is holding the source server lock. Waited for mmmm minute(s). Now exiting

MUPIP Error: Issued by MUPIP ROLLBACK -ONLINE when it finds process pppp has not released the journal pool resource for mmmm minutes.

Action: Investigate the state of process pppp and whether it should be stopped by operator action.

#### **SSATTACHSHM**

SSATTACHSHM, Error while attaching to shared memory identifier iiii

Run Time Error: A GT.M process encountered error while trying to attach to shared memory created to manage a snapshot and reports the above error in the operator log.

Action: Examine the accompanying system error message and take appropriate action.

## **SSFILCLNUPFAIL**

**SSFILCLNUPFAIL**, Error while unlinking snapshot file -- xxxx

V6.2-002 MR Manual June 09, 2015, Page 279 MUPIP Error: An attempt to terminate snapshot file maintenance by GT.M updater processes encountered a problem.

Action: Try a MUPIP RUNDOWN. If that has a similar problem, it may be prudent to shut down all access to the database in question in order to stop the burden of maintaining the snapshot file and to ensure it doesn't unnecessarily consume more space.

#### **SSFILOPERR**

**SSFILOPERR**, Error while doing oooo operation on file ffff

MUPIP Error: This operator log message indicates operation oooo on snapshot file ffff failed. Note in certain timing situations this action might be reported to the operator log after the snapshot consuming process (say MUPIP INTEG) has finished with the snapshot file, in which case it's harmless. If the consuming process issues a REGSSFAIL error, then it was definitely prevented from completing its tack because of the SSFILOPERR.

Action: Analyze the operation and the file characteristics and take appropriate action to clear the problem.

#### **SSPREMATEOF**

**SSPREMATEOF**, Premature end of file while reading block nnnn of size: bbbb bytes at offset: oooo from zzzz

MUPIP Error: The action attempted access to a block beyond the end of the snapshot file. This means either the process was confused or the file is damaged

Action: Retry the action. If the problem persists, contact FIS with information on how to recreate the problem.

## **SSSHMCLNUPFAIL**

SSSHMCLNUPFAIL, Error while doing snapshot shared memory cleanup. Operation -- ssss. Identifier -- dddd

MUPIP Error: There was an error while doing a snapshot cleanup. The operation ssss indicates what system call failed. The identifier dddd indicates the shared memory identifier that is being cleaned up.

Action: Analyze the failure details and take corrective measures. If appropriate carefully clear abandoned resources using the system ipcrm utility.

#### **SSTMPCREATE**

**SSTMPCREATE**, Cannot create the temporary file in directory dddd for the requested snapshot

MUPIP Error: An action requiring a snapshot file was unable to create it.

Action: Verify the directory has appropriate access permissions for the user performing the action.

## **SSTMPDIRSTAT**

**SSTMPDIRSTAT**, Cannot access temporary directory dddd

MUPIP Error: An action requiring a snapshot file was unable to access the temporary directory.

Action: Verify the directory exists and has appropriate access permissions for the user performing the action.

# **SSTMPFILOPEN**

Last used version: V5.4-002A

**SSTMPFILOPEN**, Failed to open shadow snapshot file ffff

MUPIP Error: An action requiring a snapshot file was unable to open it.

Action: Verify the file exists and has appropriate access permissions for the user performing the action.

## SSV4NOALLOW

SSV4NOALLOW, Database snapshots are supported only on fully upgraded V5 databases. nnnn has V4 format blocks.

MUPIP Error: An action requiring a snapshot was attempted on a database the contains V4 format blocks.

Action: Upgrade the database to V5 and re-run the action.

## **STACKCRIT**

STACKCRIT, Stack space critical

Run Time Error: This indicates that the process has consumed almost all of the available stack space.

Action: Look for infinite recursion. If you do not take immediate action to reduce your stack, a STACKOFLOW error will occur, which terminates your GT.M image. Examine the stack with ZSHOW. Trim the stack using QUIT, ZGOTO, or HALT.

# **STACKOFLOW**

STACKOFLOW, Stack overflow

Run Time Fatal: This indicates that the process required more stack space than was available in memory.

Action: Reduce the stack when you get a STACKCRIT error. This error terminates the image.

## **STACKUNDERFLO**

#### STACKUNDERFLO, Stack underflow

Run Time Error: This indicates that the process stack was corrupt.

Action: Review the accompanying messages for additional information. If necessary, report the entire incident context to your GT.M support channel for further analysis.

#### **STARFILE**

**STARFILE**, Star(\*) argument cannot be specified with xxxx

MUPIP Error: This indicates that the qualifier xxxx, specified with the MUPIP JOURNAL command does not allow star (\*) as an argument.

Action: Specify the journal file names explicitly.

## **STATCNT**

STATCNT, xxxx: Key cnt: yyyy max subsc len: zzzz max data len: wwww

MUPIP Information: LOAD uses this message to display status. xxxx is the name of the global being updated. yyyy is the number of nodes handled. zzzz is the largest subscript encountered. wwww is the size of the largest node.

Action: -

# **STDNULLCOLLREQ**

**STDNULLCOLLREQ**, Region rrrr needs Standard Null Collation enabled because global gggg spans through it

GDE Information: This indicates that the global gggg spans through region rrrr but the region has GT.M Null collation enabled.

Action: All regions containing parts of spanning globals need to have Standard Null Collation enabled. Fix region rrrr to have Standard Null Collation enabled.

## **STOPTIMEOUT**

**STOPTIMEOUT**, Waited too long for stopped process to release. Region: xxxx.

Run Time Error: This indicates that GT.M is ignoring and bypassing a locked process and a recovery mechanism has taken control of the listed region.

FIS V6.2-002

Action: Terminate the misbehaving process.

## **STPEXPFAIL**

STPEXPFAIL, Stringpool expansion failed. It could not expand to xxxx bytes

Run Time Error: The stringpool, an internally expanding data structure maintained by GT.M to store primarily M-local variable content, needs more memory than is available in the process virtual memory.

Action: Increase process memory quotas to increase available process virtual memory. Change application to reduce memory requirements of the stringpool by using lesser M-local variables.

## **STRINGOFLOW**

STRINGOFLOW, String pool overflow

Compile Time Error: This indicates that some action attempted to use the string pool when it was full.

Action: Look for very large string constants in a very large program; reduce one or both.

# **STRMISSOUOTE**

STRMISSQUOTE, Missing double-quote at end of string specification ssss

GDE Error: This indicates that a subscripted name was specified with string subscripts parts of which were enclosed inside double-quotes but the closing double-quote is missing.

Action: Specify the subscripted name with the appropriate double quote(s).

## **STRMNUMIS**

**STRMNUMIS**, Stream # is ssss

MUPIP Information: Issued by a Receiver Server to designate a stream associated with the the immediately preceding message.

Action: Refer to the associated prior message.

#### STRMNUMMISMTCH1

STRMNUMMISMTCH1, Stream nnnn exists on the receiver instance file but is unknown on the source instance

MUPIP Error: Issued by a Source Server on a Supplementary Instance when it detects a non-Supplementary stream number nnnn (which can be any value from 1 through 15) exists on the receiving instance but not on the source instance. This indicates the two instances are not in sync at least with respect to stream nnnn, so replication cannot proceed.

Action: Reinitialize the receiving instance from a backup of the source instance and restart replication between the two instances.

#### STRMNUMMISMTCH2

STRMNUMMISMTCH2, Stream nnnn exists on the source instance file but is unknown on the receiver instance

MUPIP Error: Issued by a Source Server on a supplementary instance when it detects a non-Supplementary stream number nnnn (which can be any value from 1 through 15) exists on the source instance but not on the receiving instance. This indicates the two instances are not in sync at least with respect to stream nnnn and so replication cannot proceed.

Action: Reinitialize the receiving instance from a backup of the source instance and restart replication between the two instances.

# **STRMSEQMISMTCH**

STRMSEQMISMTCH, Unable to play update on Stream nnnn with seqno xxxx as receiving instance has a different stream segno XXXX

Update Process log/MUPIP Error: Issued by the Update Process on a supplementary instance started with -UPDNOTOK (that is, local updates are disabled) when it finds the source and receiving instances have different values of stream sequence number for the non-Supplementary stream nnnn (can be any value from 1 through 15). This indicates the two instances are not in sync at least with respect to stream nnnn and so replication cannot proceed.

Action: Reinitialize the receiving instance from a backup of the source instance and restart replication between the two instances.

#### **STRNOTVALID**

STRNOTVALID, Error: cannot convert xxxx value to valid yyyy value.

DSE Error: This error shows in DSE when there is a string input that cannot be converted to a number. For example, attempting "change -fileheader -location=0x123rt456" would apply to this error.

Action: Review and correct typographical errors.

#### **STRUNXEOR**

STRUNXEOR, xxxx unexpected end of record in string subscript

MUPIP Error: This indicates that LOAD aborted because it encountered an end of file while processing string subscript xxxx.

Action: Refer to the topic MUPIP LOAD Errors in About This Manual section in this manual.

V6.2-002 GT.M Message and Recovery Procedures Manual

#### **STUCKACT**

**STUCKACT**, Process stuck script invoked: rrrr: pppp

Run Time Information: This message shows the success or failure status return rrrr of the operation of invoking the script pppp pointed to by the environment variable \$gtm\_procstuckexec

Action: If the result is success analyze the output of the script. If the result is failure, check the script and any output it produced up to the point of failure and rework the script or adjust the environment appropriately.

#### **SUB2LONG**

SUB2LONG, Subscript invalid, too long

MUPIP Error: This indicates that INTEG encountered a subscript that is too long for its display mechanism.

Action: Examine the subscript with DSE DUMP, and take action to eliminate the subscript if it is invalid.

# **SUPRCVRNEEDSSUPSRC**

SUPRCVRNEEDSSUPSRC, Instance iiii is not configured to perform local updates, so it cannot act as a receiver for non-Supplementary Instance ssss

MUPIP Error: Issued by a Receiver Server or a MUPIP JOURNAL -ROLLBACK -FETCHRESYNC on a Supplementary Instance ssss started with -UPDNOTOK attempted to connect to non-Supplementary Instance iiii. A Supplementary Instance that does not permit local updates can only replicate from another Supplementary Instance.

Action: Reconfigure the instances to a supported configuration.

## **SUSPENDING**

SUSPENDING, Suspending processing on user request or attempt to do terminal I/O while running in the background

Run Time Information: The message signifies that a GT.M process is suspended on user initiated ^Z (or key stroke that is set to shell "susp"). It is also displayed if the process attempts to do terminal I/O while running in the background. Before suspending itself, the process logs the SUSPENDING message to the operator facility. Suspended processes may be automatically released from that state if they hold a shared resource that blocks other processes.

Action: -

## **SVNEXPECTED**

**SVNEXPECTED**, Special variable expected in this context

Compile Time/Run Time Error: This indicates that GT.M encountered a dollar sign in a NEW command that was not followed by a valid special variable name.

Action: Look for misspelled special variable names or a missing \$ in an extrinsic.

#### **SVNONEW**

**SVNONEW**, Cannot NEW this special variable

Compile Time/Run Time Error: This indicates that a NEW command tried to new an intrinsic special variable that is not a valid argument for a NEW.

Action: Look for inappropriate \$ prefixes. \$ZTRAP, \$ETRAP, \$ESTACK, \$ZYERROR, \$ZGBLDIR are the only intrinsic special variables that can be NEWed.

#### **SVNOSET**

**SVNOSET**, Cannot SET this special variable

Compile Time Error: This indicates that a SET command specified an assignment that attempted to modify a read-only special variable.

Action: Look for inappropriate \$ prefixes and attempts to modify read-only special variables. \$DEVICE, \$ECODE, \$ETRAP, \$DEVICE, \$KEY, \$X, and \$Y are the only ANSI standard variables that can be SET.

#### **SYSCALL**

SYSCALL, Error received from system call xxxx -- called from module yyyy at line zzzz

Run Time Error: This indicates that system call failed due to some unusual error condition.

Action: Report to system administrator and if necessary report the entire incident context to your GT.M support channel for further analysis.

#### **TCGETATTR**

TCGETATTR, Error while getting terminal attributes on file descriptor xxxx

Run Time Error: This indicates that the terminal attributes are inaccessible where xxxx is the file descriptor for the device.

Action: Review and correct the OS configuration of the device.

#### **TCOMMITDISALLOW**

TCOMMITDISALLOW, TROLLBACK required after an unhandled error in trigger context

Run Time Error: This transaction did an update that invoked a trigger which in turn encountered an error that was not handled by the application error trap inside the trigger context. Because of this, the exit from trigger context was abnormal. GT.M does not commit such transactions since they would not preserve the atomicity of trigger updates (triggering update + triggered updates).

Action: Such transactions can only be rolled back. If this is a nested TSTART (subtransaction), it can optionally be rolled back incrementally, that is, only the nested TSTART needs to be rolled back while the parent TSTART can still be committed.

#### **TCSETATTR**

**TCSETATTR**, Error while setting terminal attributes on file descriptor xxxx

Run Time Error: This indicates that the terminal attributes are inaccessible where xxxx is the file descriptor for the device.

Action: Review and correct the OS configuration of the device.

# **TERMASTQUOTA**

TERMASTQUOTA, Process AST quota exceeded, cannot open terminal

Run Time Error: This indicates that an OPEN command failed because it required an AST that would violate the OpenVMS process quota.

Action: Reduce the number of terminals in use by a single process or ask your system administrator about changing your AST quota.

#### **TERMWRITE**

**TERMWRITE**, Error writing to terminal, status:

Run Time Error: This indicates that a WRITE to a terminal failed. Such failures may be detected and reported asynchronously to the actual WRITE command.

Action: Review the accompanying message(s) for additional information.

#### **TEXT**

TEXT, xxxx

Run Time Information: GT.M uses this message with various accompanying text, xxxx, to expand on other errors.

Action: Examine the text and review any accompanying message(s).

#### **TEXTARG**

**TEXTARG**, Invalid argument to \$TEXT function

Compile Time Error: This indicates that a \$TEXT function specified an invalid argument.

Action: Modify the \$TEXT() argument so it is in the format of an entryref.

#### **TIMERHANDLER**

TIMERHANDLER, Incorrect SIGALRM handler xxxx found by yyyy

Run Time Information: This indicates that an external user-supplied routine (C or other language) called from GT.M, incorrectly manipulated the system timer handler. The xxxx is the hexadecimal address of the handler installed by the external routine and yyyy is the routine within GT.M, which discovered the problem.

Action: Use the GT.M provided timer facility described in the Programmer's Guide.

# TIMEROVEI

**TIMEROVFL**, Timer overflow; interval probably too large

Run Time Error: This indicates that a timeout or timers calculation exceeded the maximum allowable interval.

Action: Check the system maximum interval and set the interval accordingly.

#### **TIMRBADVAL**

TIMRBADVAL, Bad value specified. Timer not changed.

DSE Error: This indicates that a CHANGE command with the FILEHEADER qualifier specified a time value that was improperly formatted or inappropriate.

Action: Modify the time value.

#### **TLSCONNINFO**

TLSCONNINFO, Failed to obtain information on the TLS/SSL connection

MUPIP Warning: This indicates that an attempt to establish TLS/SSL connection failed.

Action: Review the following TEXT message from the plug-in for additional diagnostic information and adjust the environment accordingly.

## **TLSCONVSOCK**

TLSCONVSOCK, Failed to convert UNIX TCP/IP socket to TLS/SSL aware socket>/error

Run Time/MUPIP Error: This indicates that an attempt to establish TLS/SSL connection failed.

Action: Review the following TEXT message from the plug-in for additional diagnostic information, review your keys and related certificates, and adjust the environment accordingly.

## **TLSDLLNOOPEN**

TLSDLLNOOPEN, Failed to load GT.M TLS/SSL library for secure communication

MUPIP Error: This indicates that the attempt to load the GT.M dynamically linked library for TLS/SSL operation failed.

Action: Review the following TEXT message from the plug-in for additional diagnostic information, check the path and authorizations for the library, and adjust the environment accordingly.

## **TLSHANDSHAKE**

TLSHANDSHAKE, Connection to remote side using TLS/SSL protocol failed

Run Time/MUPIP Error: This indicates that an attempt to establish SSL/TLS connection failed.

Action: Review the following TEXT message from the plug-in for additional diagnostic information, and adjust the environment accordingly.

# **TLSINIT**

**TLSINIT**, Failed to initialize GT.M TLS/SSL library for secure communication

Run Time/MUPIP Error: This indicates that the attempt to initialize a secure context for TLS/SSL operation failed.

Action: Review the following TEXT message from the plug-in for additional diagnostic information, check your certificates, and adjust the environment accordingly.

## **TLSIOERROR**

TLSIOERROR, Error during TLS/SSL oooo operation

Run Time/MUPIP Error: This indicates that while attempting oooo operation (receive or send), the TLS/ SSL library encountered an error.

V6.2-002 MR Manual June 09, 2015, Page 289 Action: Review the following TEXT message from the plug-in for additional diagnostic information, and adjust the environment accordingly.

## **TLSPARAM**

TLSPARAM, TLS parameter pppp eeee

Run Time Error: This indicates a problem with a parameter on a WRITE /TLS command. pppp identifies the parameter and eeee describes the problem.

Action: Address the reported problem described by eeee.

## **TLSRENEGOTIATE**

TLSRENEGOTIATE, Failed to renegotiate TLS/SSL connection

Run Time/MUPIP Error: This indicates that an attempt to renegotiate the SSL/TLS connection failed.

Action: Review the following TEXT message from the plug-in for additional diagnostic information, and adjust the environment accordingly.

#### **TLVLZERO**

TLVLZERO, Transaction is not in progress

Compile Time/Run Time Error: This indicates that a TCOMMIT, TROLLBACK, or TRESTART command attempted to change the state of the current transaction; however, a transaction was not in progress.

Action: Look for missing TSTARTs, extra TCOMMITs or TROLLBACKs, or an unanticipated flow of control; conditionalize the command on \$TLEVEL, if appropriate.

## **TMPFILENOCRE**

TMPFILENOCRE, Error in MUPIP BACKUP while trying to create temporary file xxxx

MUPIP Error: This indicates that MUPIP BACKUP was not able to create the temporary file xxxx needed in the course of its processing, possibly due to earlier incomplete backups.

Action: Make sure the temporary files are removed from the backup directory, and re-issue the BACKUP.

#### **TMPSTOREMAX**

TMPSTOREMAX, Maximum space for temporary values exceeded

Compile Time Error: GT.M uses 1024 temporary registers to hold intermediate results of expression evaluation. Because of the line-oriented nature of the M language, these temporary registers get reused for each line. This error indicates that there is a single calculation on a line that requires more than 1024 temporary registers.

Action: Look for excessive function nesting on a very long line of code. Reduce the amount of nesting by assigning intermediate results to a variable. Alternatively, if compiling the routine with the -DYNAMIC LITERALS qualifier, try compiling with -NODYNAMIC LITERALS.

#### **TNTOOLARGE**

TNTOOLARGE, Database file xxx has reached the transaction number limit (0xaaa). Renew database with MUPIP INTEG TN RESET

Run Time Information: This indicates that GT.M detected that the transaction numbers in the named database have reached the maximum number. There are 0xFFFFFFF ([2\*\*32 - 1] or 4,294,967,295 decimal) possible transaction numbers for V4 or 0xFFFFFFFFFFFF ([2\*\*64 - 1] or 18,446,744,073,709,551,615 decimal) possible transaction numbers for V5 version databases. Note that the actual maximum TN is less than this theoretical limit. DSE DUMP FILEHEADER shows what the limit is. The actual limit reflects some overhead used, for example, during a TN RESET operation.

Action: Use MUPIP INTEG with the qualifier TN RESET to reset the transaction numbers in the database. If the database is in the V4 format, consider converting it to the V5 format. The database cannot otherwise be used until the condition is removed by either a TN\_RESET or, if a V4 database, changing the output mode to V5 with MUPIP SET VERSION.

## **TNWARN**

**TNWARN**, Database file xxx has 0xaaa more transactions to go before reaching the transaction number limit (0xaaa). Renew database with MUPIP INTEG TN RESET

Run Time Information: This indicates that GT.M detected that the transaction numbers in the named database are approaching the maximum number. There are 0xFFFFFFF ([2\*\*32 - 1] or 4,294,967,295 decimal) possible transaction numbers for V4 or 0xFFFFFFFFFFF ([2\*\*64 - 1] or 18,446,744,073,709,551,615 decimal) possible transaction numbers for V5 version databases. This message is sent to the operator log periodically at decreasing intervals as the transaction number approaches the maximum. Note that the actual maximum TN is less than this theoretical limit. DSE DUMP FILEHEADER shows what the limit is. The actual limit reflects some overhead used, for example, during a TN\_RESET operation.

Action: Use MUPIP INTEG with the qualifier TN RESET to reset the transaction numbers in the database. If the database is in the V4 format, consider converting it to the V5 format.

## **TOOMANYCLIENTS**

**TOOMANYCLIENTS**, GT.M is serving the maximum number of clients. Try again later.

V6.2-002 MR Manual June 09, 2015, Page 291 Run Time Error: This indicates that the process failed in accessing a region served via GT.CM server, which currently cannot accept another connection. This is unlikely to happen unless many of the servers clients have abruptly disconnected and the server has been running for a long time.

Action: Try again later. Stop and restart the server to resolve the problem. If the problem persists, contact the group responsible for database operations on your network.

## **TOTALBLKMAX**

TOTALBLKMAX, Extension exceeds maximum total blocks, not extending

Run Time Error: This indicates that the database file extension specified implicitly or explicitly (using MUPIP EXTEND) would cause the GDS file to exceed the maximum size of 64 million blocks.

Action: Modify the extension to use a smaller size. This may indicate that you should move some contents of the database file to another file.

#### **TPFAIL**

TPFAIL, Transaction COMMIT failed. failure code: xxxx.

Run Time Error: This indicates that GT.M attempted to process this transaction four times, but encountered an error every time. xxxx contains the failure codes for the four attempts. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Report this database error to the group responsible for database integrity at your operation.

## **TPLOCK**

**TPLOCK**, Cannot release lock(s) held prior to current TSTART

Run Time Error: This indicates that a LOCK or ZDEALLOCATE command attempted to release named resources that were LOCKed or ZALLOCATEd prior to the initial TSTART of the current transaction.

Action: Do not release the named resource until after the TCOMMIT, or LOCK/ZALLOCATE has reserved the resource after the TSTART has begun.

## **TPLOCKRESTMAX**

Last used version: V5.5-000

TPLOCKRESTMAX, Transaction restarts due to unavailability of locks not allowed in a final TP retry more than nnnn times

Run Time Error: This indicated a timed LOCK within a transaction was consistently unavailable. In order to prevent the process from waiting for the LOCK while holding a database resource (critical section) the transaction has restarted nnnn times without success. This error limits the possibilities

**TPMIXUP** Chapter 1. Error Messages

for this issue cascading into a live-lock (consuming resources trying to do something that is "not happening").

Action: Analyze the locking protocol for issues of dead lock or unexpected LOCK durations and rework appropriately. Note that FIS recommends against using LOCKs within transactions, as GT.M protects the transaction integrity independent of LOCK protocols. If you wish to impose a conventional locking strategy for a transaction, place the LOCK and unlock around (outside) the transaction. While it is possible to use a LOCK within a transaction for signaling, that technique is typically problematic as it violates transactional Isolation and should likely be restricted to testing.

#### **TPMIXUP**

**TPMIXUP**, xxxx transaction cannot be started within yvvv transaction

Run Time Error: This indicates that the software, function, or routine may use incompatible transaction fencing.

Action: Transaction fences and ZT transaction fences cannot be used in combination. Review the code for incompatible use of T and ZT transaction fences.

## **TPNOSUPPORT**

**TPNOSUPPORT**, Operation cannot be performed while inside of a TP transaction

Run Time Error: This indicates that a \$\$set^%GBLDEF or \$\$kill^%GBLDEF was attempted while inside of a TP transaction (TSTART/TCOMMIT fence).

Action: ^%GBLDEF only supports TP from the \$\$get entry point; it does not support inclusion of \$\$set or \$\$kill entry points within a TP transaction.

# **TPNOTACID**

**TPNOTACID**, tttt at xxxx in a final TP retry violates ACID properties of a TRANSACTION; indefinite RESTARTs may occur

Run Time Information: GT.M issues this message if it is executing a TP TRANSACTION in the final retry and control gets transferred out of GT.M due to any one of the following three conditions:

- 1. ZSYSTEM command
- 2. Entering direct mode (e.g. due to a BREAK command) or
- 3. a long running command (those which accept timeout specifications) encountered potentially indefinite restarts. The xxxx indicates the \$ZPOSITION where the transfer of control occurred and the condition that caused this is identified in tttt.

Action: Review your code to determine whether the non-Isolated commands can be moved outside of transaction encapsulation. Alternatively, ensure that they are minimally disruptive by using

\$ZMAXTPTIME to prevent transactions from running unreasonably long times and setting gtm tpnotacidtime to specify the wait period for long running commands before GT.M logs a TPNOTACID message.



Because a process that gives a TPNOTACID message is in an indefinite restart, it might fail to produce an error indicating database damage should it encounter such an unlikely eventuality. In this case, indefinite restarts do not cause any additional damage.

# **TPQUIT**

**TPOUIT**, Cannot QUIT out of a routine with an active transaction

Run Time Error: This indicates that an implicit or explicit QUIT attempted to leave an invocation level where a transaction or subtransaction was TSTARTed but not matched by either a TCOMMIT or TROLLBACK.

Action: Modify the routine to TCOMMIT or TROLLBACK the transaction before QUITting, or move the TSTART to a prior invocation level.

# TPRESTART A

TPRESTART, Database mmmm; code: xxxx; blk: yyyy in glbl: zzzz; pvtmods: aaaa, blkmods: bbbb, blklvl: cccc, type: dddd, readset: eeee, writeset: ffff, local\_tn: gggg, zpos: hhhh

Run Time Information: The UNIX environment variables or OpenVMS logical names GTM\_TPRESTART\_LOG\_FIRST and GTM\_TPRESTART\_LOG\_DELTA control the logging of TPRESTART messages. GTM TPRESTART LOG FIRST indicates the number of TP restarts to log from GT.M invocation. Once that many have been logged, every GTM\_TPRESTART\_LOG\_DELTA TP restarts, GT.M logs a restart message. If GTM\_TPRESTART\_LOG\_DELTA is undefined, GT.M performs no operator logging. The default value for GTM TPRESTART LOG FIRST is 0 (zero), which leaves the control completely with GTM\_TPRESTART\_LOG\_DELTA. The facility that produces this message can serve as a diagnostic tool in developmental environments for investigating contention due to global updates. A zzzz of "\*BITMAP" indicates contention in block allocation which might involve multiple globals. hhhh is the \$ZPOSITION of the line of M code that caused the restart of the transaction; utilities leave this field blank.

Action: Disable, or adjust the frequency of, these messages with the mechanism described above. To reduce the number of restarts, consider changes to the global structure, varying the time when work is scheduled. Consider whether the business and program logic permits the use of NOISOLATION.

#### **TPRESTNESTERR**

**TPRESTNESTERR**, TP restart signaled while handing error - treated as nested error - Use TROLLBACK in error handler to avoid this

**TPSTACKCRIT** Chapter 1. Error Messages

Run Time Error: GT.M does not allow a TP restart to occur either explicitly or implicitly while doing error processing (\$ECODE is not NULL). Note that if a \$ZINTERRUPT interrupts an error handler, this restriction then extends to the \$ZInterrupt code even though \$ECODE is temporarily nullified for the duration of the \$ZInterrupt.

Action: Doing a TROLLBACK in the error handler before attempting to set any globals avoids this error.

#### **TPSTACKCRIT**

Last used version: V5.3-004A

TPSTACKCRIT, TP Stack space critical

Run Time Error: This indicates that a transaction has consumed almost all of the available stack space.

Action: Look for missing TCOMMIT commands. Modify the code to reduce the total change content of the transaction; pay special attention to recursion and variable usage.

## **TPSTACKOFLOW**

Last used version: V5.3-004A

TPSTACKOFLOW, TP Stack overflow

Run Time Error: This indicates that a transaction has consumed all of the available stack space. This error terminates the image.

Action: Modify the error handling for TPSTACKCRIT to prevent a subsequent TPSTACKOFLOW.

# **TPTIMEOUT**

#### **TPTIMEOUT**, Transaction timeout

Run Time Error: This indicates that the transaction took too long to process successfully. Timeouts prevent runaway processes, damage from software bugs, and transactions so large as to be hostile to other users.

Action: Review accompanying message(s) for more information about what caused the transaction timeout. If the transaction uses custom programs, routines, or functions, they may need to be debugged.

#### **TPTOODEEP**

TPTOODEEP, \$TLEVEL cannot exceed 127

Run Time Error: This indicates that a TSTART attempted to initiate more concurrent subtransactions than GT.M permits.

Action: Determine whether the transaction is implemented as designed. Modify the routine to reduce the levels of subtransaction nesting.

## **TRACEON**

**TRACEON**, Missing global name (with optional subscripts) to dump M-tracing information into

Compile Time Error: This indicates that no global variable was supplied on a VIEW "TRACE":1:"^gvn".

Action: Supply the global variable.

## **TRACINGON**

TRACINGON, Tracing already turned on

Run Time Information: This indicates that M profiling is already turned on when a command was issued to turn tracing on.

Action: -

#### **TRANS2BIG**

TRANS2BIG, Transaction exceeded available buffer space for region rrrr

Run Time Error: This indicates that a transaction updated more blocks than the global buffer could hold for a particular region rrrr or accessed more than the single transaction limit of 64K blocks.

Action: Look for missing TCOMMIT commands; modify the code to reduce the total content or change content of the transaction. If the transaction is as intended and the issue is the number of updates, increase the GLOBAL BUFFERS for the region using MUPIP SET, or modify the Global Directory to redistribute the relevant globals to more regions.

#### **TRANSMINUS**

**TRANSMINUS**, Negative numbers not allowed with ZTCOMMIT

Run Time Error: This indicates that a ZTCOMMIT must have a zero (0) or positive integer argument.

Action: Modify the ZTCOMMIT argument.

## **TRANSNEST**

TRANSNEST, Maximum transaction nesting levels exceeded

Run Time Error: This indicates that a ZTSTART failed an attempt to establish another level of nested subtransactions.

Action: Rework the application so that it requires no more than 255 levels of journal transaction nesting.

#### **TRANSNOSTART**

TRANSNOSTART, ZTCOMMIT(s) issued without corresponding ZTSTART(s)

Run Time Error: This indicates that a ZTCOMMIT specified an explicit number of ZTSTARTs to close that exceeded the number of ZSTARTs that were currently open.

Action: Use ZTCOMMIT with an argument of 0 to close all open transactions, or modify the ZTCOMMIT to use a positive integer argument that does not exceed the number of open ZTSTARTs.

#### **TRESTLOC**

TRESTLOC, Transaction start: xxxx, Transaction failure: yyyy

Run Time Error: This indicates that GT.M detected a resource conflict that attempted to RESTART a transaction that did not enable RESTART. This message follows TRESTNOT error message, xxxx is the starting location for the transaction and yvyy is the point of failure.

Action: Enable RESTART with the initial TSTART command argument, or add external LOCKs to serialize the transaction.

#### **TRESTMAX**

TRESTMAX, TRESTART not allowed in a final TP retry more than once

Run Time Error: The code contained one or more explicit TRESTART command(s) which called for a RESTART after more than once after \$TRESTART reached 3. Once \$TRESTART reaches 3, GT.M switches from an optimistic to a conventional locking strategy so such restarts are expensive and potentially disruptive. Therefore GT.M limits the ability of the application code to repeatedly demand such RESTARTs.

Action: Investigate the cause and reason(s) for the explicit restart. When combined with a subsequent TROLLBACK, explicit TRESTARTs may provide a way to manipulate the variable context and flow of control in useful ways, but other uses are unusual. If explicit TRESTARTs are appropriate, consider whether they should be conditional on the value of \$TRESTART.

## **TRESTNOT**

**TRESTNOT**. Cannot TRESTART, transaction is not restartable

Run Time Error: This indicates that a TRESTART command attempted to RESTART a transaction that did not enable RESTART; the error occurs at the point of the initial TSTART, so all global updates within the transaction are rolled back and any local variables specified have their values as of the TSTART.

Action: Enable RESTART with the initial TSTART command argument, add external LOCKs to serialize the transaction, or eliminate the TRESTART command.

## TRIG2NOTRIG

**TRIG2NOTRIG.** Sending transaction sequence number xxxx which used triggers to a replicator that does not support triggers

MUPIP Warning: The source server encountered a transaction that includes triggers, but its replicating node does not support triggers. Unless you are using application level filters to handle this case, your originating instance and replicating instance are no longer consistent.

Action: If this case it not handled by your application level filters, you should either enhance your filters or upgrade the replicating instance to a version of GT.M that supports triggers and load the the appropriate trigger definitions with MUPIP TRIGGER (or \$ZTRIGGER()), and then take appropriate action (such as recreating the replicating instance from a backup of the originating instance) to restore consistency.

#### TRIGCOMPFAIL

TRIGCOMPFAIL, Compilation of database trigger named tttt failed

Trigger/Run Time Error: The -Xecute code of a trigger specification has syntax errors. Because triggers are precompiled when you define them, this error may indicate that either:

- A database upgrade was performed but the trigger code was not updated to eliminate obsolete syntax
- The portion of the database holding the trigger definitions may be corrupted

Action: Validate the definitions by a SELECT option with MUPIP TRIGGER or \$ZTRIGGER(), correct the trigger code syntax and apply a trigger update.

#### **TRIGDATAIGNORE**

TRIGDATAIGNORE, Ignoring trigger data tttt. Use MUPIP TRIGGER to load trigger definitions

MUPIP Information: MUPIP LOAD displays this warning when it encounters trigger metadata during extract file processing (GO/ZWR extracts).

Action: Identify and remove trigger metadata information from GO/ZWR extract files and, if appropriate, process it with MUPIP TRIGGER or \$ZTRIGGER().

#### **TRIGDEFBAD**

**TRIGDEFBAD**, Trigger initialization failed for global ^gggg. Error while processing ^#t("xxxx",yyyy[,zzzz])

Trigger/MUPIP Error: Missing or corrupted trigger metadata causes this error.

Action: Delete and replace defective triggers. If possible analyze the cause of the trigger damage and report the incident to your GT.M support channel.

## **TRIGDEFNOSYNC**

**TRIGDEFNOSYNC**, Global 'gggg has triggers defined on the [originating/replicating] instance but none on the [replicating/originating] instance. Current journal sequence number is 0xjjjj

Update Process log/Trigger Warning: The Update Process detected that there is a mismatch in trigger definitions for global gggg between originating and replicating instances and sent this warning to the operator log.

Action: Differences in triggers between originating and replicating instances typically mean the replicating instance is not in a position to stand in as a system of record by becoming an originating instance. Unless the difference is intended because of a special use of the replicating instance, shutdown and resynchronize the replicating instance.

#### TRIGINVCHSET

TRIGINVCHSET, Trigger tttt for global gggg was created with CHSET=cccc which is different from the current \$ZCHSET of this process

Trigger/Run Time Error: TRIGINVCHSET occurs when a process invokes a trigger on a global using a \$ZCHSET that is different from the \$ZCHSET used at the time of loading the first trigger on that global. GT.M implicitly uses the \$ZCHSET of the first trigger on a global to invoke all triggers on that global. Note that tttt is the name of the first trigger on the global gggg-not necessarily the name of the trigger being invoked. cccc is the \$ZCHSET of the process at the time of loading tttt on global gggg.

Action: Ensure that the process invoking a trigger on a global uses the same \$ZCHSET that was used to load the first trigger on that global. If your application requires triggers in both M and UTF-8 modes, use different globals to load M mode and UTF-8 mode triggers.

## **TRIGIS**

TRIGIS, Trigger name: tttt

Trigger/Run Time Information: This message identifies a trigger name

Action: Refer to the accompanying message(s) for more information.

#### TRIGLOADFAIL

TRIGLOADFAIL, MUPIP TRIGGER or \$ZTRIGGER operation failed. Failure code: xxxx

Trigger/Run Time Error: This indicates that a trigger install (using \$ZTRIGGER() or MUPIP TRIGGER) encountered a database problem when it attempted to update a global variable, xxxx contains the

failure codes for the four attempts as documented in section R2 of the Maintaining Database Integrity chapter in the Administration and Operations Guide. It is very likely that the database may have integrity errors or that the process-private data structures are corrupted.

Action: Report this database error to the group responsible for database integrity at your operation

#### TRIGMODINTP

TRIGMODINTP, Triggers for a given global cannot be both used and modified or removed in the same transaction

Run Time Error: Once a transaction has used any trigger on any node associated with a given global name (the part of the variable designation between the up-arrow (^) and the left-parenthesis ("(") (or end if there's no subscript), you cannot use that same transaction to modify definitions for any trigger associated with that global name.

Action: Rework the transaction and \$ZTRIGGER() relationship to avoid this issue.

## TRIGMODREGNOTRW

TRIGMODREGNOTRW, Trigger(s) cannot be added/changed/deleted because region rrrr is read-only

Run Time Error: This error occurs when \$ZTRIGGER() or MUPIP TRIGGER attempts to write to readonly region rrrr.

Action: Check for appropriate global directory mapping and appropriate permissions on the database file mapped to region rrrr.

#### TRIGNAMBAD

**TRIGNAMBAD**, Trigger initialization failed. Error while processing ^#t(tttt,cccc)

Run Time/MUPIP Error: A trigger operation encountered a trigger definition for trigger with an apparent internal inconsistency while looking for characteristic cccc of type tttt.

Action: Delete and redefine the trigger in question. Consult with the group responsible for database integrity at your operation to discuss what actions might have led to this error.

#### **TRIGNAMENE**

**TRIGNAMENF**, Trigger name nnnn not found with the current default global directory

Run Time/MUPIP Error: This message indicates a trigger lookup by name failed. GT.M has a name cross reference in the default region of the current global directory. If you use multiple global directories with different default regions, trigger lookups by name, such as \$ZTRIGGER(), ZBREAK and ZPRINT, only work when they use the same default region as the one in use at the time of the trigger definition.

TRIGNAMEUNIQ Chapter 1. Error Messages

Action: Consider using a SET \$ZGBLDIR to change to an appropriate global directory when using name lookup. Also consider restructuring your global directories so they share a common default region.

# **TRIGNAMEUNIQ**

TRIGNAMEUNIO, Unable to make trigger name tttt unique beyond vvvv versions already loaded

Trigger/Run Time Error: GT.M encountered more than vvvv different instances of the same trigger name across database regions used by the same process.

Action: Revise trigger names to prevent such a high degree of overlap.

#### TRIGNOSPANGBL

TRIGNOSPANGBL, Triggers cannot be installed/deleted for global name gggg as it spans multiple regions in current global directory

Run Time Error: This indicates that the global gggg spans multiple regions and therefore cannot have triggers installed or deleted in its name.

Action: Triggers are not currently supported for globals that span multiple regions.

# **TRIGREPLSTATE**

TRIGREPLSTATE, Trigger cannot update replicated database file dddd since triggering update was not replicated

Run Time Error: A process performed an update on a global in a database region which is not currently replicated, and that update invoked a trigger that, in turn, attempted an update on a global in a database region that is replicated. This would produce a journal state with insufficient information to properly recover the replicated region.

Action: Investigate whether the global directories, journaling characteristics or trigger logic need revision.

## **TRIGSUBSCRANGE**

**TRIGSUBSCRANGE**, Trigger definition for global ^gggg has one or more invalid subscript range(s): SSSS

Error: GT.M/MUPIP error: This error indicates one or more subscript range(s) of order given the current collation subscript ordering - for global gggg in the trigger definition files.

Action: Verify the validity of subscript ranges in trigger definition file for the particular global, taking its collation into account, and redefine the trigger with correct subscript ranges for the collation of the global in question.

## **TRIGTCOMMIT**

**TRIGTCOMMIT**, TCOMMIT at \$ZTLEVEL=LLLL not allowed as corresponding TSTART was done at lower \$ZTLEVEL=BBBB

Trigger/Run Time Error: A TCOMMIT in trigger logic attempted to complete the active transaction that was started outside of the current trigger. Because trigger actions are atomic with the update initiating them, committing a transaction started prior to or by the triggering update cannot be committed inside the trigger.

Action: Within the trigger context, review the TCOMMIT logic to ensure that it commits only those transactions that are started within the trigger. Ensure that TCOMMIT does not attempt to commit any transaction started prior to or by the triggering update.

#### **TRIGTLVLCHNG**

**TRIGTLVLCHNG**, Detected a net transaction level (\$TLEVEL) change during trigger tttt. Transaction level must be the same at exit as when the trigger started

Trigger/Run Time Error: While the trigger logic can use balanced sub-transactions, it cannot cause a net change in \$TLEVEL.

Action: Review the transaction management (TSTART, TCOMMIT and TROLLBACK) within trigger logic to ensure that it commits or rolls back any transactions it starts and does not attempt to commit any transaction started prior to, or by, the trigger update. You can use TROLLBACK within trigger logic to block the current transaction, possibly to write error context information. Nonetheless if you use such a TROLLBACK, GT.M subsequently signals this error when you leave the trigger context in order to notify the process that the original triggering update has been discarded.

#### TRIGUPBADLABEL O

**TRIGUPBADLABEL**, Trigger upgrade cannot upgrade label NNNN to CCCC on ^GGGG in region RRRR

MUPIP Error: MUPIP TRIGGER UPGRADE cannot upgrade trigger version number NNNN to the current version number CCCC for the global GGGG in region RRRR.

Action: Reload the triggers in region RRRR.

#### TRIGZBREAKREM

TRIGZBREAKREM, ZBREAK in trigger tttt removed due to trigger being reloaded

Run Time Warning: This indicates your process had a ZBREAK defined within the XECUTE code for trigger tttt, but some action replaced the definition for trigger tttt so GT.M removed the ZBREAK.

Action: If appropriate examine the trigger with ZPRINT and reestablish the ZBREAK. The message is tied to BREAKMSG mask 16 (See VIEW BREAKMSG). The default message mask is 31, which includes

masks 1, 2, 4, 8, and 16. Using the VIEW command to set the BREAKMSG mask to 7 or any other pattern that excludes 16, disables this message.

#### **TRNLOGFAIL**

TRNLOGFAIL, Translation of [OpenVMS] logical name or [UNIX] environmental variable xxxx failed

Compile Time Error: This indicates that translation of the indicated environment variable (UNIX)/ logical name (OpenVMS) failed. The message is accompanied with another message describing the failure type and the reason behind it. Most probable cause of the failure could be resource limitation.

Action: Report to your system administrator.

## TROLLBK2DEEP

**TROLLBK2DEEP**, Intended rollback (xxxx) deeper than the current \$tlevel (yyyy)

Run Time Error: This indicates that an attempt to TROLLBACK more levels (as indicated by \$TLEVEL) of transaction nesting than are currently active.

Action: Review the logic and code path that led to the error and modify the code appropriately.

## TRUNCATE

Last used version: V4.3-001F

TRUNCATE, Error while truncating jnl-file xxxx to length aaaa

Run Time Error: This message is issued by Recovery/Rollback process when it is unable to truncate the journal file at the end of recovery. The journal file remains in the same state as it was before the processing and may contain incomplete data, in case of a GT.M crash.

Action: Look into the secondary error message and if necessary report the entire incident context to your GT.M support channel for further analysis.

## **TRUNCATEFAIL**

TRUNCATEFAIL, Truncating xxxx from aaaan OpenVMS blocks to bbbb blocks failed

MUPIP Error: This indicates that a MUPIP BACKUP copied a database that extended during the copy and the attempt to return it to the proper size failed.

Action: Examine the subsequent message for more information. It maybe possible to make the copy usable by performing a MUPIP EXTEND to the actual (current) size take the GDS blocks from the extension size in the file header, and verify the same against the reported RMS blocks. You will need to rename the file since the file in this state will have a temporary file name rather than the expected name from the BACKUP.

V6.2-002 MR Manual

#### **TSTRTPARM**

TSTRTPARM, Error parsing TSTART qualifier

Compile Time Error: This indicates that the TSTART specified an improperly formatted argument.

Action: Modify the TSTART argument.

## **TTINVFILTER**

TTINVFILTER, Invalid FILTER argument

Run Time Information: This indicates that the FILTER= deviceparameter appeared in a device command for a terminal with an argument that evaluated to something other than "[NO]CHARACTERS" or "ESCAPE", which are the only valid arguments.

Action: Remove or rework the FILTER=.

## **TTLENGTHTOOBIG**

TTLENGTHTOOBIG, Terminal LENGTH exceeds the maximum allowed limit

Run Time Error: The LENGTH specified is too large for a terminal device. The maximum page length is 255.

Action: Modify the USE to specify a smaller LENGTH.

# **TTWIDTHTOOBIG**

TTWIDTHTOOBIG, Terminal WIDTH exceeds the maximum allowed limit

Run Time Error: The WIDTH specified is too large for a terminal device. The maximum page width is 511.

Action: Modify the USE to specify a smaller WIDTH.

## **TXTNEGLIN**

TXTNEGLIN, A line prior to line number zero was referenced in \$TEXT

Run Time Error: This indicates that a \$TEXT function argument referenced a line that preceded program source line zero.

Action: Verify that \$TEXT() arguments evaluate to zero (0) or to a line subsequent to the beginning of the routine.

# **TXTSRCFMT**

TXTSRCFMT, \$TEXT encountered an invalid source program file format

Run Time Error: This indicates that a \$TEXT function encountered an improperly formatted source file. This error only occurs when the source file has been corrupted.

Action: Use a host system command to examine the source file. Determine whether the source file was properly maintained.

## **TXTSRCMAT**

TXTSRCMAT, M object module and source file do not match

Run Time Error: This indicates that a \$TEXT function referenced a routine whose source file does not correspond to the current object file. ZPRINT may deliver this message as a warning.

Action: ZLINK the source file or use host shell commands to rearrange the current source file to match the object file.

## **UIDMSG**

**UIDMSG**, Unidentified message received

Run Time Error: This indicates that the process was performing a JOB command and received an unanticipated message while attempting to communicate with the JOBbed process.

Action: Look for indiscriminate mailbox use by other processes.

#### **UIDSND**

UIDSND, Unidentified sender PID

Run Time Error: This indicates that the process was performing a JOB command and received a message from an unidentified source while attempting to communicate with the JOBbed process.

Action: Look for indiscriminate mailbox use by other processes.

## **UNDEF**

**UNDEF.** Undefined local variable: xxxx

Run Time Error: This indicates that an expression referenced a local variable xxxx, that was not defined.

Action: Ensure that all variables are assigned values before they are referenced; use \$GET(), or change the image or process to NOUNDEF mode.

V6.2-002 MR Manual

# **UNIMPLOP**

**UNIMPLOP**, Unimplemented construct encountered

Run Time Error: This indicates that GT.M encountered an unsupported data type while passing arguments between typed C and type-less M.

Action: Review the call-in table and ensure that the parameter types match the following table:

Directions	Allowed Parameter types
I	gtm_long_t, gtm_ulong_t, gtm_float_t, gtm_double_t,_gtm_long_t*, gtm_ulong_t*, gtm_float_t*, gtm_double_t*,_gtm_char_t*, gtm_string_t*
O/IO	gtm_long_t*, gtm_ulong_t*, gtm_float_t*, gtm_double_t*,_gtm_char_t*, gtm_string_t*

#### UNKNOWNFOREX

UNKNOWNFOREX, Process halted by a forced exit from a source other than MUPIP

Run Time Warning: This indicates that a process has been terminated by a source (usually a user program) other than MUPIP.

Action: Investigate why an operator or program is stopping GT.M processes without using MUPIP STOP.

#### **UNSDCLASS**

**UNSDCLASS**, Unsupported descriptor class

Run Time Error: This indicates that an external call or \$ZCALL function encountered an unsupported argument-passing mechanism in the external call table.

Action: Make sure the argument-passing mechanism is spelled correctly in the external call table.

## **UNSDDTYPE**

**UNSDDTYPE**, Unsupported descriptor data type

Run Time Error: This indicates that an external call or \$ZCALL function encountered an unsupported data type in the external call table.

Action: Review the external call table for invalid data types.

# UNSOLCNTERR

UNSOLCNTERR, An unsolicited error message has been received from the network

Run Time Error: This indicates that a GT.CM component received a network message from an unknown source.

Action: Ensure that no agents outside the GT.CM environment are improperly sending messages to GT.CM.

# **UPDATEFILEOPEN**

**UPDATEFILEOPEN**, Update file open error

Run Time Error: This indicates that file permissions were either set incorrectly or replication was turned off.

Action: Review accompanying message(s) for addition information. Correcting accompanying messages should correct this message.

# **UPDPROC**

**UPDPROC**, Update Process error

MUPIP Error: GT.M replication was not able to start the update process.

Action: Ensure that the gtm dist environment variable points to a valid GT.M distribution that is executable by the user.

## **UPDREPLSTATEOFF**

**UPDREPLSTATEOFF**, Error replicating global gggg as it maps to database xxxx which has replication turned OFF.

MUPIP Error: This indicates that the update process encountered an update record in the replication pipe that is destined for a non-replicated database file. GT.M does not allow such updates because they make the journal sequence numbers go out of sync between the replication primary and secondary. After issuing the message, the update process shuts down immediately. No more updates are processed on the secondary until replication is turned ON in the mentioned database file.

Action: Shut down the secondary instance including the receiver server, passive source server and any other helper processes accessing this instance. Turn replication ON in the mentioned database. Restart the secondary instance. The update process should now be able to process the update successfully.

## **UPDSYNC2MTINS**

UPDSYNC2MTINS, Can only UPDATERESYNC with an empty instance file

MUPIP Error: Issued by a Receiver Server started with the -UPDATERESYNC qualifier on a nonsupplementary instance or on a Supplementary Instance started specifying the -UPDNOTOK qualifier, when the replication instance file on the Receiver side contains at least one history record. The purpose of -UPDATERESYNC is to unconditionally declare the instance state as a valid state in the set of current and prior states of the originating instance disregarding any history. Note that the receiver server on a Supplementary Instance started with -UPDOK does not issue this error.

Action: Verify that -UPDATERESYNC is appropriate and if so, recreate the instance file to discard the history then reissue the command. If the replication state is not a valid match to some available current or prior state of the originating instance, either do a normal resync or refresh the replicating instance to an appropriate state.

## **UPDSYNCINSTFILE**

**UPDSYNCINSTFILE**, Error with instance file name specified in UPDATERESYNC qualifier

Receiver Server log/MUPIP Error: Issued by a Receiver Server when started with the -UPDATERESYNC qualifier in case of any error while processing the instance file specified as a value to this qualifier.

Action: An accompanying message, usually a GTM-I-TEXT message, describes the particular error situation. Take appropriate corrective action based on that.

#### USRIOINIT

**USRIOINIT**, User-defined device driver not successfully initialized

Run Time Error: This indicates that a user-implemented mnemonicspace driver image did not call the initialization entry in GT.M.

Action: Modify the user-supplied image to adhere to the mnemonicspace image-calling convention.

## **VALTOOBIG**

VALTOOBIG, xxxx is larger than the maximum of yyyy for a zzzz

GDE Error: This indicates that GDE has encountered a qualifier value that exceeds the maximum allowed. xxxx is the value that is too big. yyyy is the maximum value accepted. zzzz is the qualifier.

Action: Specify a qualifier value that is less than the maximum allowed.

## VALTOOLONG

**VALTOOLONG**, xxxx exceeds the maximum length of yyyy for a zzzz

GDE Error: This indicates that GDE encountered a value that exceeds the maximum length allowed for an object name or qualifier. xxxx is the value that is too long, yyyy is the maximum length, zzzz is the object-name or qualifier.

V6.2-002 GT.M Message and Recovery Procedures Manual VALTOOSMALL Chapter 1. Error Messages

Action: Specify an object-name or qualifier that is shorter than the maximum length.

# **VALTOOSMALL**

VALTOOSMALL, xxxx is less than the minimum of yyyy for a zzzz

GDE Error: This indicates that GDE encountered a value that is less than the minimum allowed for a qualifier. xxxx is the value that is too small. yyyy is the minimum limit. zzzz is the object-name or qualifier.

Action: Specify a value that is larger than the minimum requirement for the object-name or qualifier.

# **VALUEBAD**

VALUEBAD, xxxx is not a valid yyyy

GDE Error: This indicates that GDE encountered something other than the valid syntax element it was expecting. xxxx is the invalid element. yyyy is the valid element type.

Action: Specify a valid element. This error occurs if GDE is expecting an element (such as a filespecification, qualifier, or number) but receives a value that does not evaluate to the expected element type.

# **VALUEREQD**

VALUEREQD, Qualifier xxxx requires a value

GDE Error: This indicates that GDE encountered a qualifier with a missing value. xxxx is the qualifier with a missing value.

Action: Supply a value for the qualifier.

#### **VAREXPECTED**

**VAREXPECTED**, Variable expected in this context

Compile Time Error: This indicates that GT.M expected a variable but encountered an invalid one.

Action: Look for proper variable names. This error is reported by commands and functions that require a variable argument such as SET and KILL and \$DATA() and \$QUERY().

## VARRECBLKSZ

VARRECBLKSZ, Blocksize must be at least record size + 4 bytes

Run Time Error: This indicates that an OPEN command attempted to initialize a variable-length magnetic tape or sequential disk file with a RECORDSIZE of less than 5 bytes.

Action: Modify the routine to use a larger record size or use FIXED length records. The minimum variable RECORDSIZE reflects a single byte of data and 4 bytes of overhead in every variable-length record.

#### **VERIFY**

**VERIFY**, Verification xxxx

GDE Information: This indicates that an EXIT or VERIFY command caused GDE to verify the GDE mappings. xxxx is "OK" if the verification was successful or "BAD" if the verification failed.

Action: If the mappings are valid, GDE displays a confirmation message. GDE terminates the GDE session if the verification is OK on an EXIT command. If the mappings are not valid, review the accompanying message(s) for additional information.

#### **VERMISMATCH**

**VERMISMATCH**, Attempt to access xxxx with version yyyy, while already using zzzz

Run Time Error: This indicates that two different versions of GT.M attempted to access the same database at the same time.

Action: Update GT.M so that both systems use the same version of GT.M.

#### **VERSION**

**VERSION**, Version mismatch - This program must be recompiled

Run Time Error: This indicates that the process attempted to activate a routine that was compiled with an incompatible version of GT.M.

Action: Recompile the routine or use a compatible version of GT.M.

#### **VIEWAMBIG**

**VIEWAMBIG**, View parameter xxxx is ambiguous

Run Time Error: This indicates that the argument xxxx for a VIEW command or \$VIEW function is ambiguous due to insufficient characters.

Action: Add enough characters to make the argument unambiguous.

#### VIEWARGENT

**VIEWARGCNT**, View parameter xxxx has inappropriate number of subparameters

**VIEWCMD** Chapter 1. Error Messages

Run Time Error: The argument xxxx for a VIEW command or a \$VIEW function has too many or too few sub-arguments.

Action: Modify the argument so it has the proper number of sub-arguments.

#### **VIEWCMD**

**VIEWCMD**, View parameter is not valid with VIEW command

Run Time Error: This indicates that the VIEW command has an argument that is only valid with the \$VIEW function.

Action: Modify the argument.

#### **VIEWFN**

**VIEWFN**, View parameter is not valid with \$VIEW()

Run Time Error: This indicates that the \$VIEW function has an argument that is only valid with the VIEW command.

Action: Modify the argument.

## **VIEWGVN**

**VIEWGVN**, Invalid global key name used with VIEW/\$VIEW(): xxxx

Run Time Error: This indicates that \$VIEW("REGION":gvn) failed because of an invalid global variable name xxxx in a sub-argument.

Action: Modify the sub-argument to be a valid M global variable name.

## **VIEWLVN**

**VIEWLVN**, Invalid local variable name used with VIEW or \$VIEW(): vvvv

Run Time Error: This indicates the argument for a VIEW command or \$VIEW() function required a local variable name, but it (vvvv) was either missing or invalid.

Action: Correct the code in or investigate the logic to determine why the local variable in question is not in the expected state.

#### VIEWNOTFOUND

**VIEWNOTFOUND**, View parameter xxxx not valid

Run Time Error: This indicates that the VIEW command or \$VIEW() function has an invalid argument XXXX.

V6.2-002 MR Manual

Action: Modify the argument.

#### **VMSMEMORY**

VMSMEMORY, Central memory exhausted - check page file quota and page file size

Run Time Error: This indicates that programs are requesting more memory than the system can provide with the current PAGEFILE settings.

Action: Adjusting the pagefile size and quota can increase memory efficiency. Refer to the Guide to VAX/OpenVMS Performance Management to determine appropriate pagefile settings.

#### VMSMEMORY2

**VMSMEMORY2**, Central storage exhausted during allocation of dynamic file descriptor with !UL bytes - check page file quota and page file size

Run Time Error: In OpenVMS, dynamic file descriptors used in external routine processing have their space allocated differently from other VMS memory. If one of these special allocations fails, this new version of the VMSMEMORY error is reported.

Action: Adjusting the pagefile size and quota can increase memory efficiency. Refer to the Guide to VAX/OpenVMS Performance Management to determine appropriate pagefile settings.

#### WAITDSKSPACE

**WAITDSKSPACE**, Process xxxx will wait aaaa seconds for necessary disk space to become available for yyyy

Run Time Error: This indicates that the database yyyy is full and cannot extend due to lack of space. All updates are suspended. Failure to address this message in the specified seconds will result in an OUTOFSPACE error.

Action: Immediately make enough space for the database to extend, and if the space is still not sufficient, stop all processes until more space is available. Examine your space management procedures and take actions to prevent any reoccurrence of this error.

#### **WCBLOCKED**

WCBLOCKED, Field xxxx is set by process yyyy at transaction number aaaa for database file zzzz

MUPIP Warning: This indicates that the current state of the global buffer cache necessitates the need for cache recovery. The next process to attempt obtaining the critical lock on the database will perform the recovery.

Action: Refer to the accompanying message(s).

## **WCERRNOTCHG**

WCERRNOTCHG, Not all specified databases were changed

MUPIP Error: This indicates that SET could not modify database characteristics for at least one database.

Action: Review the accompanying message(s) for additional information.

## **WCFAIL**

WCFAIL, The database cache is corrupt

Run Time Error: This indicates that a database operation failed because the cache was damaged.

Action: Report this database cache error to the group responsible for database integrity at your operation.

## **WCWRNNOTCHG**

WCWRNNOTCHG, Not all specified databases were changed

MUPIP Warning: This indicates that a SET command could not modify database characteristics for a particular database.

Action: Review the accompanying message(s) for additional information.

## WEIRDSYSTIME Q

WEIRDSYSTIME, Time reported by the system clock is outside the acceptable range. Please check and correct the system clock.

Run Time Error: Time reported by the system clock is outside the acceptable range. Please check and correct the system clock

Action: GT.M requires the system time be set between January 1, 1970 00:00:00 UTC (the UNIX epoch) and September 27, 33658 01:46:40 UTC

## **WIDTHTOOSMALL**

WIDTHTOOSMALL, WIDTH should be at least 2 when device ICHSET or OCHSET is UTF-8 or UTF-16.

Run Time Error: This error is issued whenever the ICHSET or OCHSET of the current terminal or file device is UTF-8 or UTF-16 and the WIDTH specified is 1. The minimum width allowed is 2 for such devices.

Action: Specify a width that is 2 or greater.

# WILDCARD

WILDCARD, Wild cards are prohibited: xxxx

Run Time Error: This indicates that a \$ZROUTINES function that does not allow wild cards encountered one in xxxx.

Action: Replace the wild card with a specific directory name.

# WRITEERROR

WRITEERROR, Cannot exit because of write failure. Reason for failure: xxxx.

GDE Error: This indicates that GDE was unable to write a new or revised global directory, xxxx text describes the failure.

Action: Review the text for additional information. If the failure is due to file permissions, it may be possible to correct it from the shell, accessed by means of the SPAWN command or another session. If the reason is not tractable, QUIT from GDE and re-invoke it after correcting the problem.

#### WRITERSTUCK

WRITERSTUCK, Buffer flush stuck waiting for [xxxx] concurrent writers to finish writing to database file aaaa

Run Time Error: This indicates that GT.M timed out after waiting nearly a minute for concurrent processes to complete flushing modified global buffers to the disk.

Action: This is usually symptomatic of a stressed I/O subsystem, where disk writes take a long time. System Administration might be warranted to improve the performance.

## WRITEWAITPID

WRITEWAITPID, PID wwww waited mmmm minute(s) for PID hhhh to finish writing block bbbb in database file ffff

Run Time Warning: This operator log message indicates process wwww needed access to block bbbb in database file ffff, but had waited mmmm minutes for process hhhh to finish with that block. mmmm exceeds the expected design criteria for the processing by hhhh.

Action: Investigate the state and activities of process hhhh (possibly using the gtm\_procstuckexec facility); try to identify any coincident operating system, file system or storage sub-system issues that might contribute to this unexpected behavior.

V6.2-002 GT.M Message and Recovery Procedures Manual

## **XCVOIDRET**

**XCVOIDRET**, Attempt to return a value from function xxxx, which is declared void in external call table yyyy

Run Time Error: This indicates that the specified function was typed as void in call table yyyy, but when the function was executed it attempted to return a value.

Action: Modify either the function to make it void, or the table to declare the proper type for the function.

## **XKILLCNTEXC**

XKILLCNTEXC, Maximum number of arguments (xxxx) to exclusive kill exceeded

Compile Time Error: This indicates that a KILL command specified a list of exclusive arguments that require more temporary storage than is available. xxxx is the number of KILL arguments.

Action: Modify the routine to use an inclusive KILL or reduce the number of "protected" variables.

#### **XTRNRETSTR**

XTRNRETSTR, Return string from extended reference translation algorithm is NULL.

Run Time Error: This indicates that NULL was returned instead of a string from the user specified global variable name environment translation routine.

Action: Correct the user environment translation algorithm to return a string (which can be emtpy). Restart GT.M for the changes to become effective.

## **XTRNRETVAL**

XTRNRETVAL, Length of return value from extended reference translation algorithm is out of bound

Run Time Error: This indicates that the return string from the user specified global variable name environment translation routine is of an invalid length (i.e. greater than 32767).

Action: Correct the user environment translation algorithm to return a string of valid length (in the 0-32767 range). Restart GT.M for the changes to become effective.

#### **XTRNTRANSDLL**

XTRNTRANSDLL, Error during extended reference environment translation. Please check the above message.

Run Time Error: This indicates that the external object (dynamically linked library in UNIX /sharable image in OpenVMS), which holds the global variable name environment translation routine, or the entry point gtm env translate in this object, is not accessible.

Action: Check if the value of the gtm env translate (UNIX: environment variable, OpenVMS: logical name) points to a valid object (UNIX: dll or OpenVMS: sharable image), which has the entry point gtm env translate.

## **XTRNTRANSERR**

XTRNTRANSERR, Error attempting to generate an environment using an external algorithm.

Run Time Error: This indicates that the external environment translation routine returned an error.

Action: Check the external routine and the conditions it errors on. A supplementary TEXT message is printed if more information is provided by the external environment translation routine.

## **ZATTACHERR**

## **ZATTACHERR**, Error attaching to xxxx

Run Time Error: This indicates that a ZATTACH command failed because the argument specified a process xxxx that did not exist or was otherwise ineligible for attachment.

Action: Verify that the process exists within the job. Verify the spelling of the process name.

## **ZBREAKFAIL**

**ZBREAKFAIL**, Could not set breakpoint at xxxx due to insufficient memory

Run Time Information: This indicates that a ZBREAK command failed to set a breakpoint at the entry reference xxxx due to lack of memory. No breakpoint will be effective when control reaches the given entry reference.

Action: Check for very large local variables. The memory requirement for ZBREAK is proportional to the size of the routine containing the entry reference. If the routine is large, divide the routine into smaller routines thereby reducing the memory requirement for ZBREAK. If appropriate, increase the memory quota for the user.

## **ZCALLTABLE**

**ZCALLTABLE**, External call: Table format error

Run Time Error: This indicates that an external call or \$ZCALL() function encountered an error in the external call table.

Action: Modify the external call table. This message is usually displayed with another message.

# **ZCARGMSMTCH**

**ZCARGMSMTCH**, External call: Actual argument count, xxxx is greater than formal argument count, уууу

Run Time Error: This indicates that an external call or \$ZCALL() function specified xxxx arguments, which is more than the number yyyy, which is defined by the corresponding external call table entry.

Action: Ensure that the number of arguments in the external call matches the number of arguments in the external call table.

## **ZCCLNUPRTNMISNG**

ZCCLNUPRTNMISNG, External call: Cleanup routine name missing. Cannot continue

Run Time Error: This error occurs when there is no value assigned to the GTMSLIBEXIT (shared library exit handler keyword) in the external call table.

Action: Either remove the line that contains GTMSLIBEXIT= or provide a suitable function name in the external call table.

# **ZCCOLON**

**ZCCOLON**, Colon expected but not found

Run Time Error: This indicates that there is a syntax error in the table designated by the accompanying message.

Action: Refer to the accompanying message(s) and correct the syntax error.

#### **ZCCONMSMTCH**

**ZCCONMSMTCH**, External call: Too many input arguments

Run Time Error: This indicates that an external call or \$ZCALL() function specifies more input arguments than the matching entry in the external call table.

Action: Ensure that the number of input arguments in the external call matches the number of input arguments in the external call table.

## **ZCCONVERT**

**ZCCONVERT**, External call: error converting output argument

Run Time Error: This indicates that an external call or \$ZCALL() function failed because an output argument supplied by the external routine did not match the corresponding output description in the external call table.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 317 Chapter 1. Error Messages **ZCCSQRBR** 

Action: Change the external call table or the called routine so that they correspond.

# **ZCCSQRBR**

**ZCCSQRBR**, Closing Square bracket expected

Compile Time Error: Brackets specify the beginnings and ends of pre-allocations. This error indicates that a pre-allocation was begun with a bracket, but was not closed.

Action: Correct the syntax by placing a closing square bracket at the end of the pre-allocation.

## **ZCCTENV**

**ZCCTENV**, Environmental variable for external package xxxx not set

Compile Time Error: This indicates that the program made an external call, but could not find the external call table as specified in the UNIX environmental variable GTMXC.

Action: If this calls the default external call table, locate the external call table and specify the correct path in the UNIX environmental variable GTMXC. Otherwise, you can point to the package table in the environmental variable or specify the package name in the program GTMXC [PACKAGE NAME].

## **ZCCTNULLF**

**ZCCTNULLF**, External call table contains no records: xxxx

Compile Time Error: This indicates that the program found the requested call table, but could not find external call data.

Action: Verify that the program calls the correct call table. If the table name is correct, add external call

# **ZCCTOPN**

**ZCCTOPN**, Unable to open external call table: xxxx

Compile Time Error: This indicates that the program found the external call table but did not have permission to open it.

Action: Verify that the external call table and the user have appropriate permissions.

## **ZCENTNAME**

**ZCENTNAME**, No entry found in external call table

Run Time Error: This indicates that the entry point, which the program is trying to access cannot be found.

V6.2-002 GT.M Message and Recovery Procedures Manual **ZCINPUTREO** Chapter 1. Error Messages

Action: Create a corresponding entry point and match that link with the interface found in the C library.

# **ZCINPUTREQ**

**ZCINPUTREO**, External call: Required input argument missing

Run Time Error: This indicates that an external call or \$ZCALL function did not specify an input argument that is defined in the external call table as required.

Action: Change the external call table or the called routine so that they correspond.

## **ZCINVALIDKEYWORD**

ZCINVALIDKEYWORD, External call: Invalid keyword found. Cannot continue. Invalid keyword encountered in the ext call config file.

Run Time Error: This error occurs when the keyword for the shared library exit handler configuration is wrongly spelled. The correct keyword is "GTMSHLIBEXIT".

Action: Make sure that GTMSHLIBEXIT is correctly spelled in the external call table.

#### **ZCMAXPARAM**

**ZCMAXPARAM**, Exceeded maximum number of external call parameters

Run Time Error: GT.M allows a maximum of 31 parameters for a single external call. This error message indicates that the external call has exceeded this number.

Action: Break up the external call into two or more external calls or rewrite the program to pass a valid number of parameters.

# **ZCMLTSTATUS**

**ZCMLTSTATUS**, Multiple entries of xc status in a single entry in external call table

Run Time Error: This indicates that a call definition contains more than one XC STATUS.

Action: Check parameters for multiple occurences of TYPE XC STATUS.

# **ZCNOPREALLOUTPAR**

ZCNOPREALLOUTPAR, Parameter xxxx in external call yyyy.zzzz is an output only parameter requiring pre-allocation.

Run Time Error: This indicates that a pre-allocation value was not specified for the output only parameter xxxx in package yyyy, external call zzzz.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 319 Action: Specify a pre-allocation value for the output only parameter xxxx. A package designation of "<DEFAULT>"indicates the default package rather than an actual package name.

## **ZCOPT0**

**ZCOPT0**, External call: Qualifier OPTIONAL 0 can be used only with mechanisms REFERENCE or DESCRIPTOR

Run Time Error: This indicates that an external call or \$ZCALL function encountered an external call table input line that contained an OPTIONAL 0 QUALIFIER with a MECHANISM other than REFERENCE or DESCRIPTOR.

Action: Verify the type and spelling of the specified argument-passing mechanism in the external call table entry.

# **ZCPOSOVR**

**ZCPOSOVR**, External call: Invalid overlapping of arguments in table position xxxx

Compile Time/Run Time Error: This indicates that an external call or \$ZCALL function encountered input and output descriptions for the same position, but one or both descriptions had invalid mechanisms or types.

Action: Modify the mechanism type and/or position it to remove the conflict.

## **ZCPREALLNUMEX**

ZCPREALLNUMEX, Pre-allocation value should be a decimal number

Compile Time Error: This indicates that GT.M can only accept pre-allocation values between zero (0) to nine (9).

Action: Specify a pre-allocation value between zero and nine.

# **ZCPREALLVALINV**

**ZCPREALLVALINV**, The pre-allocation value exceeded the maximum string length

Run Time Error: Pre-allocation value of an output parameter in the external call table is greater than the maximum allowed limit (i.e. maximum string size plus one byte for terminating NULL).

Action: In the external call table, modify the pre-allocation value to less than or equal to 1,048,577.

## **ZCPREALLVALPAR**

ZCPREALLVALPAR, Pre-allocation allowed only for variables passed by reference

**ZCRCALLNAME** Chapter 1. Error Messages

Compile Time Error: This indicates that the program specified a pre-allocation for a scalar variable passed by value.

Action: Determine if the program should use a pre-allocation or should be passed by value. If it uses a pre-allocation, the variable must be passed by reference. If the variable must be passed by value, the program cannot use a pre-allocation for that variable.

## **ZCRCALLNAME**

**ZCRCALLNAME**, Routine name expected but not found

Run Time Error: This indicates that the compiler encountered an open parenthesis (indicating that parameters are listed, but found no function, which the parameters could modify.

Action: Check that the function name has been specified correctly. The function may not have been created, or the program uses an incorrect function name, or the function name may be missing.

# **ZCRPARMNAME**

ZCRPARMNAME, Parameter name expected but not found

Run Time Error: This indicates that the program specified a direction and included a colon indicating that parameters would follow, but no parameters were found.

Action: The compiler indicates where the error occurred. Review the code to determine if parameters are needed or the colon should be removed.

## **ZCRTENOTF**

**ZCRTENOTF**, External call routine xxxx not found

Compile Time/Run Time Error: This indicates that GT.M could not locate routine xxxx.

Action: Action In OpenVMS, relink your image to include the missing routine. In UNIX, relink your external call descriptor image to include the missing routine.

#### **7CRTNTYP**

**ZCRTNTYP**, Unknown return type

Compile Time Error: This indicates that the program specified an unrecognized return type. The compiler indicates where the invalid return type was found.

Action: Review the external calls table documentation for valid return types.

# **ZCSTATUS**

ZCSTATUS, External call: Unsuccessful return status

Run Time Error: This indicates that an external call or \$ZCALL() function failed because the status returned by the external routine indicates that the routine did not execute successfully.

Action: Review the external routine and the arguments passed to it. Ensure that the routine is following the OpenVMS calling standard in returning the status.

## **ZCSTATUSRET**

ZCSTATUSRET, External call returned error status

Run Time Error: This indicates that the called program may contain a logic error.

Action: Review accompanying messages for more information about the cause of this error.

# **ZCUNAVAIL**

ZCUNAVAIL, Package, xxxx unavailable

Run Time Error: This indicates that the shared library may not be specified in the external call table or the path may be specified incorrectly.

Action: Verify that the external call table and the program point to the correct shared library and path.

## **ZCUNKMECH**

**ZCUNKMECH**, External call: Unknown parameter-passing mechanism

Run Time Error: This indicates that an external call or \$ZCALL() function encountered an unsupported argument-passing MECHANISM in the external call table.

Action: Verify the spelling of the argument-passing MECHANISM values in the external call table.

# **ZCUNKQUAL**

ZCUNKQUAL, External call: Unknown input qualifier

Run Time Error: This indicates that an external call or \$ZCALL() function encountered an unsupported input QUALIFIER in the external call table.

Action: Verify the spelling of the input QUALIFIER value in the external call table.

# **ZCUNKTYPE**

**ZCUNKTYPE**, External call: Unknown argument type

Run Time Error: This indicates that an external call or \$ZCALL() function encountered an unsupported argument TYPE in the external call table.

V6.2-002 GT.M Message and Recovery Procedures Manual Action: Verify the spelling of the argument TYPE in the external call table.

# **ZCUNTYPE**

**ZCUNTYPE**, Unknown type entered

Run Time Error: This indicates that the program used an invalid external call parameter.

Action: Refer to the Programmer's Guide for valid external call parameters.

# **ZCUSRRTN**

**ZCUSRRTN**, External call: Run-time error in user routine

Run Time Error: This indicates that an external call or \$ZCALL() function failed because the external routine produced an OpenVMS error condition and terminated abnormally.

Action: Review and debug the external routine.

# **ZCVECTORINDX**

**ZCVECTORINDX**, Invalid Vector Index xxxx

Run Time Error: This indicates that GT.M can only accept positive values for vector index.

Action: Specify a valid vector index.

# **ZCWRONGDESC**

**ZCWRONGDESC**, A string longer than 65535 is passed via 32-bit descriptor

Run Time Error: A string size greater than 65,535 byte was passed while the input mechanism is descriptor.

Action: Modify the external call table's input mechanism to be descriptor64 instead of descriptor and modify the called routine to handle the new descriptor type.

# **ZDATEBADDATE**

ZDATEBADDATE, \$ZDATE() date argument dddd is less than -365 (the \$HOROLOG value for 01-JAN-1840) or greater than 364570088 (the \$HOROLOG value for 31-DEC-999999)

Run Time Error: The value of the date portion of the argument dddd to \$ZDATE() is outside the range of values the function handles.

Action: Examine the code that created the value of dddd for errors or revise the design to create dates within the range supported by \$ZDATE().

# **ZDATEBADTIME**

**ZDATEBADTIME**, \$ZDATE() time argument tttt is less than 0 or greater than 86399 (the \$HOROLOG value for a second before midnight)

Run Time Error: The value of the time portion of the argument tttt to \$ZDATE() is outside the range of values the function handles.

Action: Examine the code that created the value of tttt for errors or revise the design to create times within the range supported by \$ZDATE().

#### **ZDATEFMT**

**ZDATEFMT**, \$ZDATE format string contains invalid character

Run Time Error: This indicates that a \$ZDATE() function specified a second argument that contains one or more invalid format characters.

Action: Verify the \$ZDATE() format.

#### **ZDIROUTOFSYNC**

**ZDIROUTOFSYNC**, \$ZDIRECTORY xxxx is not the same as its cached value yyyy

Run Time Warning: For performance purposes, GT.M caches the value of \$ZDIRECTORY when it is modified using SET command. This cached value is passed to external environment translation routine. GT.M issues ZDIROUTOFSYNC error when \$ZDIRECTORY is referenced and its cached value differs from the current working directory. This might happen if an external routine called from GT.M modifies the current working directory and the application does not modify \$ZDIRECTORY to the modified directory.



#### Note

ZSHOW of intrinsic special variables appends ->%GTM-W-ZDIROUTOFSYNC error to the text corresponding to the \$ZDIRECTORY if the out of sync condition is detected.

Action: Avoid changing the current working directory except with SET \$ZDIRECTORY, or ensure that SET \$ZDIRECTORY is used along with the other mechanisms.

# **ZEDFILSPEC**

**ZEDFILSPEC**, Illegal ZEDIT file specification: xxxx

Run Time Error: This indicates that a ZEDIT command argument contains a file-specification that could not be parsed or is not a valid type for ZEDIT.

Action: Look for an attempt to edit a .o/.OBJ file.

# **ZFF2MANY**

**ZFF2MANY**, Number of characters specified for ZFF deviceparameter (xxxx) is more than the allowed (yyyy)

Run Time Error: This indicates that the number of characters specified for ZFF deviceparameter for the socked device being OPENd (or USEd) exceeds the maximum allowed.

Action: Modify the string specified for ZFF to have a length of at most the maximum allowed.

## **ZFILENMTOOLONG**

**ZFILENMTOOLONG**, xxxx is longer than 255 characters

Run Time Error: This indicates that a \$ZFILE() function argument exceeded 255 characters. xxxx is the length of the file-specification supplied.

Action: Modify the file-specification argument.

#### **7FILKEYBAD**

**ZFILKEYBAD**, xxxx is not a legal keyword for \$ZFILE()

Run Time Error: This indicates that a \$ZFILE() function specified the invalid keyword xxxx.

Action: Review the routine for correct spelling and the validity of keywords.

#### **ZFILNMBAD**

ZFILNMBAD, xxxx is not a legal file name

Run Time Error: This indicates that a \$ZFILE() function argument supplied an invalid file-specification XXXX.

Action: Look for invalid characters or improper punctuation within the file-specification.

#### **ZGBLDIRACC**

**ZGBLDIRACC**, Cannot access global directory xxxx. Continuing with yyyy.

Run Time Error: This indicates that a SET of a \$ZGBLDIR or external global reference specified a Global Directory (xxxx) that does not exist or cannot be accessed due to permissions. GT.M retains the previous Global Directory (yyyy).

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 325 Action: Ensure that you specified the intended Global Directory. Use a host shell command to verify that the specified directory exists and has the protections required for the desired access.

## **ZGOCALLOUTIN**

ZGOCALLOUTIN, ZGOTO level 0 with entry ref not valid when using call-ins

Call in/Run Time Error: Code invoked by a call-in contained a ZGOTO 0:entryref. The purpose of a ZGOTO 0:entryref is to "refresh" the GT.M routine context, but that action would invalidate the interface with the calling (in) code.

Action: Refactor the code invoked by the call-in to avoid or appropriately conditionalize the ZGOTO 0:entryref.

#### ZGOTOINVLVL

ZGOTOINVLVL, ZGOTO in a trigger running in mmmm cannot ZGOTO level LLLL

MUPIP Error: A ZGOTO command in trigger logic attempted to specify an inappropriate destination. Currently that is a ZGOTO in a trigger context with a target level of one (1) and an entryref. GT.M does not support such ZGOTO arguments in MUPIP because there is no context outside that of the trigger.

Action: Revise the trigger logic to only use ZGOTO with an entryref within the trigger context of trigger logic. Note that you can ZGOTO out of a trigger, but doing so in MUPIP terminates the MUPIP process. FIS recommends limiting the use of ZGOTO to debugging, error handling and testing. Use of ZGOTO in production code, even for error processing, should always be thoroughly tested.

# **ZGOTOINVLVL2**

**ZGOTOINVLVL2**, ZGOTO 0:entryref is not valid on VMS (UNLINK is a UNIX only feature)

Run Time Error: Because the GT.M OpenVMS environment includes links performed by the OpenVMS Linker, GT.M does not support this construct on OpenVMS.

Action: Refactor the code to avoid or appropriately conditionalize the ZGOTO 0:entryref.

# **ZGOTOLTZERO**

**ZGOTOLTZERO**, Cannot ZGOTO a level less than zero

Run Time Error: This indicates that a ZGOTO specified a negative level in its argument.

Action: Ensure that the ZGOTO level is between zero (0) and the current \$ZLEVEL.

#### **ZGOTOTOOBIG**

**ZGOTOTOOBIG**, Cannot ZGOTO a level greater than present level

ZINTDIRECT Chapter 1. Error Messages

Run Time Error: This indicates that ZGOTO command specified a level greater than the current stack depth.

Action: Check the source of the level. The level argument of a ZGOTO indicates the depth the stack is to be after the ZGOTO, which cannot be greater than the current stack depth. The only way to increase stack depth is by performing DOs or XECUTEs.

## **ZINTDIRECT**

**ZINTDIRECT**, Attempt to enter direct mode from \$ZINTERRUPT

Run Time Error: A \$ZINTERRUPT routine cannot break to direct mode if the current IO device is the same as \$PRINCIPAL.

Action: Modify the \$ZINTERRUPT routine to not break to direct mode.

#### ZINTRECURSEIO

**ZINTRECURSEIO**, Attempt to do IO to the active device in \$ZINTERRUPT

Run Time Error: A \$ZINTERRUPT routine cannot perform I/O to the current IO device if it was active when the interrupt was recognized and the device is a terminal, socket device, FIFO, or PIPE.

Action: Modify the \$ZINTERRUPT routine to not perform I/O to the active device.

# **ZLINKFILE**

**ZLINKFILE**, Error while ZLINKing "xxxx"

Run Time Error: This indicates that ZLINK command failed while trying to include routine xxxx in the image.

Action: Use host shell commands to ensure that the file to be ZLINKed is in the proper directory and has the appropriate protection. Review the accompanying message(s) for additional information.

## **ZLKIDBADARG**

**ZLKIDBADARG**, The tvexpr must be FALSE if last ZLKID not found

Run Time Error: This indicates that a \$ZLKID() function specified an argument that was TRUE when no active OpenVMS lock scan was in progress.

Action: Ensure that \$ZLKID() is initialized with a FALSE truth-valued expression. \$ZLKID() cannot be invoked with a TRUE truth-valued expression unless the last \$ZLKID() returned a lock. If the function has not been previously invoked, it must be first invoked with a FALSE truth-valued expression.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 327

## **ZLMODULE**

**ZLMODULE**, Object file name does not match module name: xxxx

Run Time Error: This indicates that GT.M did not perform a ZLINK or an auto-ZLINK because the name of the object file specified with the ZLINK xxxx is not the same as the name of the source file.

**ZLMODULE** 

Action: Look for and correct any typographical errors in the object file specified for the ZLINK, or assign the same name to the source and object.

# **ZLNOOBJECT**

**ZLNOOBJECT**, No object module was produced

Run Time Error: This indicates that a run-time compile specified a NOOBJECT qualifier. This can be accomplished with a ZLINK qualifier or by setting \$ZCOMPILE to a qualifier string that GT.M uses for auto-ZLINKs or ZLINKs with no qualifiers.

Action: Remove the NOOBJECT qualifier.

## **ZPARSETYPE**

**ZPARSETYPE**, Illegal TYPE argument to \$ZPARSE(): xxxx

Run Time Error: This indicates that a \$ZPARSE() function specified a type argument xxxx that was not a null string, SYNTAX ONLY, or NO CONCEAL.

Action: Verify the spelling of the keyword.

## **ZPARSFLDBAD**

**ZPARSFLDBAD**, Illegal \$ZPARSE() field parameter: xxxx

Run Time Error: This indicates that a \$ZPARSE() function specified a field argument xxxx that was not NODE, DEVICE, DIRECTORY, NAME, TYPE, or VERSION.

Action: Verify that the keyword is spelled correctly.

# **ZPEEKNOJNLINFO**

**ZPEEKNOJNLINFO**, \$ZPEEK() unable to access requested journal structure - region rrrr is not currently journaled

Run Time Error: A \$ZPEEK() invocation requested journal related information on region rrrr, but that region does not currently have journaling enabled and on. Note that if the process has not updated the database region, or used a VIEW or \$VIEW() referencing the region, some fields may have a value of zero (0).

Action: Use \$VIEW("JNLACTIVE", region) to determine that journaling is enabled and on for a region before attempting to access its journal-related information.

## **ZPEEKNORPLINFO**

**ZPEEKNORPLINFO**, \$ZPEEK() unable to access requested replication structure

Run Time Error: The replication structure specified in the mnemonic is not available to this process because either replication is not running or, in the case of receive pool type requests, is not running on a non-primary where such control blocks are available.

Action: Only fetch replication values when replication is active and if accessing gtmrecv.\* fields, do not run on a primary.

#### **ZPIDBADARG**

**ZPIDBADARG**, The tvexpr must be FALSE if last \$ZPID() not found

Run Time Error: This indicates that a \$ZPID() function specified an argument that was TRUE when no active PID scan was in progress.

Action: Review the routine to ensure that \$ZPID() is first initialized with a FALSE truth-valued expression. \$ZPID() cannot be invoked with a TRUE truth-valued expression unless the last \$ZPID() returned a PID. If it has not been previously invoked, it must be first invoked with a FALSE truthvalued expression.

#### **ZPRIVARGBAD**

**ZPRIVARGBAD**, xxxx is not a legal privilege for \$ZPRIV()

Run Time Error: This indicates that a \$ZPRIV() function specified an argument xxxx that contains a keyword that is not a valid OpenVMS privilege.

Action: Review for spelling errors or invalid privileges.

## **ZPRIVSYNTAXERR**

**ZPRIVSYNTAXERR**, Privilege string cannot end with a comma

Run Time Error: This indicates that a \$ZPRIV() function specified a list of privileges that ended with a comma.

Action: Look for a missing keyword or an extra comma. The form for a \$ZPRIV() argument is a string of OpenVMS privilege keywords separated by commas. The list must begin and end with a keyword.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 329

## **ZPRTLABNOTFND**

#### **ZPRTLABNOTFND**, Label not found in routine

Run Time Error: This indicates that a ZPRINT command specified a label that could not be found in the routine.

Action: Verify the spelling of the label. Ensure that the current version of the program has the label by ZPRINTing the entire routine.

# **ZROSYNTAX**

## **ZROSYNTAX**, \$ZROUTINES syntax error: xxxx

Syntax/Run Time Error: This indicates that a \$ZROUTINES related action encountered syntax error xxxx.

Action: Modify the UNIX environment variable gtmroutines/OpenVMS logical name GTM\$ROUTINES or the expression being SET into \$ZROUTINES.

## **ZSETPRVARGBAD**

**ZSETPRVARGBAD**, xxxx is not a legal privilege for \$ZSETPRIV()

Run Time Error: This indicates that a \$ZSETPRIV() function specified an argument xxxx that contains a keyword that is not a valid OpenVMS privilege.

Action: Look for spelling errors or invalid privileges.

#### **ZSETPRVSYNTAX**

**ZSETPRVSYNTAX**, \$ZSETPRIV() privileges string cannot end with a comma

Run Time Error: This indicates that \$ZSETPRIV() function specified a list of privileges that ended with a comma.

Action: Look for a missing keyword or an extra comma. The form for a \$ZSETPRIV() argument is a string of OpenVMS privilege keywords separated by commas. The list must begin and end with a keyword.

#### **ZSHOWBADFUNC**

**ZSHOWBADFUNC**, An illegal function was specified for ZSHOW

Run Time Error: This indicates that ZSHOW argument code specified an invalid action.

**ZSHOWGLOSMALL** Chapter 1. Error Messages

Action: Modify the argument to use a valid code.

#### **ZSHOWGLOSMALL**

ZSHOWGLOSMALL, Global output variable is too small for ZSHOW output

Run Time Error: This indicates that SHOW could not place data in a target global variable because the record size for the database file that holds the region containing the variable was too small to accommodate the ZSHOW output.

Action: Use a global output variable in a less restrictive region, or reorganize the database and increase the value of the qualifier RECORD\_SIZE= in the Global Directory.

# **ZSOCKETATTR**

**ZSOCKETATTR**, Attribute "xxxx" invalid for \$ZSOCKET function msg name

Run Time Error: This indicates the named attribute is not recognized for the \$ZSOCKET function.

Action: Check for spelling, review the documented list of available attributes and adjust the attribute argument.

## **ZSOCKETNOTSOCK**

**ZSOCKETNOTSOCK**, \$ZSOCKET function called but device is not a socket

Run Time Error: The code invoked the \$ZSOCKET() function with a device which is not a Socket Device.

Action: Review device usage and revise as appropriate.

## **ZSRCHSTRMCT**

ZSRCHSTRMCT, Search stream identifier out of range

Run Time Error: This indicates that \$ZSEARCH() function specified a stream less than 1 or greater than 255.

Action: Change the stream value to be within the range of 1-255.

## **ZSTEPARG**

**ZSTEPARG**, ZSTEP argument expected

Compile Time Error: This indicates that ZSTEP command did not specify an argument or a <SP> to hold the place of the missing argument.

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 331 Action: Modify the ZSTEP command so it has an argument or a trailing double space.

# **ZTRIGINVACT**

**ZTRIGINVACT**, Missing or invalid subcode (first) parameter given to \$ZTRIGGER()

Trigger/Run Time Error: The first argument to \$ZTRIGGER() is required to specify its mode of action.

Action: for the first argument of \$ZTRIGGER() use an expression that evaluates to "FILE", "ITEM" or "SELECT".

#### **ZTRIGNOTP**

Last used version: V5.4-001

**ZTRIGNOTP**, \$ZTRIGGER() cannot use update subcodes FILE or ITEM when a TP transaction is in progress (\$TLEVEL greater than zero)

Trigger/Run Time Error: A FILE or ITEM operation of \$ZTRIGGER() failed because it attempted to apply a trigger definition inside an ongoing transaction. Both FILE and ITEM operations of \$ZTRIGGER initiate an implicit transaction to achieve trigger update atomicity, therefore, GT.M does not allow nesting them inside another transaction that potentially might use the very triggers \$ZTRIGGER() is attempting to update.

Action: Move all FILE or ITEM operations of \$ZTRIGGER() outside the scope of any open transaction.

## **ZTRIGNOTRW**

ZTRIGNOTRW, ZTRIGGER cannot operate on read-only region rrrr

Run Time Error: This error occurs when ZTRIGGER attempts to write to read-only region rrrr.

Action: Check for appropriate global directory mapping and appropriate permissions on the database file mapped to region rrrr.

#### **ZTWORMHOLE2BIG**

**ZTWORMHOLE2BIG**, String length of LLLL bytes exceeds maximum length of mmmm bytes for \$ZTWORMHOLE

Trigger/Run Time Error: GT.M limits \$ZTWORMHOLE length to mmmm bytes and the application attempted to use LLLL bytes.

Action: Restrict the size of the string stored in \$ZTWORMHOLE to mmmm bytes. Ensure that \$ZTWORMHOLE only holds the information that the application needs during trigger execution. If necessary, reorganize the logic to reduce the amount of local context needed during trigger execution, possibly by using global variables.

V6.2-002

# **ZWRSPONE**

**ZWRSPONE**, Subscript patterns in ZWRITE are atomic; Invalid delimiter

Compile Time Error: This indicates that ZWRITE specification contained a pattern match that held or terminated with a punctuation character that was not within a string literal.

Action: Look for missing quotes or typographical errors and make any corrections that are necessary.

This page is intentionally left blank.

MR Manual FIS

# Message Categorization Index

## A

All GT.M Components
LASTWRITERBYPAS, 158

#### $\mathbf{C}$

Call in

CIENTNAME, 19 CIMAXLEVELS, 19 CIMAXPARAM, 20 CIPARTYPE, 20 CIRCALLNAME, 20

CIRPARMNAME, 20 CIRTNTYP, 21 CITABENV, 21 CITABOPN, 21 CITPNESTED, 21 CIUNTYPE, 21 INVGTMEXIT, 120 ZGOCALLOUTIN, 326

CCF

NOCCPPID, 202 OPRCCPSTOP, 217

Compile Time

ABNCOMPTINC, 1
ACTLSTTOOLONG, 2
ACTOFFSET, 2

ALIASEXPECTED, 3 ANCOMPTINC, 4 ARROWNTDSP, 4 BLKTOODEEP, 13 BOOLSIDEFFECT, 14

BOOLSIDEFFECT, 1-CEBIGSKIP, 17 CENOINDIR, 17 CETOOLONG, 18 CETOOMANY, 18 CEUSRERROR, 18 CMD, 22

CNOTONSYS, 23

COLON, 25

COMMA, 25

COMMAORRPAREXP, 25 COMPILEQUALS, 26 DBMAXNRSUBS, 54 DELIMSIZNA, 68 DEVPARINAP, 70

DEVPARMTOOSMALL, 70

DEVPARPROT, 70
DEVPARTOOBIG, 71
DEVPARUNK, 71
DEVPARVALREQ, 71
DZWRNOALIAS, 78
DZWRNOPAREN, 78

EQUAL, 79

ERRORSUMMARY, 80

EXPR, 82

FCHARMAXARGS, 84 FCNSVNEXPECTED, 84

FILENOTFND, 86 FMLLSTMISSING, 88 FMLLSTPRESENT, 88 FNOTONSYS, 89 FORCTRLINDX, 90 FOROFLOW, 90 GBLNAME, 93 GTMASSERT, 97 GTMASSERT2, 97

GTMCHECK, 98 GVNAKEDEXTNM, 108 GVNEXTARG, 108

INDEXTRACHARS, 114

INVBITPOS, 118
INVCMD, 118
INVFCN, 119
INVSVN, 124
JOBACTREF, 149
JOBPARNOVAL, 152
JOBPARNUM, 152
JOBPARSTR, 152
JOBPARUNK, 153
JOBPARVALREQ, 153
LABELEXPECTED, 157
LABELMISSING, 157
LABELUNKNOWN, 157
LASTFILCMPLD, 158
LITNONGRAPH, 160

LKNAMEXPECTED, 161

# Message Categorization Index

LPARENMISSING, 167	TSTRTPARM, 304
LSEXPECTED, 167	VAREXPECTED, 309
LVORDERARG, 168	XKILLCNTEXC, 315
MAXACTARG, 169	ZCCSQRBR, 318
MAXARGCNT, 169	ZCCTENV, 318
MAXFORARGS, 170	ZCCTNULLF, 318
MAXNRSUBSCRIPTS, 170	ZCCTOPN, 318
MEMORY, 172	ZCPOSOVR, 320
MRTMAXEXCEEDED, 175	ZCPREALLNUMEX, 320
MULTFORMPARM, 183	ZCPREALLVALPAR, 321
MULTLAB, 183	ZCRTENOTF, 321
NAMEEXPECTED, 195	ZCRTNTYP, 321
·	-
NESTFORMP, 200	ZSTEPARG, 332
NUMOFLOW, 214	ZWRSPONE, 333
OFFSETINV, 216	D
PATCLASS, 220	D
PATCODE, 220	DBCERTIFY
PATLIT, 220	DBCBADFILE, 40
PATLOAD, 221	DBCCMDFAIL, 41
PATMAXLEN, 221	DBCDBCERTIFIED, 41
PATTABSYNTAX, 221	DBCINTEGERR, 42
PATUPPERLIM, 222	DBCKILLIP, 42
PCONDEXPECTED, 222	DBCMODBLK2BIG, 42
QUITARGLST, 227	DBCNOEXTND, 43
QUITARGUSE, 227	DBCNOFINISH, 44
RHMISSING, 253	DBCNOTSAMEDB, 44
RPARENMISSING, 258	DBCREC2BIG, 45
RTNNAME, 259	DBCSCNNOTCMPLT, 46
RWARG, 259	DBMAXREC2BIG, 54
RWFORMAT, 259	DBMINRESBYTES, 57
SIDEEFFECTEVAL, 268	•
SOCKACTNA, 274	DYNUPGRDFAIL, 77
SPOREOL, 277	DSE
SRCFILERR, 277	AIMGBLKFAIL, 3
-	BLKCNTEDITFAIL, 12
SRCLIN, 278	BLKINVALID, 13
SRCLNNTDSP, 278	BLKSIZ512, 13
SRCLOC, 278	BUFFLUFAILED, 16
SRCNAM, 278	CANTBITMAP, 17
STRINGOFLOW, 283	CPBEYALLOC, 27
SVNEXPECTED, 286	DBBMBARE, 37
SVNONEW, 286	DBBMINV, 38
SVNOSET, 286	DBBMSIZE, 38
TEXTARG, 288	DBDIRTSUBSC, 47
TLVLZERO, 290	DBKEYORD, 53
TMPSTOREMAX, 291	DBNOREGION, 59
TRACEON, 296	DBREMOTE, 62
TRNLOGFAIL, 303	DBROOTBURN, 64
, <del></del>	DDICOTDOIN, 01

FIS Page 336, June 09, 2015

DSEBLKRDFAIL, 74	KEYWRDAMB, 155
DSEFAIL, 74	KEYWRDBAD, 155
DSEINVLCLUSFN, 74	LOADGD, 163
DSEMAXBLKSAV, 75	LOGOFF, 166
DSENOFINISH, 75	LOGON, 166
DSENOTOPEN, 75	LVSTARALON, 168
DSEONLYBGMM, 75	MAPBAD, 168
DSEWCINITCON, 75	MAPDUP, 169
DSEWCREINIT, 76	MISSINGDELIM, 173
EXECOM, 82	MMNOBEFORIMG, 174
FREEZE, 91	NAMENDBAD, 195
GTMDISTUNDEF, 98	NAMGVSUBOFLOW, 195
GTMDISTUNVERIF, 98	NAMGVSUBSMAX, 195
KEYSIZIS, 154	NAMLPARENNOTBEG, 195
NOTREPLICATED, 212	NAMNOTSTRSUBS, 196
REGOPENFAIL, 231	NAMNUMSUBSOFLOW, 196
REGOPENRETRY, 231	NAMONECOLON, 196
SEGIS, 264	NAMRANGELASTSUB, 196
STRNOTVALID, 284	NAMRANGEORDER, 197
TIMRBADVAL, 288	NAMRANGEOVERLAP, 197
,	NAMRPARENNOTEND, 197
G	NAMSTARSUBSMIX, 197
GDE	NAMSTARTBAD, 197
BLKCNTEDITFAIL, 12	NAMSTRSUBSCHARG, 198
BLKSIZ512, 13	NAMSTRSUBSCHINT, 198
BUFSIZIS, 16	NAMSTRSUBSFUN, 198
BUFTOOSMALL, 16	NAMSUBSBAD, 198
CRYPTNOMM, 31	NAMSUBSEMPTY, 198
EXECOM, 82	NOACTION, 201
GBLNAMCOLLRANGE, 92	NOEXIT, 203
GBLNAMCOLLUNDEF, 92	NOLOG, 205
GBLNAMCOLLVER, 93	NONASCII, 205
GBLNAMEIS, 93	NONEGATE, 205
GDCREATE. 94	NOVALUE, 213
GDECHECK, 95	OBJDUP, 215
GDNOTSET, 95	OBJNOTADD, 215
GDREADERR, 95	OBJNOTCHG, 215
GDUNKNFMT, 95	OBJNOTFND, 215
GDUPDATE, 96	OBJREQD, 216
GDUSEDEFS, 96	PREFIXBAD, 223
ILLCHAR, 113	QUALBAD, 225
INPINTEG, 115	QUALDUP, 226
INVGBLDIR, 120	QUALREQD, 226
JNLALLOCGROW, 129	RECSIZIS, 230
KEYFORBLK, 154	RECTOOBIG, 230
KEYSIZIS, 154	REGIS, 231
KEYTOOBIG, 154	RPAREN, 257
122100210, 101	,

# Message Categorization Index

SEGIS, 264	GTMDISTUNDEF, 98
STDNULLCOLLREQ, 282	GTMDISTUNVERIF, 98
STRMISSQUOTE, 283	LCKGONE, 158
VALTOOBIG, 308	LCKSGONE, 158
VALTOOLONG, 309	LKENOFINISH, 160
VALTOOSMALL, 309	LOCKSPACEUSE, 165
VALUEBAD, 309	NOLOCKMATCH, 205
VALUEREQD, 309	NOREGION, 207
VERIFY, 310	REGOPENFAIL, 231
WRITEERROR, 314	REGOPENRETRY, 231
GT.CM	
AIMGBLKFAIL, 3	M
BADGTMNETMSG, 7	MUPIP
CMEXCDASTLM, 23	ACTIVATEFAIL, 2
CMICHECK, 23	AIMGBLKFAIL, 3
CMINTQUE, 23	BACKUPCTRL, 5
CMSYSSRV, 23	BACKUPKILLIP, 5
DCNINPROG, 68	BADACCMTHD, 5
GTMDISTUNVERIF, 98	BCKUPBUFLUSH, 9
INVINTMSG, 121	BEGINST, 10
INVNETFILNM, 122	BEGSEQGTENDSEQ, 10
INVPROT, 123	BFRQUALREQ, 10
LNKNOTIDLE, 161	BINHDR, 11
OMISERVHANG, 216	BKUPRUNNING, 11
REGNTFND, 231	BLKCNT, 12
SERVERERR, 265	BOVTMGTEOVTM, 14
GTMSECSHR	BOVTNGTEOVTN, 14
GTMSECSHRCHDIRF, 99	BUFFLUFAILED, 16
GTMSECSHRDMNSTARTED, 100	CHNGTPRSLVTM, 18
GTMSECSHRGETSEMFAIL, 100	CORRUPT, 27
GTMSECSHRREMFILE, 102	CORRUPTNODE, 27
GTMSECSHRREMSEM, 102	CRYPTNOMM, 31
GTMSECSHRREMSEMFAIL, 102	CRYPTNOV4, 32
GTMSECSHRREMSHM, 103	DBBADKYNM, 36
GTMSECSHRSEMGET, 103	DBBADNSUB, 36
GTMSECSHRSHMCONCPROC, 103	DBBADPNTR, 36
GTMSECSHRSRVFIL, 105	DBBDBALLOC, 37
GTMSECSHRUPDDBHDR, 106	DBBFSTAT, 37
•	DBBNPNTR, 39
	DBBPLMGT2K, 39
mages	DBBPLMLT512, 39
INVMEMRESRV, 121	DBBPLNOT512, 39
•	DBBSIZZRO, 40
L	DBBTUFIXED, 40
LKE	DBBTUWRNG, 40
BADREGION, 8	DBCDBNOCERTIFY, 41
DBREMOTE, 62	DBCOLLREQ, 44

FIS

DBCOMPTOOLRG, 45 DBCREC2BIGINBLK, 45 DBCREINCOMP, 45 DBDATAMX, 47 DBDSRDFMTCHNG, 47 DBENDIAN 47

DBENDIAN, 47
DBFGTBC, 47
DBFILEXT, 49
DBFLCORRP, 49
DBFRZRESETFL, 50

DBFRZRESETSUC, 50 DBFSTBC, 50

DBFSTHEAD, 50 DBGTDBMAX, 51 DBHEADINV, 51 DBINCLVL, 51 DBINCRVER, 51 DBINVGBL, 52

DBINVGBL, 32 DBJNLNOTMATCH, 52 DBKEYGTIND, 52 DBKEYORD, 53 DBKGTALLW, 53

DBKGTALLW, 53
DBLOCMBINC, 53
DBLRCINVSZ, 53
DBLTSIBL, 54
DBLVLINC, 54
DBMAXKEYEXC, 54
DBMAXREC2BIG, 54
DBMAXRSEXBL, 55

DBMBMINCFRE, 55 DBMBPFLDIS, 55 DBMBPFLDLBM, 56 DBMBPFRDLBM, 56 DBMBPFRDLBM, 56 DBMBPFRINT, 56

DBMBPINCFL, 56 DBMBSIZMN, 57 DBMBSIZMX, 57

DBMBTNSIZMX, 57 DBMINRESBYTES, 57 DBMISALIGN, 57 DBMRKBUSY, 58 DBMRKFREE, 58

DBMRKFREE, 58 DBMXRSEXCMIN, 58 DBNOCRE, 58 DBNOREGION, 59 DBNOTDB, 59 DBNOTMLTP, 59

DBRBNLBMN, 61

DBRBNNEG, 61

DBRBNTOOLRG, 61 DBREADBM, 62

DBREMOTE, 62

DBRLEVLTONE, 62 DBRLEVTOOHI, 63

DBSPANCHUNKORD, 64 DBSPANGLOINCMP, 65

DBSVBNMIN, 65 DBSZGT64K, 65

DBTN, 66

DBTNLTCTN, 66
DBTNNEQ, 66
DBTNTOOLG, 67
DBTOTBLK, 67
DBTTLBLK0, 67
DBUNDACCMT, 67
DLRCILLEGAL, 73
DLRCTOOBIG, 73
DLRCUNXEOR, 74

DUPTN, 77 DUPTOKEN, 77 ENDIANCVT, 78 EORNOTFND, 79 EPOCHTNHI, 79 EXCLUDEREORG, 81 EXTRACTCTRLY, 82 EXTRACTFILERR, 82 EXTRCLOSEERR, 83

EXTRFAIL, 83 EXTRFMT, 83 EXTRIOERR, 83 FILECREATE, 85 FILEDEL, 85 FILEDELFAIL, 85 FILEEXISTS, 85

FILENAMETOOLONG, 86 FILENOTCREATE, 86 FILEOPENFAIL, 86 FILTERTIMEDOUT, 88

FREEZE, 91 FREEZECTRL, 91 FREEZEERR, 91 FTOKKEY, 92 GBLEXPECTED, 92

GBLNOEXIST, 93 JNLFNF, 137 GETCWD, 96 **INLINVALLOC, 138** GOQPREC, 97 JNLINVEXT, 138 GTMDISTUNDEF, 98 **INLINVSWITCHLMT**, 138 GTMDISTUNVERIF, 98 JNLMINALIGN, 139 GVINVALID, 107 JNLNAMLEN, 139 HLPPROC, 111 **JNLNEWREC**, 139 HTEXPFAIL, 111 JNLNMBKNOTPRCD, 139 HTOFLOW, 112 JNLNOBIJBACK, 140 INITORRESUME, 115 JNLNOCREATE, 140 INSNOTJOINED, 116 JNLNOREPL, 140 INSROLECHANGE, 116 **INLNOTFOUND**, 140 INSUNKNOWN, 117 JNLOPNERR, 141 INTEGERRS, 117 JNLPOOLBADSLOT, 141 INVACCMETHOD, 117 JNLPOOLSETUP, 141 INVERRORLIM, 119 JNLRDONLY, 143 INVGLOBALQUAL, 120 JNLREAD, 143 INVIDQUAL, 120 JNLREADBOF, 143 INVMVXSZ, 121 **JNLREADEOF**, 144 INVQUALTIME, 123 JNLRECFMT, 144 INVREDIRQUAL, 123 JNLRECINCMPL, 144 **INVTRNSQUAL**, 125 **JNLSETDATA2LONG**, 145 IOEOF, 126 JNLSTATE, 145 IPCNOTDEL, 127 **JNLSTATEOFF**, 145 JNLACTINCMPLT, 129 JNLSUCCESS, 146 **INLALIGNTOOSM, 129** JNLTMQUAL1, 146 JNLTMQUAL2, 147 INLALLOCGROW, 129 JNLTMQUAL3, 147 JNLBADLABEL, 130 **INLTMOUAL4, 147** INLBADRECFMT, 130 JNLBUFFDBUPD, 130 JNLTNOUTOFSEQ, 147 JNLBUFFREGUPD, 130 JNLTPNEST, 148 INLBUFFTOOLG, 130 **JNLUNXPCTERR**, 149 JNLBUFFTOOSM, 131 JRTNULLFAIL, 153 JNLCREATE, 132 LDBINFMT, 159 JNLCRESTATUS, 132 LDGOQFMT, 159 JNLCYCLE, 133 LDSPANGLOINCMP, 159 **INLDBTNNOMATCH**, 133 LOADABORT, 161 JNLDISABLE, 133 LOADBGSZ, 162 JNLDSKALIGN, 134 LOADBGSZ2, 162 JNLENDIANBIG, 134 LOADCTRLY, 162 JNLENDIANLITTLE, 134 LOADEDBG, 162 JNLEXTR, 135 LOADEDSZ, 162 JNLFILECLOSERR, 135 LOADEDSZ2, 163 **JNLFILEDUP**, 135 LOADEOF, 163 JNLFILEOPNERR, 135 LOADFILERR, 163 JNLFILNOTCHG, 136 LOADFMT, 163

V6.2-002 GT.M Message and Recovery Procedures Manual

LOADINVCHSET, 164

JNLFILRDOPN, 136

LOWSPACECRE, 166 LPARENREQD, 167 MAXBTLEVEL, 170 MAXSSREACHED, 171 MMBEFOREJNL, 173 MMNOBFORRPL, 174 MMNODYNDWNGRD, 174 MMNODYNUPGRD, 174 MUBCKNODIR, 179

MUDWNGRDNOTPOS, 179 MUDWNGRDNRDY, 179 MUDWNGRDTN, 179 MUFILRNDWNFL, 180 MUFILRNDWNFL2, 180 MUFILRNDWNSUC, 180

MUINFOSTR, 180
MUINFOUINT4, 180
MUINFOUINT6, 181
MUINFOUINT8, 181
MUINSTFROZEN, 181
MUINSTUNFROZEN, 181
MUINSTUNFROZEN, 182
MUJNLDBMISSING, 182
MUJNLPREVGEN, 182

MUJPOOLRNDWNFL, 182 MUJPOOLRNDWNSUC, 182

MUKILLIP, 183

MULOGNAMEDEF, 183 MUNOACTION, 183 MUNODBNAME, 183 MUNODWNGRD, 184 MUNOFINISH, 184 MUNOSTRMBKUP, 184 MUNOTALLINTEG, 184 MUNOTALLINTEG, 185

MUNOUPGRD, 185 MUPCLIERR, 185 MUPGDERR, 185 MUPGRDSUCC, 185 MUPIPINFO, 186 MUPIPSIG, 186

MUPJNLINTERRUPT, 186 MUPRESTERR, 186

MUQUALINCOMP, 186 MURAIMGFAIL, 187 MUREORGFAIL, 187 MUREPLPOOL, 187 MUREPLSECDEL, 187 MUREPLSECNOTDEL, 188 MUREUPDWNGRDEND, 188 MURNDWNOVRD, 188

MURPOOLRNDWNFL, 188 MURPOOLRNDWNSUC, 188

MUSECDEL, 189
MUSECNOTDEL, 189
MUSELFBKUP, 189
MUSIZEFAIL, 189
MUSIZEINVARG, 189
MUSTANDALONE, 190
MUTNWARN, 192
MUTRUNC1ATIME, 192
MUTRUNCBACKINPROG, 192

MUTRUNCERROR, 192
MUTRUNCFAIL, 193
MUTRUNCNOSPACE, 193
MUTRUNCNOTBG, 193
MUTRUNCNOV4, 193
MUTRUNCPERCENT, 193
MUTRUNCSSINPROG, 194
MUTRUNCSUCCESS, 194
MUUPGRDNRDY, 194
NEWJNLFILECREAT, 201
NODFRALLOCSUPP, 202
NOENDIANCVT, 203

NOEXCLUDE, 203 NOJNL, 204 NOJNLPOOL, 204 NOPINI, 206 NOPREVLINK, 206 NORECVPOOL, 207 NOREPLCTDREG, 207

NORESYNCSUPPLONLY, 207 NORESYNCUPDATERONLY, 208

NOSELECT, 208 NOSPACECRE, 208 NOSTARFILE, 209 NOSUPPLSUPPL, 210 NOTALLDBOPN, 210 NOTALLJNLEN, 210 NOTALLREPLON, 210

NOTGBL, 212 NOTPOSITIVE, 212 NOTRNDMACC, 212 NUMUNXEOR, 215

June 09, 2015, Page 341

ORLBKCMPLT, 217 ORLBKFRZOVER, 217 ORLBKFRZPROG, 218 ORLBKNOSTP, 218 ORLBKNOV4BLK, 218 ORLBKSTART, 219 ORLBKTERMNTD, 219 PERMGENFAIL, 222 PREALLOCATEFAIL, 223 PREMATEOF, 223 PREVJNLLINKCUT, 224 PREVINLLINKSET, 224 PREVJNLNOEOF, 224 PRIMARYISROOT, 224 PRIMARYNOTROOT, 225 RBWRNNOTCHG, 227 RCVR2MANY, 228

RCVRMANYSTRMS, 228 RECCNT, 229 RECLOAD, 229 RECORDSTAT, 230 REGSSFAIL, 232

REMOTEDBNOTRIG, 233
RENAMEFAIL, 233
REORGCTRLY, 233
REORGINC, 233
REPL2OLD, 233
REPLACCSEM, 234
REPLBRKNTRANS, 234
REPLCOMM, 234
REPLERR, 234

REPLERR, 234
REPLFILIOERR, 235
REPLFILTER, 235
REPLFTOKSEM, 235
REPLINSTACC, 236
REPLINSTDBMATCH, 237

REPLINSTDBSTRM, 237

REPLINSTFMT, 238 REPLINSTNMLEN, 239 REPLINSTNMSAME, 239 REPLINSTNMUNDEF, 239

REPLINSTNOHIST, 240 REPLINSTSECLEN, 241 REPLINSTSECMTCH, 241

REPLINSTSECNONE, 241

REPLINSTSECUNDF, 242 REPLINSTSEQORD, 242 REPLINSTSTNDALN, 243 REPLINSTUNDEF, 243 REPLJNLCNFLCT, 244 REPLLOGOPN, 245 REPLNOBEFORE, 245

REPLNOMULTILINETRG, 245

REPLNOTLS, 246 REPLNOTON, 246 REPLNOXENDIAN, 246 REPLOFFJNLON, 246 REPLPOOLINST, 247 REPLRECFMT, 247

REPLREQROLLBACK, 247 REPLREQRUNDOWN, 247

REPLSTATE, 248 REPLSTATEERR, 248 REPLSTATEOFF, 248 REPLTRANS2BIG, 248 REPLUPGRADEPRI, 249 REPLUPGRADESEC, 249

REPLWARN, 249

REPLXENDIANFAIL, 250 RESOLVESEQNO, 252 RESOLVESEQSTRM, 252 RESUMESTRMNUM, 253 REUSEINSTNAME, 253 RLBKCONFIGBNDRY, 253 RLBKJNLNOBIMG, 253

RLBKJNSEQ, 254

RLBKLOSTTNONLY, 254 RLBKNOBIMG, 254 RLBKSTRMSEQ, 254 RLNKCTLRNDWNFL, 255 RLNKCTLRNDWNSUC, 255 ROLLBKINTERRUPT, 257

RPARENREQD, 258

RSYNCSTRMSUPPLONLY, 258

RSYNCSTRMVAL, 258 SECNODZTRIGINTP, 260

SECNOTSUPPLEMENTARY, 260

SELECTSYNTAX, 264

SEMID, 264

SEMKEYINUSE, 265 SEMREMOVED, 265

SEONUMSEARCHTIMEOUT, 265

SETEXTRENV, 266 SETREG2RESYNC, 267 SHMREMOVED, 268 O SNAPSHOTNOV4, 273 Operator log SRCSRVEXISTS, 279 GTMSECSHRREMFILE, 102 SRCSRVNOTEXIST, 279 JOBEXAMDONE, 150 SRCSRVTOOMANY, 279 JOBEXAMFAIL, 150 SRVLCKWT2LNG, 279 REPLSRCEXITERR, 248 SSFILCLNUPFAIL, 280 SSFILOPERR, 280 R SSPREMATEOF, 280 Receiver Server log SSSHMCLNUPFAIL, 280 **INITORRESUME, 115** SSTMPCREATE, 281 INSNOTJOINED, 116 SSTMPDIRSTAT, 281 INSROLECHANGE, 116 SSTMPFILOPEN, 281 INSUNKNOWN, 117 SSV4NOALLOW, 281 NORESYNCSUPPLONLY, 207 STARFILE, 282 NORESYNCUPDATERONLY, 208 STATCNT, 282 NOSUPPLSUPPL, 210 STRMNUMIS, 283 RCVRMANYSTRMS, 228 STRMNUMMISMTCH1, 284 REPLNOHASHTREC, 245 STRMNUMMISMTCH2, 284 UPDSYNCINSTFILE, 308 STRMSEQMISMTCH, 284 Run Time STRUNXEOR, 285 ACOMPTBINC, 1 SUB2LONG, 285 ACTCOLLMISMTCH, 1 SUPRCVRNEEDSSUPSRC, 285 ACTLSTEXP, 2 TLSCONNINFO, 289 ACTLSTTOOLONG, 2 TLSCONVSOCK, 289 ACTRANGE, 3 TLSDLLNOOPEN, 289 ADDRTOOLONG, 3 TLSHANDSHAKE, 289 ALIASEXPECTED, 3 TLSINIT, 289 AMBISYIPARAM, 4 TLSIOERROR, 290 ARCTLMAXHIGH, 4 TLSRENEGOTIATE, 290 ARCTLMAXLOW, 4 TMPFILENOCRE, 290 ASSERT, 5 TRIG2NOTRIG, 298 BADCASECODE, 6 TRIGDATAIGNORE, 298 BADCHAR, 6 TRIGDEFBAD, 299 BADCHSET, 6 TRIGNAMBAD, 300 BADDBVER, 6 TRIGNAMENF, 301 BADGBLSECVER, 7 TRIGUPBADLABEL, 302 BADJPIPARAM, 7 TRUNCATEFAIL, 304 BADLKIPARAM, 7 UPDPROC, 307 BADQUAL, 7 UPDREPLSTATEOFF, 307 BADSRVRNETMSG, 8 UPDSYNC2MTINS, 308 BADSYIPARAM, 8 UPDSYNCINSTFILE, 308 BADTAG, 8 WCBLOCKED, 312 BADTRNPARAM, 8 WCERRNOTCHG, 313 BADZPEEKARG, 9 WCWRNNOTCHG, 313 BADZPEEKFMT, 9 ZGOTOINVLVL, 326 BADZPEEKRANGE, 9

BIGNOACL, 11	CRYPTDLNOOPEN, 29
BITMAPSBAD, 11	CRYPTDLNOOPEN, 29
•	•
BKUPTMPFILOPEN, 11	CRYPTHASHGENFAILED, 29
BKUPTMPFILWRITE, 12	CRYPTINIT, 29
BLKWRITERR, 13	CRYPTINIT2, 30
BOMMISMATCH, 13	CRYPTJNLWRONGHASH, 30
BREAK, 14	CRYPTKEYFETCHFAILED, 30
BREAKDEA, 15	CRYPTKEYFETCHFAILEDNF, 30
BREAKZBA, 15	CRYPTKEYTOOBIG, 31
BREAKZST, 15	CRYPTNOAPPEND, 31
BTFAIL, 15	CRYPTNOKEYSPEC, 31
BUFOWNERSTUCK, 16	CRYPTNOOVERRIDE, 32
BUFRDTIMEOUT, 16	CRYPTNOPSWDINTP, 32
CALLERID, 17	CRYPTNOSEEK, 32
CALLINAFTERXIT, 17	CRYPTNOTRUNC, 32
CEBIGSKIP, 17	CRYPTOPFAILED, 33
CENOINDIR, 17	CTLMNEMAXLEN, 33
CETOOLONG, 18	CTLMNEXPECTED, 33
CETOOMANY, 18	CTRAP, 33
CEUSRERROR, 18	CTRLC, 34
CHSETALREADY, 19	CTRLY, 34
CIMAXLEVELS, 19	CURRSOCKOFR, 34
CIMAXPARAM, 20	CUSTERRNOTFND, 34
CINOENTRY, 20	CUSTERRSYNTAX, 34
CITABENV, 21	CUSTOMFILOPERR, 35
CITABOPN, 21	DBADDRALIGN, 35
CITPNESTED, 21	DBADDRANGE, 35
CLIERR, 22	DBADDRANGE8, 35
CLOSEFAIL, 22	DBBADFREEBLKCTR, 36
CLSTCONFLICT, 22	DBBADUPGRDSTATE, 36
COLLARGLONG, 24	DBBLEVMN, 37
COLLATIONUNDEF, 24	DBBLEVMX, 37
COLLDATAEXISTS, 24	DBBMBARE, 37
COLLFNMISSING, 24	DBBMINV, 38
COLLTYPVERSION, 25	DBBMLCORRUPT, 38
COLTRANSSTR2LONG, 25	DBBMMSTR, 38
COMMENT, 26	DBBMSIZE, 38
COMMITWAITPID, 26	DBBSIZMN, 39
COMMITWAITSTUCK, 26	DBBSIZMX, 40
COMPILEQUALS, 26	DBCCERR, 41
CONNSOCKREQ, 27	DBCLNUPINFO, 42
	DBCMPBAD, 43
COREINPROGRESS, 27	·
CREDNOTPASSED, 28	DBCMPMZRO 42
CRITRESET, 28	DBCMPNZRO, 43
CRITSEMFAIL, 28	DBCNTRLERR, 44
CRYPTBADCONFIG, 28	DBCREINCOMP, 45
CRYPTBADWRTPOS, 28	DBCRERR, 46

FIS V6.2-002 GT.M Message and Recovery Procedures Manual DBCRERR8, 46 DEVICEREADONLY, 69 DBDANGER, 46 DEVICEWRITEONLY, 69

DBDIRTSUBSC, 47 DEVNOTIMP, 69 DBENDIAN, 47 DEVOPENFAIL, 69 DBFHEADERR, 48 DEVPARMNEG, 70

DBFHEADERR4, 48 DEVPARMTOOSMALL, 70 DBFHEADERR8, 48 **DEVPARTOOBIG, 71** 

DBFHEADERRANY, 48 DIRONLY, 71 DBFILERR, 49 DISTPATHMAX, 71

DBFILEXT, 49 DIVZERO, 71 DBFILOPERR, 49 DLCKAVOIDANCE, 72 DBFLCORRP, 49 DLLCHSETM, 72

DBFSYNCERR, 50 DLLCHSETUTF8, 72 DBIDMISMATCH, 51 DLLNOCLOSE, 72 DBIOERR, 52 DLLNOOPEN, 72 DBKEYMN, 52 DLLNORTN, 73 DBKEYMX, 53 DLLVERSION, 73

DSKNOSPCAVAIL, 76 DBKEYORD, 53 DBMBMINCFREFIXED, 55 DSKNOSPCBLOCKED, 76 DBNAMEMISMATCH, 58 DSKSPACEFLOW, 76

DBNOTGDS, 59 DVIKEYBAD, 77 DBOPNERR, 60 DYNUPGRDFAIL, 77 DBPREMATEOF, 60 DZTRIGINTRIG, 77 DBPRIVERR, 60 ECLOSTMID, 78 DBPTRMAP, 60 ERRCALL, 79 DBPTRMX, 60 ERRWETRAP, 80 DBPTRNOTPOS, 61 ERRWEXC, 80 DBQUELINK, 61 ERRWIOEXC, 80 ERRWZBRK, 80

DBRDERR, 62 DBRDONLY, 62 ERRWZINTR, 81 DBRNDWN, 63 ERRWZTRAP, 81 DBRNDWNWRN, 63 **EVENTLOGERR, 81** DBROLLEDBACK, 63 EXTGBLDEL, 82 DBROOTBURN, 64 EXTRFILEXISTS, 83 DBRSIZMN, 64 EXTSRCLIN, 84

DBRSIZMX, 64 EXTSRCLOC, 84 DBSHMNAMEDIFF, 64 FALLINTOFLST, 84 DBSTARCMP, 65 FILEDEL, 85 DBSTARSIZ, 65 FILEDELFAIL, 85 DBTNRESET, 66 FILEIDGBLSEC, 85

DBTNRESETINC, 66 FILEIDMATCH, 86

DBVERPERFWARN1, 67 FILENAMETOOLONG, 86 DBVERPERFWARN2, 68 FILENOTFND, 86

DBWCVERIFYEND, 68 FILEPARSE, 87 DBWCVERIFYSTART, 68 FILERENAME, 87 DELIMSIZNA, 68 FILTERBADCONV, 87 DELIMWIDTH, 69 FILTERCOMM, 87

MR Manual V6.2-002 GT.M Message and Recovery Procedures Manual June 09, 2015, Page 345

FILTERNOTALIVE, 88 FMLLSTMISSING, 88 FMLLSTPRESENT, 88 FNARGINC, 89 FNNAMENEG, 89 FNUMARG, 89 FORCEDHALT, 89 FORCTRLINDX, 90 FREEBLKSLOW, 90 FREEMEMORY, 90 FSEXP, 91 FSYNCTIMOUT, 91 FTOKERR, 91 GBLEXPECTED, 92 GBLMODFAIL, 92 GBLNOMAPTOREG, 94 GBLOFLOW, 94 GBLSECNOTGDS, 94 GDINVALID, 95 GETADDRINFO, 96 GETCWD, 96 GETNAMEINFO, 96 GETSOCKNAMERR, 97 GETSOCKOPTERR, 97 GTMASSERT, 97 GTMASSERT2, 97 GTMCHECK, 98 GTMDISTUNDEF, 98 GTMDISTUNVERIF, 98 GTMDUMPFAIL, 98 GTMEISDIR, 98 GTMERREXIT, 99 GTMSECSHR, 99 GTMSECSHRBADDIR, 99 GTMSECSHRDEFLOG, 100 GTMSECSHRFORKF, 100

GTMSECSHRBADDIR, 99
GTMSECSHRDEFLOG, 100
GTMSECSHRFORKF, 100
GTMSECSHRISNOT, 100
GTMSECSHRLOGF, 101
GTMSECSHRLOGSWH, 101
GTMSECSHRNOARGO, 101
GTMSECSHROPCMP, 101
GTMSECSHRPERM, 102
GTMSECSHRECVF, 102
GTMSECSHRSCKSEL, 103
GTMSECSHRSENDF, 103
GTMSECSHRSGIDF, 103
GTMSECSHRSGIDF, 103

GTMSECSHRSOCKET, 104 GTMSECSHRSRVF, 104 GTMSECSHRSRVFID, 104 GTMSECSHRSSIDF, 105 GTMSECSHRSTART, 105 GTMSECSHRSUIDF, 105 GTMSECSHRSUIDF, 105 GTMSECSHRTMOUT, 105 GVDATAFAIL, 106

GVDATAFAIL, 106 GVDATAGETFAIL, 106 GVFAILCORE, 106 GVGETFAIL, 107 GVINCRFAIL, 107

GVINCRISOLATION, 107

**GVIS**, 107

GVKILLFAIL, 108
GVNAKED, 108
GVORDERFAIL, 109
GVPUTFAIL, 109
GVQUERYFAIL, 109
GVQUERYGETFAIL, 109
GVREPLERR, 109
GVRUNDOWN, 110
GVSUBOFLOW, 110

GVSUBSERR, 110 GVUNDEF, 110 GVZPREVFAIL, 110 GVZTRIGFAIL, 111 HOSTCONFLICT, 111 HTEXPFAIL, 111 HTOFLOW, 112 HTSHRINKFAIL, 112 ICUERROR, 112

ICUSYMNOTFOUND, 112

ICUVERLT36, 112 IFBADPARM, 113 IFNOTINIT, 113

IGNBMPMRKFREE, 113
ILLESOCKBFSIZE, 114
IMAGENAME, 114
INDMAXNEST, 114
INDRCOMPFAIL, 114
INDRMAXLEN, 115
INSFFBCNT, 115
INSTFRZDEFER, 116
INVADDRSPEC, 117
INVALIDRIP, 117
INVBITLEN, 118

INVBITPOS, 118 INVBITSTR, 118 INVCTLMNE, 118 INVDLRCVAL, 119 INVECODEVAL, 119 **INVGTMEXIT, 120** INVICUVER, 120 INVLINKTMPDIR, 121 INVMNEMCSPC, 121 INVOBJ, 122 INVOBJFILE, 122 INVPORTSPEC, 122 INVROLLBKLVL, 123 INVSPECREC, 123 INVSTACODE, 123 INVSTRLEN, 124 INVTRCGRP, 124 INVZBREAK, 125 INVZDIRFORM, 125 INVZROENT, 125 INVZSTEP, 125 IOEOF, 126 IOERROR, 126 IONOTOPEN, 126 IORUNDOWN, 126 **IOWRITERR**, 126 IPADDRREO, 127 ISOLATIONSTSCHN, 127 ISSPANGBL, 127 IVTIME, 128 JIUNHNDINT, 128 JNI, 128 JNLACCESS, 128 **INLALIGNSZCHG**, 129 JNLBUFINFO, 131 JNLCLOSE, 131 JNLCLOSED, 132 JNLCNTRL, 132

JNLFSYNCERR, 137 JNLFSYNCLSTCK, 137 JNLINVALID, 137 JNLMEMDSK, 138 JNLMOVED, 139 JNLOPNERR, 141 JNLORDBFLU, 141 JNLPOOLSETUP, 141 JNLPREVRECOV, 142 JNLPROCSTUCK, 142 JNLPVTINFO, 142 **INLOIOLOCKED**, 142 JNLQIOSALVAGE, 143 JNLRDERR, 143 JNLRECFMT, 144 JNLRECTYPE, 144 **JNLSENDOPER**, 145 JNLSPACELOW, 145 **INLSWITCHSZCHG**, 146 JNLSWITCHTOOSM, 146 JNLTRANS2BIG, 148 **INLTRANSGTR, 148** JNLTRANSLSS, 148 JNLVSIZE, 149 JNLWRERR, 149 JNLWRTDEFER, 149 JOBARGMISSING, 150 JOBEXAMDONE, 150 JOBEXAMFAIL, 150 JOBFAIL, 150 JOBLABOFF, 151 JOBLVN2LONG, 151 JOBLVNDETAIL, 151 JOBPARM, 152 JOBPARTOOLONG, 152

JOBSETUP, 153 JOBSTARTCMDFAIL, 153 JUSTFRACT, 154 KEY2BIG, 154 KILLABANDONED, 155 KILLBYSIG, 155 KILLBYSIGSINFO1, 155 KILLBYSIGSINFO2, 156

KILLBYSIGUINFO, 156 KRNLKILL, 156 LABELNOTFND, 157

KILLBYSIGSINFO3, 156

JNLFLUSH, 136 JNLFLUSHNOPROG, 137

**JNLCREATERR**, 132

JNLDBERR, 133

JNLEXTEND, 134 **JNLFILEXTERR**, 135

JNLFILOPN, 136

JNLCRESTATUS, 132

**INLEOFPREZERO**, 134

June 09, 2015, Page 347

LABELONLY, 157 LCKSCANCELLED, 158 LCKSTIMOUT, 159 LINKVERSION, 160 LISTENPASSBND, 160 LKRUNDOWN, 161 LKSECINIT, 161 LOADRUNNING, 164 LOCALSOCKREO, 164 LOCKINCR2HIGH, 164

LOCKIS, 165

LOCKSPACEFULL, 165 LOCKSPACEINFO, 165 LOCKSUB2LONG, 166 LQLENGTHNA, 167 LVNULLSUBS, 167

MALLOCMAXUNIX, 168 MALLOCMAXVMS, 168 MAXARGCNT, 169 MAXBTLEVEL, 170 MAXGTMPATH, 170 MAXSEMGETRETRY, 170

MAXSTRLEN, 171

MAXTRACEHEIGHT, 171 MAXTRACELEVEL, 171 MAXTRIGNEST, 172 MBXRDONLY, 172 MBXWRTONLY, 172

MEMORY, 172

MEMORYRECURSIVE, 172 MERGEDESC, 173 MERGEINCOMPL, 173 MMFILETOOLARGE, 173 MMNODYNDWNGRD, 174 MMNODYNUPGRD, 174 MMREGNOACCESS, 175 MPROFRUNDOWN, 175

MRTMAXEXCEEDED, 175 MTANSIFOR, 175 MTANSILAB, 175 MTBLKTOOBIG, 176 MTBLKTOOSM, 176 MTDOSFOR, 176 MTDOSLAB, 176 MTFIXRECSZ, 176 MTINVLAB, 177 MTIOERR, 177

MTIS, 177

MTNOSKIP, 177 MTRDBADBLK, 177 MTRDONLY, 178 MTRDTHENWRT, 178 MTRECGTRBLK, 178 MTRECTOOBIG, 178 MTRECTOOSM, 178 MUINSTFROZEN, 181 MUINSTUNFROZEN, 181 MUPRECFLLCK, 186 MUTEXERR, 190

MUTEXFRCDTERM, 190 MUTEXLCKALERT, 191 MUTEXRELEASED, 191 MUTEXRSRCCLNUP, 192 MUUSERECOV, 194 MUUSERLBK, 194 NCTCOLLDIFF, 199 NCTCOLLSPGBL, 199 NEEDTRIGUPGRD, 199 NEGFRACPWR, 200 NETDBOPNERR, 200 NETFAIL, 200

NETLCKFAIL, 200

NEWJNLFILECREAT, 201 NLMISMATCHCALC, 201

NOALIASLIST, 201

NOCANONICNAME, 201

NOCHLEFT, 202 NOEDITOR, 202 NOEXCNOZTRAP, 203 NOFORKCORE, 203 NOJNLPOOL, 204 NOLBRSRC, 204 NONUTF8LOCALE, 206

NOPLACE, 206 NOPRINCIO, 207 NORECVPOOL, 207 NOSOCKETINDEV, 208 NOSOCKHANDLE, 208 NOSPACEEXT, 209 NOSUBSCRIPT, 209 NOSUCHPROC, 209 NOTALLDBRNDWN, 210 NOTERMENTRY, 211 NOTERMENV, 211

NOTERMINFODB, 211 NOTEXTRINSIC, 211 NOTGBL, 212 NOTPRINCIO, 212 NOTTOEOFONPUT, 213

NOZBRK, 213

NOZTRAPINTRIG, 213

NULLCOLLDIFF, 214 NULLENTRYREF, 214 NULSUBSC, 214 NUMOFLOW, 214

NUMPROCESSORS, 214 OBJFILERR, 215 OFFSETINIV 216

OFFSETINV, 216 OLDBINEXTRACT, 216 OPENCONN, 217 ORDER2, 217

ORLBKINPROG, 218 OUTOFSPACE, 219 PADCHARINVALID, 219

PARBUFSM, 219 PARFILSPC, 220 PARNORMAL, 220

PATNOTFOUND, 221 PATTABNOTFND, 221 PATTABSYNTAX, 221 PEERPIDMISMATCH, 222

PERMGENDIAG, 222 PERMGENFAIL, 222 PRCNAMLEN, 223 PREALLOCATEFAIL, 223 PREVJNLLINKCUT, 224 PROTNOTSUP, 225 QUALEXP, 226

QUITALSINV, 226 QUITARGREQD, 227 RANDARGNEG, 227 RDFLTOOLONG, 228 RDFLTOOSHORT, 228

REC2BIG, 229

QUALVAL, 226

RECNOCREJNL, 229 RECSIZENOTEVEN, 230 RECVPOOLSETUP, 230 RELINKCTLERR, 232

RELINKCTLFULL, 232 REMOTEDBNOSPGBL, 232 REMOTEDBNOTRIG, 233

REPLEXITERR, 235 REPLINFO, 236 REPLINSTACC, 236 REPLINSTCLOSE, 236 REPLINSTCREATE, 236 REPLINSTFMT, 238

REPLINSTFREEZECOMMENT, 238

REPLINSTFROZEN, 238
REPLINSTMISMTCH, 239
REPLINSTNOSHM, 240
REPLINSTOPEN, 240
REPLINSTREAD, 240
REPLINSTUNDEF, 243
REPLINSTUNFROZEN, 243
REPLINSTWRITE, 243
REPLINSTWRITE, 243
REPLINSTWRITE, 244
REPLREQRUNDOWN, 247
REQ2RESUME, 250
REODVIEWPARM, 250

REQDVIEWPARM, 250 REQRECOV, 250

 $REQRLNKCTLRNDWN,\,251$ 

REQROLLBACK, 251 REQRUNDOWN, 251 RESCRCWAIT, 251

RESRCINTRLCKBYPAS, 252 RLNKSHMLATCH, 255 RMBIGSHARE, 255 RMNOBIGRECORD, 256 RMSRDONLY, 256 RMWIDTHPOS, 256 RMWIDTHTOOBIG, 256 RNDWNSEMFAIL, 256 RNDWNSKIPCNT, 257 ROUTINEUNKNOWN, 257

RSVDBYTE2HIGH, 258

RTSLOC, 259

RUNPARAMERR, 259 SCNDDBNOUPD, 260 SDSEEKERR, 260 SECONDAHEAD, 260 SECSHRCHDIRFAILED, 261 SECSHRCLEARENVFAILED, 261 SECSHREXECLFAILED, 261

SECSHRGTMDBGLVL2LONG, 261 SECSHRGTMDIST2LONG, 261 SECSHRGTMTMP2LONG, 262

SECSHRNOGTMDIST, 262 SOCKETEXIST, 275 SECSHRNOTOWNEDBYROOT, 262 SOCKINIT, 275 SECSHRNOTSETUID, 262 SOCKLISTEN, 275 SECSHRPERMINCRCT, 262 SOCKMAX, 275 SECSHRSETGTMDISTFAILED, 262 SOCKNOTFND, 276 SECSHRSETGTMTMPFAILED, 263 SOCKNOTPASSED, 276 SECSHRSETUIDFAILED, 263 SOCKPARMREO, 276 SECSHRSTATFAILED, 263 SOCKPASS, 276 SECSHRWRITABLE, 263 SOCKPASSDATAMIX, 276 SEFCTNEEDSFULLB, 264 SOCKWAIT, 277 SELECTFALSE, 264 SOCKWRITE, 277 SEMKEYINUSE, 265 SPCLZMSG, 277 SEMWT2LONG, 265 SRCLOCUNKNOWN, 278 SETECODE, 266 SSATTACHSHM, 279 SETINSETTRIGONLY, 266 STACKCRIT, 281 SETINTRIGONLY, 266 STACKOFLOW, 282 SETITIMERFAILED, 266 STACKUNDERFLO, 282 STOPTIMEOUT, 283 SETSOCKOPTERR, 267 SETZDIR, 267 STPEXPFAIL, 283 SHMPLRECOV, 267 STUCKACT, 285 SHRMEMEXHAUSTED, 268 SUSPENDING, 285 SIGACCERR, 268 SVNEXPECTED, 286 SVNONEW, 286 SIGADRALN, 269 SYSCALL, 286 SIGADRERR, 269 SIGBADSTK, 269 TCGETATTR, 287 SIGCOPROC, 269 TCOMMITDISALLOW, 287 SIGFLTDIV, 270 TCSETATTR, 287 TERMASTQUOTA, 287 SIGFLTINV, 270 SIGFLTOVF, 270 TERMWRITE, 287 SIGFLTRES, 270 **TEXT**, 288 SIGFLTUND, 270 TIMERHANDLER, 288 SIGILLADR, 271 TIMEROVFL, 288 SIGILLOPC, 271 TLSCONVSOCK, 289 SIGILLOPN, 271 TLSHANDSHAKE, 289 SIGILLTRP, 271 TLSINIT, 289 SIGINTDIV, 272 TLSIOERROR, 290 SIGINTOVF, 272 TLSPARAM, 290 SIGMAPERR, 272 TLSRENEGOTIATE, 290 SIGOBJERR, 272 TLVLZERO, 290 SIGPRVOPC, 273 TNTOOLARGE, 291 SIGPRVREG, 273 TNWARN, 291 SIZENOTVALID4, 273 TOOMANYCLIENTS, 292 SIZENOTVALID8, 273 TOTALBLKMAX, 292 SOCKACCEPT, 274 TPFAIL, 292 SOCKACPT, 274 TPLOCK, 292 SOCKBFNOTEMPTY, 274 TPLOCKRESTMAX, 293

FIS

SOCKBIND, 274

TPMIXUP, 293

V6.2-002

TPNOSUPPORT, 293 UPDATEFILEOPEN, 307

TPNOTACID, 294 USRIOINIT, 308 TPQUIT, 294 VARRECBLKSZ, 310 TPRESTART, 294 VERMISMATCH, 310 TPRESTNESTERR, 295 VERSION, 310 TPSTACKCRIT, 295 VIEWAMBIG, 310 TPSTACKOFLOW, 295 VIEWARGCNT, 311 TPTIMEOUT, 295 VIEWCMD, 311 TPTOODEEP, 296 VIEWFN, 311 TRACINGON, 296 VIEWGVN, 311

TRANS2BIG, 296 VIEWLVN, 311 TRANSMINUS, 296 VIEWNOTFOUND, 312 TRANSNEST, 297 VMSMEMORY, 312 TRANSNOSTART, 297 VMSMEMORY2, 312 TRESTLOC, 297 WAITDSKSPACE, 312

TRESTMAX, 297 WCFAIL, 313

TRESTNOT, 298 WEIRDSYSTIME, 313 TRIGCOMPFAIL, 298 WIDTHTOOSMALL, 314

TRIGINVCHSET, 299 WILDCARD, 314 TRIGIS, 299 WRITERSTUCK, 314

TRIGLOADFAIL, 300 WRITEWAITPID, 315 TRIGMODINTP, 300 XCVOIDRET, 315

TRIGMODREGNOTRW, 300 XTRNRETSTR, 315 TRIGNAMBAD, 300 XTRNRETVAL, 315 TRIGNAMENF, 301 XTRNTRANSDLL, 316 TRIGNAMEUNIQ, 301 XTRNTRANSERR, 316 TRIGNOSPANGBL, 301 ZATTACHERR, 316 TRIGREPLSTATE, 301 ZBREAKFAIL, 316

TRIGTCOMMIT, 302 ZCALLTABLE, 316 TRIGTLVLCHNG, 302 ZCARGMSMTCH, 317 TRIGZBREAKREM, 303 ZCCLNUPRTNMISNG, 317

TROLLBK2DEEP, 303 ZCCOLON, 317

TRUNCATE, 303 ZCCONMSMTCH, 317 TTINVFILTER, 304 ZCCONVERT, 318 TTLENGTHTOOBIG, 304 ZCENTNAME, 319 TTWIDTHTOOBIG, 304 ZCINPUTREQ, 319

TXTNEGLIN, 304 ZCINVALIDKEYWORD, 319

TXTSRCFMT, 305 ZCMAXPARAM, 319 TXTSRCMAT, 305 ZCMLTSTATUS, 319

UIDMSG, 305 ZCNOPREALLOUTPAR, 320

UIDSND, 305 ZCOPT0, 320 UNDEF, 306 ZCPOSOVR, 320

UNIMPLOP, 306 ZCPREALLVALINV, 320 UNKNOWNFOREX, 306 ZCRCALLNAME, 321 UNSDCLASS, 306 ZCRPARMNAME, 321 UNSDDTYPE, 306 ZCRTENOTF, 321

UNSOLCNTERR, 307 ZCSTATUS, 322

ZCUNAVAIL, 322 ZCUNKOLAI, 322 ZCUNKQUAL, 322 ZCUNKQUAL, 322 ZCUNKQUAL, 322 ZCUNKQUAL, 322 ZCUNKYPE, 323 ZCUNTYPE, 323 ZCUSRRTN, 323 ZCUSRRTN, 323 ZCUSRRTN, 323 ZCUSRONGDESC, 323 ZCUSRONGDESC, 323 ZDATEBADDATE, 323 ZDATEBADDATE, 324 ZDATEBADDATE, 324 ZDATEBADTIME, 324 ZDATEBADTIME, 324 ZDBELSPEC, 325 ZFILSPEC, 325 ZFILSPEC, 325 ZFILSPEC, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILKEYBAD, 325 ZFILNBAD, 325 ZFILNBAD, 325 ZFILNBAD, 325 ZFILNBAD, 325 ZFILNBAD, 325 ZFILNBAD, 325 ZGOCALLOUTIN, 326 ZGOTOINVLVL, 326 ZGOTOITZERO, 326 ZGOTOITZERO, 327 ZINTDRECT, 327 ZINTDRECT, 327 ZINTDRECT, 327 ZINTDRECT, 327 ZLINKFILE, 328 ZPARSFLYPE, 328 ZPARSFLDBAD, 328 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPERINSTSCRAPS ZPERINSTSCRAPS ZEPINARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 331 ZSOCKETAOTS, 331 ZSOCKETAOTS, 331 ZSOCKETAOTS, 331 ZSOCKETNOTS, 331 ZSOCKETNOTS, 331 ZTRIGINVACT, 332 ZTRIGNOTP, 332 ZTR	ZCSTATUSRET, 322	ZTRIGNOTRW, 332
ZCUNKMECH, 322         S           ZCUNKTYPE, 323         Source Server log           ZCUNKTYPE, 323         JNLFURDOPN, 136           ZCUNTYPE, 323         JNLNOREPL, 140           ZCUSRETN, 323         JNLNOREPL, 140           ZCVROROBESC, 323         JNLNOLBADSLOT, 141           ZCWRONGEDESC, 323         JNLRECINCMPL, 144           ZDATEBADDATE, 323         REPLEBLLONG, 235           ZDATEBADTIME, 324         REPLINSTSECMTCH, 241           ZDATEBADTIME, 324         REPLINOTISECMTCH, 241           ZDATEBADTIME, 324         REPLINOMILITILINETRG, 245           ZDIROUTOFSYNC, 324         REPLINOMULTILINETRG, 245           ZEDFILSPEC, 325         REPLNOMULTILINETRG, 245           ZEDFILSPEC, 325         REPLNOMULTILINETRG, 245           ZEDFILSPEC, 325         REPLNOMULTILINETRG, 245           ZEDFILSPEC, 325         REPLNOMULTILINETRG, 245           ZEDFILSPEC, 325         SECNOTSUPPLEMENTARY, 260           SECNOTSUPPLEMENTARY, 260         SECNOTSUPPLEMENTARY, 260           SECNOTSUPLEMENTARY, 260         SECNOTSUPLEMENTARY, 260           SECNOTSUPLEMENTARY, 260         SECNOTSUPLEMENTARY, 260           SECNOTSUPLEMENTARY, 260         SECNOTSUPLEMENTARY, 260           SECOLLIOUTIN, 326         SECNOTSUPLEMENTARY, 260           ZEGOLIO	•	•
ZCUNKQUAL, 322         S           ZCUNKTYPE, 323         Source Server log           ZCUNTYPE, 323         JNLFILRDOPN, 136           ZCUSRTN, 323         JNLNOREPL, 140           ZCVECTORINDX, 323         JNLPOOLBADSLOT, 141           ZCWRONGDESC, 323         JNLPOOLBADSLOT, 141           ZDATEBADDATE, 323         JNLRECINCMPL, 144           ZDATEBADDTIME, 324         REPLOBLZLONG, 235           ZDATEBADTIME, 324         REPLINSTSECMTCH, 241           ZDIROUTOFSYNC, 324         REPLNOHASHTREC, 245           ZEDFILSPEC, 325         REPLNOHASHTREC, 245           ZEDROUTOLORS, 325         SECNOTSUPPLEMENTARY, 260           SECNOTSUPPLEMENTARY, 260         SECNOTSUPLEMENTARY, 260           SECOLLOUTIN, 326         SECNOTSUPLEMENTARY, 260           SUBCOMBAD		Z1 W ORWITOLLZBIG, 333
ZCUNKTYPE, 323 ZCUNTYPE, 323 ZCUSRTIN, 323 ZCUSRTIN, 323 ZCUSRTIN, 323 ZCUSRTIN, 323 ZCUSCTORINDX, 323 JINLPOOLBADSLOT, 141 ZCWRONGDESC, 323 JINLRECINCMPL, 144 ZDATEBADDATE, 323 ZDATEBADTIME, 324 ZDEPILSPEC, 325 ZEPLONDHASHTREC, 245 ZEDFILSPEC, 325 ZFILMOUTOFSYNC, 324 ZEDFILSPEC, 325 ZFILMEYBAD, 325 ZFILMEYBAD, 325 ZFILMEYBAD, 325 ZFILMEYBAD, 325 ZFILMBAD, 325 ZFILMBAD, 325 ZGGOZALLOUTIN, 326 ZGGOCALLOUTIN, 326 ZGGOCALLOUTIN, 326 ZGGOTOINVLVL2, 326 ZGGOTOINVLYL2, 326 ZGGOTOINVLYL2, 326 ZGGOTOINVLYL2, 326 ZGGTOTOOBIG, 327 ZINTRECURSEIO, 327 ZINTRECURSEIO, 327 ZINTRECURSEIO, 327 ZINTRECURSEIO, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 328 ZLMOOBJECT, 328 ZPARSFLDBAD, 328 ZPARSFLDBAD, 328 ZPARSFLDBAD, 328 ZPARSFLDBAD, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZSETPRVSYNTAX, 331 ZSOCKETATTR, 331 ZSOCKETATTR, 331 ZSOCKETATTR, 331 ZSOCKETNOTSOCK, 331 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332		S
ZCUNTYPE, 323 ZCUSRRTN, 323 ZCUSRRTN, 323 ZCUSRRTN, 323 JINLNOREPL, 140 ZCWRONGDESC, 323 JINLRECINCMPL, 144 ZCWRONGDESC, 323 ZDATEBADDATE, 323 ZDATEBADDATE, 324 ZDATEBADDIME, 324 ZDATEBADTIME, 324 ZDATEBADTIME, 324 ZDATEBADTIME, 324 ZDATEBADTIME, 324 ZDIROUTOFSYNC, 324 ZEDFILSPEC, 325 ZFFZMANY, 325 ZFFZMANY, 325 ZFFZMANY, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZGBLDIRACC, 326 ZGGCALLOUTIN, 326 ZGGCALLOUTIN, 326 ZGGOTOINVLVL2, 326 ZGGOTOINVLVL2, 326 ZGGOTOINVLVL2, 326 ZGGTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTBECURSEIO, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 328 ZLMODULE, 328 ZLMODULE, 328 ZLMODULE, 328 ZPARSFLDBAD, 328 ZPARSFLDBAD, 329 ZPREKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPREKNORPLINFO, 330 ZSETPRVSYNTAXER, 330 ZSETPRVSYNTAXER, 330 ZSETPRVSYNTAX, 330 ZSETPROSYNC, 299 ZSHOWBADFUNC, 331 ZSOCKETNOTSOCK, 331 ZSOCKETNOTSOCK, 331 ZRIGINVACT, 332 ZRIGINDACT, 332 Z		
ZCUSRRTN, 323 ZCVECTORINDX, 323 ZCWRONGDESC, 323 ZDATEBADDATE, 323 ZDATEBADDATE, 323 ZDATEBADDATE, 324 ZDATEBADTIME, 324 ZDATEBADTIME, 324 ZDATEMT, 324 ZDIROUTOFSYNC, 324 ZEDFILSPEC, 325 ZFF2MANY, 325 ZFILKYBAD, 325 ZFILKYBAD, 325 ZFILKYBAD, 325 ZGOCALLOUTIN, 326 ZGOCALLOUTIN, 326 ZGOTOINVLVL, 326 ZGOTOINVLVL, 326 ZGOTOINVLYL, 326 ZGOTOINVLYL, 327 ZINTDIRECT, 327 ZINTBIRECT, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 328 ZLMODULE, 328 ZLMODULE, 328 ZLMODULE, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPARSETYPE, 329 ZPIEVARGBAD, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 320 ZROSYNTAX, 330 ZSETPRVSNTAX, 330 ZSETPRVSNTAX, 330 ZSETPRVSNTAX, 330 ZSETPRVSNCA, 331 ZSENCHTMIC, 301 ZINGLOSPALL, 329 ZSCHONTAME, 331 ZSCHONTOLS, 331 ZSCHONTOLS, 331 ZTRIGNVACT, 331 ZTRIGNVACT, 332 ZRIGIOLOUTI, 331 ZTRIGNVACT, 332 ZRIGIONALL, 331 ZTRIGNVACT, 332 ZRIGIONALL, 331 ZTRIGNVACT, 332 ZRIGIONALL, 301 ZRIGINOVACT, 331 ZTRIGNOMET, 302 ZRIGIONALL, 301 ZRIGINOVACT, 331 ZTRIGIONACT, 332 ZRIGIONALT, 301 ZRIGINOMET, 302 ZRIGIONALT, 301 ZRIGINOMET, 301 ZRIGINOMET, 302 ZRIGIONALT, 331 ZRIGIONACT, 331 ZRIGIONACT, 332 ZRIGIONALT, 302	·	S
ZCVECTORINDX, 323 ZCWRONGDESC, 323 JNLPOOLBADSLOT, 141 ZCWRONGDESC, 323 JNLRECINCMPL, 144 ZDATEBADDATE, 324 ZDATEBADDTIME, 324 ZDATEBADTIME, 324 ZDATEBADTIME, 324 ZDATEFMT, 324 ZDATEFMT, 324 ZDATEFMT, 324 ZDATEFMT, 324 ZDATEFMT, 324 ZDATEFMT, 324 ZEDFILSPEC, 325 ZEFILSPEC, 325 ZFFZMANY, 325 ZFILENMTOOLONG, 325 ZGBLDIRACC, 326 ZGOCALLOUTIN, 326 ZGBLDIRACC, 326 ZGOCALLOUTIN, 326 ZGOTOINVLVL2, 326 ZGOTOINVLVL2, 326 ZGOTOINVLVL2, 326 ZGOTOINVLVL2, 326 ZGOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZILKIDBADARG, 328 ZLMODULE, 328 ZLMODULE, 328 ZLMODULE, 328 ZLMODULE, 328 ZLMODULE, 328 ZPARSFLYBE, 328 ZPARSFLYBE, 328 ZPARSFLYBE, 329 ZPARSETYPE, 329 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPRIVSYNTAXERR, 330 ZPRIVSYNTAXERR, 330 ZROSYNTAX, 330 ZROSYNT	•	
ZCWRONGDESC, 323 ZDATEBADDATE, 323 ZDATEBADDATE, 323 ZDATEBADTIME, 324 ZDATEBATTIME, 324 ZDATEFMT, 324 REPLINSTSECMTCH, 241 ZDATEFMT, 324 REPLNOHASHTREC, 245 ZDIROUTOFSYNC, 324 ZEDFILSPEC, 325 ZFELSMANY, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILENMED, 325 ZFILENMED, 325 ZGOCALLOUTIN, 326 ZGOCALLOUTIN, 326 ZGOTOINVLVL2, 326 ZGOTOINVLVL2, 326 ZGOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTBRECURSEIO, 327 ZILINEFILE, 327 ZLKIIDBADARG, 328 ZLMODULE, 328 ZLMODULE, 328 ZLMODULE, 328 ZLMODULE, 328 ZPARSFLYPE, 328 ZPARSFLYPE, 328 ZPARSFLYPE, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEINARGBAD, 320 ZPRIVARGBAD, 320 ZPRIVARGBAD, 320 ZPRIVSYNTAXERR, 330 ZPRILABNOTFND, 330 ZPETLABNOTFND, 330 ZSETTRVARGBAD, 330 ZSETTRVARGBAD, 330 ZSETTRVARGBAD, 330 ZSETTRVARGBAD, 331 ZSENGWACT, 331 ZSOCKETATIR, 331 ZSOCKETATIR, 331 ZSOCKETATIR, 331 ZSOCKETATIR, 331 ZSOCKETNOTSOCK, 331 ZSRCHSTRMCT, 332 ZTRIGINVACT, 332 ZTRICHMINTSTERC, 245 ZTRIVACT, 331 ZTRIGINVACT, 332 ZTRICHMACT, 331 ZTRIGINVACT, 332 ZTRICHMACT, 331 ZTRIGINVACT, 332 ZTRICHMACT, 331 ZTRIGINVACT, 332 ZTRICHMACT, 332	•	_
ZDATEBADDATE, 323 ZDATEBADTIME, 324 ZDATEBADTIME, 324 ZDATEFMT, 324 ZDATEFMT, 324 ZDIROUTOFSYNC, 324 ZEDFILSPEC, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 325 ZGBLDIRACC, 326 ZGOCALLOUTIN, 326 ZGOCALLOUTIN, 326 ZGOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTRECURSEIO, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 328 ZLMODULE, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPARSETYDE, 328 ZPARSETJDBAD, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEINARGBAD, 329 ZPRILABNOTFND, 330 ZROYNTAX, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 331 ZSHOWACT, 331 ZSCKETTMCT, 321 ZNOOBJECT, 331 ZSCKETTMCT, 331 ZTRIGINVACT, 331 ZTRIGINVACT, 331 ZTRIGINVACT, 331 ZTRIGINVACT, 331 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 331 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 331 ZTRIGINVACT, 332 ZTRICHOMUTILINETER, 245 ZTRICHAMOUNTILINETER, 245 ZTRICHAMOUNTILINETER	•	•
ZDATEBADTIME, 324 ZDATEFMT, 324 ZDATEFMT, 324 ZDIROUTOFSYNC, 324 ZEDFILSPEC, 325 ZEDFILSPEC, 325 ZFILSPEC, 325 ZFILSPEC, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 325 ZFILNMBAD, 325 ZGBLDIRACC, 326 ZGOCALLOUTIN, 326 ZGOCALLOUTIN, 326 ZGOTOINVLVL2, 326 ZGOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINODULE, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPEEKNOINLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEINSAN AS		
ZDATEFMT, 324 ZDIROUTOFSYNC, 324 ZEDFILSPEC, 325 ZFEDRANY, 325 ZFEDRANY, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 326 ZGOCALLOUTIN, 326 ZGOCALLOUTIN, 326 ZGOTOINVLVL2, 326 ZGOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 328 ZLMODULE, 328 ZPARSFLDBAD, 328 ZPARSFLDBAD, 329 ZPEEKNOJNLINFO, 329 ZPEEKNOJNLINFO, 329 ZPEEKNOJNLINFO, 329 ZPEEKNOJNLINFO, 329 ZPEEKNOJNLINFO, 329 ZPRIVSYNTAXERR, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZPRTVSYNTAXERR, 330 ZPRTVSYNTAX, 330		
ZDIROUTOFSYNC, 324 ZEDFILSPEC, 325 ZFEPLANY, 325 ZFILENMTOOLONG, 325 ZFILENMTOOLONG, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 325 ZFILKYBAD, 326 ZGOCALLOUTIN, 326 ZGOCALLOUTIN, 326 ZGOTOINVLV12, 326 ZGOTOINVLV12, 326 ZGOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTECURSEIO, 327 ZINTRECURSEIO, 327 ZLINKFILE, 327 ZLKIDBADARG, 328 ZLMODULE, 328 ZLMODULE, 328 ZLMODULE, 328 ZPARSFLDBAD, 328 ZPARSFLDBAD, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSHOWBADFUNC, 331 ZSHOWBADFUNC, 331 ZSHOWBLIN, 331 ZSHOWBLIN, 331 ZSHOWBLIN, 331 ZSHOWBADFUNC, 331 ZSHOWBADFUNC, 331 ZSHOWBADFUNC, 331 ZSHOWBLIN, 331 ZSHOWBLIN, 331 ZSRCHSTRMCT, 331 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 331 ZTRIGINVACT, 331 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332		•
ZEDFILSPEC, 325 ZFF2MANY, 325 ZFILENMTOOLONG, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 325 ZGBLDIRACC, 326 ZGOCALLOUTIN, 326 ZGOTOINVLV12, 326 ZGOTOINVLV12, 326 ZGOTOINVLV12, 326 ZGOTOINVLV12, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTRECURSEIO, 327 ZLINKFILE, 327 ZLKIDBADARG, 328 ZLMODULE, 328 ZLMODULE, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPIDBADARG, 329 ZPRIVARGBAD, 330 ZPRIVARGBAD, 330 ZPRIVARGBAD, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSHOWBADFUNC, 331 ZSHOWBICN, 331 ZSHOWACT, 331 ZSCKETTNIC, 331 ZTRIGINVACT, 331 ZTRIGINVACT, 331 ZTRIGINVACT, 332 ZTRIGINVACT, 331 ZTRIGINVACT, 332	•	
ZFF2MANY, 325 ZFILENMTOOLONG, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 325 ZFILNMBAD, 325 ZFILNMBAD, 325 ZFILNMBAD, 325 ZGBLDIRACC, 326 ZGOCALLOUTIN, 326 ZGOTOINVLVL2, 326 ZGOTOINVLVL2, 326 ZGOTOINTZERO, 326 ZGOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTBECURSEIO, 327 ZLINKFILE, 327 ZLINOBJECT, 328 ZLMODULE, 328 ZLMODULE, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPEEKNOJNLINFO, 329 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPRIVSYNTAXERR, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZSPTLABNOTFND, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSHOWBADFUNC, 331 ZSHOWBADFUNC, 331 ZSHOWBADFUNC, 331 ZSHOWBADFUNC, 331 ZSOCKETATTR, 331 ZSOCKETATTR, 331 ZSOCKETATR, 331 ZSRCHSTRMCT, 331 ZTRIGINVACT, 332 ZTRIGINVACT, 332	•	•
ZFILENMTOOLONG, 325 ZFILKEYBAD, 325 ZFILKEYBAD, 325 ZFILNMBAD, 325 ZFILNMBAD, 325 ZGBLDIRACC, 326 ZGOCALLOUTIN, 326 ZGOTOINVLV12, 326 ZGOTOINVLV12, 326 ZGOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTECURSEIO, 327 ZLINKFILE, 327 ZLINGBADAG, 328 ZLMODULE, 328 ZLMODULE, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPIDBADARG, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 330 ZPRILABNOTFND, 330 ZPRILABNOTFND, 330 ZPRILABNOTFND, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 331 ZSHOWGLOSMALL, 331 ZSOCKETNOTSOCK, 331 ZROSMIT, 302 ZROSMIT, 302 ZROSMIT, 302 ZROSMALL, 301 ZRIGINVACT, 332 ZROSMALL, 301 ZRIGINVACT, 332	•	·
ZFILKEYBAD, 325         SRCSRVEXISTS, 279           ZFILNMBAD, 325         SRCSRVNOTEXIST, 279           ZGBLDIRACC, 326         Success           ZGOCALLOUTIN, 326         DBCOMMITCLNUP, 45           ZGOTOINVLVL2, 326         DSKSPCAVAILABLE, 76           ZGOTOINTERO, 326         Syntax           ZGOTOTOOBIG, 327         CIDIRECTIVE, 19           ZINTDIRECT, 327         CIENTNAME, 19           ZINTRECURSEIO, 327         CIPARTYPE, 20           ZLINKFILE, 327         CIRCALLNAME, 20           ZLINGBADARG, 328         CIRTNTYP, 21           ZLMODULE, 328         CIRTNTYP, 21           ZLNOOBJECT, 328         CIUNTYPE, 21           ZPARSETYPE, 328         ZROSYNTAX, 330           ZPEEKNOJNLINFO, 329         T           ZPEEKNOJNLINFO, 329         T           ZPEEKNORPLINFO, 329         Trigger           ZPRIVARGBAD, 329         GVDATAGETFAIL, 106           ZPRIVSYNTAXERR, 330         NOZTRAPINTRIG, 213           ZPRIVSYNTAX, 330         REPLNOMULTILINETRG, 245           ZROSYNTAX, 330         SETINTRIGONLY, 266           ZSETPRVSYNTAX, 330         TRIGDEFBAD, 299           ZSHOWBADFUNC, 331         TRIGDEFNOSYNC, 299           ZSHOWBADFUNC, 331         TRIGIOADFAIL, 300 <tr< td=""><td>•</td><td>·</td></tr<>	•	·
ZFILNMBAD, 325         SRCSRVNOTEXIST, 279           ZGBLDIRACC, 326         Success           ZGOCALLOUTIN, 326         DBCOMMITCLNUP, 45           ZGOTOINVLVL2, 326         DSKSPCAVAILABLE, 76           ZGOTOTOOBIG, 326         Syntax           ZGOTOTOOBIG, 327         CIDIRECTIVE, 19           ZINTDIRECT, 327         CIENTNAME, 19           ZINTRECURSEIO, 327         CIPARTYPE, 20           ZLINKFILE, 327         CIRCALLNAME, 20           ZLINGBADARG, 328         CIRTNTYP, 21           ZLMODULE, 328         CIRTNTYP, 21           ZLNOOBJECT, 328         CIUNTYPE, 21           ZPARSETYPE, 328         ZROSYNTAX, 330           ZPEEKNOJNLINFO, 329         T           ZPEEKNOJNLINFO, 329         T           ZPEEKNOPLINFO, 329         Trigger           ZPIIDBADARG, 329         MAXTRIGNEST, 172           ZPRIVARGBAD, 329         MAXTRIGNEST, 172           ZPRIVSYNTAX, 330         REPLNOMULTILINETRG, 213           ZPRTLABNOTFND, 330         REPLNOMULTILINETRG, 245           ZSCTPRVSYNTAX, 330         TRIGCOMPFAIL, 298           ZSETPRVSYNTAX, 330         TRIGDEFNOSYNC, 299           ZSHOWBADFUNC, 331         TRIGDEFNOSYNC, 299           ZSHOWBADFUNC, 331         TRIGINVCHSET, 299		~
ZGBLDIRACC, 326         Success           ZGOCALLOUTIN, 326         DBCOMMITCLNUP, 45           ZGOTOINVLVL2, 326         DSKSPCAVAILABLE, 76           ZGOTOLTZERO, 326         Syntax           ZGOTOTOOBIG, 327         CIDIRECTIVE, 19           ZINTDIRECT, 327         CIENTNAME, 19           ZINTRECURSEIO, 327         CIPARTYPE, 20           ZLINKFILE, 327         CIRCALLNAME, 20           ZLKIDBADARG, 328         CIRPARMNAME, 20           ZLMODULE, 328         CIRTNTYP, 21           ZLNOOBJECT, 328         CIUNTYPE, 21           ZPARSETYPE, 328         ZROSYNTAX, 330           ZPARSFLDBAD, 328         T           ZPEEKNOJNLINFO, 329         T           ZPEEKNOPLINFO, 329         T           ZPRIVARGBAD, 329         GVDATAGETFAIL, 106           ZPRIVARGBAD, 329         MAXTRIGNEST, 172           ZPRIVSYNTAXERR, 330         NOZTRAPINTRIG, 213           ZPRTLABNOTFND, 330         REPLNOMULTILINETRG, 245           ZROSYNTAX, 330         SETINTRIGONLY, 266           ZSETPRVSYNTAX, 330         TRIGCOMPFAIL, 298           ZSETPRVSYNTAX, 330         TRIGDEFNOSYNC, 299           ZSHOWBADFUNC, 331         TRIGDEFNOSYNC, 299           ZSHOWBADFUNC, 331         TRIGINVCHSET, 299 <tr< td=""><td>•</td><td>SRCSRVEXISTS, 279</td></tr<>	•	SRCSRVEXISTS, 279
ZGOCALLOUTIN, 326 ZGOTOINVLVL2, 326 ZGOTOINVLVL2, 326 ZGOTOLTZERO, 326 ZGOTOLTZERO, 326 ZGOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTRECURSEIO, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 328 ZLMODULE, 328 ZLMODULE, 328 ZLNOOBJECT, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 331 ZSETPRVSYNTAX, 331 ZSETPRVSYNTAX, 331 ZSHOWBADFUNC, 331 ZSHOWGLOSMALL, 331 ZSCKETNOTSOCK, 331 ZRIGINVACT, 332 ZRIGINVACT, 331 ZRIGINVACT, 332 ZRIGINVACT, 332 ZRIGINVACT, 332 ZRIGINVACT, 331 ZRIGINVACT, 332 ZRIGINTACT, 19 ZRIGINVACT, 45 ZRICINTAC, 19 ZRICINTAC, 19 ZRICINTAC, 19 ZRICI		SRCSRVNOTEXIST, 279
ZGOTOINVLVL2, 326 ZGOTOLTZERO, 326 ZGOTOLTZERO, 326 ZGOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTRECURSEIO, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 328 ZLMODULE, 328 ZLMODULE, 328 ZLNOOBJECT, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPARSFLDBAD, 328 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPIDBADARG, 329 ZPIUBADARG, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX	·	Success
ZGOTOLTZERO, 326 ZGOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTDIRECT, 327 ZINTRECURSEIO, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINODULE, 328 ZLMODULE, 328 ZLMODULE, 328 ZLMODISECT, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPIDBADARG, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 330 ZPRILABNOTFND, 330 ZPRILABNOTFND, 330 ZROSYNTAX, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 331 ZSCHSTRMCT, 331 ZSCKETNOTSOCK, 331 ZSCKETNOTSOCK, 331 ZRIGIONACT, 332 ZRIGIONACT,	ZGOCALLOUTIN, 326	DBCOMMITCLNUP, 45
ZIOTOTOOBIG, 327 ZINTDIRECT, 327 ZINTRECURSEIO, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLINKFILE, 327 ZLKIDBADARG, 328 ZLMODULE, 328 ZLMODULE, 328 ZLNOOBJECT, 328 ZLNOOBJECT, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 329 ZPRIVASYNTAXERR, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZROSYNTAX, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 331 ZSETPRVARGBAD, 331 ZSCHSTRACT, 331 ZSOCKETATTR, 331 ZSOCKETNOTSOCK, 331 ZRIGINVACT, 332 ZROSYNTAM, 19 ZIRICINAME, 19 ZIRICINAME Z	ZGOTOINVLVL2, 326	DSKSPCAVAILABLE, 76
ZINTDIRECT, 327  ZINTRECURSEIO, 327  ZLINKFILE, 327  ZLKIDBADARG, 328  ZLMODULE, 328  ZLMODULE, 328  ZLNOOBJECT, 328  ZPARSETYPE, 328  ZPARSETYPE, 328  ZPEEKNOJNLINFO, 329  ZPEEKNORPLINFO, 329  ZPIDBADARG, 329  ZPRIVARGBAD, 329  ZPRIVARGBAD, 330  ZPRTLABNOTFND, 330  ZPRTLABNOTFND, 330  ZSETPRVARGBAD, 331  ZSETPRVARGBAD, 331  ZSETPRVARGBAD, 331  ZSHOWGLOSMALL, 331  ZSCKETATTR, 331  ZSCKETNOTSOCK, 331  ZRIGINVACT, 332  TRIGINAMEUNIQ, 301  ZTRIGINVACT, 332	ZGOTOLTZERO, 326	Syntax
ZINTRECURSEIO, 327  ZLINKFILE, 327  ZLKIDBADARG, 328  ZLMODULE, 328  ZLMOOBJECT, 328  ZPARSETYPE, 328  ZPARSFLDBAD, 328  ZPEEKNOJNLINFO, 329  ZPIDBADARG, 329  ZPIUBADARG, 329  ZPRIVARGBAD, 329  ZPRIVARGBAD, 329  ZPRIVARGBAD, 330  ZPRILABNOTFND, 330  ZERTYPNAX, 330  ZSETPRVARGBAD, 331  ZSETPRVARGBAD, 331  ZSETPRVARGBAD, 331  ZSOCKETATTR, 331  ZSOCKETATTR, 331  ZSOCKETNOTSOCK, 331  ZRIGINVACT, 332  TRIGINAMEUNIQ, 301  ZTRIGINVACT, 332	ZGOTOTOOBIG, 327	CIDIRECTIVE, 19
ZLINKFILE, 327  ZLKIDBADARG, 328  ZLMODULE, 328  ZLNOOBJECT, 328  ZPARSETYPE, 328  ZPARSETYPE, 328  ZPEKNOJNLINFO, 329  ZPEKNORPLINFO, 329  ZPIDBADARG, 329  ZPRIVARGBAD, 329  ZPRIVARGBAD, 329  ZPRIVARGBAD, 329  ZPRIVARGBAD, 329  ZPRIVARGBAD, 329  ZPRIVSYNTAXERR, 330  ZPRTLABNOTFND, 330  ZPRTLABNOTFND, 330  ZSETPRVARGBAD, 330  ZSETPRVARGBAD, 330  ZSETPRVARGBAD, 330  ZSETPRVARGBAD, 330  ZSETPRVARGBAD, 330  ZSETPRVARGBAD, 331  ZSOCKETATTR, 331  ZSOCKETATTR, 331  ZSOCKETNOTSOCK, 331  ZRIGINVACT, 332  CIRTNTYP, 21  CIRNTYP, 21  CIRTNTYP, 21  CIUNTYPE, 21  CROSYNTAX, 330  TRIGERMANE, 20  CIENTAL SAMPLE  TRIGERMANE, 20  CIENTAL SAMPLE  TRIGERMANE, 20  CIENTAL SAMPLE  TRIGERMANE, 20  CIENTAL SAMPLE  TRIGERMANE, 20  CIUNTYPE, 21  CIUNTYPE, 21  CIUNTYPE, 21  CROSYNTAX, 330  TRIGERMANE, 20  CIENTAL SAMPLE  TRIGERMANE, 20  CIUNTYPE, 21  CIUNT	ZINTDIRECT, 327	CIENTNAME, 19
ZLKIDBADARG, 328 ZLMODULE, 328 ZLMODULE, 328 ZLNOOBJECT, 328 ZPARSETYPE, 328 ZPARSETYPE, 328 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPIDBADARG, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVSYNTAX, 331 ZSOCKETATTR, 331 ZSOCKETATTR, 331 ZSOCKETNOTSOCK, 331 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZTRIGITOMMIT, 302	ZINTRECURSEIO, 327	CIPARTYPE, 20
ZLMODULE, 328 ZLNOOBJECT, 328 ZLNOOBJECT, 328 ZPARSETYPE, 328 ZPARSFLDBAD, 328 ZPARSFLDBAD, 328 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPIDBADARG, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 329 ZPRIVSYNTAXERR, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 331 ZSOCKETATTR, 331 ZSOCKETATTR, 331 ZSOCKETNOTSOCK, 331 ZSRCHSTRMCT, 331 ZTRIGINVACT, 332 ZTRIGINVACT, 332 ZROSYNTAY, 330 ZROSYNTAY, 330 TRIGDEFNOSYNC, 299 TRIGDEFNOSYNC, 299 TRIGINVCHSET, 299 TRIGLOADFAIL, 300 TRIGNAMEUNIQ, 301 TRIGNAMEUNIQ, 301 TRIGTCOMMIT, 302	ZLINKFILE, 327	CIRCALLNAME, 20
ZLNOOBJECT, 328 ZPARSETYPE, 328 ZPARSFLDBAD, 328 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPIDBADARG, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 329 ZPRIVSYNTAXERR, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVSYNTAX, 330 TRIGDEFBAD, 299 ZSHOWBADFUNC, 331 TRIGDEFNOSYNC, 299 ZSHOWGLOSMALL, 331 TRIGINVCHSET, 299 ZSOCKETATTR, 331 TRIGIS, 299 ZSOCKETNOTSOCK, 331 ZTRIGINVACT, 332 TRIGINAMEUNIQ, 301 ZTRIGINVACT, 332 TRIGTCOMMIT, 302	ZLKIDBADARG, 328	CIRPARMNAME, 20
ZPARSETYPE, 328 ZPARSFLDBAD, 328 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 329 ZPRIVSYNTAXERR, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 331 ZSHOWBADFUNC, 331 ZSHOWGLOSMALL, 331 ZSOCKETATTR, 331 ZSOCKETNOTSOCK, 331 ZSRCHSTRMCT, 331 ZTRIGINVACT, 332 ZROSYNTAX, 330 ZROSYNTAX, 330 TRIGGEFBAD, 299 ZSHOWGLOSMALL, 331 TRIGINVCHSET, 299 ZSOCKETNOTSOCK, 331 ZTRIGINVACT, 332 TRIGINAMEUNIQ, 301 ZTRIGINVACT, 332	ZLMODULE, 328	CIRTNTYP, 21
ZPARSFLDBAD, 328 ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPRIVARGBAD, 329 ZPRIVARGBAD, 329 ZPRIVSYNTAXERR, 330 ZPRTLABNOTFND, 330 ZROSYNTAX, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 331 ZSHOWBADFUNC, 331 ZSHOWBADFUNC, 331 ZSHOWGLOSMALL, 331 ZSOCKETATTR, 331 ZSOCKETATTR, 331 ZSOCKETNOTSOCK, 331 ZRIGINVACT, 332 TRIGINAMEUNIQ, 301 ZTRIGINVACT, 332 TRIGTCOMMIT, 302	ZLNOOBJECT, 328	CIUNTYPE, 21
ZPEEKNOJNLINFO, 329 ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPIDBADARG, 329 ZPRIVARGBAD, 329 ZPRIVSYNTAXERR, 330 ZPRTLABNOTFND, 330 ZPRTLABNOTFND, 330 ZROSYNTAX, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 331 ZSHOWBADFUNC, 331 ZSHOWGLOSMALL, 331 ZSOCKETATTR, 331 ZSOCKETATTR, 331 ZSOCKETNOTSOCK, 331 ZTRIGINVACT, 332 ZTRIGINVACT, 332 TRIGTCOMMIT, 302	ZPARSETYPE, 328	ZROSYNTAX, 330
ZPEEKNORPLINFO, 329 ZPIDBADARG, 329 ZPRIVARGBAD, 329 ZPRIVSYNTAXERR, 330 ZPRTLABNOTFND, 330 ZROSYNTAX, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSHOWBADFUNC, 331 ZSHOWGLOSMALL, 331 ZSOCKETATTR, 331 ZSOCKETATTR, 331 ZSOCKETNOTSOCK, 331 ZRIGINVACT, 332 TRIGINAMEUNIQ, 301 ZTRIGINVACT, 332 TRIGTCOMMIT, 302	ZPARSFLDBAD, 328	·
ZPIDBADARG, 329 ZPRIVARGBAD, 329 ZPRIVSYNTAXERR, 330 ZPRTLABNOTFND, 330 ZROSYNTAX, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVARGBAD, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSETPRVSYNTAX, 330 ZSHOWBADFUNC, 331 ZSHOWGLOSMALL, 331 ZSOCKETATTR, 331 ZSOCKETATTR, 331 ZSOCKETNOTSOCK, 331 ZRIGNVACT, 332 ZTRIGINVACT, 332 ZNOATAGETFAIL, 106 MAXTRIGNEST, 172 NOZTRAPINTRIG, 213 REPLNOMULTILINETRG, 245 REPLNOMULT, 300 REPLNOMULT, 301 REPLNOMULT, 300 REPLNOMULT, 301 REPLNOMULT, 301 REPLNOMULT, 302	ZPEEKNOJNLINFO, 329	Т
ZPIDBADARG, 329 ZPRIVARGBAD, 329 MAXTRIGNEST, 172 ZPRIVSYNTAXERR, 330 NOZTRAPINTRIG, 213 ZPRTLABNOTFND, 330 REPLNOMULTILINETRG, 245 ZROSYNTAX, 330 SETINTRIGONLY, 266 ZSETPRVARGBAD, 330 TRIGCOMPFAIL, 298 ZSETPRVSYNTAX, 330 TRIGDEFBAD, 299 ZSHOWBADFUNC, 331 TRIGDEFNOSYNC, 299 ZSHOWGLOSMALL, 331 TRIGINVCHSET, 299 ZSOCKETATTR, 331 TRIGIS, 299 ZSOCKETNOTSOCK, 331 TRIGLOADFAIL, 300 ZSRCHSTRMCT, 331 TRIGNAMEUNIQ, 301 ZTRIGINVACT, 332 TRIGTCOMMIT, 302	ZPEEKNORPLINFO, 329	Trigger
ZPRIVARGBAD, 329  ZPRIVSYNTAXERR, 330  NOZTRAPINTRIG, 213  REPLNOMULTILINETRG, 245  ZROSYNTAX, 330  ZSETPRVARGBAD, 330  ZSETPRVSYNTAX, 330  TRIGCOMPFAIL, 298  ZSETPRVSYNTAX, 330  TRIGDEFBAD, 299  ZSHOWBADFUNC, 331  ZSHOWGLOSMALL, 331  TRIGINVCHSET, 299  ZSOCKETATTR, 331  ZSOCKETNOTSOCK, 331  TRIGLOADFAIL, 300  ZSRCHSTRMCT, 331  TRIGNAMEUNIQ, 301  TRIGTCOMMIT, 302	ZPIDBADARG, 329	
ZPRIVSYNTAXERR, 330  ZPRTLABNOTFND, 330  REPLNOMULTILINETRG, 245  ZROSYNTAX, 330  SETINTRIGONLY, 266  ZSETPRVARGBAD, 330  TRIGCOMPFAIL, 298  ZSETPRVSYNTAX, 330  TRIGDEFBAD, 299  ZSHOWBADFUNC, 331  TRIGDEFNOSYNC, 299  ZSHOWGLOSMALL, 331  TRIGINVCHSET, 299  ZSOCKETATTR, 331  TRIGIS, 299  ZSOCKETNOTSOCK, 331  TRIGLOADFAIL, 300  ZSRCHSTRMCT, 331  TRIGNAMEUNIQ, 301  ZTRIGINVACT, 332  TRIGTCOMMIT, 302	ZPRIVARGBAD, 329	
ZPRTLABNOTFND, 330  ZROSYNTAX, 330  ZSETPRVARGBAD, 330  ZSETPRVSYNTAX, 330  ZSETPRVSYNTAX, 330  ZSHOWBADFUNC, 331  ZSHOWGLOSMALL, 331  ZSOCKETATTR, 331  ZSOCKETATTR, 331  ZSOCKETNOTSOCK, 331  ZRIGNAMEUNIQ, 301  ZTRIGINVACT, 332  TRIGTCOMMIT, 302	ZPRIVSYNTAXERR, 330	· · · · · · · · · · · · · · · · · · ·
ZROSYNTAX, 330 ZSETPRVARGBAD, 330 TRIGCOMPFAIL, 298 ZSETPRVSYNTAX, 330 TRIGDEFBAD, 299 ZSHOWBADFUNC, 331 TRIGDEFNOSYNC, 299 ZSHOWGLOSMALL, 331 TRIGINVCHSET, 299 ZSOCKETATTR, 331 TRIGIS, 299 ZSOCKETNOTSOCK, 331 TRIGLOADFAIL, 300 ZSRCHSTRMCT, 331 TRIGNAMEUNIQ, 301 ZTRIGINVACT, 332 TRIGTCOMMIT, 302	ZPRTLABNOTFND, 330	
ZSETPRVARGBAD, 330  ZSETPRVSYNTAX, 330  ZSHOWBADFUNC, 331  ZSHOWGLOSMALL, 331  ZSOCKETATTR, 331  ZSOCKETNOTSOCK, 331  ZSRCHSTRMCT, 331  ZTRIGINVACT, 332  TRIGCOMPFAIL, 298  TRIGDEFBAD, 299  TRIGINVCHSET, 299  TRIGINVCHSET, 299  TRIGIS, 299  TRIGLOADFAIL, 300  TRIGNAMEUNIQ, 301  TRIGINVACT, 332  TRIGTCOMMIT, 302	•	•
ZSETPRVSYNTAX, 330  ZSHOWBADFUNC, 331  ZSHOWGLOSMALL, 331  ZSOCKETATTR, 331  ZSOCKETNOTSOCK, 331  ZSRCHSTRMCT, 331  ZTRIGINVACT, 332  TRIGDEFBAD, 299  TRIGDEFNOSYNC, 299  TRIGINVCHSET, 299  TRIGIS, 299  TRIGLOADFAIL, 300  TRIGNAMEUNIQ, 301  TRIGINVACT, 332  TRIGTCOMMIT, 302	•	•
ZSHOWBADFUNC, 331  ZSHOWGLOSMALL, 331  ZSOCKETATTR, 331  ZSOCKETNOTSOCK, 331  ZSRCHSTRMCT, 331  ZTRIGINVACT, 332  TRIGLOADFAIL, 300  TRIGNAMEUNIQ, 301  TRIGTCOMMIT, 302	•	·
ZSHOWGLOSMALL, 331  ZSOCKETATTR, 331  ZSOCKETNOTSOCK, 331  ZRCHSTRMCT, 331  TRIGINVCHSET, 299  TRIGIS, 299  TRIGLOADFAIL, 300  TRIGNAMEUNIQ, 301  TRIGINVACT, 332  TRIGTCOMMIT, 302	•	·
ZSOCKETATTR, 331 TRIGIS, 299 ZSOCKETNOTSOCK, 331 TRIGLOADFAIL, 300 ZSRCHSTRMCT, 331 TRIGNAMEUNIQ, 301 ZTRIGINVACT, 332 TRIGTCOMMIT, 302	•	
ZSOCKETNOTSOCK, 331 TRIGLOADFAIL, 300 ZSRCHSTRMCT, 331 TRIGNAMEUNIQ, 301 ZTRIGINVACT, 332 TRIGTCOMMIT, 302	•	•
ZSRCHSTRMCT, 331 TRIGNAMEUNIQ, 301 ZTRIGINVACT, 332 TRIGTCOMMIT, 302		
ZTRIGINVACT, 332 TRIGTCOMMIT, 302		•
	•	~
TRIGILVECTING, 502		
		TROTE VECTIVO, 502

ZTRIGINVACT, 332 ZTRIGNOTP, 332 ZTWORMHOLE2BIG, 333

## U

Update Process log JRTNULLFAIL, 153 STRMSEQMISMTCH, 284 TRIGDEFNOSYNC, 299 Utility NOGTCMDB, 204 NOUSERDB, 213 PROCTERM, 225

This page is intentionally left blank.

MR Manual FIS GT.M Message and Recovery Procedures Manual

# Appendix A. Error Message Quick Reference

Revision History		
Revision V6.2-002	9 June 2015	Updated for V6.2-002.
Revision V6.1-000	30 December 2013	Updated for V6.1-000.
Revision V6.0-001	04 April 2013	First published version.

## **Standard Error Codes**

Standard Code	GT.M Message(s)
M1, Naked indicator undefined	GVNAKED, Illegal naked global reference
M2, Invalid combination with P _fncodatom_	None
M3, \$RANDOM seed less than 1	RANDARGNEG, Random number generator argument must be greater than or equal to one
M4, No true condition in \$SELECT	SELECTFALSE, No argument to \$SELECT was true
M5, _lineref_ less than zero	TEXTARG, Invalid argument to \$TEXT function
M6, Undefined _lvn_	UNDEF, Undefined local variable: xxxx
M7, Undefined _gvn_	GVUNDEF, Global variable undefined: xxxx
M8, Undefined _svn_	INVSVN, Invalid special variable name
M9, Divide by zero	DIVZERO, Attempt to divide by zero
M10, Invalid pattern match range	PATCODE, Illegal syntax for pattern
	PATUPPERLIM, Pattern code upper limit is less than lower limit
M11, No parameters passed	FALLINTOFLST, Fall-through to a label with formallist is not allowed
M12, Invalid _lineref_ (negative offset)	GVNAKED, Illegal naked global reference
M13, Invalid _lineref_ (label not found)	JOBLABOFF, Label and offset not found in created process
	• LABELMISSING, Label referenced but not defined : xxxx
	LABELNOTFND, GOTO referenced a label that does not exist

Standard Code	GT.M Message(s)
	LABELUNKNOWN, Label referenced but not defined
	OFFSETINV, Entry point xxxx+yyyy not valid
	ZPRTLABNOTFND, Label not found in routine
M14, _line_ level not 1	None
M15, Undefined index variable	None
M16, Argumented QUIT not allowed	NOTEXTRINSIC, Quit does not return to an extrinsic function, argument not allowed
	QUITARGLST, Quit cannot take a list of arguments
	QUITARGUSE, Quit cannot take an argument in this context
M17, Argumented QUIT required	QUITARGREQD, Quit from an extrinsic must have an argument
M18, Fixed length READ not greater than zero	RDFLTOOSHORT, Length specified for fixed length read less than or equal to zero
M19, Cannot copy a tree or subtree into itself	MERGEDESC, Merge operation not possible. xxxx is descendent of yyyy.
M20, _line_ must have _formallist_	None
M21, Formal parameter occurs multiple times (original text: Algorithm specification invalid)	None
M22, SET or KILL to ^\$GLOBAL when data in global	None
M23, SET or KILL to ^\$JOB for non-existent job number	None
M24, Change to collation algorithm while subscripted local variables defined	None
M25, Attempt to modify currently executing routine	None
M26, Non-existent _environment_	None
M27, Attempt to rollback a transaction that is not restartable	None
M28, Mathematical function, parameter out of range	None
M29, SET or KILL on _ssvn_ not allowed by implementation	None
M30, Reference to _glvn_ with different collating sequence within a collating algorithm	None

Standard Code	GT.M Message(s)
M31, _controlmnemonic_ used for device without a _mnemonicspace_ selected	None
M32, _controlmnemonic_ used in user-defined _mnemonicspace_ which has no associated line	RANDARGNEG, Random number generator argument must be greater than or equal to one
M33, SET or KILL to ^\$ROUTINE when _routine_ exists	None
M34, currently unassigned	None
M35, Device does not support _mnemonicspace_	INVMNEMCSPC, Unsupported mnemonicspace xxxx
M36, Incompatible _mnemonicspace_s	None
M37, READ from device identified by the empty string	None
M38, Invalid _ssvn_ subscript	None
M39, Name of variable expected (original text: Invalid \$NAME argument)	VAREXPECTED, Variable expected in this context
M40, Call-by-reference in JOB _actual_	JOBACTREF, Actual parameter in job command passed by reference
M41, Invalid LOCK argument within a TRANSACTION	TPLOCK, Cannot release lock(s) held prior to current TSTART
M42, Invalid QUIT within a TRANSACTION	SELECTFALSE, No argument to \$SELECT was true
M43, Invalid range (\$X, \$Y)	None
M44, Invalid _command_ outside of a TRANSACTION	TLVLZERO, Transaction is not in progress TRANSNOSTART, ZTCOMMIT(s) issued without corresponding ZTSTART(s)
M45, Invalid GOTO reference	None
M46, Invalid attribute name	None
M47, Invalid attribute value (original text: Invalid attribute name)	None
M48, Nonexistent window, element or choice	None
M49, Invalid attempt to set focus	None
<b>M50</b> , Attempt to reference a non M-Term window in an OPEN command	None
<b>M51,</b> Attempt to destroy M-Term window prior to CLOSE	None

V6.2-002 MR Manual June 09, 2015, Page 357

Standard Code	GT.M Message(s)
M52, Required attribute missing	TEXTARG, Invalid argument to \$TEXT function
M53, Invalid argument for font function	None
M54, Attempt to create non-modal child of a modal parent	None
M55, Invalid nested TSTART command	None
M56, Name length exceeds implementation's limit	None
<b>M57</b> , More than one defining occurrence of label in routine	MULTLAB, This label has been previously defined
M58, Too few formal parameters	<ul> <li>ACTLSTTOOLONG, More actual parameters than formal parameters: xxxx</li> <li>ZCARGMSMTCH, External call: Actual argument count, xxxx is greater than formal argument count, yyyy</li> <li>ZCCONMSMTCH, External call: Too many input arguments</li> </ul>
M59, Environment reference not permitted for this _ssvn_	None
M60, Undefined _ssvn_	None
<b>M61,</b> Attempt to OPEN file with conflicting ACCESS parameters	None
M62, Illegal value for ACCESS parameter while attempting to OPEN file	UNDEF, Undefined local variable: xxxx
M63, Illegal value for DISPOSITION parameter while attempting to CLOSE file	None
M64, Illegal value for RENAME parameter while attempting to CLOSE file	None
M65, Illegal value for VOLUME label	None
M66, Illegal value for DENSITY parameter	None
M67, Illegal value for ACCESS parameter	None
M68, Illegal value for MOUNT parameter	None
M69, Attempted tape I/O while no tape mounted	None
M70, Illegal value for BLOCKSIZE parameter	MTBLKTOOBIG, Magtape BLOCK_SIZE exceeds maximum size allowed

Standard Code	GT.M Message(s)
	MTBLKTOOSM, Magtape BLOCK_SIZE is less than xxxx bytes
	MTFIXRECSZ, BLOCK_SIZE xxxx must be a multiple of fixed record size yyyy
M71, Attempt to read data block larger than buffer size	MTRECGTRBLK, Magtape record size cannot exceed block size
M72, Illegal value for recordsize parameter	GVUNDEF, Global variable undefined: xxxx
M73, Invalid usage of _devicekeyword_ NEWFILE	None
M74, Illegal value for TRANSLATION parameter	None
M75, String length exceeds implementation's limit	<ul> <li>MAXSTRLEN, Maximum string length exceeded</li> <li>REC2BIG, Record size (xxxx) is greater than maximum (yyyy) for region: zzzz</li> <li>ZFILENMTOOLONG, xxxx is longer than 255 characters</li> </ul>
M76, TCP socket state incorrect for CONNECT or LISTEN	LISTENPASSBND, Controlmnemonic LISTEN can be applied to PASSIVE socket which is in the state BOUND ONLY
M77, TCP _deviceattribute_ missing	None
M78, TCP _devicekeyword_ missing	None
M79, TCP socket allocated to another device	SOCKETEXIST, Socket xxxx already exists
M80, Network error not otherwise specified	<ul> <li>SOCKINIT, Error initializing socket: (errno == aaaa) xxxx</li> <li>SOCKMAX, Attempt to exceed maximum sockets xxx for the SOCKET device</li> <li>SOCKWAIT, Error waiting for socket connection</li> </ul>
M81, Unable to establish network connection	OPENCONN, Error opening socket connection     SOCKACPT, Error accepting socket connection
M82, Network connection suspended: wait to resume	INVSVN, Invalid special variable name
M83, Network connection lost	None
M84, Network protocol error: invalid client message	None
M85, Network protocol error: invalid server message	None
M86, Cannot relinquish device with I/O pending	None

V6.2-002 MR Manual June 09, 2015, Page 359

Standard Code	GT.M Message(s)
M87, Network buffer overflow	None
M88, Non-existent _routine_	ROUTINEUNKNOWN, Routine could not be found
M89, Specified pattern is not a _subpattern_	None
M90, Invalid _namevalue_	NOCANONICNAME, Value is not a canonic name (xxxx).
M91, Routine source is not available	None
M92, Mathematical overflow	DIVZERO, Attempt to divide by zero
M93, Mathematical underflow	None
M94, Attempt to compute zero to the zero-eth power	None
M95, Exponentiation returns complex number with non-zero imaginary part	NEGFRACPWR, Invalid operation: fractional power of negative number
M96, Attempt to assign value to already valued write-once _ssvn_	None
M97, Routine associated with user-defined _ssvn_ does not exist	None
M98, Resource unavailable	None
M99, Invalid operation for context	None
M100, Output time-out expired	None
M101, Attempt to assign incorrect value to \$ECODE	INVECODEVAL, Invalid value for \$ECODE (xxxx).
M102, Simultaneous synchronous and asynchronous event class	<ul> <li>PATCODE, Illegal syntax for pattern</li> <li>PATUPPERLIM, Pattern code upper limit is less than lower limit</li> </ul>
M103, Invalid event identifier	None
M104, IPC event identifier is not a valid job-number	None
M105, Object not currently accessible	None
<b>M106,</b> Object does not support requested method or property	None
M107, Object has no default value	None
M108, Value if not of data type OREF	None
M109, Undefined _devicekeyword_	None
M110, Event identifier not available	None

Standard Code	GT.M Message(s)
M111, Invalid number of days for date	None
M112, Invalid number of seconds for time	FALLINTOFLST, Fall-through to a label with formallist is not allowed

## **ZMESSAGE Codes**

The following table lists ZMESSAGE numbers and the severity levels of all messages documented in this manual.

ZM #	GT.M Message, Description
150339600	BREAKZST, Break instruction encountered during ZSTEP action
150339608	BADACCMTHD, Invalid access method was specified
150339616	BADJPIPARAM, !AD is not a legal parameter for \$ZGETJPI()
150339624	BADSYIPARAM, !AD is not a legal parameter for \$ZGETSYI()
150339632	BITMAPSBAD, Database bit maps are incorrect
150339640	BREAK, Break instruction encountered
150339648	BREAKDEA, Break instruction encountered during Device error action
150339656	BREAKZBA, Break instruction encountered during ZBREAK action
150339664	STATCNT, !AD:!_ Key cnt: !UL max subsc len: !UL max data len: !UL
150339672	BTFAIL, The database block table is corrupt; error type !UL
150339680	MUPRECFLLCK, Database file !AD is locked by MUPIP RECOVER. Could not secure access.
150339688	CMD, Command expected but not found
150339696	COLON, Colon (:) expected in this context
150339704	COMMA, Comma expected in this context
150339712	COMMAORRPAREXP, Comma or right parenthesis expected but not found
150339720	COMMENT, Comment line. Placed zbreak at next executable line.
150339728	CTRAP, Character trap \$C(!UL) encountered
150339736	CTRLC, CTRL_C encountered
150339744	CTRLY, User interrupt encountered
150339752	DBCCERR, Interlock instruction failure in critical mechanism for region !AD
150339760	DUPTOKEN, Token 0x!16@XQ is duplicate in the journal file !AD for database !AD

V6.2-002 MR Manual GT.M Message and Recovery Procedures Manual June 09, 2015, Page 361

to database f  150339776 DBFILERR, F  150339784 DBNOTGDS  150339792 DBOPNERR,  150339800 DBRDERR, C  150339816 DEVPARINA  150339824 RECORDSTA	
150339784 DBNOTGDS 150339792 DBOPNERR, 150339800 DBRDERR, C 150339816 DEVPARINA 150339824 RECORDSTA	MATCH, Database !AD points to journal file name !AD but the journal file points file !AD
150339792 DBOPNERR, C 150339800 DBRDERR, C 150339816 DEVPARINA 150339824 RECORDSTA	Error with database file !AD
150339800 DBRDERR, C 150339816 DEVPARINA 150339824 RECORDSTA UL	, !AD
150339816 DEVPARINA 150339824 RECORDSTA UL	Error opening database file !AD
150339824 RECORDSTA	Cannot read database file !AD after opening
UL	AP, Device parameter inappropriate to this command
150339832 NOTGBL, Ex	AT, !AD:!_ Key cnt: !@ZQ max subsc len: !UL max rec len: !UL max node len: !
	xpected a global variable name starting with an up
150339840 DEVPARPRO	OT, The protection specification is invalid
150339848 PREMATEO	F, Premature end of file detected
150339856 GVINVALID	, !_!AD!/!_!_!_Invalid global name
150339864 DEVPARTO	OBIG, String deviceparameter exceeds 255 character limit
150339872 DEVPARUN	K, Deviceparameter unknown
150339880 DEVPARVA	LREQ, A value is required for this device parameter
150339888 DEVPARMN	IEG, Deviceparameter must be a positive value
150339896 DSEBLKRDF	FAIL, Failed attempt to read block
150339904 DSEFAIL, DS	SE failed. Failure code: !AD.
150339912 NOTALLREI	PLON, Replication state is not on for all regions
150339920 BADLKIPAR	AM, !AD is not a legal parameter for \$ZGETLKI()
150339928 JNLREADBO	DF, Beginning of journal file encountered for !AD
150339936 DVIKEYBAI	), \$ZGETDVI("!AD"
150339952 EQUAL, Equ	al sign expected but not found
150339960 ERRORSUM	MARY, Errors occurred during compilation
150339968 ERRWEXC,	Error while processing exception string
150339976 ERRWIOEXO	C, Error while processing I/O exception string
150339984 ERRWZBRK	
150339992 ERRWZTRA	, Error while processing ZBREAK action string
150340000 NUMUNXEO	, Error while processing ZBREAK action string P, Error while processing \$ZTRAP

GT.M Message, Description
EXPR, Expression expected but not found
STRUNXEOR, !_!AD!/!_!_!unexpected end of record in string subscript
JNLEXTEND, Journal file extension error for file !AD
FCHARMAXARGS, Argument count of \$CHAR function exceeded the maximum of 255
FCNSVNEXPECTED, Function or special variable expected in this context
FNARGINC, Format specifiers to \$FNUMBER are incompatible: "!AD"
JNLACCESS, Error accessing journal file !AD
TRANSNOSTART, ZTCOMMIT(s) issued without corresponding ZTSTART(s)
FNUMARG, \$FNUMBER format specifier "!AD" contains an illegal character: "!AD"
FOROFLOW, FOR commands nested more than !UL deep on a line
JNLSUCCESS, !AD successful
GBLNAME, Either an identifier or a left parenthesis is expected after a ^ in this context
GBLOFLOW, Database segment is full
CORRUPT, Corrupt input in Blk # !UL
GTMCHECK, Internal GT.M error
GVDATAFAIL, Global variable \$DATA function failed. Failure code: !AD.
EORNOTFND, !_!AD!/!_!_End of record not found
GVGETFAIL, Global variable retrieval failed. Failure code: !AD.
GVIS, !_!_Global variable: !AD
GVKILLFAIL, Global variable kill failed. Failure code: !AD.
GVNAKED, Illegal naked global reference
GVNEXTARG, Argument to global variable \$NEXT must be subscripted
GVORDERFAIL, Global variable \$ORDER or \$NEXT function failed. Failure code: !AD.
GVPUTFAIL, Global variable put failed. Failure code: !AD.
PATTABSYNTAX, Error in !AD at line !UL
GVSUBOFLOW, Maximum combined length of subscripts exceeded
GVUNDEF, Global variable undefined: !AD
TRANSNEST, Maximum transaction nesting levels exceeded
INDEXTRACHARS, Indirection string contains extra trailing characters

V6.2-002 MR Manual June 09, 2015, Page 363 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150340248	CORRUPTNODE, Corrupt input in Record # !UL
150340256	INDRMAXLEN, Maximum length !UL of an indirection argument was exceeded
150340264	INSFFBCNT, Insufficient byte count quota left for requested operation
150340272	INTEGERRS, Database integrity errors
150340280	INVCMD, Invalid command keyword encountered
150340288	INVFCN, Invalid function name
150340296	INVOBJ, Cannot ZLINK object file due to unexpected format
150340304	INVSVN, Invalid special variable name
150340312	IOEOF, Attempt to read past an end
150340320	IONOTOPEN, Attempt to USE an I/O device which has not been opened
150340328	MUPIPINFO, !AD
150340336	IVTIME, Invalid time specification: !AD
150340344	JOBFAIL, JOB command failure
150340352	JOBLABOFF, Label and offset not found in created process
150340360	JOBPARNOVAL, This job parameter cannot take a value
150340368	JOBPARNUM, The value of this job parameter must be an integer
150340376	JOBPARSTR, The value of this job parameter must be a string
150340384	JOBPARUNK, Job parameter unknown
150340392	JOBPARVALREQ, A value is required for this job parameter
150340400	JUSTFRACT, Fraction specifier to \$JUSTIFY cannot be negative
150340408	KEY2BIG, Key size (!UL) is greater than maximum (!UL) for region: !AD
150340416	LABELEXPECTED, Label expected in this context
150340424	LABELMISSING, Label referenced but not defined: !AD
150340432	LABELUNKNOWN, Label referenced but not defined
150340440	DIVZERO, Attempt to divide by zero
150340448	LKNAMEXPECTED, An identifier is expected after a ^ in this context
150340456	JNLRDERR, Error reading journal file !AD. Unable to initialize.
150340464	LOADRUNNING, Cannot ZLINK an active routine !AD
150340472	LPARENMISSING, Left parenthesis expected

ZM #	GT.M Message, Description
150340480	LSEXPECTED, A line separator is expected here
150340488	LVORDERARG, Argument to local variable \$NEXT must be subscripted
150340496	MAXFORARGS, Maximum number of arguments to a single FOR command exceeded
150340504	TRANSMINUS, Negative numbers not allowed with ZTCOMMIT
150340512	MAXNRSUBSCRIPTS, Maximum number of subscripts exceeded
150340520	MAXSTRLEN, Maximum string length exceeded
150340528	JNLDBERR, Journal file !AD does not correspond to database file !AD
150340536	JNLFILOPN, Error opening journal file !AD for database file !AD
150340544	MBXRDONLY, Mailbox is read only
150340552	JNLINVALID, !AD is not a valid journal file !/ for database file: !AD
150340560	MBXWRTONLY, Mailbox is write only
150340568	MEMORY, Central memory exhausted during request for !UJ bytes from 0x!XJ
150340576	MTBLKTOOBIG, Magtape BLOCK_SIZE exceeds maximum size allowed
150340584	MTBLKTOOSM, Magtape BLOCK_SIZE is less than !UL bytes
150340592	MTFIXRECSZ, BLOCK_SIZE !UL must be multiple of fixed record size !UL
150340600	MTIS, Magnetic tape: !AD
150340608	MTRDBADBLK, Block read too small
150340616	MTRDONLY, Cannot write to a READONLY magtape
150340624	MTRDTHENWRT, Attempt to read after a write to a magtape
150340632	MTRECGTRBLK, Magtape record size cannot exceed block size
150340640	MTRECTOOBIG, Magtape record size exceeds maximum allowed
150340648	MTRECTOOSM, Magtape record size is too small for record type
150340656	JNLTMQUAL3, Time qualifier BEFORE_TIME="!AZ" is less than the journal file(s) minimum timestamp="!AZ"
150340664	MULTLAB, This label has been previously defined
150340672	BLKCNT, Last LOAD Block/RMS Record number: !UL
150340688	NOPLACE, Line specified in a ZBREAK cannot be found
150340696	JNLCLOSE, Error closing journal file !AD
150340704	NOTPRINCIO, Output currently directed to device !AD

V6.2-002 MR Manual June 09, 2015, Page 365 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150340712	NOTTOEOFONPUT, Not positioned to EOF on write (sequential organization only)
150340720	NOZBRK, No zbreak at that location
150340728	NULSUBSC, Null subscripts are not allowed for region: !AD
150340736	NUMOFLOW, Numeric overflow
150340744	PARFILSPC, Parameter: !AD file specification: !AD
150340752	PATCLASS, Illegal character class for pattern code
150340760	PATCODE, Illegal syntax for pattern
150340768	PATLIT, Illegal character or unbalanced quotes for pattern literal
150340776	PATMAXLEN, Pattern code exceeds maximum length
150340784	LPARENREQD, !_!AD!/!_!_Left parenthesis expected
150340792	PATUPPERLIM, Pattern code upper limit is less than lower limit
150340800	PCONDEXPECTED, Post
150340808	PRCNAMLEN, Process name !AD length is greater than !SL
150340816	RANDARGNEG, Random number generator argument must be greater than or equal to one
150340824	DBPRIVERR, No privilege for attempted update operation for file: !AD
150340832	REC2BIG, Record size (!UL) is greater than maximum (!UL) for region: !AD
150340840	RHMISSING, Right
150340848	DEVICEREADONLY, Cannot write to read
150340856	COLLDATAEXISTS, Collation type cannot be changed while data exists
150340864	ROUTINEUNKNOWN, Routine could not be found
150340872	RPARENMISSING, Right parenthesis expected
150340880	RTNNAME, Routine name expected here
150340888	VIEWGVN, Invalid global key name used with VIEW/\$VIEW(): !AD
150340896	RTSLOC, !_!_At M source location !AD
150340904	RWARG, This is not a legal argument for a READ command
150340912	RWFORMAT, A valid format expression (!!
150340920	JNLWRTDEFER, Journal write start deferred
150340928	SELECTFALSE, No argument to \$SELECT was true
150340936	SPOREOL, Either a space or an end

ZM #	GT.M Message, Description
150340944	SRCLIN, !_!AD!/!_!AD
150340952	SRCLOC, !_!_At column !UL
150340960	SRCLOCUNKNOWN, !_!_M source location unknown
150340968	STACKCRIT, Stack space critical
150340976	STACKOFLOW, Stack overflow
150340984	STACKUNDERFLO, Stack underflow
150340992	STRINGOFLOW, String pool overflow
150341000	SVNOSET, Cannot SET this special variable
150341008	VIEWFN, View parameter is not valid with \$VIEW()
150341016	TERMASTQUOTA, Process AST quota exceeded
150341024	TEXTARG, Invalid argument to \$TEXT function
150341032	TMPSTOREMAX, Maximum space for temporary values exceeded
150341040	VIEWCMD, View parameter is not valid with VIEW command
150341048	JNI, !AD
150341056	TXTSRCFMT, \$TEXT encountered an invalid source program file format
150341064	UIDMSG, Unidentified message received
150341072	UIDSND, Unidentified sender PID
150341080	UNDEF, Undefined local variable: !AD
150341088	UNIMPLOP, Unimplemented construct encountered
150341096	VAREXPECTED, Variable expected in this context
150341104	VARRECBLKSZ, Blocksize must be at least record size + 4 bytes
150341112	MAXARGCNT, Maximum number of arguments !UL exceeded
150341120	GTMSECSHRSEMGET, semget error errno = !UL
150341128	VIEWARGCNT, View parameter !AD has inappropriate number of subparameters
150341136	GTMSECSHRDMNSTARTED, gtmsecshr daemon started (key: 0x!XL) for version !AD from ! AD
150341144	ZATTACHERR, Error attaching to "!AD"
150341152	ZDATEFMT, \$ZDATE format string contains invalid character
150341160	ZEDFILSPEC, Illegal ZEDIT file specification: !AD

V6.2-002 MR Manual June 09, 2015, Page 367 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150341168	ZFILENMTOOLONG, !AD is longer than 255 characters
150341176	ZFILKEYBAD, !AD is not a legal keyword for \$ZFILE()
150341184	ZFILNMBAD, !AD is not a legal file name
150341192	ZGOTOLTZERO, Cannot ZGOTO a level less than zero
150341200	ZGOTOTOOBIG, Cannot ZGOTO a level greater than present level
150341208	ZLINKFILE, Error while zlinking "!AD"
150341216	ZPARSETYPE, Illegal TYPE argument to \$ZPARSE(): !AD
150341224	ZPARSFLDBAD, Illegal \$ZPARSE() field parameter: !AD
150341232	ZPIDBADARG, The tvexpr must be FALSE if last \$ZPID() not found
150341240	ZPRIVARGBAD, !AD is not a legal privilege for \$ZPRIV()
150341248	ZPRIVSYNTAXERR, Privilege string cannot end with a comma
150341256	ZPRTLABNOTFND, Label not found in routine
150341264	VIEWAMBIG, View parameter !AD is ambiguous
150341272	VIEWNOTFOUND, View parameter !AD not valid
150341280	ZSETPRVARGBAD, !AD is not a legal privilege for \$ZSETPRIV()
150341288	INVSPECREC, Invalid global modifier record
150341296	ZSETPRVSYNTAX, \$ZSETPRIV() privileges string cannot end with a comma
150341304	ZSRCHSTRMCT, Search stream identifier out of range
150341312	VERSION, Version mismatch
150341320	MUNOTALLSEC, WARNING: not all global sections accessed were successfully rundown
150341328	MUSECDEL, Section !AD deleted
150341336	MUSECNOTDEL, Section !AD not deleted
150341344	RPARENREQD, !_!AD!/!_!_Right parenthesis expected
150341352	ZGBLDIRACC, Cannot access global directory !AD!AD!AD.
150341360	GVNAKEDEXTNM, Cannot reference different global directory in a naked reference
150341368	EXTGBLDEL, Invalid delimiter for extended global syntax
150341376	DSEWCINITCON, No action taken
150341384	LASTFILCMPLD, The file currently being compiled is !AD
150341392	NOEXCNOZTRAP, Neither an exception nor a Ztrap is specified

ZM #	GT.M Message, Description
150341400	UNSDCLASS, Unsupported descriptor class
150341408	UNSDDTYPE, Unsupported descriptor data type
150341416	ZCUNKTYPE, External call: Unknown argument type
150341424	ZCUNKMECH, External call: Unknown parameter
150341432	ZCUNKQUAL, External call: Unknown input qualifier
150341440	JNLDBTNNOMATCH, Journal file !AD has !AD transaction number [0x!16@XQ]
150341448	ZCALLTABLE, External call Table format error
150341456	ZCARGMSMTCH, External call: Actual argument count
150341464	ZCCONMSMTCH, External call: Too many input arguments
150341472	ZCOPT0, External call: Qualifier OPTIONAL_0 can be used only with mechanisms REFERENCE or DESCRIPTOR
150341480	ZCSTATUS, External call: Unsuccessful return status
150341488	ZCUSRRTN, External call: Run
150341496	ZCPOSOVR, External call: Invalid overlapping of arguments in table position !UL
150341504	ZCINPUTREQ, External call: Required input argument missing
150341512	JNLTNOUTOFSEQ, End transaction [0x!16@XQ] of journal !AD different from Begin transaction [0x!16@XQ] of next generation journal !AD
150341520	ACTRANGE, Alternate Collating Type !UL is out of range
150341528	ZCCONVERT, External call: error converting output argument
150341536	ZCRTENOTF, External call routine !AD not found
150341544	GVRUNDOWN, Error during global database rundown
150341552	LKRUNDOWN, Error during lock database rundown
150341560	IORUNDOWN, Error during image rundown
150341568	FILENOTFND, File !AD not found
150341576	MUFILRNDWNFL, File !AD rundown failed
150341584	JNLTMQUAL1, Time qualifier BEFORE_TIME="!AZ" is less than SINCE_TIME="!AZ"
150341592	FORCEDHALT, Image HALTed by MUPIP STOP
150341600	LOADEOF, Load error: EOF reached prior to BEGIN record !UL. No records loaded.
150341616	LOADEDBG, Load error: END smaller than BEGIN. No records loaded.
150341624	LABELONLY, Routine !AD was compiled for label

MR Manual V6.2-002
GT.M Message and Recovery Procedures Manual June 09, 2015, Page 369

ZM #	GT.M Message, Description
150341632	MUREORGFAIL, MUPIP REORG failed. Failure code: !AD.
150341640	GVZPREVFAIL, Global variable \$ZPREVIOUS function failed. Failure code: !AD.
150341648	MULTFORMPARM, This formal parameter is multiply defined
150341656	QUITARGUSE, Quit cannot take an argument in this context
150341664	NAMEEXPECTED, A local variable name is expected in this context
150341672	FALLINTOFLST, Fall
150341680	NOTEXTRINSIC, Quit does not return to an extrinsic function: argument not allowed
150341688	GTMSECSHRREMSEMFAIL, error removing semaphore errno = !UL
150341696	FMLLSTMISSING, The formal list is absent from a label called with an actual list: !AD
150341704	ACTLSTTOOLONG, More actual parameters than formal parameters: !AD
150341712	ACTOFFSET, Actuallist not allowed with offset
150341720	MAXACTARG, Maximum number of actual arguments exceeded
150341728	GTMSECSHRREMSEM, [client pid !UL] Semaphore (!UL) removed
150341736	JNLTMQUAL2, Time qualifier LOOKBACK_TIME="!AZ" is later than SINCE_TIME="!AZ"
150341744	GDINVALID, Unrecognized Global Directory file format: !AD
150341752	ASSERT, Assert failed in !AD line !UL for expression (!AD)
150341760	MUFILRNDWNSUC, File !AD successfully rundown
150341768	LOADEDSZ, Load error: END too small. No records loaded.
150341776	QUITARGLST, Quit cannot take a list of arguments
150341784	QUITARGREQD, Quit from an extrinsic must have an argument
150341792	CRITRESET, The critical section crash count for region !AD has been incremented
150341800	UNKNOWNFOREX, Process halted by a forced exit from a source other than MUPIP
150341808	FSEXP, File specification expected but not found
150341816	WILDCARD, Wild cards are prohibited: !AD
150341824	DIRONLY, Directories only are allowed in file specs: !AD
150341832	FILEPARSE, Error parsing file specification: !AD
150341840	QUALEXP, Qualifier expected but not found
150341848	BADQUAL, Unrecognized qualifier: !AD
150341856	QUALVAL, Qualifier value required but not found

ZM #	GT.M Message, Description
150341864	ZROSYNTAX, \$ZROUTINES syntax error: !AD
150341872	COMPILEQUALS, Error in compiler qualifiers: !AD
150341880	ZLNOOBJECT, No object module was produced
150341888	ZLMODULE, Object file name does not match module name: !AD
150341896	DBBLEVMX, !AD Block level higher than maximum
150341904	DBBLEVMN, !AD Block level less than zero
150341912	DBBSIZMN, !AD Block too small
150341920	DBBSIZMX, !AD Block larger than file block size
150341928	DBRSIZMN, !AD Physical record too small
150341936	DBRSIZMX, !AD Physical record too large
150341944	DBCMPNZRO, !AD First record of block has nonzero compression count
150341952	DBSTARSIZ, !AD Star record has wrong size
150341960	DBSTARCMP, !AD Star record has nonzero compression count
150341968	DBCMPMX, !AD Record compression count is too large
150341976	DBKEYMX, !AD Key too long
150341984	DBKEYMN, !AD Key too short
150341992	DBCMPBAD, !AD Compression count not maximal
150342000	DBKEYORD, !AD Keys out of order
150342008	DBPTRNOTPOS, !AD Block pointer negative
150342016	DBPTRMX, !AD Block pointer larger than file maximum
150342024	DBPTRMAP, !AD Block pointer is a bit map block number
150342032	IFBADPARM, External Interface Bad Parameter
150342040	IFNOTINIT, External Interface must first call GTM\$INIT or M routine
150342048	GTMSECSHRSOCKET, !AD
150342056	LOADBGSZ, Load error: BEGIN too small. No records loaded.
150342064	LOADFMT, Load error: invalid format type. Must be ZWR
150342072	LOADFILERR, Error with load file !AD
150342080	NOREGION, REGION not found: !AD
150342088	PATLOAD, Error loading pattern file !AD

V6.2-002 MR Manual June 09, 2015, Page 371 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150342096	EXTRACTFILERR, Error with extract file !AD
150342104	FREEZE, Region: !AD is already frozen
150342112	NOSELECT, None of the selected variables exist
150342120	EXTRFAIL, Extract failed for the global ^!AD. MUPIP INTEG should be run.
150342128	LDBINFMT, Unrecognized header for load file
150342136	NOPREVLINK, Journal file !AD has a null previous link
150342184	REQRUNDOWN, Error accessing database !AD. Must be rundown on cluster node !AD.
150342208	CNOTONSYS, Command is not supported by this operating system
150342232	OPRCCPSTOP, The Cluster Control Program has been halted by an operator stop request
150342240	SELECTSYNTAX, Argument to !AD clause is not valid
150342248	LOADABORT, Aborting load at record !UL
150342256	FNOTONSYS, Function or special variable is not supported by this operating system
150342264	AMBISYIPARAM, Parameter !AD is ambiguous to \$ZGETSYI()
150342272	PREVJNLNOEOF, A previous generation journal file !AD does not have valid EOF
150342280	LKSECINIT, Error creating lock section for database !AD
150342288	MTDOSLAB, Tape label is not in valid DOS
150342296	MTDOSFOR, Use of DOS
150342304	MTINVLAB, Invalid label type specified in magtape OPEN
150342312	TXTSRCMAT, M object module and source file do not match
150342328	BADDBVER, Incorrect database version: !AD
150342336	LINKVERSION, This image must be relinked with the current version of GT.M
150342344	TOTALBLKMAX, Extension exceeds maximum total blocks. Not extending.
150342352	LOADCTRLY, User interrupt encountered during load. Load halting.
150342360	CLSTCONFLICT, Cluster conflict opening database file !AD; could not secure access. Already open on node !AD.
150342368	SRCNAM, in source module !AD
150342376	LCKGONE, Lock removed: !AD
150342384	SUB2LONG, Subscript invalid
150342392	EXTRACTCTRLY, User interrupt encountered during extract

ZM #	GT.M Message, Description
150342408	GVQUERYFAIL, Global variable \$QUERY function failed. Failure code: !AD.
150342416	LCKSCANCELLED, Error on remote node holding locks or zallocates. All locks and zallocates cancelled.
150342424	INVNETFILNM, Invalid file name following node designation in global directory
150342432	NETDBOPNERR, Error while attempting to open database across net
150342440	BADSRVRNETMSG, Invalid message received from GT.CM server
150342448	BADGTMNETMSG, Invalid message sent to GT.CM server
150342456	SERVERERR, Severe error on server: !AD
150342464	NETFAIL, Failure of Net operation
150342472	NETLCKFAIL, Lock operation across Net failed
150342480	TTINVFILTER, Invalid FILTER argument
150342488	MTANSILAB, Tape label is not in valid ANSI format
150342496	MTANSIFOR, Use of ANSI labels does not allow stream format
150342504	BADTRNPARAM, !AD is not a legal parameter to \$ZTRNLNM
150342512	DSEONLYBGMM, !AD is supported only for BG/MM access methods
150342520	DSEINVLCLUSFN, Specified function is invalid for clustered databases
150342528	RDFLTOOSHORT, Length specified for fixed length read less than or equal to zero
150342536	TIMRBADVAL, Bad value specified. Timer not changed.
150342560	UNSOLCNTERR, An unsolicited error message has been received from the network
150342568	BACKUPCTRL, Control Y or control C encountered during backup
150342576	NOCCPPID, Cannot find CCP process id
150342592	LCKSGONE, Locks selected for deletion removed
150342600	ZLKIDBADARG, The tvexpr must be FALSE if last ZLKID not found
150342608	DBFILOPERR, Error doing database I/O to region !AD
150342704	ZSHOWBADFUNC, An illegal function was specified for ZSHOW
150342712	NOTALLJNLEN, Journaling not enabled and on for all regions
150342720	ZSHOWGLOSMALL, Global output variable is too small for ZSHOW output
150342728	NOLBRSRC, Object libraries cannot have SRC paths associated
150342736	INVZSTEP, Invalid ZSTEP qualifier

V6.2-002 MR Manual June 09, 2015, Page 373 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150342744	ZSTEPARG, ZSTEP argument expected
150342752	INVSTRLEN, Invalid string length !UL: max !UL
150342760	RECCNT, Last LOAD record number: !UL
150342768	TEXT, !AD
150342776	ZWRSPONE, Subscript patterns in ZWRITE are atomic; Invalid delimiter
150342784	FILEDEL, File !AD successfully deleted
150342792	JNLBADLABEL, Journal file !AD has a bad GT.M Journal File Label. Expected !AD. Found ! AD.
150342800	JNLREADEOF, End of journal file encountered for !AD
150342808	JNLRECFMT, Journal file record format error encountered
150342816	BLKTOODEEP, Block level too deep
150342824	NESTFORMP, Formal parameter list cannot be combined with nested line
150342832	BINHDR, !AD!/!/Date: !AD!/Time: !AD!/Extract Region Characteristics!/!_Blk Size: !AD!/! _Rec Size: !AD!/!_Key Size: !AD!/!_Std Null Coll: !AD!/!AD!/
150342840	GOQPREC, Numeric precision in key error: Blk #!UL
150342848	LDGOQFMT, Corrupt GOQ format header information!/
150342856	BEGINST, Beginning LOAD at record number: !UL
150342864	INVMVXSZ, Invalid block size for GOQ load format
150342880	GTMSECSHRSHMCONCPROC, More than one process attached to Shared memory segment (!UL) not removed (!UL)
150342888	JNLINVALLOC, Journal file allocation !UL is not within the valid range of !UL to !UL. Journal file not created.
150342896	JNLINVEXT, Journal file extension !UL is greater than the maximum allowed size of !UL. Journal file not created.
150342904	MUPCLIERR, Action not taken due to CLI errors
150342912	JNLTMQUAL4, Time qualifier BEFORE_TIME="!AZ" is less than AFTER_TIME="!AZ"
150342920	GTMSECSHRREMSHM, [client pid !UL] Shared memory segment (!UL) removed
150342928	GTMSECSHRREMFILE, [client pid !UL] File (!AD) removed
150342936	MUNODBNAME, A database name or the region qualifier must be specified
150342944	FILECREATE, !AD file !AD created
150342952	FILENOTCREATE, !AD file !AD not created

ZM #	GT.M Message, Description
150342960	JNLPROCSTUCK, Journal file writes blocked by process !UL
150342968	INVGLOBALQUAL, Error in GLOBAL qualifier : Parse error at offset !UL in !AD
150342976	COLLARGLONG, Collation sequence !UL does not contain routines for long strings
150342984	NOPINI, PINI journal record expected but not found in journal file !AD at offset [0x!XL]
150342992	DBNOCRE, Not all specified database files
150343000	JNLSPACELOW, Journal file !AD nearing maximum size
150343008	DBCOMMITCLNUP, Pid !UL [0x!XL] handled error (code = !UL) during commit of !AZ transaction in database file !AD
150343016	BFRQUALREQ, The [NO]BEFORE qualifier is required for this command
150343024	REQDVIEWPARM, Required View parameter is missing
150343032	COLLFNMISSING, Routine !AD is not found for collation sequence !UL
150343040	JNLACTINCMPLT, Mupip journal action might be incomplete
150343048	NCTCOLLDIFF, Source and destination for MERGE cannot have different numerical collation type
150343056	DLRCUNXEOR, !_!AD!/!_!_!unexpected end of record in \$CHAR()/\$ZCHAR() subscript
150343064	DLRCTOOBIG, !_!AD!/!_!_!AD value cannot be greater than 255
150343072	WCERRNOTCHG, Not all specified database files were changed
150343080	WCWRNNOTCHG, Not all specified database files were changed
150343088	ZCWRONGDESC, A string longer than 65535 is passed via 32
150343096	MUTNWARN, Database file !AD has 0x!16@XQ more transactions to go before reaching the transaction number limit (0x!16@XQ). Renew database with MUPIP INTEG TN_RESET
150343104	GTMSECSHRUPDDBHDR, [client pid !UL] database fileheader (!AD) updated !AD
150343112	LCKSTIMOUT, DAL timed lock request expired
150343120	CTLMNEMAXLEN, The maximum length of a control mnemonic has been exceeded
150343128	CTLMNEXPECTED, Control mnemonic is expected in this context
150343136	USRIOINIT, User
150343144	CRITSEMFAIL, Error with semaphores for region !AD
150343152	TERMWRITE, Error writing to terminal
150343160	COLLTYPVERSION, Collation type !UL
150343168	LVNULLSUBS, Null subscripts not allowed in local variables

ZM #	GT.M Message, Description
150343176	GVREPLERR, Error replicating global in region !AD
150343184	MTIOERR, I/O Error with magnetic tape device !AD
150343192	RMWIDTHPOS, File record size or width must be greater than zero
150343200	OFFSETINV, Entry point !AD+!SL not valid
150343208	JOBPARTOOLONG, Total parameter length is too long for job command
150343216	JOBARGMISSING, Missing job argument !UL
150343224	RUNPARAMERR, Error accessing parameter for run command
150343232	FNNAMENEG, Depth argument to \$NAME cannot be negative
150343240	ORDER2, Invalid second argument to \$ORDER. Must be
150343248	MUNOUPGRD, Database not upgraded because of preceding errors
150343256	REORGCTRLY, User interrupt encountered during database reorg
150343264	TSTRTPARM, Error parsing TSTART qualifier
150343272	TRIGNAMENF, Trigger name !AD not found with the current default global directory
150343280	TRIGZBREAKREM, ZBREAK in trigger !AD removed due to trigger being reloaded
150343288	TLVLZERO, Transaction is not in progress
150343296	TRESTNOT, Cannot TRESTART
150343304	TPLOCK, Cannot release lock(s) held prior to current TSTART
150343312	TPQUIT, Cannot QUIT out of a routine with an active transaction
150343320	TPFAIL, Transaction COMMIT failed. Failure code: !AD.
150343336	TPTOODEEP, \$TLEVEL cannot exceed 127
150343360	MUPRESTERR, MUPIP restore aborted due to preceding errors
150343368	MUBCKNODIR, MUPIP backup aborted due to error in output directory
150343376	TRANS2BIG, Transaction exceeded available buffer space for region !AD
150343384	INVBITLEN, Invalid size of the bit string
150343392	INVBITSTR, Invalid bit string
150343400	INVBITPOS, Invalid position in the bit string
150343408	PARNORMAL, Parse successful
150343416	PARBUFSM, Parse buffer too small
150343424	RMWIDTHTOOBIG, File record size or width too big

ZM #	GT.M Message, Description
150343432	PATTABNOTFND, Pattern table !AD not found
150343440	OBJFILERR, Error with object file I/O on file !AD
150343448	SRCFILERR, Error with source file I/O on file !AD
150343456	NEGFRACPWR, Invalid operation: fractional power of negative number
150343464	MTNOSKIP, SKIP operation not supported on this device
150343472	CETOOMANY, Too many compiler escape substitutions in a single statement
150343480	CEUSRERROR, Compiler escape user routine returned error code !UL
150343488	CEBIGSKIP, Compiler escape user routine skip count is too large
150343496	CETOOLONG, Compiler escape substitution exceeds maximum line size
150343504	CENOINDIR, Indirection type information not available for compiler escape feature
150343512	COLLATIONUNDEF, Collation type !UL is not defined
150343520	RBWRNNOTCHG, Not all specified database files were changed
150343528	GTMSECSHRSRVF, !AD
150343536	FREEZECTRL, Control Y or control C encountered during attempt to freeze the database. Aborting freeze.
150343544	JNLFLUSH, Error flushing journal buffers to journal file !AD
150343560	NOPRINCIO, Unable to write to principal device
150343568	INVPORTSPEC, Invalid port specification
150343576	INVADDRSPEC, Invalid IP address specification
150343600	SOCKWAIT, Error waiting for socket connection
150343608	SOCKACPT, Error accepting socket connection
150343616	SOCKINIT, Error initializing socket: (errno == !UL) !AD
150343624	OPENCONN, Error opening socket connection
150343632	DEVNOTIMP, !AD device not implemented on in this environment
150343640	JNLEXTR, Error writing journal extract file: !AD
150343648	DBREMOTE, Database region !AD is remote; perform maintenance on the server node
150343664	TPMIXUP, !AZ transaction cannot be started within !AZ transaction
150343672	HTOFLOW, Hash table overflow: Failed to allocate !UL elements
150343680	RMNOBIGRECORD, File record size requires BIGRECORD parameter

V6.2-002 MR Manual June 09, 2015, Page 377 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150343688	DBBMSIZE, !AD Bit map has incorrect size
150343696	DBBMBARE, !AD Bit map does not protect itself
150343704	DBBMINV, !AD Bit map contains an invalid pattern
150343712	DBBMMSTR, !AD Bit map does not match master map
150343720	DBROOTBURN, !AD Root block has data level
150343728	REPLSTATEERR, Replication state cannot be changed to the specified value for database file !AD
150343736	VMSMEMORY, Central memory exhausted during request for !UL bytes from 0x!XJ
150343744	DBDIRTSUBSC, !AD Directory tree block contains non name
150343752	TIMEROVFL, Timer overflow; interval probably too large
150343760	GTMASSERT, !AD
150343768	DBFHEADERR4, Database file !AD: control problem: !AD was 0x!XL expecting 0x!XL
150343776	DBADDRANGE, Database file !AD
150343784	DBQUELINK, Database file !AD
150343792	DBCRERR, Database file !AD
150343800	MUSTANDALONE, Could not get exclusive access to !AD
150343808	MUNOACTION, MUPIP unable to perform requested action
150343816	RMBIGSHARE, File with BIGRECORD specified may only be shared if READONLY
150343824	TPRESTART, Database !AD; code: !AD; blk: 0x!XL in glbl: ^!AD; pvtmods: !UL
150343832	SOCKWRITE, Write to a socket failed
150343840	DBCNTRLERR, Database file !AD: control error suspected but not found
150343848	NOTERMENV, Environment variable TERM not set. Assuming "unknown."
150343856	NOTERMENTRY, TERM = "!AD" has no "terminfo" entry. Possible terminal handling problems.
150343864	NOTERMINFODB, No "terminfo" database. Terminal handling problems likely.
150343872	INVACCMETHOD, Invalid access method
150343880	JNLOPNERR, Error opening journal file !AD!/ for database !AD
150343888	JNLRECTYPE, Journal record type does not match expected type
150343896	JNLTRANSGTR, Transaction number in journal is greater than in database
150343904	JNLTRANSLSS, Transaction number in journal is less than in database

ZM #	GT.M Message, Description
150343912	JNLWRERR, Error writing journal file !AD. Unable to update header.
150343920	FILEIDMATCH, Saved File ID does not match the current ID
150343928	EXTSRCLIN, !_!AD!/!_!AD
150343936	EXTSRCLOC, !_!_At column !UL
150343944	BIGNOACL, Existing file found when BIGRECORD specified with UDF format but no GT.M ACE
150343952	ERRCALL, Error called from !AD line !UL
150343960	ZCCTENV, Environmental variable for external package !AD not set
150343968	ZCCTOPN, Unable to open external call table: !AD
150343976	ZCCTNULLF, External call table contains no records: !AD
150343984	ZCUNAVAIL, Package
150343992	ZCENTNAME, No entry name found in external call table
150344000	ZCCOLON, Colon expected but not found
150344008	ZCRTNTYP, Unknown return type
150344016	ZCRCALLNAME, Routine name expected but not found
150344024	ZCRPARMNAME, Parameter name expected but not found
150344032	ZCUNTYPE, Unknown type encountered
150344040	ZCMLTSTATUS, Multiple entries of xc_status in a single entry in external call table
150344048	ZCSTATUSRET, External call returned error status
150344056	ZCMAXPARAM, Exceeded maximum number of external call parameters
150344064	ZCCSQRBR, Closing Square bracket expected
150344072	ZCPREALLNUMEX, Pre
150344080	ZCPREALLVALPAR, Pre
150344088	VERMISMATCH, Attempt to access !AD with version !AD
150344096	JNLCNTRL, Journal control unsynchronized for !AD.
150344104	TRIGNAMBAD, Trigger initialization failed. Error while processing ^#t("!AD"
150344112	BUFRDTIMEOUT, Pid [0x!XL] timed out waiting for buffered read of blk [0x!XL] into cr [0x! XL] by process [0x!XL] to complete in database file !AD
150344120	INVALIDRIP, Invalid read
150344128	BLKSIZ512, Block size !UL rounds to !UL

ZM #	GT.M Message, Description
150344136	MUTEXERR, Mutual Exclusion subsystem failure
150344144	JNLVSIZE, Journal File !AD has incorrect virtual_filesize !UL. Allocation : !UL
150344152	MUTEXLCKALERT, Mutual Exclusion subsystem ALERT
150344160	MUTEXFRCDTERM, Mutual Exclusion subsystem detected forced termination of process! UL. Crit salvaged from region!AD.
150344168	GTMSECSHR, !UL : Error during gtmsecshr operation
150344176	GTMSECSHRSRVFID, !AD: !UL
150344184	GTMSECSHRSRVFIL, !AD: !UL
150344192	FREEBLKSLOW, Only !UL free blocks left out of !UL total blocks for !AD
150344200	PROTNOTSUP, Protocol !AD not supported
150344208	DELIMSIZNA, Delimiter size is not appropriate
150344216	INVCTLMNE, Invalid control mnemonics
150344224	SOCKLISTEN, Error listening on a socket
150344232	LQLENGTHNA, Listening queue length !UL not appropriate. Must be between 1 and 5.
150344240	ADDRTOOLONG, Socket address !AD of length !UL is longer than the maximum permissible length !UL
150344248	GTMSECSHRGETSEMFAIL, error getting semaphore errno = !UL
150344256	CPBEYALLOC, Attempt to copy beyond the allocated buffer
150344264	DBRDONLY, Database file !AD read only
150344272	DUPTN, Duplicate transaction found [TN = 0x!16@XQ] at offset 0x!XL in journal file !AD
150344280	TRESTLOC, Transaction start: !AD
150344288	REPLPOOLINST, Error with replication pool (id = !UL) for instance file !AD
150344296	ZCVECTORINDX, Invalid Vector Index !UL
150344304	REPLNOTON, Replication is not on for journal file !AD
150344312	JNLMOVED, Journal file appears to have been moved. Journaling activity will not be done.
150344320	EXTRFMT, Extract error: invalid format type. Must be ZWR
150344328	CALLERID, Routine !AD called from 0x!XJ
150344336	KRNLKILL, Process was terminated by SIGDANGER signal from the system
150344344	MEMORYRECURSIVE, Memory Subsystem called recursively
150344360	BLKWRITERR, Unable to queue disk write for block 0x!XL. Will keep trying.

ZM #	GT.M Message, Description
150344368	STOPTIMEOUT, Waited too long for stopped process to release. Region: !AD.
150344384	BCKUPBUFLUSH, Unable to flush buffer for online backup
150344392	NOFORKCORE, Unable to fork off process to create core. Core creation postponed.
150344400	JNLREAD, Error reading from journal file !AD at offset [0x!XL]
150344408	JNLMINALIGN, Journal Record Alignment !UL is less than the minimum value of !UL
150344416	JOBSTARTCMDFAIL, JOB command STARTUP script invocation failed
150344424	JNLPOOLSETUP, Journal Pool setup error
150344432	JNLSTATEOFF, ROLLBACK or RECOVER BACKWARD cannot proceed as database file !AD does not have journaling ENABLED and ON
150344440	RECVPOOLSETUP, Receive Pool setup error
150344448	REPLCOMM, Replication subsystem communication failure
150344456	NOREPLCTDREG, Replication subsystem found no region replicated for !AD !AZ
150344464	REPLINFO, !AD
150344472	REPLWARN, !AD
150344480	REPLERR, !AD
150344488	JNLNMBKNOTPRCD, Journal file !AD does not match the current journal file !AD of database file !AD
150344496	REPLFILIOERR, Replication subsystem file I/O error !AD
150344504	REPLBRKNTRANS, Replication subsystem found seqno !16@XQ broken or missing in the journal files
150344512	TTWIDTHTOOBIG, Terminal WIDTH exceeds the maximum allowed limit
150344520	REPLLOGOPN, Replication subsystem could not open log file !AD: !AD. Logging done to ! AD.
150344528	REPLFILTER, Replication filter subsystem failure
150344536	GBLMODFAIL, Global variable Conflict Test failed. Failure code: !AD.
150344544	TTLENGTHTOOBIG, Terminal LENGTH exceeds the maximum allowed limit
150344552	TPTIMEOUT, Transaction timeout
150344568	JNLFILNOTCHG, Journal file not changed
150344576	EVENTLOGERR, Error in event logging subsystem
150344584	UPDATEFILEOPEN, Update file open error

V6.2-002 MR Manual June 09, 2015, Page 381 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150344592	JNLBADRECFMT, Journal File Record Format Error encountered for file !AD at disk address 0x!XL
150344600	NULLCOLLDIFF, Null collation order must be the same for all regions
150344608	MUKILLIP, Kill in progress indicator is set for file !AD
150344616	JNLRDONLY, Journal file !AD read only
150344624	ANCOMPTINC, Deviceparameter !AD is not compatible with any other deviceparameters in the !AD command
150344632	ABNCOMPTINC, Deviceparameter !AD and deviceparameter !AD are not compatible in the ! AD command
150344640	RECLOAD, Error loading record number: !@UQ!/
150344648	SOCKNOTFND, Socket !AD not found
150344656	CURRSOCKOFR, Current socket of index !UL is out of range. There are only !UL sockets.
150344664	SOCKETEXIST, Socket !AD already exists
150344672	LISTENPASSBND, Controlmnemonic LISTEN can be applied to PASSIVE socket in the state BOUND only
150344680	DBCLNUPINFO, Database file !AD !/!AD
150344688	MUNODWNGRD, Database not downgraded because of preceding errors
150344696	REPLTRANS2BIG, Transaction !16@XQ of size !UL (pre
150344704	RDFLTOOLONG, Length specified for fixed length read exceeds the maximum string size
150344712	MUNOFINISH, MUPIP unable to finish all requested actions
150344720	DBFILEXT, Database file !AD extended from 0x!XL blocks to 0x!XL at transaction 0x!16@XQ
150344728	JNLFSYNCERR, Error synchronizing journal file !AD to disk
150344736	FSYNCTIMOUT, Timed out on fsync for journal file !AD
150344744	ZCPREALLVALINV, The pre
150344752	NEWJNLFILECREAT, Journal file !AD nearing maximum size. New journal file created.
150344760	DSKSPACEFLOW, Disk Space for file !AD nearing maximum size. !UL blocks available.
150344768	GVINCRFAIL, Global variable \$INCR failed. Failure code: !AD.
150344776	ISOLATIONSTSCHN, Error changing NOISOLATION status for global ^!AD within a TP transaction from !UL to !UL
150344784	REPLGBL2LONG, Global names longer than 8 characters cannot be handled at the secondary
150344792	TRACEON, Missing global name (with optional subscripts) for recording M

ZM #	GT.M Message, Description
150344800	TOOMANYCLIENTS, GT.CM is serving the maximum number of clients. Try again later.
150344808	NOEXCLUDE, None of the excluded variables exist
150344816	GVINCRISOLATION, \$INCREMENT cannot be performed on global ^!AD as it has NOISOLATION turned ON
150344824	EXCLUDEREORG, Global: !AD is present in the EXCLUDE option. REORG will skip the global.
150344832	REORGINC, Reorg was incomplete. Not all globals were reorged.
150344848	GTMSECSHRSTART, !AD
150344856	DBVERPERFWARN1, Performance warning: Database !AD is running in compatibility mode which degrades performance. Run MUPIP REORG UPGRADE for best overall performance
150344864	FILEIDGBLSEC, File ID in global section does not match with the database file !AD
150344872	GBLSECNOTGDS, Global Section !AD is not a GT.M global section
150344880	BADGBLSECVER, Global Section !AD does not match the current database version
150344888	RECSIZENOTEVEN, RECORDSIZE [!UL] needs to be a multiple of 2 if ICHSET or OCHSET is UTF
150344896	BUFFLUFAILED, Error flushing buffers from !AD for database file !AD
150344904	MUQUALINCOMP, Incompatible qualifiers
150344912	DISTPATHMAX, \$gtm_dist path is greater than maximum (!UL)
150344920	FILEOPENFAIL, Failed to open file !AD
150344928	IMAGENAME, The executing module name should be !AD instead of !AD
150344936	GTMSECSHRPERM, The gtmsecshr module in \$gtm_dist does not have the correct permission and uid
150344944	GTMDISTUNDEF, Environment variable \$gtm_dist is not defined
150344952	SYSCALL, Error received from system call !AD
150344960	MAXGTMPATH, The executing module path is greater than the maximum !UL
150344968	TROLLBK2DEEP, Intended rollback(!SL) deeper than the current \$tlevel(!UL)
150344976	INVROLLBKLVL, Rollback level (!UL) not less than current \$TLEVEL(!UL). Can't rollback.
150344984	OLDBINEXTRACT, Loading an older version(!UL) of binary extract. !/Database or global collation changes since the extract
150344992	ACOMPTBINC, Deviceparameter !AD is compatible with only !AD in the command !AD
150345000	NOTREPLICATED, Transaction number !16@XQ generated by the !AD process (PID = !UL) is not replicated to the secondary

ZM #	GT.M Message, Description
150345008	DBPREMATEOF, Premature end of file with database file !AD
150345016	KILLBYSIG, !AD process !UL has been killed by a signal !UL
150345024	KILLBYSIGUINFO, !AD process !UL has been killed by a signal !UL from process !UL with userid number !UL
150345032	KILLBYSIGSINFO1, !AD process !UL has been killed by a signal !UL at address 0x!XJ (vaddr 0x!XJ)
150345040	KILLBYSIGSINFO2, !AD process !UL has been killed by a signal !UL at address 0x!XJ
150345048	SIGILLOPC, Signal was caused by an illegal opcode
150345056	SIGILLOPN, Signal was caused by an illegal operand
150345064	SIGILLADR, Signal was caused by illegal addressing mode
150345072	SIGILLTRP, Signal was caused by an illegal trap
150345080	SIGPRVOPC, Signal was caused by a privileged opcode
150345088	SIGPRVREG, Signal was caused by a privileged register
150345096	SIGCOPROC, Signal was caused by a coprocessor error
150345104	SIGBADSTK, Signal was caused by an internal stack error
150345112	SIGADRALN, Signal was caused by invalid address alignment
150345120	SIGADRERR, Signal was caused by a non
150345128	SIGOBJERR, Signal was caused by an object specific hardware error
150345136	SIGINTDIV, Signal was caused by an integer divided by zero
150345144	SIGINTOVF, Signal was caused by an integer overflow
150345152	SIGFLTDIV, Signal was caused by a floating point divide by zero
150345160	SIGFLTOVF, Signal was caused by a floating point overflow
150345168	SIGFLTUND, Signal was caused by a floating point underflow
150345176	SIGFLTRES, Signal was caused by a floating point inexact result
150345184	SIGFLTINV, Signal was caused by an invalid floating point operation
150345192	SIGMAPERR, Signal was caused by an address not mapped to an object
150345200	SIGACCERR, Signal was caused by invalid permissions for mapped object
150345208	TRNLOGFAIL, Translation of (VMS) logical name or (UNIX) environment variable !AD failed
150345224	DBMAXNRSUBS, !AD Maximum number of subscripts exceeded
150345232	GTMSECSHRSCKSEL, gtmsecshr select on socket failed

ZM #	GT.M Message, Description
150345240	GTMSECSHRTMOUT, gtmsecshr exiting due to idle timeout
150345248	GTMSECSHRRECVF, gtmsecshr receive on server socket failed
150345256	GTMSECSHRSENDF, gtmsecshr send on server socket failed
150345264	SIZENOTVALID8, Size (in bytes) must be either 1
150345272	GTMSECSHROPCMP, gtmsecshr operation may be compromised
150345280	GTMSECSHRSUIDF, gtmsecshr server setuid to root failed
150345288	GTMSECSHRSGIDF, gtmsecshr server setgid to root failed
150345296	GTMSECSHRSSIDF, gtmsecshr server setsid failed
150345304	GTMSECSHRFORKF, gtmsecshr server unable to fork off a child process
150345312	DBFSYNCERR, Error synchronizing database file !AD to disk
150345320	SECONDAHEAD, Secondary ahead of primary. !/ Secondary database possibly updated by process other than the update process. First perform rollback.
150345328	SCNDDBNOUPD, Database Updates not allowed on the secondary
150345336	MUINFOUINT4, !AD : !UL [0x!XL]
150345344	NLMISMATCHCALC, Location of !AD expected at 0x!XL
150345352	RELINKCTLFULL, Relinkctl file for directory !AD is full (maximum entries !UL)
150345368	DBBADNSUB, !AD Bad numeric subscript
150345376	DBBADKYNM, !AD Bad key name
150345384	DBBADPNTR, !AD Bad pointer value in directory
150345392	DBBNPNTR, !AD Bit map block number as pointer
150345400	DBINCLVL, !AD Block at incorrect level
150345408	DBBFSTAT, !AD Block busy/free status unknown (local bitmap corrupted)
150345416	DBBDBALLOC, !AD Block doubly allocated
150345424	DBMRKFREE, !AD Block incorrectly marked free
150345432	DBMRKBUSY, !AD Block incorrectly marked busy
150345440	DBBSIZZRO, !AD Block size equals zero
150345448	DBSZGT64K, !AD Block size is greater than 64K
150345456	DBNOTMLTP, !AD Block size not a multiple of 512 bytes
150345464	DBTNTOOLG, !AD Block transaction number too large

V6.2-002 MR Manual June 09, 2015, Page 385 GT.M Message and Recovery Procedures Manual

DBBPLMLT512, !AD Blocks per local map is less than 512  DBBPLMGT2K, !AD Blocks per local map is greater than 2K  DBBPLMGT2K, !AD Blocks per local map is greater than 2K  DBBPLNGT512, !AD : !@ZQ [0x!16@XQ]  DBBPLNOT512, !AD Blocks per local map is not 512  DBBPLNOT512, !AD Blocks per local map is not 512  DBUNDACCMT, !AD : !AD  DBUNDACCMT, !AD Cannot determine access method; trying with BG  DBTNNEQ, !AD Current tn and early tn are not equal  DBUNDACCMT, !AD cannot determine access method; trying with BG  DBTNNEQ, !AD Current tn and early tn are not equal  DBUNDACCMT, !AD DBUNDACCMT, !AD to !AD  DBDSRDFMTCHNG, Database file !AD successfully !AD to !AD  DBDSRDFMTCHNG, Database file !AD  DBFGTBC, !AD File size larger than block count would indicate  DBFSTBC, !AD File size smaller than block count would indicate  DBFSTHEAD, !AD File smaller than database header  DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion  DBFLCORRP, !AD Header indicates database file is corrupt  DBHEADINV, !AD Header size not valid for database
150345488 MUINFOUINT8, !AD : !@ZQ [0x!16@XQ]  150345496 DBBPLNOT512, !AD Blocks per local map is not 512  150345504 MUINFOSTR, !AD : !AD  150345512 DBUNDACCMT, !AD Cannot determine access method; trying with BG  150345520 DBTNNEQ, !AD Current tn and early tn are not equal  150345528 MUPGRDSUCC, Database file !AD successfully !AD to !AD  150345536 DBDSRDFMTCHNG, Database file !AD  150345544 DBFGTBC, !AD File size larger than block count would indicate  150345552 DBFSTBC, !AD File size smaller than block count would indicate  150345560 DBFSTHEAD, !AD File smaller than database header  150345568 DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion  150345576 DBFLCORRP, !AD Header indicates database file is corrupt
150345496 DBBPLNOT512, !AD Blocks per local map is not 512  150345504 MUINFOSTR, !AD : !AD  150345512 DBUNDACCMT, !AD Cannot determine access method; trying with BG  150345520 DBTNNEQ, !AD Current tn and early tn are not equal  150345528 MUPGRDSUCC, Database file !AD successfully !AD to !AD  150345536 DBDSRDFMTCHNG, Database file !AD  150345544 DBFGTBC, !AD File size larger than block count would indicate  150345552 DBFSTBC, !AD File size smaller than block count would indicate  150345560 DBFSTHEAD, !AD File smaller than database header  150345568 DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion  150345576 DBFLCORRP, !AD Header indicates database file is corrupt
150345504 MUINFOSTR, !AD : !AD  150345512 DBUNDACCMT, !AD Cannot determine access method; trying with BG  150345520 DBTNNEQ, !AD Current tn and early tn are not equal  150345528 MUPGRDSUCC, Database file !AD successfully !AD to !AD  150345536 DBDSRDFMTCHNG, Database file !AD  150345544 DBFGTBC, !AD File size larger than block count would indicate  150345552 DBFSTBC, !AD File size smaller than block count would indicate  150345560 DBFSTHEAD, !AD File smaller than database header  150345568 DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion  150345576 DBFLCORRP, !AD Header indicates database file is corrupt
150345512 DBUNDACCMT, !AD Cannot determine access method; trying with BG 150345520 DBTNNEQ, !AD Current tn and early tn are not equal 150345528 MUPGRDSUCC, Database file !AD successfully !AD to !AD 150345536 DBDSRDFMTCHNG, Database file !AD 150345544 DBFGTBC, !AD File size larger than block count would indicate 150345552 DBFSTBC, !AD File size smaller than block count would indicate 150345560 DBFSTHEAD, !AD File smaller than database header 150345568 DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion 150345576 DBFLCORRP, !AD Header indicates database file is corrupt
150345520 DBTNNEQ, !AD Current tn and early tn are not equal 150345528 MUPGRDSUCC, Database file !AD successfully !AD to !AD 150345536 DBDSRDFMTCHNG, Database file !AD 150345544 DBFGTBC, !AD File size larger than block count would indicate 150345552 DBFSTBC, !AD File size smaller than block count would indicate 150345560 DBFSTHEAD, !AD File smaller than database header 150345568 DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion 150345576 DBFLCORRP, !AD Header indicates database file is corrupt
150345528 MUPGRDSUCC, Database file !AD successfully !AD to !AD  150345536 DBDSRDFMTCHNG, Database file !AD  150345544 DBFGTBC, !AD File size larger than block count would indicate  150345552 DBFSTBC, !AD File size smaller than block count would indicate  150345560 DBFSTHEAD, !AD File smaller than database header  150345568 DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion  150345576 DBFLCORRP, !AD Header indicates database file is corrupt
150345536 DBDSRDFMTCHNG, Database file !AD  150345544 DBFGTBC, !AD File size larger than block count would indicate  150345552 DBFSTBC, !AD File size smaller than block count would indicate  150345560 DBFSTHEAD, !AD File smaller than database header  150345568 DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion  150345576 DBFLCORRP, !AD Header indicates database file is corrupt
150345544 DBFGTBC, !AD File size larger than block count would indicate 150345552 DBFSTBC, !AD File size smaller than block count would indicate 150345560 DBFSTHEAD, !AD File smaller than database header 150345568 DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion 150345576 DBFLCORRP, !AD Header indicates database file is corrupt
150345552 DBFSTBC, !AD File size smaller than block count would indicate 150345560 DBFSTHEAD, !AD File smaller than database header 150345568 DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion 150345576 DBFLCORRP, !AD Header indicates database file is corrupt
150345560 DBFSTHEAD, !AD File smaller than database header  150345568 DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion  150345576 DBFLCORRP, !AD Header indicates database file is corrupt
150345568 DBCREINCOMP, !AD Header indicates database file creation was interrupted before completion  150345576 DBFLCORRP, !AD Header indicates database file is corrupt
completion  150345576 DBFLCORRP, !AD Header indicates database file is corrupt
150345584 DBHEADINV, !AD Header size not valid for database
150345592 DBINCRVER, !AD Incorrect version of GT.M database
150345600 DBINVGBL, !AD Invalid mixing of global names
150345608 DBKEYGTIND, !AD Key greater than index key
150345616 DBGTDBMAX, !AD Key larger than database maximum
150345624 DBKGTALLW, !AD Key larger than maximum allowed length
150345632 DBLTSIBL, !AD Keys less than sibling's index key
150345640 DBLRCINVSZ, !AD Last record of block has invalid size
150345648 MUREUPDWNGRDEND, Region !AD : MUPIP REORG UPGRADE/DOWNGRADE finished by pid !UL [0x!XL] at transaction number [0x!16@XQ]
150345656 DBLOCMBINC, !AD Local bit map incorrect
150345664 DBLVLINC, !AD Local bitmap block level incorrect
150345672 DBMBSIZMX, !AD Map block too large
150345680 DBMBSIZMN, !AD Map block too small
150345688 DBMBTNSIZMX, !AD Map block transaction number too large

DBMBPINCFL, !AD Master bit map incorrectly marks this local map full  DBMBPFLDLBM, !AD Master bit map shows this map full  DBMBPFLDLS, !AD Master bit map shows this map full  DBMBPFLDLS, !AD Master bit map shows this map full  DBMBPFLDLS, !AD Master bit map shows this map full  DBMBPFLDLBM, !AD Master bit map shows this map has space  DBMBPFRDLBM, !AD Master bit map shows this map has space  DBMBPFRDLBM, !AD Master bit map shows this map has space  DBMAXKEYEXC, !AD Maximum key size for database exceeds design maximum  DBMAXEYEXC, !AD Maximum record size for database is less than the design minimum  DBMAXEXCMIN, !AD Maximum record size for database is less than the design minimum  DBMAXEXCMIN, !AD Read error on bitmap  DBREADBM, !AD Read error on bitmap  DBVERPERFWARN2, Peformance warning: Database !AD is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance  DBRBNTOOLRG, !AD Root block number greater than last block number in file  DBRBNTOOLRG, !AD Root block number is a local bit map number  DBRBNLBMN, !AD Root block number negative  DBRLEVTOOH, !AD Root block number negative  DBRLEVTOOH, !AD Root level higher than maximum  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Total blocks equal zero  DBNOTDB, !AD File does not have a valid GDS file header  DBSVBNMIN, !AD Total blocks should be 0x!XL  DBTOTBLK, Total blocks should be 0x!XL  DBTOTBLK, Total blocks should be 0x!XL  DBTOREGGON, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSCCLNUP, Mutex subsystem leftover resource !AD removed	ZM #	GT.M Message, Description
DBMBPFLDISM, !AD Master bit map shows this map full  DBMBPFLDIS, !AD Master bit map shows this map full  DBMBPFLDIS, !AD Master bit map shows this map full  DBMBPFLDIS, !AD Master bit map shows this map full  DBMBPFRDLBM, !AD Master bit map shows this map has space  DBMBPFRDLBM, !AD Master bit map shows this map has space  DBMBPFRINT, !AD Master bit map shows this map has space  DBMAXKEYEXC, !AD Maximum key size for database exceeds design maximum  DBMXRSEXCMIN, !AD Maximum record size for database is less than the design minimum  DBMAXKEYEXC, !AD Maximum record size for database is less than the design minimum  DBMAXFACOMIN, !AD Maximum record size for database is less than the design minimum  DBMEADBM, !AD Read error on bitmap  DBCOMPTOOLRG, !AD Record has too large compression count  DBVERPERFWARN2, Peformance warning: Database !AD is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance  DBRBNTOOLRG, !AD Root block number greater than last block number in file  DBRBNTOOLRG, !AD Root block number negative  DBRBNLEMN, !AD Root block number negative  DBRBNNEG, !AD Root block number negative  DBRLEVTOOHI, !AD Root level higher than maximum  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Total blocks equal zero  DBNOTDB, !AD File does not have a valid GDS file header  DBSVBNSH, Total blocks should be 0x!XL  DBTOTBLK, Total blocks should be 0x!XL  DBTOTBLK Total blocks should be 0x!XL  DBTOTBLK Total blocks should be 0x!X	150345696	DBMBMINCFRE, !AD Master bit map incorrectly asserts this local map has free space
DBMBPFLINT, !AD Master bit map shows this map full  DBMBPFLDIS, !AD Master bit map shows this map full  DBMBPFLDIS, !AD Master bit map shows this map has space  DBMBPFRDLBM, !AD Master bit map shows this map has space  DBMBPFRINT, !AD Master bit map shows this map has space  DBMAXKEYEXC, !AD Maximum key size for database exceeds design maximum  DBMXRSEXCMIN, !AD Maximum record size for database is less than the design minimum  DBREADBM, !AD Read error on bitmap  DBCOMPTOOLRG, !AD Record has too large compression count  DBVERPERFWARN2, Peformance warning: Database !AD is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance  DBRBNTOOLRG, !AD Root block number greater than last block number in file  DBRBNTBM, !AD Root block number negative  DBRBNTBM, !AD Root block number negative  DBRBNTBG, !AD Root level higher than maximum  DBRLEVTOOHI, !AD Root level less than one  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Total blocks equal zero  DBSVBNMIN, !AD Total blocks equal zero  DBNOTDB, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345704	DBMBPINCFL, !AD Master bit map incorrectly marks this local map full
DBMBPFLDIS, !AD Master bit map shows this map full  DBMBPFRDLBM, !AD Master bit map shows this map has space  DBMBPFRINT, !AD Master bit map shows this map has space  DBMAXKEYEXC, !AD Maximum key size for database exceeds design maximum  DBMAXESEXCMIN, !AD Maximum record size for database is less than the design minimum  DBREADBM, !AD Read error on bitmap  DBCOMPTOOLRG, !AD Record has too large compression count  DBVERPERFWARN2, Peformance warning: Database !AD is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance  DBRBNTOOLRG, !AD Root block number greater than last block number in file  DBRBNLBMN, !AD Root block number is a local bit map number  DBRBNNEG, !AD Root block number negative  DBRBNNEG, !AD Root block number negative  DBRLEVITONE, !AD Root level higher than maximum  DBRLEVITONE, !AD Root level less than one  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Total blocks equal zero  DBSVBNMIN, !AD Total blocks equal zero  DBSVBNOTB, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTOSA45880  DBTOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345712	DBMBPFLDLBM, !AD Master bit map shows this map full
DBMBPFRDLBM, !AD Master bit map shows this map has space  DBMBPFRINT, !AD Master bit map shows this map has space  DBMBPFRINT, !AD Master bit map shows this map has space  DBMAXKEYEXC, !AD Maximum key size for database exceeds design maximum  DBMXRSEXCMIN, !AD Maximum record size for database is less than the design minimum  DBREADBM, !AD Read error on bitmap  DBREADBM, !AD Read error on bitmap  DBVERPERFWARN2, Peformance warning: Database !AD is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance  DBRBNTOOLRG, !AD Root block number greater than last block number in file  DBRBNLBMN, !AD Root block number is a local bit map number  DBRBNLBMN, !AD Root block number negative  DBRBNNEG, !AD Root block number negative  DBRLEVITOOHI, !AD Root level higher than maximum  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Total blocks equal zero  DBSVBNMIN, !AD File does not have a valid GDS file header  DBTTLBLK0, !AD Total blocks should be 0x!XL  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345720	DBMBPFLINT, !AD Master bit map shows this map full
DBMBPFRINT, !AD Master bit map shows this map has space  DBMAXKEYEXC, !AD Maximum key size for database exceeds design maximum  DBMXRSEXCMIN, !AD Maximum record size for database is less than the design minimum  DBREADBM, !AD Read error on bitmap  DBCOMPTOOLRG, !AD Record has too large compression count  DBVERPERFWARN2, Peformance warning: Database !AD is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance  DBRBNTOOLRG, !AD Root block number greater than last block number in file  DBRBNLBMN, !AD Root block number negative  DBRBNNEG, !AD Root block number negative  DBRBNNEG, !AD Root block number negative  DBRLEVITOOHI, !AD Root level higher than maximum  DBRLEVITONE, !AD Root level less than one  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD File does not have a valid GDS file header  DBTLBLK0, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345728	DBMBPFLDIS, !AD Master bit map shows this map full
DBMAXKEYEXC, !AD Maximum key size for database exceeds design maximum  DBMXRSEXCMIN, !AD Maximum record size for database is less than the design minimum  DBMAXKEYEXC, !AD Maximum record size for database is less than the design minimum  DBMEADBM, !AD Read error on bitmap  DBCOMPTOOLRG, !AD Record has too large compression count  DBVERPERFWARN2, Peformance warning: Database !AD is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance  DBRBNTOOLRG, !AD Root block number greater than last block number in file  DBRBNLBMN, !AD Root block number is a local bit map number  DBRBNNEG, !AD Root block number negative  DBRBNNEG, !AD Root block number negative  DBRLEVITONE, !AD Root level less than one  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Start VBN smaller than possible  DBTLBLK0, !AD Total blocks equal zero  DBTOTBLK, Total blocks should be 0x!XL  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNRESETINC, WARNING: tn_reset for this region  MUTEXRSCCLNUP, Mutex subsystem leftover resource !AD removed	150345736	DBMBPFRDLBM, !AD Master bit map shows this map has space
DBMXRSEXCMIN, !AD Maximum record size for database is less than the design minimum DBREADBM, !AD Read error on bitmap DBCOMPTOOLRG, !AD Record has too large compression count DBVERPERFWARN2, Peformance warning: Database !AD is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance DBRBNTOOLRG, !AD Root block number greater than last block number in file DBRBNLBMN, !AD Root block number is a local bit map number DBRBNNEG, !AD Root block number negative DBRBNNEG, !AD Root block number negative DBRLEVTOOHI, !AD Root level higher than maximum DBSVBNMIN, !AD Start VBN smaller than possible DBSVBNMIN, !AD Start VBN smaller than possible DBSVBNMIN, !AD Total blocks equal zero DBNOTDB, !AD File does not have a valid GDS file header DBTOTBLK, Total blocks should be 0x!XL DBTN, Block TN is 0x!16@XQ DBNOREGION, None of the database regions accessible DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors DBTNRESET, Cannot reset transaction number for this region MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345744	DBMBPFRINT, !AD Master bit map shows this map has space
DBREADBM, !AD Read error on bitmap DBCOMPTOOLRG, !AD Record has too large compression count DBVERPERFWARN2, Peformance warning: Database !AD is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance DBRBNTOOLRG, !AD Root block number greater than last block number in file DBRBNLBMN, !AD Root block number is a local bit map number DBRBNNEG, !AD Root block number negative DBRBNNEG, !AD Root block number negative DBRLEVTOOHI, !AD Root level higher than maximum DBRLEVLTONE, !AD Root level less than one DBSVBNMIN, !AD Start VBN smaller than possible DBSVBNMIN, !AD Total blocks equal zero DBNOTDB, !AD File does not have a valid GDS file header DBTOTBLK, Total blocks should be 0x!XL DBTN, Block TN is 0x!16@XQ DBNOREGION, None of the database regions accessible DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors DBTNRESET, Cannot reset transaction number for this region MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345752	DBMAXKEYEXC, !AD Maximum key size for database exceeds design maximum
DBCOMPTOOLRG, !AD Record has too large compression count  DBVERPERFWARN2, Peformance warning: Database !AD is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance  DBRBNTOOLRG, !AD Root block number greater than last block number in file  DBRBNLBMN, !AD Root block number is a local bit map number  DBRBNNEG, !AD Root block number negative  DBRLEVTOOHI, !AD Root level higher than maximum  DBRLEVLTONE, !AD Root level less than one  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Total blocks equal zero  DBNOTDB, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345760	DBMXRSEXCMIN, !AD Maximum record size for database is less than the design minimum
DBVERPERFWARN2, Peformance warning: Database !AD is not fully upgraded. Run MUPIP REORG UPGRADE for best overall performance  DBRBNTOOLRG, !AD Root block number greater than last block number in file  DBRBNLBMN, !AD Root block number is a local bit map number  DBRBNNEG, !AD Root block number negative  DBRBNNEG, !AD Root block number negative  DBRLEVTOOHI, !AD Root level higher than maximum  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Start VBN smaller than possible  DBSTLBLKO, !AD Total blocks equal zero  DBNOTDB, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345776	DBREADBM, !AD Read error on bitmap
REORG UPGRADE for best overall performance  DBRBNTOOLRG, !AD Root block number greater than last block number in file  DBRBNLBMN, !AD Root block number is a local bit map number  DBRBNNEG, !AD Root block number negative  DBRBNNEG, !AD Root level higher than maximum  DBRLEVTOOHI, !AD Root level less than one  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Start VBN smaller than possible  DBTTLBLK0, !AD Total blocks equal zero  DBNOTDB, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSCCLNUP, Mutex subsystem leftover resource !AD removed	150345784	DBCOMPTOOLRG, !AD Record has too large compression count
DBRBNLBMN, !AD Root block number is a local bit map number  DBRBNNEG, !AD Root block number negative  DBRLEVTOOHI, !AD Root level higher than maximum  DBRLEVLTONE, !AD Root level less than one  DBSVBNMIN, !AD Start VBN smaller than possible  DBSVBNMIN, !AD Start VBN smaller than possible  DBTLELKO, !AD Total blocks equal zero  DBNOTDB, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345792	
DBRBNNEG, !AD Root block number negative  DBRLEVTOOHI, !AD Root level higher than maximum  DBRLEVLTONE, !AD Root level less than one  DBSVBNMIN, !AD Start VBN smaller than possible  DBTTLBLK0, !AD Total blocks equal zero  DBNOTDB, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345800	DBRBNTOOLRG, !AD Root block number greater than last block number in file
DBRLEVTOOHI, !AD Root level higher than maximum  DBRLEVLTONE, !AD Root level less than one  DBSVBNMIN, !AD Start VBN smaller than possible  DBTTLBLK0, !AD Total blocks equal zero  DBNOTDB, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345808	DBRBNLBMN, !AD Root block number is a local bit map number
DBRLEVLTONE, !AD Root level less than one  DBSVBNMIN, !AD Start VBN smaller than possible  DBTTLBLKO, !AD Total blocks equal zero  DBNOTDB, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345816	DBRBNNEG, !AD Root block number negative
DBSVBNMIN, !AD Start VBN smaller than possible DBTTLBLK0, !AD Total blocks equal zero DBNOTDB, !AD File does not have a valid GDS file header DBTOTBLK, Total blocks should be 0x!XL DBTN, Block TN is 0x!16@XQ DBNOREGION, None of the database regions accessible DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors DBTNLTCTN, Transaction numbers greater than the current transaction were found DBTNRESET, Cannot reset transaction number for this region MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345824	DBRLEVTOOHI, !AD Root level higher than maximum
DBTTLBLK0, !AD Total blocks equal zero  DBNOTDB, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345832	DBRLEVLTONE, !AD Root level less than one
DBNOTDB, !AD File does not have a valid GDS file header  DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345840	DBSVBNMIN, !AD Start VBN smaller than possible
DBTOTBLK, Total blocks should be 0x!XL  DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345848	DBTTLBLK0, !AD Total blocks equal zero
DBTN, Block TN is 0x!16@XQ  DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345856	DBNOTDB, !AD File does not have a valid GDS file header
DBNOREGION, None of the database regions accessible  DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345864	DBTOTBLK, Total blocks should be 0x!XL
DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors  DBTNLTCTN, Transaction numbers greater than the current transaction were found  DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345872	DBTN, Block TN is 0x!16@XQ
DBTNLTCTN, Transaction numbers greater than the current transaction were found DBTNRESET, Cannot reset transaction number for this region MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345880	DBNOREGION, None of the database regions accessible
DBTNRESET, Cannot reset transaction number for this region  MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345888	DBTNRESETINC, WARNING: tn_reset for database is incomplete due to integrity errors
150345912 MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed	150345896	DBTNLTCTN, Transaction numbers greater than the current transaction were found
·	150345904	DBTNRESET, Cannot reset transaction number for this region
SEMWT2LONG, Process !UL waited !UL second(s) for the !AD lock for region !AD	150345912	MUTEXRSRCCLNUP, Mutex subsystem leftover resource !AD removed
	150345920	SEMWT2LONG, Process !UL waited !UL second(s) for the !AD lock for region !AD

V6.2-002 MR Manual June 09, 2015, Page 387 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150345928	REPLINSTOPEN, Error opening replication instance file !AD
150345936	REPLINSTCLOSE, Error closing replication instance file !AD
150345944	JOBSETUP, Error receiving !AD from parent process
150345952	DBCRERR8, Database file !AD
150345960	NUMPROCESSORS, Could not determine number of processors
150345968	DBADDRANGE8, Database file !AD
150345976	RNDWNSEMFAIL, Attempting to acquire gds_rundown semaphore when it is already owned
150345984	GTMSECSHRSHUTDN, gtmsecshr process has received a shutdown request
150345992	NOSPACECRE, Not enough space to create database file !AD. !@ZQ blocks are needed
150346000	LOWSPACECRE, Disk space for database file !AD is not enough for !UL future extensions. ! @ZQ !UL
150346008	WAITDSKSPACE, Process 0x!XL will wait !UL seconds for necessary disk space to become available for !AD
150346016	OUTOFSPACE, Database file !AD ran out of disk space. Detected by process !UL. !/Exit without clearing shared memory due to the disk space constraints. !/Make space and then perform mupip rundown to ensure database integrity.
150346024	JNLPVTINFO, Pid 0x!XL!/ cycle 0x!XL fd_mismatch 0x!XL channel 0x!XL sync_io 0x!XL!/ pini_addr 0x!XL qio_active 0x!XL old_channel 0x!XL
150346032	NOSPACEEXT, Not enough disk space for file !AD to extend. !UL blocks needed. !UL blocks available.
150346040	WCBLOCKED, Field !AD is set by process !UL at transaction number 0x!16@XQ for database file !AD
150346048	REPLJNLCLOSED, Replication in jeopardy as journaling got closed for database file !AD. Current region sequo is !@ZQ [0x!16@XQ] and system sequo is !@ZQ [0x!16@XQ]
150346056	RENAMEFAIL, Rename of file !AD to !AD failed
150346064	FILERENAME, File !AD is renamed to !AD
150346072	JNLBUFINFO, Pid 0x!XL!/ dsk 0x!XL free 0x!XL bytcnt 0x!XL io_in_prog 0x!XL fsync_in_prog 0x!XL!/ dskaddr 0x!XL freeaddr 0x!XL qiocnt 0x!XL now_writer 0x!XL fsync_pid 0x!XL!/filesize 0x!XL cycle 0x!XL errcnt 0x!XL wrtsize 0x!XL
150346080	SDSEEKERR, Sequential device seek error
150346088	LOCALSOCKREQ, LOCAL socket required
150346096	TPNOTACID, !AD at !AD in a final TP retry violates ACID properties of a TRANSACTION; indefinite RESTARTs may occur !AD !AD

ZM #	GT.M Message, Description
150346104	JNLSETDATA2LONG, SET journal record has data of length !UL. Target system cannot handle data more than !UL bytes.
150346112	JNLNEWREC, Target system cannot recognize journal record of type !UL
150346120	REPLFTOKSEM, Error with replication semaphores for instance file !AD
150346128	SOCKNOTPASSED, Socket message contained no passed socket descriptors
150346136	EXTRIOERR, Error writing extract file !AD
150346144	EXTRCLOSEERR, Error closing extract file !AD
150346152	CONNSOCKREQ, Socket not connected
150346160	REPLEXITERR, Replication process encountered an error while exiting
150346176	DBRNDWN, Error during global database rundown for region !AD.!/Notify those responsible for proper database operation.
150346192	NOTALLDBOPN, Not all required database files were opened
150346200	MUSELFBKUP, Database file !AD can not be backed upon itself
150346208	DBDANGER, Process !UL [0x!XL] killed while committing update for database file !AD. Possibility of damage to block 0x!XL.
150346216	TRUNCATEFAIL, Truncating !AD from 0x!XL VMS blocks to 0x!XL blocks failed
150346224	TCGETATTR, Error while getting terminal attributes on file descriptor !UL
150346232	TCSETATTR, Error while setting terminal attributes on file descriptor !UL
150346240	IOWRITERR, IO Write by pid 0x!XL to blk 0x!XL of database file !AD failed. Pid 0x!XL retrying the IO.
150346248	REPLINSTWRITE, Error writing [0x!XL] bytes at offset [0x!16@XQ] in replication instance file !AD
150346256	DBBADFREEBLKCTR, Database !AD free blocks counter in file header: 0x!XL appears incorrect
150346264	REQ2RESUME, Request to resume suspended processing received from process !UL owned by userid !UL
150346272	TIMERHANDLER, Incorrect SIGALRM handler (0x!XJ) found by !AD
150346280	FREEMEMORY, Error occurred freeing memory from 0x!XJ
150346288	MUREPLSECDEL, Replication section !AD deleted
150346296	MUREPLSECNOTDEL, Replication section !AD not deleted
150346304	MUJPOOLRNDWNSUC, Jnlpool section (id = !AD) belonging to the replication instance !AD successfully rundown

V6.2-002 MR Manual June 09, 2015, Page 389 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150346312	MURPOOLRNDWNSUC, Recvpool section (id = !AD) belonging to the replication instance ! AD successfully rundown
150346320	MUJPOOLRNDWNFL, Jnlpool section (id = !AD) belonging to the replication instance !AD rundown failed
150346328	MURPOOLRNDWNFL, Recvpool section (id = !AD) belonging to the replication instance !AD rundown failed
150346336	MUREPLPOOL, Error with replpool section !AD
150346344	REPLACCSEM, Error with replication access semaphore (id = !UL) for instance file !AD
150346352	JNLFLUSHNOPROG, No progress while attempting to flush journal file !AD
150346360	REPLINSTCREATE, Error creating replication instance file !AD
150346368	SUSPENDING, Process Received Signal !UL. Suspending processing on user request or attempt to do terminal I/O while running in the background
150346376	SOCKBFNOTEMPTY, Socket buffer size cannot be set to 0x!XL due to 0x!XL bytes of buffered data. Read first.
150346384	ILLESOCKBFSIZE, The specified socket buffer size is 0x!XL
150346392	NOSOCKETINDEV, There is no socket in the current socket device
150346400	SETSOCKOPTERR, Setting the socket attribute !AD failed: (errno == !UL) !AD
150346408	GETSOCKOPTERR, Getting the socket attribute !AD failed: (errno == !UL) !AD
150346416	NOSUCHPROC, Process !UL does not exist
150346424	DSENOFINISH, DSE unable to finish all requested actions
150346432	LKENOFINISH, LKE unable to finish all requested actions
150346440	NOCHLEFT, Unhandled condition exception (all handlers exhausted)
150346448	MULOGNAMEDEF, Logical name !AD
150346456	BUFOWNERSTUCK, Pid !UL waiting for Pid !UL to finish disk
150346464	ACTIVATEFAIL, Cannot activate passive source server on instance !AD while a receiver server and/or update process is running
150346472	DBRNDWNWRN, Global section of database file !AD not rundown successfully by pid !UL [0x!XL]. Global section was not removed.
150346480	DLLNOOPEN, Failed to load external dynamic library !AD
150346488	DLLNORTN, Failed to look up the location of the symbol !AD
150346496	DLLNOCLOSE, Failed to unload external dynamic library

ZM #	GT.M Message, Description
150346504	FILTERNOTALIVE, Replication server detected that the filter is not alive while attempting to send seqno !16@XQ
150346512	FILTERCOMM, Error communicating seqno !16@XQ with the filter
150346520	FILTERBADCONV, Bad conversion of seqno !16@XQ by filter
150346528	PRIMARYISROOT, Attempted operation not valid on root primary instance !AD
150346536	GVQUERYGETFAIL, Global variable QUERY and GET failed. Failure code: !AD.
150346544	DBCREC2BIGINBLK, A Record in block 0x!XL has a length greater than the maximum (!UL) in database !AD
150346552	MERGEDESC, Merge operation not possible. !AD is descendent of !AD.
150346560	MERGEINCOMPL, Error encountered during MERGE; operation may be incomplete
150346568	DBNAMEMISMATCH, Database file !AD points to shared memory (id = !UL) which in turn points to an inaccessible database file !AZ
150346576	DBIDMISMATCH, Database file !AZ (region !AD) id does not match file id in shared memory (id = !UL).
150346584	DEVOPENFAIL, Error opening !AD
150346592	IPCNOTDEL, !AD : !AD did not delete IPC resources for region !AD
150346600	XCVOIDRET, Attempt to return a value from function !AD
150346608	MURAIMGFAIL, Mupip recover or rollback failed while processing an after
150346616	REPLINSTUNDEF, Replication instance environment variable \$gtm_repl_instance is undefined
150346624	REPLINSTACC, Error accessing replication instance file !AD
150346632	NOJNLPOOL, No journal pool info found in the replication instance of !AD
150346640	NORECVPOOL, No receiver pool info found in the replication instance of !AD
150346648	FTOKERR, Error getting ftok of the file !AD
150346656	REPLREQRUNDOWN, Error accessing replication instance !AD. Must be rundown on cluster node !AD.
150346664	BLKCNTEDITFAIL, Mupip recover or rollback failed to correct the block count field in the file header for file !AD
150346672	SEMREMOVED, Semaphore id !UL removed from the system
150346680	REPLINSTFMT, Format error encountered while reading replication instance file !AD. Expected !AD. Found !AD.
150346688	SEMKEYINUSE, Semaphore key 0x!XL is already in use (possibly by an older version)

V6.2-002 MR Manual June 09, 2015, Page 391

ZM #	GT.M Message, Description
150346696	XTRNTRANSERR, Error attempting to generate an environment using an external algorithm
150346704	XTRNTRANSDLL, Error during extended reference environment translation. Check the above message.
150346712	XTRNRETVAL, Length of return value (!SL) from extended reference translation algorithm is not in the range [0
150346720	XTRNRETSTR, Return string from extended reference translation algorithm is NULL
150346728	INVECODEVAL, Invalid value for \$ECODE (!AD)
150346736	SETECODE, Non
150346744	INVSTACODE, Invalid value for second parameter of \$STACK (!AD)
150346760	NOCANONICNAME, Value is not a canonic name (!AD)
150346768	NOSUBSCRIPT, No such subscript found (!SL)
150346784	SIZENOTVALID4, Size (in bytes) must be either 1
150346792	STRNOTVALID, Error: cannot convert !AD value to valid value
150346800	CREDNOTPASSED, Socket message contained no passed credentials
150346808	ERRWETRAP, Error while processing \$ETRAP
150346816	TRACINGON, Tracing already turned on
150346824	CITABENV, Environment variable for call
150346832	CITABOPN, Unable to open call
150346840	CIENTNAME, No label reference found for this entry in call
150346848	CIRTNTYP, Invalid return type
150346856	CIRCALLNAME, Call
150346864	CIRPARMNAME, Invalid parameter specification for call
150346872	CIDIRECTIVE, Invalid directive parameter passing. Expected I
150346880	CIPARTYPE, Invalid type specification for O/IO directive
150346888	CIUNTYPE, Unknown parameter type encountered
150346896	CINOENTRY, No entry specified for !AD in the call
150346904	JNLINVSWITCHLMT, Journal AUTOSWITCHLIMIT [!UL] falls outside of allowed limits [! UL] and [!UL]
150346912	SETZDIR, Cannot change working directory to !AD
150346920	JOBACTREF, Actual parameter in job command passed by reference

ZM #	GT.M Message, Description
150346928	ECLOSTMID, \$ECODE overflow
150346936	ZFF2MANY, Number of characters specified for ZFF deviceparameter (!UL) is more than the maximum allowed (!UL)
150346944	JNLFSYNCLSTCK, Journaling fsync lock is stuck in journal file !AD
150346952	DELIMWIDTH, Delimiter length !UL exceeds device width !UL
150346960	DBBMLCORRUPT, Database !AD : Bitmap blk [0x!XL] is corrupt (size = [0x!XL]
150346968	DLCKAVOIDANCE, Possible deadlock detected: Database !AD : Dbtn [0x!16@XQ] : t_tries [0x!XL] : dollar_trestart [0x!XL] : now_crit [0x!XL] : TP transaction restarted
150346976	WRITERSTUCK, Buffer flush stuck waiting for [0x!XL] concurrent writers to finish writing to database file !AD
150346984	PATNOTFOUND, Current pattern table has no characters with pattern code !AD
150346992	INVZDIRFORM, Invalid value (!UL) specified for ZDIR_FORM
150347000	ZDIROUTOFSYNC, \$ZDIRECTORY !AD is not the same as its cached value !AD
150347008	GBLNOEXIST, Global !AD no longer exists
150347016	MAXBTLEVEL, Global ^!AD in region !AD reached maximum level
150347024	INVMNEMCSPC, Unsupported mnemonicspace !AD
150347032	JNLALIGNSZCHG, Journal ALIGNSIZE is rounded up to !UL blocks (closest next higher power of two)
150347040	SEFCTNEEDSFULLB, Current side effect setting does not permit full Boolean to be turned off
150347048	GVFAILCORE, A core file is being created for later analysis if necessary
150347056	DBCDBNOCERTIFY, Database !AD HAS NOT been certified due to the preceding errors
150347064	DBFRZRESETSUC, Freeze released successfully on database file !AD
150347072	JNLFILEXTERR, Error during extension of journal file !AD
150347080	JOBEXAMDONE, GT.M process !UL completed job examine to !AD
150347088	JOBEXAMFAIL, GT.M process !UL executing \$ZJOBEXAM function failed with the preceding error message
150347104	ERRWZINTR, Error while processing \$ZINTERRUPT
150347112	CLIERR, !AD
150347120	REPLNOBEFORE, NOBEFORE option cannot be used when the current replication state is ON for database file !AD
150347128	REPLJNLCNFLCT, Journaling cannot be turned !AD on database file !AD as the replication state is !AD and must also be turned !AD in the same command

ZM #	GT.M Message, Description
150347136	JNLDISABLE, Specified journal option(s) cannot take effect as journaling is DISABLED on database file !AD
150347144	FILEEXISTS, File !AD already exists
150347152	JNLSTATE, Journaling state for !AD !AD is now !AD
150347160	REPLSTATE, Replication state for !AD !AD is now !AD
150347168	JNLCREATE, Journal file !AD created for !AD !AD with !AD
150347176	JNLNOCREATE, Journal file !AD not created
150347184	JNLFNF, Journal file !AD not found
150347192	PREVJNLLINKCUT, Previous journal file name link set to NULL in new journal file !AD created for database file !AD
150347200	PREVJNLLINKSET, Previous generation journal file name is changed from !AD to !AD
150347208	FILENAMETOOLONG, File name too long
150347216	REQRECOV, Error accessing database !AD. Must be recovered on cluster node !AD.
150347224	JNLTRANS2BIG, Transaction needs an estimated [!UL blocks] in journal file !AD which exceeds the AUTOSWITCHLIMIT of !UL blocks
150347232	JNLSWITCHTOOSM, Journal AUTOSWITCHLIMIT [!UL blocks] is less than Journal ALLOCATION [!UL blocks] for database file !AD
150347240	JNLSWITCHSZCHG, Journal AUTOSWITCHLIMIT [!UL blocks] is rounded down to [!UL blocks] to equal the sum of Journal ALLOCATION [!UL blocks] and a multiple of Journal EXTENSION [!UL blocks] for database file !AD
150347248	NOTRNDMACC, Only random access files are supported as backup files for non
150347256	TMPFILENOCRE, Error in MUPIP BACKUP while trying to create temporary file !AD
150347264	SHRMEMEXHAUSTED, Attempt by process to use more shared memory than currently permitted by VMS
150347272	JNLSENDOPER, pid = 0x!XL : status = 0x!XL : jpc_status = 0x!XL : jpc_status2 = 0x!XL : iosb.cond = 0x!XW
150347416	MUTEXRELEASED, Process !UL [0x!XL] has released the critical section for database !AD to avoid deadlock. \$TLEVEL: !UL t_tries: !UL
150347424	JNLCRESTATUS, !AD at line !UL for journal file !AD
150347432	ZBREAKFAIL, Could not set breakpoint at !AD due to insufficient memory
150347440	DLLVERSION, Routine !AD in library !AD was compiled with an incompatible version of GT.M. Recompile with the current version and re
150347448	INVZROENT, !AD is neither a directory nor an object library(DLL)

FIS

ZM #	GT.M Message, Description
150347464	GETSOCKNAMERR, Getting the socket name failed from getsockname(): (errno==!UL) !AD
150347472	INVGTMEXIT, Inappropriate invocation of gtm_exit. gtm_exit cannot be invoked from external calls.
150347480	CIMAXPARAM, Exceeded maximum number of parameters in the call
150347488	CITPNESTED, Call
150347496	CIMAXLEVELS, Too many nested Call
150347512	STARFILE, Star(*) argument cannot be specified with !AD
150347520	NOSTARFILE, Only star(*) argument can be specified with !AD
150347528	MUJNLSTAT, !AD at !AD
150347536	JNLTPNEST, Mupip journal command found nested TP transactions for journal file !AD at offset 0x!XL at transaction number 0x!16@XQ
150347544	REPLOFFJNLON, Replication state for database file !AD is OFF but journaling state is enabled
150347552	FILEDELFAIL, Deletion of file !AD failed
150347560	INVQUALTIME, Invalid time qualifier value. Specify as !AD=delta_or_absolute_time.
150347568	NOTPOSITIVE, !AD qualifier must be given a value greater than zero
150347576	INVREDIRQUAL, Invalid REDIRECT qualifier value. !AD
150347584	INVERRORLIM, Invalid ERROR_LIMIT qualifier value. Must be at least zero
150347592	INVIDQUAL, Invalid ID qualifier value !AD
150347600	INVTRNSQUAL, Invalid TRANSACTION qualifier. Specify only one of TRANSACTION=[NO]SET or TRANSACTION=[NO]KILL.
150347608	JNLNOBIJBACK, MUPIP JOURNAL BACKWARD cannot continue as journal file !AD does not have before image journaling
150347616	SETREG2RESYNC, Setting resync sequence number 0x!16@XQ to region sequence number 0x!16@XQ for database !AD
150347624	JNLALIGNTOOSM, Alignsize !UL (bytes) is too small for a block size of !UL (bytes) for !AD ! AD. Using alignsize of !UL (bytes) instead.
150347632	JNLFILEOPNERR, Error opening journal file !AD
150347640	JNLFILECLOSERR, Error closing journal file !AD
150347648	REPLSTATEOFF, ROLLBACK cannot proceed as database !AD does not have replication ON
150347656	MUJNLPREVGEN, Previous generation journal file !AD included for database file !AD
150347664	MUPJNLINTERRUPT, Database file !AD indicates interrupted MUPIP JOURNAL command. Restore from backup for forward recovery.

ZM #	GT.M Message, Description
150347672	ROLLBKINTERRUPT, Database file !AD indicates interrupted ROLLBACK. Reissue the MUPIP JOURNAL ROLLBACK command.
150347680	RLBKJNSEQ, Journal seqno of the instance after rollback is !@ZQ [0x!16@XQ]
150347688	REPLRECFMT, Replication journal record format error encountered
150347696	PRIMARYNOTROOT, Attempted operation not valid on non
150347704	DBFRZRESETFL, Freeze release failed on database file !AD
150347712	JNLCYCLE, Journal file !AD causes cycle in the journal file generations of database file !AD
150347720	JNLPREVRECOV, Journal file has nonzero value in prev_recov_end_of_data field
150347728	RESOLVESEQNO, Resolving until sequence number !@ZQ [0x!16@XQ]
150347736	BOVTNGTEOVTN, Journal file !AD has beginning transaction [0x!16@XQ] which is greater than end transaction [0x!16@XQ]
150347744	BOVTMGTEOVTM, Journal file !AD has beginning timestamp [0x!16@XQ] greater than end timestamp [0x!16@XQ]
150347752	BEGSEQGTENDSEQ, Journal file !AD has beginning sequence number [0x!16@XQ] greater than end sequence number [0x!16@XQ]
150347760	DBADDRALIGN, Database file !AD
150347768	DBWCVERIFYSTART, Database file !AD
150347776	DBWCVERIFYEND, Database file !AD
150347784	MUPIPSIG, !AD (signal !UL) issued from process !UL [0x!XL] to process !UL [0x!XL]
150347792	HTSHRINKFAIL, Hash table compaction failed to allocate new smaller table due to lack of memory
150347800	STPEXPFAIL, Stringpool expansion failed. It could not expand to !UL bytes.
150347808	DBBTUWRNG, The blocks
150347816	DBBTUFIXED, The blocks
150347824	DBMAXREC2BIG, Maximum record size (!UL) is too large for this block size (!UL)
150347832	DBCSCNNOTCMPLT, Specified DBCERTIFY SCAN output file is not complete
150347840	DBCBADFILE, Source file !AD does not appear to have been generated by DBCERTIFY SCAN
150347848	DBCNOEXTND, Unable to extend database !AD
150347856	DBCINTEGERR, Encountered integrity error in database !AD
150347864	DBMINRESBYTES, Minimum RESERVED BYTES value required for certification/upgrade is ! UL

ZM #	GT.M Message, Description
150347872	DBCNOTSAMEDB, Database has been moved or restored since DBCERTIFY SCAN
150347880	DBCDBCERTIFIED, Database !AD has been certified for use with !AD
150347888	DBCMODBLK2BIG, Block 0x!XL has been modified since DBCERTIFY SCAN but is still too large or now has an earlier TN than in the scan phase
150347896	DBCREC2BIG, Record with key !AD is length !UL in block 0x!XL which is greater than the maximum length !UL in database !AD
150347904	DBCCMDFAIL, Executed command failed with return code !SL: !AD which executed !AD ! AD
150347912	DBCKILLIP, Cannot proceed with kill in progress indicator set for database !AD
150347920	DBCNOFINISH, DBCERTIFY unable to finish all requested actions
150347928	DYNUPGRDFAIL, Unable to dynamically upgrade block 0x!XL in database !AD due to lack of free space in block
150347936	MMNODYNDWNGRD, Unable to use dynamic downgrade with MM access method for region !AD. Use BG access method for downgrade
150347944	MMNODYNUPGRD, Unable to use MM access method for region !AD until all database blocks are upgraded
150347952	MUDWNGRDNRDY, Database !AD is not ready to downgrade
150347960	MUDWNGRDTN, Transaction number 0x!16@XQ in database !AD is too big for MUPIP [REORG] DOWNGRADE. Renew database with MUPIP INTEG TN_RESET
150347968	MUDWNGRDNOTPOS, Start VBN value is [!UL] while downgraded GT.M version can support only [!UL]. Downgrade not possible
150347976	MUUPGRDNRDY, Database !AD has not been certified as being ready to upgrade to !AD format
150347984	TNWARN, Database file !AD has 0x!16@XQ more transactions to go before reaching the transaction number limit (0x!16@XQ). Renew database with MUPIP INTEG TN_RESET
150347992	TNTOOLARGE, Database file !AD has reached the transaction number limit (0x!16@XQ). Renew database with MUPIP INTEG TN_RESET
150348000	SHMPLRECOV, Shared memory pool block recovery invoked for region !AD
150348008	MUNOSTRMBKUP, Database !AD has a block size larger than !UL and thus cannot use stream (incremental) backup
150348016	EPOCHTNHI, At the EPOCH record at offset !UL of !AD transaction number [0x!16@XQ] is higher than database transaction number [0x!16@XQ]
150348024	CHNGTPRSLVTM, Mupip will change tp_resolve_time from !UL to !UL because expected EPOCH or EOF record was not found in Journal File !AD
150348032	JNLUNXPCTERR, Unexpected error encountered for Journal !AD at disk address 0x!XL

V6.2-002 MR Manual June 09, 2015, Page 397

ZM #	GT.M Message, Description
150348040	OMISERVHANG, GTCM OMI server is hung
150348048	RSVDBYTE2HIGH, Record size (!UL) is greater than the maximum allowed for region !AD with Block size (!UL) and Reserved bytes (!UL)
150348056	BKUPTMPFILOPEN, Open of backup temporary file !AD failed
150348064	BKUPTMPFILWRITE, Write to backup temporary file !AD failed
150348072	VMSMEMORY2, Central storage exhausted during allocation of dynamic file descriptor with !UL bytes
150348080	LOADBGSZ2, Load error: BEGIN too large. No records loaded.
150348088	LOADEDSZ2, Load error: END too large. No records loaded.
150348096	REPLINSTMISMTCH, Process has replication instance file !AD (jnlpool shmid = !UL) open but database !AD is bound to instance file !AD (jnlpool shmid = !UL)
150348104	REPLINSTREAD, Error reading [0x!XL] bytes at offset [0x!16@XQ] from replication instance file !AD
150348112	REPLINSTDBMATCH, Replication instance file !AD has seqno [0x!16@XQ] while database has a different seqno [0x!16@XQ]
150348120	REPLINSTNMSAME, Primary and Secondary instances have the same replication instance name !AD
150348128	REPLINSTNMUNDEF, Replication instance name not defined
150348136	REPLINSTNMLEN, Replication instance name !AD should be 1 to 15 characters long
150348144	REPLINSTNOHIST, History information for !AD not found in replication instance file !AD
150348152	REPLINSTSECLEN, Secondary replication instance name !AD should be 1 to 15 characters long
150348160	REPLINSTSECMTCH, Secondary replication instance name !AD sent by receiver does not match !AD specified at source server startup
150348168	REPLINSTSECNONE, No information found for secondary instance !AD in instance file !AD
150348176	REPLINSTSECUNDF, Secondary replication instance name not defined
150348184	REPLINSTSEQORD, !AD has seqno [0x!16@XQ] which is less than last record seqno [0x! 16@XQ] in replication instance file !AD
150348192	REPLINSTSTNDALN, Could not get exclusive access to replication instance file !AD
150348200	REPLREQROLLBACK, Replication instance file !AD indicates abnormal shutdown or an incomplete ROLLBACK. Run MUPIP JOURNAL ROLLBACK first
150348208	REQROLLBACK, Error accessing database !AD. Run MUPIP JOURNAL ROLLBACK on cluster node !AD.

ZM #	GT.M Message, Description
150348216	INVOBJFILE, Cannot ZLINK object file !AD due to unexpected format
150348224	SRCSRVEXISTS, Source server for secondary instance !AD is already running with pid !UL
150348232	SRCSRVNOTEXIST, Source server for secondary instance !AD is not alive
150348240	SRCSRVTOOMANY, Cannot start more than !UL source servers in replication instance !AD
150348248	JNLPOOLBADSLOT, Source server slot for secondary instance !AD is in an inconsistent state. Pid = [!UL]
150348256	NOENDIANCVT, Unable to convert the endian format of file !AD due to !AD
150348264	ENDIANCVT, Converted database file !AD from !AZ endian to !AZ endian on a !AZ endian system
150348272	DBENDIAN, Database file !AD is !AZ endian on a !AZ endian system
150348280	BADCHSET, !AD is not a valid character mapping in this context
150348288	BADCASECODE, !AD is not a valid case conversion code
150348296	BADCHAR, \$ZCHAR(!AD) is not a valid character in the !AD encoding form
150348304	DLRCILLEGAL, !_!AD!/!_!_!Illegal \$CHAR() value !UL
150348312	NONUTF8LOCALE, Locale has character encoding (!AD) which is not compatible with UTF
150348320	INVDLRCVAL, Invalid \$CHAR() value !UL
150348328	DBMISALIGN, Database file !AD has !UL blocks which does not match alignment rules. Reconstruct the database from a backup or extend it by at least !UL blocks.
150348336	LOADINVCHSET, Extract file CHSET (!AD) is incompatible with gtm_chset
150348344	DLLCHSETM, Routine !AD in library !AD was compiled with CHSET=M which is different from \$ZCHSET. Recompile with CHSET=UTF
150348352	DLLCHSETUTF8, Routine !AD in library !AD was compiled with CHSET=UTF
150348360	BOMMISMATCH, !AD Byte Order Marker found when !AD character set specified
150348368	WIDTHTOOSMALL, WIDTH should be at least 2 when device ICHSET or OCHSET is UTF
150348376	SOCKMAX, Attempt to exceed maximum sockets (!UL) for the SOCKET device
150348384	PADCHARINVALID, PAD deviceparameter cannot be greater than 127
150348392	ZCNOPREALLOUTPAR, Parameter !UL in external call !AD.!AD is an output only parameter requiring pre
150348400	SVNEXPECTED, Special variable expected in this context
150348408	SVNONEW, Cannot NEW this special variable
150348416	ZINTDIRECT, Attempt to enter direct mode from \$ZINTERRUPT

V6.2-002 MR Manual June 09, 2015, Page 399 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150348424	ZINTRECURSEIO, Attempt to do IO to the active device in \$ZINTERRUPT
150348432	MRTMAXEXCEEDED, Maximum value of !UL for SOCKET device parameter MOREREADTIME exceeded
150348440	JNLCLOSED, Journaling closed for database file !AD at transaction number 0x!16@XQ
150348448	RLBKNOBIMG, ROLLBACK cannot proceed as database !AD has NOBEFORE_IMAGE journaling
150348456	RLBKJNLNOBIMG, Journal file !AD has NOBEFORE_IMAGE journaling
150348464	RLBKLOSTTNONLY, ROLLBACK will only create a lost transaction file (database and journal files will not be modified)
150348472	KILLBYSIGSINFO3, !AD process !UL has been killed by a signal !UL accessing vaddress 0x!XJ
150348480	GTMSECSHRTMPPATH, gtmsecshr path is !AD
150348488	GTMERREXIT, GTM image has exited with errors
150348496	INVMEMRESRV, Could not allocate GT.M memory reserve (!AD)
150348504	OPCOMMISSED, !UL errors and !UL MBFULLs sending prior operator messages
150348512	COMMITWAITSTUCK, Pid !UL timed out after waiting !UL minute(s) for !UL concurrent GT.M process(es) to finish commits in database file !AD
150348520	COMMITWAITPID, Pid !UL waited !UL minute(s) for pid !UL to finish commits to block 0x! XL in database file !AD
150348528	UPDREPLSTATEOFF, Error replicating global ^!AD as it maps to database !AD which has replication turned OFF
150348536	LITNONGRAPH, M standard requires graphics in string literals; found non
150348544	DBFHEADERR8, Database file !AD: control problem: !AD was 0x!16@XQ expecting 0x! 16@XQ
150348552	MMBEFOREJNL, BEFORE image journaling cannot be set with MM access method in database file !AD
150348560	MMNOBFORRPL, Replication cannot be used in database file !AD which uses MM access method and NOBEFORE image journaling
150348568	KILLABANDONED, Abandoned kills counter is greater than zero for file !AD
150348576	BACKUPKILLIP, Kill in progress indicator is set for file !AD
150348584	LOGTOOLONG, Environment variable !AD is too long. Maximum length allowed is !UL bytes.
150348592	NOALIASLIST, Parenthetical lists of multiple arguments cannot have a preceding alias introducer or include alias (*) forms

ZM #	GT.M Message, Description
150348600	ALIASEXPECTED, Alias or alias container variable expected in this context
150348608	VIEWLVN, Invalid local variable name used with VIEW/\$VIEW(): !AD
150348616	DZWRNOPAREN, \$ZWRTACxxx is not allowed inside a parenthesized SET target
150348624	DZWRNOALIAS, \$ZWRTAC cannot be aliased
150348632	FREEZEERR, Error while trying to !AD region !AD
150348640	CLOSEFAIL, Error while closing file descriptor !SL
150348648	CRYPTINIT, Could not initialize encryption library while opening encrypted file !AD. !AD
150348656	CRYPTOPFAILED, Encrypt/Decrypt operation failed for file !AD. !AD
150348664	CRYPTDLNOOPEN, Could not load encryption library while opening encrypted file !AD. ! AD
150348672	CRYPTNOV4, !AD is an encrypted database. Cannot downgrade(to V4) with Encryption option enabled.
150348680	CRYPTNOMM, !AD is an encrypted database. Cannot support MM access method.
150348688	CRYPTJNLWRONGHASH, Encryption key hash mismatch between journal file !AD and corresponding database file !AD
150348696	CRYPTKEYFETCHFAILED, Could not retrieve encryption key corresponding to file !AD. ! AD
150348704	CRYPTKEYFETCHFAILEDNF, Could not retrieve encryption key during !AD operation key. ! AD
150348712	CRYPTHASHGENFAILED, Could not generate cryptographic hash for symmetric key corresponding to file !AD. !AD
150348728	BADTAG, Unable to use file !AD (CCSID !UL) with CCSID !UL
150348736	ICUVERLT36, !AD !UL.!UL. ICU version greater than or equal to 3.6 should be used
150348744	ICUSYMNOTFOUND, Symbol !AD not found in the ICU libraries. ICU needs to be built with symbol
150348752	STUCKACT, Process stuck script invoked: !AD : !AD
150348760	CALLINAFTERXIT, After a gtm_exit
150348768	LOCKSPACEFULL, No more room for LOCK slots on database file !AD
150348776	IOERROR, Error occured while doing !AD in !AD operation
150348784	MAXSSREACHED, Maximum snapshots
150348792	SNAPSHOTNOV4, Cannot downgrade (to V4) while snapshots are in progress. Currently !UL snapshots are in progress for region !AD.

V6.2-002 MR Manual June 09, 2015, Page 401 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150348800	SSV4NOALLOW, Database snapshots are supported only on fully upgraded V5 databases. ! AD has V4 format blocks.
150348808	SSTMPDIRSTAT, Cannot access temporary directory !AD
150348816	SSTMPCREATE, Cannot create the temporary file in directory !AD for the requested snapshot
150348824	JNLFILEDUP, Journal files !AD and !AD are the same
150348832	SSPREMATEOF, Premature end of file while reading block !UL of size: !UL bytes at offset: !UL from !AD
150348840	SSFILOPERR, Error while doing !AD operation on file !AD
150348848	REGSSFAIL, Process !UL encountered error contributing to the snapshot for region !AD
150348856	SSSHMCLNUPFAIL, Error while doing snapshot shared memory cleanup. Operation
150348864	SSFILCLNUPFAIL, Error while unlinking snapshot file
150348872	SETINTRIGONLY, ISV !AD cannot be modified outside of the trigger environment
150348880	MAXTRIGNEST, Maximum trigger nesting level (!UL) exceeded
150348888	TRIGCOMPFAIL, Compilation of database trigger named !AD failed
150348896	NOZTRAPINTRIG, Use of \$ZTRAP in a database trigger environment (\$ZTLEVEL greater than 0) is not supported
150348904	ZTWORMHOLE2BIG, String length of !UL bytes exceeds maximum length of !UL bytes for \$ZTWORMHOLE
150348912	JNLENDIANLITTLE, Journal file !AD is LITTLE endian on a BIG endian system
150348920	JNLENDIANBIG, Journal file !AD is BIG endian on a LITTLE endian system
150348928	TRIGINVCHSET, Trigger !AD for global ^!AD was created with CHSET=!AD which is different from the current \$ZCHSET of this process
150348936	TRIGREPLSTATE, Trigger cannot update replicated database file !AD since triggering update was not replicated
150348944	GVDATAGETFAIL, Global variable DATAGET sub
150348952	TRIG2NOTRIG, Sending transaction sequence number 0x!16@XQ which used triggers to a replicator that does not support triggers
150348960	ZGOTOINVLVL, ZGOTO in a trigger running in !AD cannot ZGOTO level !UL
150348968	TRIGTCOMMIT, TCOMMIT at \$ZTLEVEL=!UL not allowed as corresponding TSTART was done at lower \$ZTLEVEL=!UL
150348976	TRIGTLVLCHNG, Detected a net transaction level (\$TLEVEL) change during trigger !AD. Transaction level must be the same at exit as when the trigger started

FIS V6.2-002 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150348984	TRIGNAMEUNIQ, Unable to make trigger name !AD unique beyond !UL versions already loaded
150348992	ZTRIGINVACT, Missing or invalid parameter in position !UL given to \$ZTRIGGER()
150349000	INDRCOMPFAIL, Compilation of indirection failed
150349008	QUITALSINV, QUIT * return when the extrinsic was not invoked with SET *
150349016	PROCTERM, !AD process termination due to !AD (return code !UL) from !AD
150349024	SRCLNNTDSP, Source lines exceeding !UL character width are not displayed
150349032	ARROWNTDSP, Unable to display ^
150349040	TRIGDEFBAD, Trigger initialization failed for global ^!AD. Error while processing ^#t("!AD"
150349048	TRIGSUBSCRANGE, Trigger definition for global ^!AD has one or more invalid subscript range(s): !AD
150349056	TRIGDATAIGNORE, Ignoring trigger data !AD. Use MUPIP TRIGGER to load trigger definitions
150349064	TRIGIS, !_!_Trigger name: !AD
150349072	TCOMMITDISALLOW, TROLLBACK required after an unhandled error in trigger context
150349080	SSATTACHSHM, Error while attaching to shared memory identifier !UL
150349088	TRIGDEFNOSYNC, Global ^!AD has triggers defined on the !AD instance but none on the !AD instance. Current journal sequence number is 0x!16@XQ
150349096	TRESTMAX, TRESTART not allowed in a final TP retry more than once
150349112	GBLEXPECTED, Global variable reference expected in this context
150349120	GVZTRIGFAIL, ZTRIGGER of a global variable failed. Failure code: !AD.
150349128	MUUSERLBK, Abnormal shutdown of replication
150349136	SETINSETTRIGONLY, ISV !AD can only be modified in a 'SET' type trigger
150349144	DZTRIGINTRIG, \$ZTRIGGER() is not allowed inside trigger context. Trigger name: !AD
150349160	BOOLSIDEFFECT, Extrinsic (\$\$)
150349168	DBBADUPGRDSTATE, Correcting conflicting values for fields describing database version upgrade state in the file header for region !AD (!AD)
150349176	WRITEWAITPID, PID !UL waited !UL minute(s) for PID !UL to finish writing block 0x!XL in database file !AD
150349184	ZGOCALLOUTIN, ZGOTO level 0 with entry ref not valid when using call
150349192	REPLNOXENDIAN, !AD side is running on a GT.M version that does not support cross

V6.2-002 MR Manual June 09, 2015, Page 403 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150349200	REPLXENDIANFAIL, !AD side encountered error while doing endian conversion at journal sequence number 0x!16@XQ
150349208	ZGOTOINVLVL2, ZGOTO 0:entryref is not valid on VMS (UNLINK is a UNIX only feature)
150349216	GTMSECSHRCHDIRF, gtmsecshr unable to chdir to its temporary directory (!AD)
150349224	JNLORDBFLU, Error flushing database blocks to !AD. See related messages in the operator log
150349232	ZCCLNUPRTNMISNG, External call: Cleanup routine name missing. Cannot continue
150349240	ZCINVALIDKEYWORD, External call: Invalid keyword found. Cannot continue
150349256	DBSHMNAMEDIFF, Database file !AD points to shared memory (id = !UL) which points to a different database file !AZ
150349264	SHMREMOVED, Removed Shared Memory id !UL corresponding to file !AD
150349272	DEVICEWRITEONLY, Cannot read from a write
150349280	ICUERROR, ICU returned status !UL which is either unrecognized or inconsistent with the operating context
150349288	ZDATEBADDATE, \$ZDATE() date argument !AD is less than
150349296	ZDATEBADTIME, \$ZDATE() time argument !AD is less than 0 or greater than 86399 (the \$HOROLOG value for a second before midnight)
150349304	COREINPROGRESS, Previous core attempt failed; core generation bypassed
150349312	MAXSEMGETRETRY, Failed to get ftok semaphore after !UL tries because it is being continually deleted
150349320	JNLNOREPL, Replication not enabled for journal file !AD (database file !AD)
150349328	JNLRECINCMPL, Incomplete journal record at disk address 0x!XL for file !AD while attempting to read seqno 0x!16@XQ
150349336	JNLALLOCGROW, Increased Journal ALLOCATION from [!UL blocks] to [!UL blocks] to match AUTOSWITCHLIMIT for !AZ !AD
150349344	INVTRCGRP, Invalid trace group specified in \$gtm_trace_groups: !AD
150349352	MUINFOUINT6, !AD : !UL [0x!XL] ; \$H=!UL
150349360	NOLOCKMATCH, No matching locks were found in !AD
150349368	BADREGION, Region is not BG
150349376	LOCKSPACEUSE, Estimated free lock space: !UL% of !UL pages
150349384	JIUNHNDINT, An error during \$ZINTERRUPT processing was not handled: !AD
150349392	GTMASSERT2, !AD

ZM #	GT.M Message, Description
150349400	ZTRIGNOTRW, ZTRIGGER cannot operate on read
150349408	TRIGMODREGNOTRW, Trigger(s) cannot be added/changed/deleted/upgraded because region !AD is read
150349416	INSNOTJOINED, Replicating Instance !AD is not a member of the same Group as Instance ! AD
150349424	INSROLECHANGE, Supplementary Instance !AD and non
150349432	INSUNKNOWN, Supplementary Instance !AD has no instance definition for non
150349440	NORESYNCSUPPLONLY, NORESYNC only supported for Supplementary Instances
150349448	NORESYNCUPDATERONLY, NORESYNC qualifier only allowed on a Supplementary Instance which allows local updates
150349456	NOSUPPLSUPPL, Instance !AD is configured to perform local updates so it cannot receive from Supplementary Instance !AD
150349464	REPL2OLD, Instance !AD uses a GT.M version that does not support connection with the current version on instance !AD
150349472	EXTRFILEXISTS, Error opening output file: !AD
150349480	MUUSERECOV, Abnormal shutdown of journaled database !AD detected
150349488	SECNOTSUPPLEMENTARY, !AD is a Supplementary Instance and so cannot act as a source to non
150349496	SUPRCVRNEEDSSUPSRC, Instance !AD is not configured to perform local updates so it cannot act as a receiver for non
150349504	PEERPIDMISMATCH, Local socket peer with PID=!UL does not match specified PID=!UL
150349512	SETITIMERFAILED, A setitimer() call returned an error status of !UL
150349520	UPDSYNC2MTINS, Can only UPDATERESYNC with an empty instance file
150349528	UPDSYNCINSTFILE, Error with instance file name specified in UPDATERESYNC qualifier
150349536	REUSEINSTNAME, Error with instance name specified in REUSE qualifier
150349544	RCVRMANYSTRMS, Receiver server now connecting to source stream [!2UL] but had previously connected to a different stream [!2UL]
150349552	RSYNCSTRMVAL, RSYNC_STRM qualifier can only take on a value from 0 to 15
150349560	RLBKSTRMSEQ, Stream journal sequo of the instance after rollback is Stream !2UL : Sequo ! @ZQ [0x!16@XQ]
150349568	RESOLVESEQSTRM, Resolving until stream sequence number Stream !2UL : Seqno !@ZQ [0x!16@XQ]

ZM #	GT.M Message, Description
150349576	REPLINSTDBSTRM, Replication instance file !AD has seqno [0x!16@XQ] for Stream !2UL while database has a different seqno [0x!16@XQ]
150349584	RESUMESTRMNUM, Error with stream number specified in RESUME qualifier
150349592	ORLBKSTART, ONLINE ROLLBACK started on instance !AD corresponding to !AD
150349600	ORLBKTERMNTD, ONLINE ROLLBACK terminated on instance !AD corresponding to !AD with the above errors
150349608	ORLBKCMPLT, ONLINE ROLLBACK completed successfully on instance !AD corresponding to !AD
150349616	ORLBKNOSTP, ONLINE ROLLBACK proceeding with database updates. MUPIP STOP will no longer be allowed
150349624	ORLBKFRZPROG, !AD : waiting for FREEZE on region !AD (!AD) to clear
150349632	ORLBKFRZOVER, !AD : FREEZE on region !AD (!AD) cleared
150349640	ORLBKNOV4BLK, Region !AD (!AD) has V4 format blocks. Database upgrade required. ONLINE ROLLBACK cannot continue
150349648	DBROLLEDBACK, Concurrent ONLINE ROLLBACK detected on one or more regions. The current operation is no longer valid
150349656	DSEWCREINIT, Database cache reinitialized by DSE for region !AD
150349664	MURNDWNOVRD, OVERRIDE qualifier used with MUPIP RUNDOWN on database file !AD
150349680	SRVLCKWT2LNG, PID !UL is holding the source server lock. Waited for !UL minute(s). Now exiting
150349688	IGNBMPMRKFREE, Ignoring bitmap free
150349696	PERMGENFAIL, Failed to determine access permissions to use for creation of !AD for file ! AD
150349704	PERMGENDIAG, Permissions: Proc(uid:!UL
150349712	MUTRUNC1ATIME, Process with PID !UL already performing truncate in region !AD
150349720	MUTRUNCBACKINPROG, Truncate detected concurrent backup in progress for region !AD
150349728	MUTRUNCERROR, Truncate of region !AD encountered service error !AD
150349736	MUTRUNCFAIL, Truncate failed after reorg
150349744	MUTRUNCNOSPACE, Region !AD has insufficient space to meet truncate target percentage of !UL
150349752	MUTRUNCNOTBG, Region !AD does not have access method BG
150349760	MUTRUNCNOV4, Region !AD is not fully upgraded from V4 format.
150349768	MUTRUNCPERCENT, Truncate threshold percentage should be from 0 to 99

ZM #	GT.M Message, Description
150349776	MUTRUNCSSINPROG, Truncate detected concurrent snapshot in progress for region !AD
150349784	MUTRUNCSUCCESS, Database file !AD truncated from 0x!XL blocks to 0x!XL at transaction 0x!16@XQ
150349792	RSYNCSTRMSUPPLONLY, RSYNC_STRM qualifier only supported for Supplementary Instances
150349800	STRMNUMIS, Stream # is !2UL
150349808	STRMNUMMISMTCH1, Stream !2UL exists on the receiver instance file but is unknown on the source instance
150349816	STRMNUMMISMTCH2, Stream !2UL exists on the source instance file but is unknown on the receiver instance
150349824	STRMSEQMISMTCH, Unable to play update on Stream !2UL with seqno [0x!16@XQ] as receiving instance has a different stream seqno [0x!16@XQ]
150349832	LOCKSPACEINFO, Region: !AD: processes on queue: !UL/!UL; LOCK slots in use: !UL/!UL; name space!ADfull
150349840	JRTNULLFAIL, Applying NULL journal record failed. Failure code: !AD.
150349848	LOCKSUB2LONG, Following subscript is !UL bytes long which exceeds 255 byte limit.
150349864	RESRCINTRLCKBYPAS, !AD with PID !UL bypassing the !AD semaphore for region !AD (! AD) was held by PID !UL.
150349872	DBFHEADERRANY, Database file !AD: control problem: !AD was 0x!XJ expecting 0x!XJ
150349880	REPLINSTFROZEN, Instance !AZ is now Frozen
150349888	REPLINSTFREEZECOMMENT, Freeze Comment: !AZ
150349896	REPLINSTUNFROZEN, Instance !AZ is now Unfrozen
150349904	DSKNOSPCAVAIL, Attempted write to file !AD failed due to lack of disk space. Retrying indefinitely.
150349912	DSKNOSPCBLOCKED, Retry of write to file !AD suspended due to new instance freeze. Waiting for instance to be unfrozen.
150349920	DSKSPCAVAILABLE, Write to file !AD succeeded after out
150349928	ENOSPCQIODEFER, Write to file !AD deferred due to lack of disk space
150349936	CUSTOMFILOPERR, Error while doing !AD operation on file !AD
150349944	CUSTERRNOTFND, Error mnemonic !AD specified in custom errors file is not valid for this version of GT.M
150349952	CUSTERRSYNTAX, Syntax error in file !AD at line number !UL
150349960	ORLBKINPROG, Online ROLLBACK in progress by PID !UL in region !AD

V6.2-002 MR Manual June 09, 2015, Page 407 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150349968	DBSPANGLOINCMP, !AD Spanning node is missing. Block no !UL of spanning node is missing
150349976	DBSPANCHUNKORD, !AD Chunk of !UL blocks is out of order
150349984	DBDATAMX, !AD Record too large
150349992	DBIOERR, Error while doing write operation on region !AD (!AD)
150350000	INITORRESUME, UPDATERESYNC on a Supplementary Instance must additionally specify INITIALIZE or RESUME
150350008	GTMSECSHRNOARG0, gtmsecshr cannot identify its origin
150350016	GTMSECSHRISNOT, gtmsecshr is not running as gtmsecshr but !AD
150350024	GTMSECSHRBADDIR, gtmsecshr is not running from \$gtm_dist/gtmsecshrdir or \$gtm_dist cannot be determined
150350032	JNLBUFFREGUPD, Journal file buffer size for region !AD has been adjusted from !UL to !UL.
150350040	JNLBUFFDBUPD, Journal file buffer size for database file !AD has been adjusted from !UL to !UL.
150350048	LOCKINCR2HIGH, Attempt to increment a LOCK more than !UL times
150350056	LOCKIS, !_!_Resource name: !AD
150350064	LDSPANGLOINCMP, Incomplete spanning node found during load!/!_!_at File offset : [0x! 16@XQ]
150350072	MUFILRNDWNFL2, Database section (id = !UL) belonging to database file !AD rundown failed
150350080	MUINSTFROZEN, !AD : Instance !AZ is frozen. Waiting for instance to be unfrozen before proceeding with writes to database file !AD
150350088	MUINSTUNFROZEN, !AD : Instance !AZ is now Unfrozen. Continuing with writes to database file !AD
150350096	GTMEISDIR, !AD : Is a directory
150350104	SPCLZMSG, The following error message cannot be driven through ZMESSAGE
150350112	MUNOTALLINTEG, At least one region skipped. See the earlier messages
150350120	BKUPRUNNING, Process !UL is currently backing up region !AD. Cannot start another backup.
150350128	MUSIZEINVARG, MUPIP SIZE : Invalid parameter value for: !AD
150350136	MUSIZEFAIL, MUPIP SIZE : failed. Failure code: !AD.
150350144	SIDEEFFECTEVAL, Extrinsic (\$\$)
150350152	CRYPTINIT2, Could not initialize encryption library !AD. !AD

FIS Page 408, June 09, 2015

ZM #	GT.M Message, Description
150350160	CRYPTDLNOOPEN2, Could not load encryption library !AD. !AD
150350168	CRYPTBADCONFIG, Could not retrieve data from encrypted file !AD due to bad encryption configuration. !AD
150350176	DBCOLLREQ, JOURNAL EXTRACT proceeding without collation information for globals in database. !AD !AD
150350184	SETEXTRENV, Database files are missing or Instance is frozen; supply the database files
150350192	NOTALLDBRNDWN, Not all regions were successfully rundown
150350200	TPRESTNESTERR, TP restart signaled while handing error
150350208	JNLFILRDOPN, Error opening journal file !AD for read for database file !AD
150350216	SEQNUMSEARCHTIMEOUT, Timed out trying to find sequence number !@ZQ [0x!16@XQ] in Journal File(s). See above messages for details. Source server exiting
150350224	FTOKKEY, FTOK key 0x!XL
150350232	SEMID, Semaphore id !UL
150350240	JNLQIOSALVAGE, Journal IO lock salvaged
150350256	MMFILETOOLARGE, Size of !AD region (!AD) is larger than maximum size supported for memory mapped I/O on this platform
150350264	BADZPEEKARG, Missing
150350272	BADZPEEKRANGE, Access exception raised in memory range given to \$ZPEEK()
150350280	BADZPEEKFMT, \$ZPEEK() value length inappropriate for selected format
150350288	DBMBMINCFREFIXED, Master bitmap incorrectly marks local bitmap 0x!XL as free. Auto
150350296	NULLENTRYREF, JOB command did not specify entryref
150350304	ZPEEKNORPLINFO, \$ZPEEK() unable to access requested replication structure
150350312	MMREGNOACCESS, Region !AD (!AD) is no longer accessible. See prior error messages in the operator and application error logs
150350320	MALLOCMAXUNIX, Exceeded maximum allocation defined by \$gtm_max_storalloc
150350328	MALLOCMAXVMS, Exceeded maximum allocation defined by GTM_MAX_STORALLOC
150350336	HOSTCONFLICT, Host !AD could not open database file !AD because it is marked as already open on node !AD
150350344	GETADDRINFO, Error in getting address info
150350352	GETNAMEINFO, Error in getting name info
150350360	SOCKBIND, Error in binding socket

ZM #	GT.M Message, Description
150350368	INSTFRZDEFER, Instance Freeze initiated by !AD error on region !AD deferred due to critical resource conflict
150350376	REGOPENRETRY, Attempt to open region !AD (!AD) using startup shortcut failed due to conflicting database shutdown. Retrying
150350384	REGOPENFAIL, Failed to open region !AD (!AD) due to conflicting database shutdown activity
150350392	REPLINSTNOSHM, Database !AD has no active connection to a replication journal pool
150350400	DEVPARMTOOSMALL, Deviceparameter must be greater than zero (0)
150350408	REMOTEDBNOSPGBL, Database region !AD contains portion of a spanning global and so cannot point to a remote file
150350416	NCTCOLLSPGBL, Database region !AD contains portion of spanning global ^!AD and so cannot support non
150350424	ACTCOLLMISMTCH, Global ^!AD inherits alternative collation sequence #!UL from global directory but database file !AD contains different collation sequence #!UL for this global
150350432	GBLNOMAPTOREG, Global !AD does not map to region !AD in current global directory
150350440	ISSPANGBL, Operation cannot be performed on global ^!AD as it spans multiple regions in current global directory
150350448	TPNOSUPPORT, Operation cannot be performed while inside of a TP transaction
150350456	GVSUBSERR, Invalid subscripted global name specification in \$VIEW() function
150350472	FILTERTIMEDOUT, Replication server timed out attempting to read sequo !16@XQ from external filter
150350480	TLSDLLNOOPEN, Failed to load GT.M TLS/SSL library for secure communication
150350488	TLSINIT, Failed to initialize GT.M TLS/SSL library for secure communication
150350496	TLSCONVSOCK, Failed to convert Unix TCP/IP socket to TLS/SSL aware socket
150350504	TLSHANDSHAKE, Connection to remote side using TLS/SSL protocol failed
150350512	TLSCONNINFO, Failed to obtain information on the TLS/SSL connection
150350520	TLSIOERROR, Error during TLS/SSL !AD operation
150350528	TLSRENEGOTIATE, Failed to renegotiate TLS/SSL connection
150350536	REPLNOTLS, !AD requested TLS/SSL communication but the !AD was either not started with TLSID qualifier or does not support TLS/SSL protocol
150350544	COLTRANSSTR2LONG, Output string after collation transformation is too long
150350552	SOCKPASS, Socket pass failed
150350560	SOCKACCEPT, Socket accept failed

ZM #	GT.M Message, Description
150350568	NOSOCKHANDLE, No socket handle specified in WRITE /PASS
150350576	TRIGLOADFAIL, MUPIP TRIGGER or \$ZTRIGGER operation failed. Failure code: !AD.
150350584	SOCKPASSDATAMIX, Attempt to use a LOCAL socket for both READ/WRITE and PASS/ACCEPT
150350592	NOGTCMDB, !AD does not support operation on GT.CM database region: !AD
150350600	NOUSERDB, !AD does not support operation on non
150350608	DSENOTOPEN, DSE could not open region !AD
150350616	ZSOCKETATTR, Attribute "!AD" invalid for \$ZSOCKET function
150350624	ZSOCKETNOTSOCK, \$ZSOCKET function called but device is not a socket
150350632	CHSETALREADY, CHSET !AD already specified for socket device
150350640	DSEMAXBLKSAV, DSE cannot SAVE another block as it already has the maximum of !UL
150350648	BLKINVALID, !XL is not a valid block as database file !AD has !XL total blocks
150350656	CANTBITMAP, Can't perform this operation on a bit map (block at a 200 hexadecimal boundary)
150350664	AIMGBLKFAIL, After image build for block !XL in region !AD failed in DSE or MUPIP
150350672	GTMDISTUNVERIF, Environment variable \$gtm_dist (!AD) could not be verified against the executables path (!AD)
150350680	CRYPTNOAPPEND, APPEND disallowed on the encrypted file !AD
150350688	CRYPTNOSEEK, SEEK disallowed on the encrypted file !AD
150350696	CRYPTNOTRUNC, Not positioned at file start or EOF. TRUNCATE disallowed on the encrypted file !AD
150350704	CRYPTNOKEYSPEC, Key name needs to be specified with KEY
150350712	CRYPTNOOVERRIDE, Cannot override IVEC and/or key without compromising integrity
150350720	CRYPTKEYTOOBIG, Specified key has length !UL
150350728	CRYPTBADWRTPOS, Encrypted WRITE disallowed from a position different than where the last WRITE completed
150350736	LABELNOTFND, GOTO referenced a label that does not exist
150350744	RELINKCTLERR, Error with relink control structure for \$ZROUTINES directory !AD
150350752	INVLINKTMPDIR, Value for \$gtm_linktmpdir is either not found or not a directory: !AD
150350760	NOEDITOR, Can't find an executable editor: !AD
150350768	UPDPROC, Update Process error

V6.2-002 MR Manual June 09, 2015, Page 411 GT.M Message and Recovery Procedures Manual

ZM #	GT.M Message, Description
150350776	HLPPROC, Helper Process error
150350784	REPLNOHASHTREC, Sequence number 0x!16@XQ contains trigger definition updates. !AD side must be at least V6.2
150350792	REMOTEDBNOTRIG, Trigger operations on global !AD not supported as it maps to database region !AD that points to a remote file
150350800	NEEDTRIGUPGRD, Cannot do trigger operation on database file !AD until it is upgraded; Run MUPIP TRIGGER
150350808	REQRLNKCTLRNDWN, Error accessing relinkctl file for \$ZROUTINES directory !AD. Must be rundown
150350816	RLNKCTLRNDWNSUC, Relinkctl file for \$ZROUTINES directory !AD successfully rundown
150350824	RLNKCTLRNDWNFL, Relinkctl file for \$ZROUTINES directory !AD failed to rundown as it is open by !UL process(es)
150350832	MPROFRUNDOWN, Error during M
150350840	ZPEEKNOJNLINFO, \$ZPEEK() unable to access requested journal structure
150350848	TLSPARAM, TLS parameter !AD !AD
150350856	RLNKRECLATCH, Failed to get latch on relinkctl record for routine name !AZ in \$ZROUTINES directory !AD
150350864	RLNKSHMLATCH, Failed to get latch on relinkctl shared memory for \$ZROUTINES directory !AD
150350872	JOBLVN2LONG, The zwrite representation of a local variable transferred to a JOB'd process can not exceed !UL. Encountered size: !UL

## Appendix B. Reference Implementation Error messages

The error messages listed in this appendix are generated by the reference plug-in. If you change the plug-in, the messages will be those generated by your plug-in. Note that the messages from the plug-in (incorrectly) use the term "DB keys file" for the master key file.

### Cannot find DB keys file <path>

Plugin error: The plugin cannot find the master key file.

Action: Set the \$gtm\_dbkeys environment variable to point to the correct master key file.

### Cannot find MUMPS executable in <path>

Plugin error: The plugin cannot find the MUMPS executable.

Action: Set the \$gtm\_dist environment variable to the directory containing MUMPS executable. Verify proper permissions for directory path and file.

### Cannot open DB keys file - <path>

Plugin error: The plugin cannot open the master key file.

Action: Verify the master key file exists and there are appropriate authorizations on the directory path and master key file.

## DB keys file of unknown file type: <path>

Plugin error: The plugin reports that the master key file is not the proper type file.

Action: Point the gtm\_dbkeys environment variable to an appropriately formatted master key file.

## Database file <path> missing in DB keys file or does not exist

Plugin error: The plugin reports that the master key file does not contain a valid entry pointing to the database file.

Action: Create an entry in the master key file for the specified database file, verify that the database file exists and appropriate authorizations exist on the directory and database file name.

## Database file <path> not found

Plugin error: The plugin is unable to find the specified database file.

Action: Verify that the database file exists, the corresponding entry in the master key file points to the database file, and appropriate authorizations exist in the directory path and the database file.

### **Encryption handle corrupted**

Plugin error: The plugin detected an internal error.

Action: This error indicates that there is a communication error between GT.M and the gtmcrypt plugin. Replace the process with undamaged one. Report the entire incident context to your GT.M support channel.

### **Encryption key file <path> not found**

Plugin error: The plugin was not able to find the key file on the specified path.

Action: Verify that the master key file entry for this key file points to the correct path. Verify that the key file itself exists. Verify proper authorizations on directory path and file.

## Encryption library has not been initialized

Plugin error: A gtmcrypt function was called before gtmcrypt\_init().

Action: Call gtmcrypt\_init() before calling any other encryption functions.

### Environment variable <environment\_variable> not set

Plugin error: An environment variable needed by the plugin was not set.

Action: Set the environment variable <environment\_variable> to an appropriate value.

# Environment variable gtm\_dbkeys set to empty string

Plugin error: The \$gtm\_dbkeys environment variable was set to the empty string.

Recovery Action: Set \$gtm\_dbkeys to point to the master key file.

# Environment variable gtm\_dbkeys undefined. Cannot find <path>/.gtm\_dbkeys

Plugin error: The plugin was unable to locate the master key file.

Action: Place the master key file in the users home directory or point the gtm\_dbkeys environment variable to the master key file.

# Environment variable gtm\_passwd set to empty string. Password prompting not allowed for utilities

Plugin error: The plugin detected that it needed the obfuscated password but the \$gtm\_passwd environment variable was set to the empty string.

Action: Use maskpass to set \$gtm\_passwd to the obfuscated password prior to invoking MUPIP or DSE, or wrap the utility invocation with a MUMPS process which will prompt for the password and set the obfuscated password.

## Error initializing GpgME: <reason\_for\_error>/<specific\_Gpg\_ME\_error>

Plugin error: libgpgme reported an error to the plugin.

Action: Consult GpgME documentation for the specific error message.

# Error parsing database key file. At line line\_number>: No matching 'dat' entry found in <contents\_of\_line>

Plugin error: The plugin was unable to find a matching "dat" entry for a "key" entry in the master key file.

Action: Verify that each "key" entry has a corresponding "dat" entry.

# Error parsing database key file. At line e\_number>: contents> does not start with 'dat' / 'key'

Plugin error: The plugin detected that the master key file was not properly formatted.

Action: Verify entries in the master key file start with "dat" or "key".

# Error parsing database key file. At line entry found in <contents\_of\_line>

Plugin error: The plugin was not able to find a "key" entry for a "dat" entry.

Action: Verify the database file exists, that the corresponding entry in the master key file points to the database file, that appropriate authorizations exist on the directory path and the database file, and that each "dat" entry has a corresponding "key" entry.

### Incorrect password

Plugin error: The plugin detected that the correct private key password was not supplied.

Action: Provide the correct password.

# libgcrypt version mismatch. Expected <expected\_version>, found <found\_version>

Plugin error: The plugin could not locate an appropriate libgcrypt library version.

Action: Verify the <expected\_version> is installed and in the library search path.

### Matching encryption key <hash> not found in database key file

Plugin error: The plugin was not able to find a needed database file key.

Action: Add an entry for this encryption key. If needed, use DSE DUMP -FILE -ALL on all of the database files to find the database file that matches the <hash>. With extracts and backups, multiple database files may have contributed encrypted records.

### No entries found in DB keys file

Plugin error: The plugin was unable to find any entries in the master key file.

Action: Add entries to the master key file.

### Symmetric key <path> found to be empty

Plugin error: The plugin was unable to find a valid encrypted key in the specified file.

Action: Create a valid key file.