


# Detectors


PSI Lab Course 2014  
Dirk Wiedner

# Individual Detector Types

- Modern detectors consist of many different pieces of equipment to measure different aspects of an event.
- Measuring a particle's properties:
  - Position
  - Momentum
  - Energy
  - Charge
  - Type




# Particle Decay Signatures




- Particles are detected via their interaction with matter.
- Many types of interactions are involved,
  - mainly electromagnetic.
- In the end, always rely on ionization and excitation of matter.

# Particle Decay Signatures in CMS



# Particle Decay Signatures in CMS



# Energy loss by Ionization

• • •

# Bethe-Bloch formula

- Ionization main electromagnetic energy loss for charged particles.
  - Except when the projectile is highly relativistic
- The mean energy loss due to ionization given by the **Bethe-Bloch** formula:

$$-\left\langle \frac{dE}{dx} \right\rangle = K z^2 \frac{Z}{A} \frac{1}{\beta^2} \left[ \frac{1}{2} \ln \frac{2m_e c^2 \beta^2 \gamma^2 T_{\max}}{I^2} - \beta^2 - \frac{\delta(\beta\gamma)}{2} \right]$$

[ $\cdot \rho$ ]

# Bethe-Bloch formula

- Ionization main electromagnetic energy loss for charged particles.
  - Except when the projectile is highly relativistic
- The mean energy loss due to ionization given by the **Bethe-Bloch** formula:

$$-\left\langle \frac{dE}{dx} \right\rangle = K z^2 \frac{Z}{A} \frac{1}{\beta^2} \left[ \frac{1}{2} \ln \frac{2m_e c^2 \beta^2 \gamma^2 T_{\max}}{I^2} - \beta^2 - \frac{\delta(\beta\gamma)}{2} \right]$$

[· ρ]

density

$$K = 4\pi N_A r_e^2 m_e c^2 = 0.307 \text{ MeV g}^{-1} \text{ cm}^2$$

$$N_A = 6.022 \cdot 10^{23}$$

[Avogardo's number]

$$T_{\max} = 2m_e c^2 \beta^2 \gamma^2 / (1 + 2\gamma m_e/M + (m_e/M)^2)$$

$$r_e = e^2 / 4\pi \epsilon_0 m_e c^2 = 2.8 \text{ fm}$$

[Max. energy transfer in single collision]

[Classical electron radius]

$z$  : Charge of incident particle

$$m_e = 511 \text{ keV}$$

[Electron mass]

$M$  : Mass of incident particle

$$\beta = v/c$$

[Velocity]

$Z$  : Charge number of medium

$$\gamma = (1 - \beta^2)^{-1/2}$$

$A$  : Atomic mass of medium

[Lorentz factor]

$I$  : Mean excitation energy of medium


Validity:

$\delta$  : Density correction [transv. extension of electric field]

$$0.05 < \beta\gamma < 500$$

$$M > m_\mu$$

# Energy loss of $\pi$ in Cu



Minimum ionizing particles (MIP):  $\beta\gamma = 3-4$

$dE/dx$  falls  $\sim \beta^{-2}$ ; kinematic factor  
[precise dependence:  $\sim \beta^{-5/3}$ ]

$dE/dx$  rises  $\sim \ln(\beta\gamma)^2$ ; relativistic rise  
[rel. extension of transversal E-field]

Saturation at large ( $\beta\gamma$ ) due to  
density effect (correction  $\delta$ )  
[polarization of medium]

# Energy loss of Pi in Cu

1/ $\beta^2$ -dependence:




Remember:

$$\Delta p_{\perp} = \int F_{\perp} dt = \int F_{\perp} \frac{dx}{v}$$

i.e. slower particles feel electric force of atomic electron for longer time ...

Relativistic rise for  $\beta\gamma > 4$ :

High energy particle: transversal electric field increases due to Lorentz transform;  $E_y \rightarrow \gamma E_y$ . Thus interaction cross section increases ...




Corrections:

- low energy : shell corrections
- high energy : density corrections

# $dE/dx$ and Particle Identification

- Measurements of energy loss to identify particles
  - when giving enough care to calibration problems
- simultaneous measurement of momentum required



# Calorimetry

• • •


# Introduction

- Energy of a particle measured destructively
- Particle must be completely stopped in detectors to measure its full energy

# Introduction


- Energy of a particle measured destructively
- Particle must be completely stopped in detectors to measure its full energy
- Energy is deposited in a localized space
  - position can be determined with accuracy dependent on:
  - transverse energy fluctuations
  - detector design.
- Accuracy of energy measurement:
  - Constant term: Uniformity of the detector medium
  - Stochastic term: Active sampling wrt total detector volume
- Calorimetry can provide momentum of a particle
  - redundantly to the inner tracking measurements
  - useful in cleaning up backgrounds.

# Shower in cloud chamber



# Electron and $\gamma$ Interactions

- At  $E > 10 \text{ MeV}$ , interactions of  $\gamma$ s and  $e^-s$  in matter dominated by:
  - $e^+e^-$  pair production and
  - Bremsstrahlung
- At lower energies, ionization becomes important.
- The ratio of the energy loss for these processes is:



$$R = \left( \frac{dE}{dx} \right)_{Brems} / \left( \frac{dE}{dx} \right)_{Ion}$$
$$\approx \frac{ZE}{580 \text{ MeV}}$$


## Critical Energy:

When energy loss due to Bremsst. and energy loss due to ionization are equal.

$$E_c \approx \frac{610 \text{ MeV}}{Z + 1.24}$$

# Electron energy loss and critical energy

relative energy loss for electrons






$$E_c = 7 \text{ MeV in Pb}$$

- Critical energy loss due to
  - Bremsstrahlung and
  - ionization are equal to
- High Z material gives more signal: shower stop later

$$E_c \approx \frac{610 \text{ MeV}}{Z + 1.24}$$

# Photon interactions in matter

(A, Z)




photo




Rayleigh




Compton



Pair




Pair



Pair production  
 $\gamma Z \rightarrow e^+ e^-$  dominates above  $\sim 4 \text{ MeV}$


# Electromagnetic Showers



- Radiation Length  $X_0$ :
  - Scaling variable for the probability of occurrence of bremsstrahlung pair production
  - and for the variance of the angle of multiple scattering.
- Average energy loss due to bremsstrahlung for an electron of energy  $E$  is related to the radiation length:

$$(dE/dx)_{\text{brems}} = E/X_0$$

# Electromagnetic Showers




- Radiation Length  $X_0$ :
  - Scaling variable for the probability of occurrence of bremsstrahlung pair production
  - and for the variance of the angle of multiple scattering.
- Average energy loss due to bremsstrahlung for an electron of energy  $E$  is related to the radiation length:

$$(dE/dx)_{\text{brems}} = E/X_0$$


# Simple Shower Model

- Start with a **high energy electron**:  $E_0$
- After  $1 X_0$ :  $1 e^-$  and  $1 \gamma$  each with  $E_0/2$
- After  $2 X_0$ :  $2 e^-$ ,  $1 e^+$  and  $1 \gamma$  each with  $E_0/4$
- After  $k X_0$ : total  **$N=2^k$** , each with  $\langle E \rangle = E_0/2^k$
- At  $\langle E \rangle = E_c$  pair production and bremsstrahlung stop
- Compton- or photo-effect and ionization take over.
- The shower ranges out.
- $k_{\max} = \lg_2(E_0/E_c) \rightarrow$  Shower depth grows logarithmically with  $E_0$
- $N_{\max} = 2^{k_{\max}} = E_0/E_c \rightarrow$  Number of shower particles grows linearly with  $E_0$ .



# Simple Shower Model

- Start with a **high energy electron**:  $E_0$
- After  $1 X_0$ :  $1 e^-$  and  $1 \gamma$  each with  $E_0/2$
- After  $2 X_0$ :  $2 e^-$ ,  $1 e^+$  and  $1 \gamma$  each with  $E_0/4$
- After  $k X_0$ : total  **$N=2^k$** , each with  $\langle E \rangle = E_0/2^k$
- At  $\langle E \rangle = E_c$  pair production and bremsstrahlung stop
- Compton- or photo-effect and ionization take over.
- The shower ranges out.
- $k_{\max} = \lg_2(E_0/E_c) \rightarrow$  Shower depth grows logarithmically with  $E_0$
- $N_{\max} = 2k_{\max} = E_0/E_c \rightarrow$  Number of shower particles grows linearly with  $E_0$ .



# Energy Measurement


- Total number of particle in the shower in the simple model:  
$$\Rightarrow N_{\text{tot}} = \sum_k 2^k = 2^{2^{\text{kmax}} - 1} \simeq 2 E_0 / E_c$$
- $2/3$  of  $N_{\text{tot}}$  are charged ( $e^+ + e^-$ ),  $\Rightarrow N_{\text{ch}} = 4/3 E_0 / E_c$
- Each  $e$  travels  $1 X_0$  between interactions  
$$\Rightarrow$$
 total path length  $L_{\text{ch}} \simeq 4/3 X_0 E_0 / E_c$
- Electrons and positrons also ionize the medium, collect charge or fluorescence light.  
$$\Rightarrow$$
 The measured signal  $S \sim X_0 E_0 / E_c$
- After calibration,  $S$  is an energy measurement!
- Shower fluctuations: particle production is a Poisson process:  
$$\Rightarrow \sigma(N) = \sqrt{N}$$
- $\Rightarrow \sigma(S) / S = 1 / \sqrt{S}$
- The relative energy resolution improves as  $1/\sqrt{E_0}$

# Energy Measurement

- Total number of particle in the shower in the simple model:  
$$\Rightarrow N_{\text{tot}} = \sum_k 2^k = 2^{2^{\text{kmax}} - 1} \simeq 2 E_0 / E_c$$
- $2/3$  of  $N_{\text{tot}}$  are charged ( $e^+ + e^-$ ),  $\Rightarrow N_{\text{ch}} = 4/3 E_0 / E_c$
- Each  $e$  travels  $1 X_0$  between interactions  
$$\Rightarrow \text{total path length } L_{\text{ch}} \simeq 4/3 X_0 E_0 / E_c$$
- Electrons and positrons also ionize the medium, collect charge or fluorescence light.  
$$\Rightarrow \text{The measured signal } S \sim X_0 E_0 / E_c$$
- After calibration,  $S$  is an energy measurement!
- Shower fluctuations: particle production is a Poisson process:  
$$\Rightarrow \sigma(N) = \sqrt{N}$$
- $\Rightarrow \sigma(S) / S = 1 / \sqrt{S}$
- The relative energy resolution improves as  $1/\sqrt{E_0}$

# A sophisticated shower simulation

energy profile




# Electromagnetic Calorimeter Types

- Homogeneous “shower counters”:
  - Best performance from unorganic scintillating crystals.
  - Also use lead glass, detects Cerenkov light of electrons, limited by photoelectrons statistics.
- Sampling calorimeters:
  - Layers of inactive absorber (such as Pb) alternating with active detector layers, such as scintillator or liquid. Resolutions  $\sim 7\%/\sqrt{E}$  or so.
- Liquid noble gases:
  - Counters based on liquid noble gases (with lead plates, for example) can act as ionization chambers. LAr - Pb versions obtain  $\sim 10\%/\sqrt{E}$ . Ionization read out by electrodes attached to plates (no PMTs!).
  - Disadvantage: slow collection times ( $\sim 1 \mu\text{s}$ ).

# Electromagnetic Calorimeter Types

- “Lead-scintillator sandwich” calorimeter      Energy resolutions:



$$\Delta E/E \sim 20\%/\sqrt{E}$$


- Exotic crystals (BGO, PbW, ...)       $\Delta E/E \sim 1\%/\sqrt{E}$



- Liquid argon calorimeter       $\Delta E/E \sim 18\%/\sqrt{E}$


# CMS PbWO Crystals

Charged particles  
create scintillation  
light: ~120 /MeV  
fast: 95% < 25 ns.




# CMS ECAL

- CMS  
 $\text{PbWO}_4$   
crystal calorimeter




$\phi = 85^\circ$



- Barrel: 62k crystals  $2.2 \times 2.2 \times 23 \text{ cm}$
- End-caps: 15k crystals  $3 \times 3 \times 22 \text{ cm}$


# Energy Resolution

- Look at Detector Response for given energy  $E_0$ .
- For interaction following Poisson statistics
  - Detector Response for many interactions become Gaussian.
- Fit Response with Gaussian and look at  $\sigma$  (Resolution).




# Test beam calibration

Response of a PbWO<sub>4</sub> calo to a 120 GeV e<sup>-</sup> test beam:




# CMS ECAL Test beam with final electronics.

Energy



Position



$$\frac{\sigma(E)}{E} = \frac{2.4 \%}{\sqrt{E}} \oplus \frac{142 \text{ MeV}}{E} \oplus 0.44 \%$$


**0.6% at 50 GeV.**

$$\sigma_Y (\mu\text{m}) = \frac{5040}{\sqrt{E}} + 430$$

**0.85 mm at 50 GeV.**

# Energy resolution terms

- The intrinsic shower fluctuations give  $\sigma(E) \sim \sqrt{E}$
- Fluctuations in the photo-electron yield also give  $\sigma(E) \sim \sqrt{E}$
- Noise (electronics, radiation) gives a constant term:  $\sigma(E) = c$
- Inhomogeneities and leakage give  $\sigma(E) \sim E$




$$\frac{\sigma(E)}{E} = \frac{2.4\%}{\sqrt{E}} \oplus \frac{142 \text{ MeV}}{E} \oplus 0.44\%$$

# Hadron Calorimeters

- Strongly interacting particle  $> 5 \text{ GeV}$  enters matter
  - inelastic and
  - elastic scattering between particles and nucleons occur.
- Cascade ceases when hadron energies small enough to
  - stop by ionization energy loss
  - or nuclear absorption.
- Hadronic Shower:
  - Spatial scale for shower development given by nuclear absorption length  $\lambda N$ .
  - Mean free path of a particle before undergoing a non-elastic interaction in a given medium.
- Compare  $X_0$  for high-Z materials
- hadron calorimeters large compared to EM calorimeters.

Material	$X_0$ (g/cm <sup>2</sup> )	$\lambda$ (g/cm <sup>2</sup> )
H <sub>2</sub>	63	52.4
Al	24	106
Fe	13.8	132
Pb	6.3	193

# Hadronic showers




- Hadronic interaction have high multiplicity:
- Shower 95% contained in  $\sim 7\lambda$  at 50 GeV (1.2m of iron)
- Hadronic interactions produce  $\pi^0$ :
  - $\pi^0 \rightarrow \gamma\gamma$ , leading to local EM showers ('hot spots', ~30%)
- Some energy lost in nuclear breakup and neutrons
  - 'invisible energy', 15-35%
- Stronger fluctuations in a hadronic shower:
  - Worse energy resolution

# Hadronic showers

Schritt I

Internukleare Kaskade




Schritt II


Hochangeregte Kerne

Verdampfung


$10^{-18} \text{ s}$




Spaltung gefolgt von  
Verdampfung



# Electromagnetic & Hadronic showers



# Electromagnetic & Hadronic showers




# Hadronic showers

Tracker

EM cal

Hadronic calorimeter

Muon tracker



Hadronic showers may already start in the ECAL and extend into the HCAL.


# Hadronic interaction length

- Pion-proton cross section  $\sigma(\pi p) \approx 25 \text{ mbarn}$  above a few GeV.
- $\sigma(\pi A) \approx \sigma(\pi p) A^{2/3}$  (black disk limit).
- hadronic interaction length:


$$\lambda_I = \frac{A}{\sigma N_A \rho} = \frac{35 \text{ cm}}{\rho} A^{1/3}$$

- $\lambda_I = 17 \text{ cm}$  in Fe or Pb.
- Much larger than  $X_0$ .

# 2 hadronic showers



blue = hadronic component




red = electromagnetic component

A good hadron calorimeter should have

- equal response to hadrons and electrons ('hardware compensation')
- or high granularity to isolate the hot spots ('software compensation')

# Hadron shower transverse



- Transverse shower development:
  - Secondaries have significant transverse momenta
  - They produce a wide shower
    - compared with EM showers
  - Part of the shower gets an electromagnetic nature
    - i.e. The decay of the  $\pi^0$  produced in the interaction
    - remains inside a narrow cylinder:
    - two times the Moliere radius

T.S.Virdee, Proc. of the 1998 European School of High-Energy Physics, CERN 99-04

# Compensating Calorimeters

- Improvements in energy resolution can be achieved if
  - showers induced by electrons and hadrons of same energy
    - produce same visible energy (detector response).
- Requires the losses to be “compensated”
- Three methods:
  - Energy lost by nuclear reactions made up for by fission of  $^{238}\text{U}$
  - liberating n and soft  $\gamma$ -rays
  - response close to equal:
  - proton-rich detector → em shower decreases
  - hadron shower increases due to more nuclear reactions
- If have lots of  $\text{H}_2$ :
  - compensation achieved with high absorber material:
  - in inelastic collision of hadrons w/ absorber nuclei,
  - neutrons are produced → recoil protons, larger signal.
- Reduce fluctuation in EM component:
  - weight individual counter responses
  - even response out across the board

# Sampling calorimeter


Absorber and detector are separated as passive and active layers.

**Absorber:**

Lead,  
Tungsten,  
Uranium

**Detector:**



MWPC,  
scintillator,  
silicon pads,  
noble liquid



- The active detector material **samples** a fraction  $F$  of the shower.
- The detector signal is proportional to the incident energy.
- Allows longitudinal segmentation
- Good for hadrons
- Energy resolution is degraded  $\sim 1/\sqrt{F}$  ('sampling fluctuations').
- Less expensive.


# Sampling Calorimeters

Scintillators as active layer;  
signal readout via photo multipliers




Possible setups



Scintillators as active layer; wave length shifter  
to convert light



Ionization chambers  
between absorber  
plates



# ATLAS LAr ECAL




3 sections:


- strips for position resolution
- middle for energy measurement
- back for leakage control

- Pb absorber in LAr
- Accordion geometry for routing of readout signals to the back
- Allows dense packing and fine granularity.

# ATLAS LAr ECAL



- Cu electrodes at +HV
- Spacers define LAr gap  
 $2 \times 2 \text{ mm}$
- 2 mm Pb absorber  
clad in stainless steel.




# Scintillators:


- A scintillator is a material which exhibits the property of luminescence when excited by ionizing radiation.
- Luminescent materials, when struck by an incoming particle, absorb its energy and scintillate, i.e. re-emit the absorbed energy in the form of a small flash of light, typically in the visible range.

# Scintillators General Characteristics


- Principle:
  - $dE/dx$  converted to visible light
  - Light detection via photo-sensors
- Main features:
  - Sensitivity to energy of particle
  - Fast response
  - Pulse Shape discrimination
- Requirements:
  - High efficiency for the conversion of exciting energy to fluorescent radiation
  - Transparency to its fluorescent radiation to allow light transmission
  - Emission of light in a detectable spectral range
  - Short decay time to allow fast response



# Scintillators - Basic Setup



- Photo-sensors
  - Photomultiplier
  - Avalanche Photodiodes
  - ...
- Scintillator Types
  - Organic Scintillators
  - Inorganic Scintillators
  - Noble Gases




# Inorganic Crystals

- Material


- Sodium iodide (NaI)
- Cesium iodide (CsI)
- BGO
- ...

- Mechanism

- Energy deposition by ionization
- Energy transfer to impurities
- Radiation of scintillation photons





Energy bands in  
impurity activated crystal




# Inorganic Crystals - Light Output

Scintillation Spectrum  
for NaI and CsI




Strong  
Temperature Dependence  
[in contrast to organic scintillators]

# Inorganic Crystals - Light Output




# Organic Scintillators

- Aromatic hydrocarbon compounds:
  - Naphthalene ( $C_{10}H_8$ )
  - Antracene ( $C_{14}H_{10}$ )
  - Stilbene ( $C_{14}H_{12}$ )
- ...
- Very fast decay time
- Scintillation light arises from delocalized electrons in  $\pi$ -orbitals



Scintillation is based on electrons of the  $C=C$  bond ...



# Scintillators Comparison

## Inorganic Scintillators


- Advantages:
  - high light yield
  - high density
  - good energy resolution
- Disadvantages:
  - complicated crystal growth
  - large temperature dependence
  - Expensive

## Organic Scintillators




- Advantages:
  - very fast
  - easily shaped
  - small temperature dependence
- Disadvantages:
  - Lower light yield
  - radiation damage
  - Cheap

# Transport of Optical Photons


- Unavoidable or desirable to have the photo-detector remote from the scintillator:
  - Space limitations
  - Photo detector out of the magnetic field
  - Couple a large scintillator surface (volume) to a single photo-detector
  - ...
- Use optical wave guides:
  - Total internal reflection



# Transport of Optical Photons




# CMS Hcal read out



- Scintillators coupled to readout fibers.
- Bundles of fibers coupled to an avalanche photodiode







# Time Constants




# $\gamma$ , e separation based on time constant

- e interacts in plastic sc.
- $\gamma$  interacts in BGO
  - Decay times BGO  $\sim 300\text{ns}$
  - plastic sc  $\sim 10\text{ns}$
- use different integration times!




# $\gamma$ , e separation based on time constant


- scatter plot of  $^{22}\text{Na}$  decay spectrum
- no short signal for  $\gamma$



- $^{22}\text{Na}$  decay spectrum




- only BGO, no fast signal



# Wavelength Shifting



Principle:

- converts the short wavelength light ( $\lambda < 400\text{nm}$ ) emitted by scintillation or Cherenkov radiation
- into a longer wavelength (blue light,  $\lambda > 400\text{nm}$ )
- Adapt light to spectral sensitivity of photosensor




# BGO

- Best suited for gamma detection (high Z)
- High density
- Temperature dependence!!!





# Scintillation Detector

- Couple scintillator to an electronic light sensor



# Energy Measurement with BGO

$$E_{\gamma, \text{pos.}} = ?$$




- BGO:  $\text{Bi}_4\text{Ge}_3\text{O}_{12}$
- Luminescence: Optical transition of  $\text{Bi}^{3+}$  ion
- $n(t)$ : #exited  $\text{Bi}^{3+}$  ions per  $dt$
- ==>  $N = \int_0^\infty n(t) dt \approx \int_0^{t_{\text{gate}}} n(t) dt = N_{\text{measured}}$        $N_{\text{meas.}} \sim 4 \text{photons/keV (BGO)}$
- ==>  $E_{\gamma, \text{pos.}} = N \alpha E_{\gamma, \text{Bi}^{3+}}$

# Light Detectors

...

# Photomultiplier Tube (PM)

- Light falls on a **photo-cathode**
- Photo-electron is emitted
  - **Photo effect**
  - Quantum Efficiency depends on
    - Cathode material and
    - Wavelength (QE ~ 25%)
- Photo-electron focused and accelerated towards the first **dynode** by electric field
- Photo-electron strikes dynode
  - Several electrons are emitted
- Several dynodes (10-15) give **high gain**  $10^7$
- **High speed:** few ns transmit time
- Gain much lower in magnetic field





Source: Cutnell and Johnson, 7th edition image gallery

# PM Response

peaks: single photo electrons



- Integrated PM response of 2 PM with different dynode multiplication factors:

$$\delta = \frac{\text{number of secondary electrons emitted}}{\text{number of primary incident electrons}}$$




# Avalanche Photodiode (APD)

- 85% quantum efficiency
- Photoelectrons create cascade of electron-hole pairs in the bulk.
- Gain ~100 in linear mode
- Low sensitivity to magnetic field.
- APD gain decreases by 2.3%/°C .
  - Need temperature stabilization within 0.1°C in ECAL!



# Vacuum photo-triodes

- ~20% quantum efficiency
- Single stage photomultiplier
- Gain  $\sim 10$  at  $B=4T$



radiation resistant UV glass  
window used in CMS ECAL

# Time of Flight



Basic idea:

Measure signal time difference between  
two detectors with good time resolution  
[start and stop counter; also: beam-timing & stop counter]

Typical detectors:

Scintillation counter  
Resistive Plate Chamber (RPC)

Coincidence setup or TDC measurement  
with common start/stop from interaction time



# Time of Flight

Distinguishing particles with ToF:  
 [particles have same momentum p]

$$\begin{aligned}\Delta t &= L \left( \frac{1}{v_1} - \frac{1}{v_2} \right) = \frac{L}{c} \left( \frac{1}{\beta_1} - \frac{1}{\beta_2} \right) \\ &= \frac{L}{pc^2} (E_1 - E_2) = \frac{L}{pc^2} \left( \sqrt{p^2 c^2 + m_1^2 c^4} - \sqrt{p^2 c^2 + m_2^2 c^4} \right)\end{aligned}$$

Relativistic particles,  $E \simeq pc \gg m_i c^2$ :

$$\Delta t \approx \frac{L}{pc^2} \left[ \left( pc + \frac{m_1^2 c^4}{2pc} \right) - \left( pc + \frac{m_2^2 c^4}{2pc} \right) \right]$$

$$\Delta t = \frac{Lc}{2p^2} (m_1^2 - m_2^2)$$

Example:

Pion/Kaon separation ...  
 $[m_K \approx 500 \text{ MeV}, m_\pi \approx 140 \text{ MeV}]$

Assume:

$p = 1 \text{ GeV}$ ,  $L = 2 \text{ m}$  ...

Particle 1 : velocity  $v_1, \beta_1$ ; mass  $m_1$ , energy  $E_1$   
 Particle 2 : velocity  $v_2, \beta_2$ ; mass  $m_2$ , energy  $E_2$   
 Distance L : distance between ToF counters

For  $L = 2 \text{ m}$ :


Requiring  $\Delta t \gtrsim 4\sigma_t$  K/π separation possible  
 up to  $p = 1 \text{ GeV}$  if  $\sigma_t \approx 200 \text{ ps}$  ...

Cherenkov counter, RPC :  $\sigma_t \approx 40 \text{ ps}$  ...  
 Scintillator counter :  $\sigma_t \approx 80 \text{ ps}$  ...

$$\begin{aligned}\rightarrow \Delta t &\approx \frac{2 \text{ m} \cdot c}{2 (1000)^2 \text{ MeV}^2/c^2} (500^2 - 140^2) \text{ MeV}^2/c^4 \\ &\approx 800 \text{ ps}\end{aligned}$$

# Time of Flight

Difference in  
time-of-flight in  $\sigma_t$  ...  
 $[L = 2 \text{ m}]$



# Time of Flight

Mass resolution ...

$$p = \beta \gamma m$$

Use:  $\beta = L/\tau$

$$\gamma = (1 - \beta^2)^{-1}$$

$[c = 1]$

$$\rightarrow \delta(m^2) = 2p \delta p \underbrace{\left( \frac{\tau^2}{L^2} - 1 \right)}_{m^2/p^2} + 2\tau \delta \tau \underbrace{\frac{p^2}{L^2}}_{\text{use } *} - 2 \frac{\delta L}{L^3} p^2 \tau^2$$

$$= 2m^2 \frac{\delta p}{p} + 2E^2 \frac{\delta \tau}{\tau} - 2E^2 \frac{\delta L}{L}$$

$${}^* \frac{p^2 \tau^2}{L^2} = m^2 + p^2 = E^2$$

$$\rightarrow \sigma(m^2) = 2 \left[ m^4 \left( \frac{\sigma_p}{p} \right)^2 + E^4 \left( \frac{\sigma_\tau}{\tau} \right)^2 + E^4 \left( \frac{\sigma_L}{L} \right)^2 \right]^{1/2}$$

Usually:

$$\frac{\delta L}{L} \ll \frac{\delta p}{p} \ll \frac{\delta \tau}{\tau} \quad \rightarrow \quad \sigma(m^2) = 2E^2 \frac{\sigma_\tau}{\tau}$$

Uncertainty in time  
measurement dominates ...

# Some Literature

- **Web:**
  - The Particle Detector BriefBook:  
<http://rkb.home.cern.ch/rkb/PH14pp/node1.html>
  - (there is also a Data Analysis BriefBook)
  - <http://pdg.lbl.gov/> --> Summary and Reviews
- **Lectures:**
  - <http://wwwhephy.oeaw.ac.at/p3w/halbleiter/VOTeilchendetektoren.html>
  - <http://www.kip.uni-heidelberg.de/~coulon/Lectures/Detectors/>
  - <http://www.desy.de/~blist/vl-detektor-ws07/>
  - [www.physics.ucdavis.edu/Classes/Physics252b/Lectures/252b\\_lectureXX.ppt](http://www.physics.ucdavis.edu/Classes/Physics252b/Lectures/252b_lectureXX.ppt) XX = 1,2,3,4
- **Script:**
  - <http://www.physik.tu-dortmund.de/E5/E5-alt-alt/index.php?content=25&lang=de>


# More Literature

- **Text books:**
  - C.Grupen: Particle Detectors, Cambridge UP 22008, 680p
  - D.Green: The physics of particle Detectors, Cambridge UP 2000
  - K.Kleinknecht: Detectors for particle radiation, Cambridge UP, 21998
  - W.R. Leo: Techniques for Nuclear and Particle Physics Experiments, Springer 1994
  - G.F.Knoll: Radiation Detection and Measurement, Wiley, 32000
  - W.Blum, L.Rolandi: Particle Detection with Driftchambers, Springer, 1994
  - G.Lutz: Semiconductor radiation detectors, Springer, 1999
  - R. Wigmans: Calorimetry, Oxford Science Publications, 2000
- **Review articles:**
  - T.Ferbel (ed): Experimental Techniques in High Energy Physics, Addison-Wesley 1987
- **Web:**
  - Particle Data Group: Review of Particle Properties: pdg.lbl.gov

# Backup Slides


...

# The Standard Model




- The SM:
  - world is made up of **quarks** and **leptons**
  - interacting by exchanging **bosons**
    - only photons directly visible
- How do we see without seeing?
- What makes Particle Detection possible?


# Particle Reactions



- Idealistic View:
    - Elementary Particle Reaction
  - Usually cannot “see” the reaction itself
  - To reconstruct the
    - **process** and the
    - **particle properties**
- need **maximum information** about **end-products**



# Principle of an Elementary Particle Measurement



- Need good:
  - Detectors
  - Triggers,
  - Readout


➤ to reconstruct the mess.
- Need good:
  - Analyzers

➤ to put the raw data into a piece of physics.

# Example of two Reactions


Tracks in a Bubble Chamber

(Bubble chambers are not used any more).



Simulated Super LHC event.

(People started to think about a LHC upgrade).




The decay products of elementary particle reactions can look very complicated!

# Global Detector Systems


- Overall design depends on:
    - Number of particles
    - Event topology
    - Momentum/energy
    - Particle identity
- } {
- No single detector measures it all...
  - Create detector systems

# Global Detector Systems

Fixed Target Geometry




Collider Geometry



- Limited solid angle  $d\Omega$  coverage
- Easy access (cables, maintenance)

- Full" solid angle  $d\Omega$  coverage
- Very restricted access

# Ideal Detectors




## End products:

- charged particles
- neutral particles
- photons

- An “ideal” particle detector would provide...
  - Coverage of **full solid angle**, no cracks, fine segmentation (why?)
  - Measurement of momentum and energy
  - Detection, tracking, and identification of all particles (mass, charge, lifetime)
  - Fast response: no dead time (what is dead time?)
  - Contain no dead material (what is dead material?)
- However, practical limitations:
  - Technology, Space, Budget

# Ideal Detectors




## End products:

- charged particles
- neutral particles
- photons

- An “ideal” particle detector would provide...
  - Coverage of full solid angle, no cracks, fine segmentation (why?)
  - Measurement of **momentum** and **energy**
  - Detection, tracking, and identification of all particles (mass, charge, lifetime)
  - Fast response: no dead time (what is dead time?)
  - Contain no dead material (what is dead material?)
- However, practical limitations:
  - Technology, Space, Budget

# Ideal Detectors




## End products:

- charged particles
- neutral particles
- photons

- An “ideal” particle detector would provide...
  - Coverage of full solid angle, no cracks, fine segmentation (why?)
  - Measurement of momentum and energy
  - **Detection, tracking, and identification** of all particles (mass, charge, lifetime)
  - Fast response: no dead time (what is dead time?)
  - Contain no dead material (what is dead material?)
- However, practical limitations:
  - Technology, Space, Budget

# Ideal Detectors




## End products:

- charged particles
- neutral particles
- photons

- An “ideal” particle detector would provide...
  - Coverage of full solid angle, no cracks, fine segmentation (why?)
  - Measurement of momentum and energy
  - Detection, tracking, and identification of all particles (mass, charge, lifetime)
  - **Fast** response: no dead time (what is dead time?)
  - Contain no dead material (what is dead material?)
- However, practical limitations:
  - Technology, Space, Budget

# Ideal Detectors




## End products:

- charged particles
- neutral particles
- photons

- An “ideal” particle detector would provide...
  - Coverage of full solid angle, no cracks, fine segmentation (why?)
  - Measurement of momentum and energy
  - Detection, tracking, and identification of all particles (mass, charge, lifetime)
  - Fast response: no dead time (what is dead time?)
  - Contain **no dead material** (what is dead material?)
- However, practical limitations:
  - Technology, Space, Budget

# Ideal Detectors




## End products:


- charged particles
- neutral particles
- photons

- An “ideal” particle detector would provide...
  - Coverage of full solid angle, no cracks, fine segmentation (why?)
  - Measurement of momentum and energy
  - Detection, tracking, and identification of all particles (mass, charge, lifetime)
  - Fast response: no dead time (what is dead time?)
  - Contain no dead material (what is dead material?)
- However, practical limitations:
  - **Technology, Space, Budget**

# Particle Decay Signatures in Atlas




# Particle Decay Signatures in Atlas



# Particle Identification Methods


Constituante	Vertex	Track	PID	Ecal	Hcal	Muon
Electron	Primary	✓	✓	✓	-	-
Photon	Primary	-	-	✓	-	-
u, d, gluon	Primary	✓	-	✓	✓	-
Neutrino	-	-	-	-	-	-
s	Primary	✓	✓	✓	✓	-
c, b, tau	Secondary	✓	✓	✓	✓	-
Muon	Primary	✓	-	MIP	MIP	✓

- PID = Particle ID (TOF, dE/dx)
- MIP = Minimum Ionizing Particle






# Particle Detection Methods

Signature	Detector Type	Particle
Jet of hadrons	Calorimeter, Tracking	$u, c, t \rightarrow W b, d, s, b, g$
Missing energy	Calorimeter	$\nu_e, \nu_\mu, \nu_\tau$
Electromagnetic shower	EM Calorimeter	$e, \gamma$
Purely ionization interactions, $dE/dx$	Muon absorber	$M, \tau \rightarrow \mu \nu_\mu \nu_\tau$
Life time, $c\tau \geq 100 \mu\text{m}$	Si-Tracking	$b, c, \tau$







# Quiz: Decays of a Z boson

- Z bosons have a very short lifetime, decaying in  $\sim 10^{-27}$  s, so that:
  - only decay particles are seen in the detector.
  - By looking at these detector signatures, identify the daughters of the Z boson.





But some daughters can also decay:



- More fun with Z bosons: <http://opal.web.cern.ch/Opal/events/opalpics.html>

# Principles of a measurement


- The particle must **interact** with the detector material:
  - **transfer** directly or indirectly **energy** to the medium they are traversing
  - via **ionization** or **excitation** of its constituent atoms.
- An effect of the interaction must be measured:
  - Ionization:A diagram showing a blue dot representing a particle entering a circular detector from the left. Inside the detector, there is a pink circle representing an atom. A blue arrow labeled  $e^-$  points outwards from the detector, indicating an ionized electron. A yellow lightning bolt symbol is at the end of the arrow, and a grey rectangular block representing a signal readout is also shown.
  - Excitation and scintillation:A diagram showing a blue dot representing a particle entering a series of three concentric circular detectors from the left. Inside each detector, there is a pink circle representing an atom. A blue arrow labeled  $e^-$  points outwards from the third detector, indicating an ionized electron. A wavy blue line labeled  $\gamma$  represents Cerenkov radiation, which is emitted from the second detector and points towards a yellow lightning bolt symbol. A grey rectangular block representing a signal readout is also shown.
  - Cerenkov radiation
  - Signals from electron-hole pairs (Si-detectors)
- The particle may also be affected by the interaction:
  - energy loss, scattering and absorption

# Measurable Properties of particles

- Production / passage of a particle
- Four-Momentum of particle
- Charge of particle
- Lifetime of particle


# How does one measure the Four-Momentum?

- Energy:
  - with a "calorimeter" (see tomorrow)
- Momentum:
  - with a "magnetic field + track detector"



Lorentz-Force

$$q v_T B = m v_T^2 / R$$



$$q B R = m v_T = p_T$$


# Tracking:

• • •

Proportional Counters  
and Drift Chambers

# Charged Particle Tracking



- Two main types:
  - Gas wire chambers
  - Silicon
- Innermost detectors:
  - precise tracking → use Si-Detectors!
- Outer detectors:
  - silicon too expensive!
  - (not true for LHC-detectors also use silicon).
- Basic design: ionization chamber with HV sense wire:



Amplification of  
 $10^3$  -  $10^5$  in high  
field near wire

# Ionization Wire Chambers

- Wire Chambers:
  - Most commonly used detection devices in high energy physics experiments.
- The Basics of Wire Chambers:
  - Charged particles travel through a gas
  - Gas is ionized by the particle
  - Ionization drifts & diffuses in an electric field toward an electrode
  - Collection and amplification of anode signal charge  
➤ detectable signals
  - Measurement of points on trajectory determines p



# Processes in Gases

- When a charged particle passes through gases subject to an E field, it loses energy by:
  - Elastic scattering (small)
  - Excitation: gas atoms/molecules
  - Excite then de-excite by  $\gamma$  emission
  - Ionization** (most important)
- Ionization:
  - One or more electrons are liberated from atoms of the medium,
  - leaving positive ions and electrons.
  - Energy imparted to atom exceeds ionization potential of gas.





TABLE IX.


Gas.	Ionization Potential.
Argon .....	15.6
Nitrogen.....	15.8
Carbon Monoxide.....	15.0
Hydrogen.....	15.1
Helium.....	20.5
Mercury vapor .....	10.1
Iodine vapor .....	8.5

# Principle of Gas Detectors




- Primary Ionization
- Secondary Ionization (due to  $\delta$ -electrons)

# Number of Ions v. Voltage




Simplest case: Parallel plate capacitor




# Number of Ions v. Voltage

- Ionization chamber:
  - Voltage increased such that the charge arriving on plates =
  - charge formed
- Proportional region:
  - Initial electrons accelerated enough to ionize more;
  - avalanche pulse proportional to primary ionization
  - reaches  $\sim 10^8$



# Proportional Chambers

- Cylindrical proportional tube of
  - outer radius  $b$  at voltage  $V_0$  and
  - inner (wire) of radius  $a$  at voltage zero.
- Electric field inside the chamber:
- $E = \frac{2l}{r}, V_0 = 2l \ln\left(\frac{b}{a}\right), V(r) = V_0 \frac{\ln(r/a)}{\ln(b/a)}, E(r) = \frac{V_0}{r \ln(b/a)}$
- Charged particle ->
  - Ionization.
  - $e^-$  move toward anode
  - High fields near wire
  - Multiplication of  $e^-$ s by collisions:
  - at small  $r$  the energy gain can exceed ionization potential.
  - Runaway process, like avalanche in PMTs.
- Typical Gas gain  $\sim 10^5 - 10^8$ , Geiger region!



# Multi-wire Proportional Chambers

- MWPC invented by Charpak at CERN
  - Principle of proportional counter is extended to large areas:
  - Stack several wire planes up in different direction to get position location.









Photo: CERN, Switzerland


# Multi-wire Proportional Chambers

G. Charpak  
Nobel Prize 1992




Avalanche developing

# Drift Chambers - Field Formation



# Large Area Drift Chambers


- The “open cell” drift chamber uses
  - field and sense wires:
  - field wires create shape of electric field,
  - sense wires detect time of arrival of pulse.
- Position of particle:  $x = x_{\text{wire}} + v_{\text{drift}} t_{\text{drift}}$




# Drift Chamber - Ambiguities

Methods to resolve left-right ambiguities ...


B Inclined anode wires



A Two separate anode wires



C Staggered anode wires



# Drift Chamber - Jade


**MAGNETDETEKTOR JADE**  
MAGNET DETECTOR

1 Strahlrohrzähler BEAM PIPE COUNTERS  
2 Endseitige Bleiglaszähler END PLUG LEAD GLASS COUNTERS  
3 Drucktank PRESSURE TANK  
4 Myon-Kammern MUON CHAMBERS  
5 Jet-Kammern JET CHAMBERS  
6 Flugzeit-Zähler TIME OF FLIGHT COUNTERS  
7 Spule COIL  
8 Zentrale Bleiglaszähler CENTRAL LEAD GLASS COUNTERS  
9 Magnetjoch MAGNET YOKE  
10 Myon-FILTER MUON FILTERS  
11 Beweglicher Endstopfen REMOVABLE END PLUG  
12 Strahlrohr BEAM PIPE  
13 Vorwärts-Detektor TAGGING COUNTER  
14 Mini-Beta Quadrupol MINI BETA QUADROPOLE  
15 Fahrwerk MOVING DEVICES

Gesamtgewicht TOTAL WEIGHT: ~1200 t  
Magnetfeld MAGNETIC FIELD: 0.5 T  
Beteiligte Institute PARTICIPANTS  
DESY, Hamburg, Heidelberg,  
Lancaster, Manchester,  
Rutherford Lab., Tokio

First Jet-Chamber


# Drift Chamber - Jade




# Drift Chamber - Jade



# Drift Chamber - Jade




# Segmented Silicon Diode Sensors for Particle Detection




- For charged tracks resolution depend on:
  - segmentation pitch (strips, pixels)
  - charge sharing (angle, B-field, diffusion)
  - S/N performance of readout electronics
  - $\delta$ -rays

# Segmented Silicon Diode Sensors for Particle Detection



- Shared Charge collection on segmented electrodes due to:
  - Diffusion during drift time
  - Lorentz angle due to presence of B-field
  - Tilted tracks
- Individual readout of charge signal on electrodes allows position interpolation that is better than pitch of segmentation.


# Segmented Silicon Diode Sensors for Particle Detection



- Silicon microstrip detectors in HEP:
- Strip pitch =  $50\mu\text{m}$
- Position resolution  $\sim 1.5\mu\text{m}$  achieved


# Charge collection

- Electrons and holes
  - separated in the electric field and
  - collected on the implanted strips:
    - Electrons drift 10 ns
    - Holes drift 25 ns
    - Need high-purity silicon to avoid trapping.



# Charge collection


- Position resolution:
  - 5-30  $\mu\text{m}$
  - for strip pitch of 50-100  $\mu\text{m}$
  - better with pulse-height interpolation
- Silicon detectors are
  - fast and have
  - high resolution
- Further readout electronics required to amplify the charge
  - Need many channels to cover large areas.



# From Strips to Pixels

- very high rate & high multiplicity
  - requires 2 D – segmentation of silicon sensors.
- connection to readout electronic chips !!


Micro strip Detectors  
**LEP, HERA, Tevatron**



**1 D – connection**

**wire-bonding**


→  
 $10^5$  increase  
Pixel Detectors  
**LHC**



**2 D – connection**

**- bump-bonding**  
**- wafer bonding**  
**- 3D integration**

# Hybrid Pixel Detectors




**Particle / X-ray** → **Signal Charge** → **Electr. Amplifier** → **Readout** → **Digital Data**


# CMS Pixel Detector

for the Large Hadron  
Collider

768 pixel modules  
 $\sim 0.75 \text{ m}^2$



# 48Mega Pixel Detector with 40 MHz Frame Rate



# Cherenkov Radiation




A light cone, so called Cherenkov radiation is emitted

- whenever charged particles pass through matter
- with a velocity  $v$  exceeding the velocity of light in the medium.
- Measure angle of light cone  $\rightarrow v$  of particle; Particle ID possible

P. Cherenkov: 1935  
Nobelpreis 1958



airplane passing the sonic wall



Event of Super Kamiokande


See <http://webphysics.davidson.edu/applets/applets.html> for a nice illustration

# Application in Astroparticle Physics

- Detection of high energetic  $\gamma$ 's via Cherenkov light in the atmosphere

Hess telescope


Magic telescope



● Dirk Wiedner



Event Display Magic



● 125