CSC 252: Computer Organization Spring 2019: Lecture 6

Instructor: Yuhao Zhu

Department of Computer Science University of Rochester

Action Items:

Assignment 2 is out

Announcement

- Programming Assignment 2 is out
 - Due on Feb 15, 11:59 PM
 - You may still have 3 slip days...

3	4	5 Today	6	7	8	9
10	11	12	13	14	Due	16

Announcement

- Programming Assignment 2 is out
 - Due on Feb 15, 11:59 PM
 - You may still have 3 slip days...
- Read the instructions before getting started!!!
 - You get 1/4 point off for every wrong answer
 - Maxed out at 10
- No submissions will be accepted through email. If you can't figure out how to submit, ask the TAs.

C Code (sum.c)

C Code (sum.c)

Generated x86-64 Assembly

```
sumstore:
   pushq %rbx
   movq %rdx, %rbx
   call plus
   movq %rax, (%rbx)
   popq %rbx
   ret
```

Generated x86-64 Assembly

```
sumstore:
   pushq %rbx
   movq %rdx, %rbx
   call plus
   movq %rax, (%rbx)
   popq %rbx
   ret
```

Generated x86-64 Assembly

Binary Code for **sumstore**

```
sumstore:
   pushq %rbx
   movq %rdx, %rbx
   call plus
   movq %rax, (%rbx)
   popq %rbx
   ret
```

Memory

0x530x480x890xd30xe8 0xf20xff 0xff 0xff 0×48 0x890x030x5b0xc3

Generated x86-64 Assembly

Binary Code for **sumstore**

sumstore: pushq %rbx movq %rdx, %rbx call plus movq %rax, (%rbx) popq %rbx ret

Address Memory

 0×0400595

0x530x480x890xd30xe8 0xf20xff 0xff 0xff 0×48 0x890x030x5b0xc3

Generated x86-64 Assembly


Binary Code for **sumstore**

```
sumstore:
   pushq %rbx
   movq %rdx, %rbx
   call plus
   movq %rax, (%rbx)
   popq %rbx
   ret
```

- Total of 14 bytes
- Instructions have variable lengths: e.g., 1, 3, or 5 bytes
- Code starts at memory address 0x0400595


Memory Address 0×0400595 0x530x480x890xd30xe8 0xf20xff 0xff 0xff 0x480x890x030x5b0xc3

Assembly
Programmer's
Perspective
of a Computer




Fetch Instruction (According to PC)

Assembly
Programmer's
Perspective
of a Computer



Fetch Instruction (According to PC)


0x4801d8




```
Fetch Instruction (According to PC)


Decode Instruction


addq %rax, (%rbx)
```








































- Compute Instruction: Perform arithmetics on register or memory data
 - addq %eax, %ebx
 - C constructs: +, -, >>, etc.



- Compute Instruction: Perform arithmetics on register or memory data
 - addq %eax, %ebx
 - C constructs: +, -, >>, etc.
- Data Movement Instruction: Transfer data between memory and register
 - movq %eax, (%ebx)




- Compute Instruction: Perform arithmetics on register or memory data
 - addq %eax, %ebx
 - C constructs: +, -, >>, etc.
- Data Movement Instruction: Transfer data between memory and register
 - movq %eax, (%ebx)
- Control Instruction: Alter the sequence of instructions (by changing PC)
 - jmp, call
 - C constructs: if-else, do-while, function call, etc.


Today: Compute and Control Instructions

- Move operations (and addressing modes)
- Arithmetic & logical operations
- Control: Conditional branches (if... else...)
- Control: Loops (for, while)
- Control: Switch Statements (case... switch...)


Assembly
Programmer's
Perspective
of a Computer




Initially all data is in the memory




- Initially all data is in the memory
- But memory is slow: e.g., 15 ns for each access




- Initially all data is in the memory
- But memory is slow: e.g., 15 ns for each access
- Idea: move the frequently used data to a faster memory




- Initially all data is in the memory
- But memory is slow: e.g., 15 ns for each access
- Idea: move the frequently used data to a faster memory
- Register file is faster (but much smaller) memory: e.g., 0.5 ns



- Initially all data is in the memory
- But memory is slow: e.g., 15 ns for each access
- Idea: move the frequently used data to a faster memory
- Register file is faster (but much smaller) memory: e.g., 0.5 ns
- There are other kinds of faster memory that we will talk about later



- Initially all data is in the memory
- But memory is slow: e.g., 15 ns for each access
- Idea: move the frequently used data to a faster memory
- Register file is faster (but much smaller) memory: e.g., 0.5 ns
- There are other kinds of faster memory that we will talk about later
- Key: register file is programmer visible, i.e., you could use instructions to explicitly move data between memory and register file.




- Initially all data is in the memory
- But memory is slow: e.g., 15 ns for each access
- Idea: move the frequently used data to a faster memory
- Register file is faster (but much smaller) memory: e.g., 0.5 ns
- There are other kinds of faster memory that we will talk about later
- Key: register file is programmer visible, i.e., you could use instructions to explicitly move data between memory and register file.
- Software-managed vs. Hardware-managed faster memory.

Data Movement Instruction Example

movq %rdx, (%rdi)


- Semantics:
 - Move (really, copy) data in register %rdx to memory location whose address is the value stored in %rdi

Data Movement Instruction Example



- Semantics:
 - Move (really, copy) data in register %rdx to memory location whose address is the value stored in %rdi

Data Movement Instruction Example



Semantics:

 Move (really, copy) data in register %rdx to memory location whose address is the value stored in %rdi

Memory Addressing Modes

- An addressing mode specifies:
 - how to calculate the effective memory address of an operand
 - by using information held in registers and/or constants

Memory Addressing Modes

- An addressing mode specifies:
 - how to calculate the effective memory address of an operand
 - by using information held in registers and/or constants
- Normal: (R)
 - Memory address: content of Register R (Reg[R])
 - Pointer dereferencing in C

```
movq (%rcx),%rax; // address = %rcx
```

Memory Addressing Modes

- An addressing mode specifies:
 - how to calculate the effective memory address of an operand
 - by using information held in registers and/or constants
- Normal: (R)
 - Memory address: content of Register R (Reg[R])
 - Pointer dereferencing in C

```
movq (%rcx),%rax; // address = %rcx
```

- Displacement: D(R)
 - Memory address: Reg[R]+D
 - Register R specifies start of memory region
 - Constant displacement D specifies offset

```
movq 8(%rbp),%rdx; // address = %rbp + 8
```

movq Source, Dest

movq Source, Dest
Operator Operands

movq Source, Dest
Operator Operands

- Memory:
 - Simplest example: (%rax)
 - How to obtain the address is called "addressing mode"

movq Source, Dest Operator Operands

Memory:

- Simplest example: (%rax)
- How to obtain the address is called "addressing mode"

Register:

- Example: %rax, %r13
- But %rsp reserved for special use


movq Source, Dest Operator Operands


Memory:


- Simplest example: (%rax)
- How to obtain the address is called "addressing mode"


Register:


- Example: %rax, %r13
- But %rsp reserved for special use
- Immediate: Constant integer data
 - Example: \$0x400, \$-533; like C constant, but prefixed with '\$'
 - Encoded with 1, 2, or 4 bytes; can only be source





















```
Source Dest Src, Dest
                                                                                            C Analog
| Imm | Reg | movq $0x4,%rax | temp = 0x4; | Mem | movq $-147,(%rax) | *p = -147; | Reg | Reg | movq %rax,%rdx | temp2 = temp1; | Mem | movq %rax,(%rdx) | *p = temp; | Mem | Reg |
```

```
Source Dest Src, Dest
             C Analog
```

```
Source Dest Src, Dest
             C Analog
```

```
void swap
    (long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```


```
void swap
    (long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```



```
void swap
    (long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```


Memory Addr *xp xp

```
void swap
    (long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```





```
void swap
    (long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```






```
void swap
    (long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```






```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
movq %rdx, (%rdi) # *xp = t1
movq %rax, (%rsi) # *yp = t0
ret
```

```
void swap
    (long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```






How Does This Work?

```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
movq %rdx, (%rdi) # *xp = t1
movq %rax, (%rsi) # *yp = t0
ret
```

Registers

%rdi	0x120
%rsi	0x100
%rax	
%rdx	

Memory Addr





movq	(%rdi), %rax	# t0 = *xp
movq	(%rsi), %rdx	# t1 = *yp
movq	%rdx, (%rdi)	# *xp = t1
movq	%rax, (%rsi)	# *yp = t0
ret		

Registers

%rdi	0x120
%rsi	0x100
%rax	
%rdx	

Memory Addr






```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
movq %rdx, (%rdi) # *xp = t1
movq %rax, (%rsi) # *yp = t0
ret
```


Registers	
rdi	0x1

%rsi	0x100

%rdx	

Memory Addr







Registers


%rdi	0x120
%rsi	0x100
%rax	123
%rdx	456

Memory Addr







Registers



Memory Addr



```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
movq %rdx, (%rdi) # *xp = t1
movq %rax, (%rsi) # *yp = t0
ret
```



```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
movq %rdx, (%rdi) # *xp = t1
movq %rax, (%rsi) # *yp = t0
ret
```

Complete Memory Addressing Modes

- Most General Form: D(Rb,Ri,S)
 - Memory address: Reg[Rb] + S * Reg[Ri] + D
 - E.g., 8 (%eax, %ebx, 4); // address = %eax + 4 * %ebx + 8
 - D: Constant "displacement"
 - Rb: Base register: Any of 16 integer registers
 - Ri: Index register: Any, except for %rsp
 - S: Scale: 1, 2, 4, or 8

Complete Memory Addressing Modes

- Most General Form: D(Rb,Ri,S)
 - Memory address: Reg[Rb] + S * Reg[Ri] + D
 - E.g., 8 (%eax, %ebx, 4); // address = %eax + 4 * %ebx + 8
 - D: Constant "displacement"
 - Rb: Base register: Any of 16 integer registers
 - Ri: Index register: Any, except for %rsp
 - S: Scale: 1, 2, 4, or 8

Special Cases

(Rb,Ri) Reg[Rb]+Reg[Ri]

D(Rb,Ri) Reg[Rb]+Reg[Ri]+D

(Rb,Ri,S) Reg[Rb]+S*Reg[Ri]

Address Computation Examples

%rdx	0xf000
%rcx	0x0100

Expression	Address Computation	Address
0x8(%rdx)		
(%rdx,%rcx)		
(%rdx,%rcx,4)		
0x80(,%rdx,2)		

Address Computation Examples

%rdx	0xf000
%rcx	0x0100

Expression	Address Computation	Address
0x8 (%rdx)	0xf000 + 0x8	0xf008
(%rdx,%rcx)		
(%rdx,%rcx,4)		
0x80(,%rdx,2)		

Address Computation Examples

%rdx	0xf000
%rcx	0x0100

Expression	Address Computation	Address
0x8(%rdx)	0xf000 + 0x8	0xf008
(%rdx,%rcx)	0xf000 + 0x100	0xf100
(%rdx,%rcx,4)		
0x80(,%rdx,2)		.,

Address Computation Examples

%rdx	0xf000
%rcx	0x0100

Expression	Address Computation	Address
0x8(%rdx)	0xf000 + 0x8	0xf008
(%rdx,%rcx)	0xf000 + 0x100	0xf100
(%rdx,%rcx,4)	0xf000 + 4*0x100	0xf400
0x80(,%rdx,2)		

Address Computation Examples

%rdx	0xf000
%rcx	0x0100

Expression	Address Computation	Address
0x8(%rdx)	0xf000 + 0x8	0xf008
(%rdx,%rcx)	0xf000 + 0x100	0xf100
(%rdx,%rcx,4)	0xf000 + 4*0x100	0xf400
0x80(,%rdx,2)	2*0xf000 + 0x80	0x1e080

leaq 4(%rsi,%rdi,2), %rax

• leaq Src, Dst

- Src is address mode expression
- Set Dst to address denoted by expression
- No actual memory reference is made

• leaq Src, Dst

- Src is address mode expression
- Set Dst to address denoted by expression
- No actual memory reference is made

Uses

- Computing addresses without a memory reference
 - E.g., translation of p = &x[i];

- Interesting Use
 - Computing arithmetic expressions of the form x + k*y
 - Faster arithmetic computation

- Interesting Use
 - Computing arithmetic expressions of the form x + k*y
 - Faster arithmetic computation


```
long m12(long x)
{
   return x*12;
}
```


- Interesting Use
 - Computing arithmetic expressions of the form x + k*y
 - Faster arithmetic computation

```
long m12(long x)
{
   return x*12;
}
```


Converted to assembly by compiler:

```
leaq (%rdi,%rdi,2), %rax # t <- x+x*2
salq $2, %rax # return t<<2</pre>
```






- Data Movement Instruction: Transfer data between memory and register
 - movq %eax, (%ebx)



- Data Movement Instruction: Transfer data between memory and register
 - movq %eax, (%ebx)
- Compute Instruction: Perform arithmetics on register or memory data
 - addq %eax, %ebx
 - C constructs: +, -, >>, etc.



- Data Movement Instruction: Transfer data between memory and register
 - movq %eax, (%ebx)
- Compute Instruction: Perform arithmetics on register or memory data
 - addq %eax, %ebx
 - C constructs: +, -, >>, etc.
- Control Instruction: Alter the sequence of instructions (by changing PC)
 - jmp, call
 - C constructs: if-else, do-while, function call, etc.

Today: Compute and Control Instructions

- Move operations (and addressing modes)
- Arithmetic & logical operations
- Control: Conditional branches (if... else...)
- Control: Loops (for, while)
- Control: Switch Statements (case... switch...)

Format	Computation	Notes
addq src, dest	Dest = Dest + Src	

Format	Computation	Notes
addq src, dest	Dest = Dest + Src	

addq %rax, %rbx

Format	Computation	Notes
addq src, dest	Dest = Dest + Src	
и	• • •	
+ <i>v</i>	• • •	
u + v	• • •	
$TAdd_{w}(u, v)$	• • •	

addq %rax, %rbx

Format	Computation	Notes
addq src, dest	Dest = Dest + Src	
u	• • •	
+ <i>v</i>	• • •	
u + v	• • •	
$TAdd_{w}(u, v)$	• • •	

addq %rax, %rbx

%rbx = %rax + %rbx
Truncation if overflow,
set carry bit (more later...)

Format	Computation	Notes
addq src, dest	Dest = Dest + Src	
<pre>subq src, dest</pre>	Dest = Dest - Src	
imulq src, dest	Dest = Dest * Src	
salq src, dest	Dest = Dest << Src	Also called shlq
sarq src, dest	Dest = Dest >> Src	Arithmetic shift
shrq src, dest	Dest = Dest >> Src	Logical shift
xorq src, dest	Dest = Dest ^ Src	
andq src, dest	Dest = Dest & Src	
orq src, dest	Dest = Dest Src	

- No distinction between signed and unsigned (why?)
 - Bit level behaviors for signed and unsigned arithmetic are exactly the same — assuming truncation

- No distinction between signed and unsigned (why?)
 - Bit level behaviors for signed and unsigned arithmetic are exactly the same — assuming truncation

```
long signed_add
(long x, long y)
{
  long res = x + y;
  return res;
}

#x in %rdx, y in %rax
addq %rdx, %rax
```

- No distinction between signed and unsigned (why?)
 - Bit level behaviors for signed and unsigned arithmetic are exactly the same — assuming truncation

```
long signed_add
(long x, long y)
{
  long res = x + y;
  return res;
}
```

addq %rdx, %rax

```
long unsigned_add
(unsigned long x, unsigned long y)
{
  unsigned long res = x + y;
  return res;
}

#x in %rdx, y in %rax
  addq %rdx, %rax
```

- No distinction between signed and unsigned (why?)
 - Bit level behaviors for signed and unsigned arithmetic are exactly the same — assuming truncation

Bit-level

```
010
+) 101
111
```

```
long signed_add
(long x, long y)
{
  long res = x + y;
  return res;
}
```

```
#x in %rdx, y in %rax
addq %rdx, %rax
```

```
long unsigned_add
(unsigned long x, unsigned long y)
{
  unsigned long res = x + y;
  return res;
}
```

```
#x in %rdx, y in %rax
addq %rdx, %rax
```

- No distinction between signed and unsigned (why?)
 - Bit level behaviors for signed and unsigned arithmetic are exactly the same — assuming truncation

Bit-level

```
010
+) 101
111
```

Signed

```
2
+) -3
-1
```

```
long signed_add
(long x, long y)
{
  long res = x + y;
  return res;
}
```

```
#x in %rdx, y in %rax
addq %rdx, %rax
```

```
long unsigned_add
(unsigned long x, unsigned long y)
{
  unsigned long res = x + y;
  return res;
}
```

```
#x in %rdx, y in %rax
addq %rdx, %rax
```

- No distinction between signed and unsigned (why?)
 - Bit level behaviors for signed and unsigned arithmetic are exactly the same — assuming truncation

Bit-level 010 +) 101 111

```
Signed
                    Unsigned
```

```
long signed add
(long x, long y)
  long res = x + y;
  return res;
```

```
#x in %rdx, y in %rax
addq %rdx, %rax
```

```
long unsigned add
(unsigned long x, unsigned long y)
 unsigned long res = x + y;
 return res;
```

```
#x in %rdx, y in %rax
addq
       %rdx, %rax
```

Unary Instructions (one operand)

Format	Computation
<pre>incq dest</pre>	Dest = Dest + 1
decq dest	Dest = Dest - 1
negq dest	Dest = -Dest
notq dest	Dest = ~Dest

Unary Instructions (one operand)


Format	Computation
<pre>incq dest</pre>	Dest = Dest + 1
decq dest	Dest = Dest - 1
negq dest	Dest = -Dest
notq dest	Dest = ~Dest

Questions?

Today: Compute and Control Instructions

- Move operations (and addressing modes)
- Arithmetic & logical operations
- Control: Conditional branches (if... else...)
- Control: Loops (for, while)
- Control: Switch Statements (case... switch...)

Sequential




$$a = x + y;$$


 $y = a - c;$

• • •

Sequential

Conditional







$$a = x + y;$$

 $y = a - c;$


$$a = x + y;$$
 if $(x > y) r = x - y;$
 $y = a - c;$ else $r = y - x;$



Conditional




 Both conditional and iterative programming requires altering the sequence of instructions (control flow)




if
$$(x > y)$$
 $r = x - y$;
else $r = y - x$;

- Both conditional and iterative programming requires altering the sequence of instructions (control flow)
- We need a set of control instructions to do so



Three Basic Programming Constructs

- Both conditional and iterative programming requires altering the sequence of instructions (control flow)
- We need a set of control instructions to do so
- Two fundamental questions:
 - How to test condition and how to represent test results?
 - How to alter control flow according to the test results?



```
long absdiff
  (long x, long y)
{
  long result;
  if (x > y)
    result = x-y;
  else
    result = y-x;
  return result;
}
```

gcc -Og -S -fno-if-conversion control.c

```
long absdiff
  (long x, long y)
{
  long result;
  if (x > y)
    result = x-y;
  else
    result = y-x;
  return result;
}
```

```
absdiff:
          %rsi,%rdi # x:y
  cmpq
  jle
         . L4
         %rdi,%rax
  movq
          %rsi,%rax
  subq
  ret
.L4:
          # x <= y
          %rsi,%rax
  movq
          %rdi,%rax
  subq
  ret
```

gcc -Og -S -fno-if-conversion control.c

```
long absdiff
  (long x, long y)
{
  long result;
  if (x > y)
    result = x-y;
  else
    result = y-x;
  return result;
}
```

Register	Use(s)
%rdi	x
%rsi	У
%rax	Return value

absdiff:	
cmpq	%rsi,%rdi # x:y
jle	.L4
movq	%rdi,%rax
subq	%rsi,%rax
ret	
.L4:	# x <= y
movq	%rsi,%rax
subq	%rdi,%rax
ret	

gcc -Og -S -fno-if-conversion control.c

```
long absdiff
  (long x, long y)
{
  long result;
  if (x > y)
    result = x-y;
  else
    result = y-x;
  return result;
}
```

Register	Use(s)
%rdi	x
%rsi	У
%rax	Return value

```
absdiff:
            %rsi,%rdi # x:y
   cmpq
            .L4
   jle
            %rdi,%rax
   movq
   subq
            %rsi,%rax
   ret
            \# x \le y
            %rsi,%rax
   movq
   subq
            %rdi,%rax
   ret
```

Labels are symbolic names used to refer to instruction addresses.

```
cmpq %rsi, %rdi
jle .L4
```

cmpq
jle

%rsi, %rdi
.L4 ←

cmpq %rsi, %rdi
jle .L4 Jump to label if less
than or equal to

- Semantics:
 - If %rdi is less than or equal to %rsi (both interpreted as signed value), jump to the part of the code with a label .L4

cmpq jle %rsi, .L4

%rdi

- Semantics:
 - If %rdi is less than or equal to %rsi (both interpreted as signed value), jump to the part of the code with a label .L4
- Under the hood:

cmpq jle %rsi, .L4

%rdi

- Semantics:
 - If %rdi is less than or equal to %rsi (both interpreted as signed value), jump to the part of the code with a label .L4
- Under the hood:
 - cmpq instruction sets the condition codes

cmpq jle %rsi, .L4

%rdi

- Semantics:
 - If %rdi is less than or equal to %rsi (both interpreted as signed value), jump to the part of the code with a label .L4
- Under the hood:
 - cmpq instruction sets the condition codes
 - jle reads and checks the condition codes

cmpq jle %rsi, .L4

%rdi

- Semantics:
 - If %rdi is less than or equal to %rsi (both interpreted as signed value), jump to the part of the code with a label .L4
- Under the hood:
 - cmpq instruction sets the condition codes
 - jle reads and checks the condition codes
 - If condition met, modify the Program Counter to point to the address of the instruction with a label . L4

cmpq %rsi, %rdi

cmpq %rsi, %rdi

• Essentially, how do we know %rdi <= %rsi?

cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi

cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0

cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0

ZF Zero Flag (result is zero)



cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0
- %rdi < %rsi if and only if: %rdi %rsi < 0 (is it correct??)

ZF Zero Flag (result is zero)



cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0
- %rdi < %rsi if and only if: %rdi %rsi < 0 (is it correct??)
 - %rdi %rsi < 0 and the result doesn't overflow, or

ZF Zero Flag (result is zero)



cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0
- %rdi < %rsi if and only if: %rdi %rsi < 0 (is it correct??)
 - %rdi %rsi < 0 and the result doesn't overflow, or

No
$$\frac{-) \ 010}{111} \quad \frac{-) \ 2}{-1}$$

ZF Zero Flag (result is zero)



ZF

cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0
- %rdi < %rsi if and only if: %rdi %rsi < 0 (is it correct??)
 - %rdi %rsi < 0 and the result doesn't overflow, or

No
$$\frac{-) 010}{111}$$
 $\frac{-) 2}{-1}$ Overflow $\frac{101}{010}$ $\frac{-3}{-0}$ $\frac{-3}{010}$ $\frac{-6}{010}$

ZF Zero Flag (result is zero)



ZF

cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0
- %rdi < %rsi if and only if: %rdi %rsi < 0 (is it correct??)
 - %rdi %rsi < 0 and the result doesn't overflow, or
 - %rdi %rsi > 0 and the result does overflow

No
$$\frac{-) \ 010}{111}$$
 $\frac{-) \ 2}{-1}$ Overflow $\frac{101}{-0}$ $\frac{-3}{-0}$ $\frac{-0}{-0}$ $\frac{3}{-0}$

ZF Zero Flag (result is zero)



ZF


cmpq

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0
- %rdi < %rsi if and only if: %rdi %rsi < 0 (is it correct??)
 - %rdi %rsi < 0 and the result doesn't overflow, or
 - %rdi %rsi > 0 and the result does overflow

No
$$\frac{-) 010}{111}$$
 $\frac{-) 2}{-1}$ Overflow $\frac{101}{-0}$ $\frac{-3}{-0}$ $\frac{-3}{-0}$ $\frac{-0}{-0}$ $\frac{-0}{-0}$ $\frac{-0}{-0}$ $\frac{-0}{-0}$ $\frac{-0}{-0}$ $\frac{-0}{-0}$ $\frac{-0}{-0}$ $\frac{-0}{-0}$

ZF Zero Flag (result is zero)

SF Sign Flag (result is negative)




cmpq

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0
- %rdi < %rsi if and only if: %rdi %rsi < 0 (is it correct??)
 - %rdi %rsi < 0 and the result doesn't overflow, or
 - %rdi %rsi > 0 and the result does overflow

No Overflow
$$\frac{-) 010}{111}$$
 $\frac{-) 2}{-1}$ $\frac{-) 2}{-1}$ Overflow $\frac{101}{-) 011}$ $\frac{-3}{-) 3}$

ZF Zero Flag (result is zero)

SF Sign Flag (result is negative)




cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0
- %rdi < %rsi if and only if: %rdi %rsi < 0 (is it correct??)
 - %rdi %rsi < 0 and the result doesn't overflow, or
 - %rdi %rsi > 0 and the result does overflow

```
11111111 10000000 cmpq 0xFF, 0x80
```

ZF Zero Flag (result is zero)

SF Sign Flag (result is negative)



cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0
- %rdi < %rsi if and only if: %rdi %rsi < 0 (is it correct??)
 - %rdi %rsi < 0 and the result doesn't overflow, or
 - %rdi %rsi > 0 and the result does overflow

ZF Zero Flag (result is zero)

SF Sign Flag (result is negative)




cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0
- %rdi < %rsi if and only if: %rdi %rsi < 0 (is it correct??)
 - %rdi %rsi < 0 and the result doesn't overflow, or
 - %rdi %rsi > 0 and the result does overflow

ZF Zero Flag (result is zero)

SF Sign Flag (result is negative)



cmpq %rsi, %rdi

- Essentially, how do we know %rdi <= %rsi?
- Calculate %rdi %rsi
- %rdi == %rsi if and only if %rdi %rsi == 0
- %rdi < %rsi if and only if: %rdi %rsi < 0 (is it correct??)
 - %rdi %rsi < 0 and the result doesn't overflow, or
 - %rdi %rsi > 0 and the result does overflow
- %rdi <= %rsi if and only if
 - ZF is set, or
 - SF is set but OF is not set, or
 - SF is not set, but OF is set
- or simply: ZF | (SF ^ OF)

ZF Zero Flag (result is zero)

SF Sign Flag (result is negative)

