■ NetApp

Creating a sync relationship

Cloud Manager

Ben Cammett February 09, 2021

Table of Contents

| Creating a sync relationship | |
|--|--|
| Creating a sync relationship | |
| Creating a sync relationship for an existing working environment | |

Creating a sync relationship


When you create a sync relationship, the Cloud Sync service copies files from the source to the target. After the initial copy, the service syncs any changed data every 24 hours.

Creating a sync relationship

Use these steps to sync data to or from any supported storage type. The steps below provide an example that shows how to set up a sync relationship from an NFS server to an S3 bucket.

- 1. In Cloud Manager, click Sync.
- 2. On the **Define Sync Relationship** page, choose a source and target.

The following steps provide an example of how to create a sync relationship from an NFS server to an S3 bucket.




- On the NFS Server page, enter the IP address or fully qualified domain name of the NFS server that you want to sync to AWS.
- 4. On the **Data Broker** page, follow the prompts to create a data broker virtual machine in AWS, Azure, or Google Cloud Platform, or to install the data broker software an existing Linux host.

For more details, refer to the following pages:

- Installing the data broker in AWS
- · Installing the data broker in Azure
- Installing the data broker in GCP
- Installing the data broker on a Linux host
- 5. After you install the data broker, click **Continue**.

The following image shows a successfully deployed data broker in AWS:




On the **Directories** page, select a top-level directory or subdirectory.

If Cloud Sync is unable to retrieve the exports, click **Add Export Manually** and enter the name of an NFS export.



If you want to sync more than one directory on the NFS server, then you must create additional sync relationships after you are done.

- 7. On the AWS S3 Bucket page, select a bucket:
 - Drill down to select an existing folder within the bucket or to select a new folder that you create inside the bucket.
 - Click Add to the list to select an S3 bucket that is not associated with your AWS account. Specific permissions must be applied to the S3 bucket.
- 8. On the Bucket Setup page, set up the bucket:
 - Choose whether to enable S3 bucket encryption and then select an AWS KMS key, enter the ARN of a KMS key, or select AES-256 encryption.
 - Select an S3 storage class. View the supported storage classes.



9. On the Settings page, define how source files and folders are synced and maintained in the target

location:

Schedule

Choose a recurring schedule for future syncs or turn off the sync schedule. You can schedule a relationship to sync data as often as every 1 minute.

Retries

Define the number of times that Cloud Sync should retry to sync a file before skipping it.

Recently Modified Files

Choose to exclude files that were recently modified prior to the scheduled sync.

Delete Files on Source

Choose to delete files from the source location after Cloud Sync copies the files to the target location. This option includes the risk of data loss because the source files are deleted after they're copied.

If you enable this option, you also need to change a parameter in the local.json file on the data broker. Open the file and change the parameter named *workers.transferrer.delete-on-source* to **true**.

Delete Files on Target

Choose to delete files from the target location, if they were deleted from the source. The default is to never deletes files from the target location.

Object tagging

When AWS S3 is the target in a sync relationship, Cloud Sync tags S3 objects with metadata that's relevant to the sync operation. You can disable tagging of S3 objects, if it's not desired in your environment. There's no impact to Cloud Sync if you disable tagging—Cloud Sync just stores the sync metadata in a different way.

File Types

Define the file types to include in each sync: files, directories, and symbolic links.

Exclude File Extensions

Specify file extensions to exclude from the sync by typing the file extension and pressing **Enter**. For example, type *log* or *.log* to exclude *.log files. A separator isn't required for multiple extensions. The following video provides a short demo:

https://docs.netapp.com/us-en/occm/media/video_file_extensions.mp4 (video)

File Size

Choose to sync all files regardless of their size or just files that are in a specific size range.

Date Modified

Choose all files regardless of their last modified date, files modified after a specific date, before a specific date, or between a time range.

10. On the **Relationship Tags** page, enter up to 9 relationship tags and then click **Continue**.

The Cloud Sync service assigns the tags to each object that it syncs to the S3 bucket.

11. Review the details of the sync relationship and then click **Create Relationship**.

Result

Cloud Sync starts syncing data between the source and target.


Creating a sync relationship for an existing working environment

Use these steps to sync data to or from any of the following:

- Amazon S3
- Azure NetApp Files
- Cloud Volumes ONTAP
- · On-prem ONTAP cluster

Steps

- 1. In Cloud Manager, click Canvas.
- 2. Select a working environment that matches any of the types listed above.
- 3. Select the action menu next to Sync.



4. Select **Sync data from this location** or **Sync data to this location** and follow the prompts to set up the sync relationship.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.