



VWAP Flux Trader Manual

Dear Trader,

If you are reading this document, it means you now have access to the VWAP Flux indicator.

VWAP Flux is not designed as a simple plotting indicator. Instead, it is a real-time fair-value identification indicator. When applied properly, it helps you understand where control currently sits in the market and which areas carry the highest trade probability.

This manual is created to help you understand the core mechanics of VWAP Flux, the purpose of each parameter, and how the indicator derives its signals and support/resistance zones.

1. Overview of VWAP Flux

The traditional VWAP is a widely used trading indicator, calculated as the volume-weighted average price over a defined period.

However, it carries a major limitation:

It provides only a single price line that represents the market's average price, without capturing the underlying price distribution or the evolving money flow over time.



In highly volatile markets, or when liquidity shifts rapidly, a single VWAP line is often insufficient to represent real-time fair value accurately.

VWAP Flux addresses these limitations. The indicator introduces several key components, including:

- **Trend:** Helps traders identify the current trend and evaluate its strength through the accumulated volume reflected in the Fair Value Plot.




- **Dynamic Support/Resistance zones (VWAP Bands):** These zones are calculated based on VWAP and help traders identify potential trading areas. The VWAP Bands are formed by 5 primary plots: Max – Upper – Median – Lower – Low.



- Trade signals (pullback signals)



- **Static Support/Resistance zones:** These zones are derived from major swing highs and lows where clear bullish or bearish reactions took place. Each static S/R zone is analyzed with Buy/Sell volume to help traders determine whether the zone was formed by initiative pressure or absorption. In addition, static S/R zones also reveal the internal POC and VWAP levels, enabling traders to anticipate potential reaction points when price returns to the zone.



2. Parameter

▼ Parameters	
Volume Base	BidAskPrice_RealVolume ▼
Anchor Period (Minutes)	20
VWAP Amount	5
Trend: Period	14
Trend: MA Type	EMA ▼
Level: Max (%)	100
Level: Upper (%)	70
Level: Median (%)	50
Level: Lower (%)	30
Level: Min (%)	0
Signal: Quantity Per Trend	4
Signal: Close Threshold (%)	80
Signal: Split (Bars)	30
▼ General	
Zone Period	3

2.1. Volume Base

Volume Base	BidAskPrice_RealVolume ▼
-------------	--------------------------

- **"BidAskPrice_RealVolume"**: This mode should be used for instruments with real volumes (**futures & stocks**).

Buy volume & sell volume are defined as follows:

- **Buy Volume**: If the price of a tick is greater than or equal to the ask price, the real volume of the tick is categorized as buy volume and added to the total buy volume of the bar that the tick belongs to.
- **Sell Volume**: If the price of a tick is less than or equal to the bid price, the real volume of the tick is categorized as sell volume and added to the total sell volume of the bar that the tick belongs to.

In this mode, if Tick Replay is enabled, the indicator functions on both **historical & real-time data**. Please visit https://ninjatrader.com/support/helpGuides/nt8/en-us/?tick_replay.htm for instructions on how to enable Tick Replay.

If Tick Replay is disabled, the indicator functions only on **real-time data** and there are no calculations on historical data. Any actions that lead to chart reloading will erase all calculations.

- **"UpDownTick_RealVolume"**: This mode should be used for instruments with real volumes (**futures & stocks**).

Buy volume & sell volume are defined as follows:

- **Buy Volume**: If a tick is up or remains up, the real volume of the tick is categorized as buy volume and added to the total buy volume of the bar that the tick belongs to.
- **Sell Volume**: If a tick is down or remains down, the real volume of the tick is categorized as sell volume and added to the total sell volume of the bar that the tick belongs to.

In this mode, the indicator functions on both **historical & real-time data**. However, please be advised that historical and real-time calculations of the same bar may not be 100% identical, due to technical limitations.

- **"UpDownTick_UnitVolume"**: This mode is the one & only choice for instruments without real volumes (**forex, CFDs, indices**).


Buy volume & sell volume are defined as follows:

- **Buy Volume**: If a tick is up or remains up, a unit volume (1) is credited as buy volume for the tick and added to the total buy volume of the bar that the tick belongs to.
- **Sell Volume**: If a tick is down or remains down, a unit volume (1) is credited as sell volume for the tick and added to the total sell volume of the bar that the tick belongs to.

In this mode, the indicator functions on both **historical & real-time data**. However, please be advised that historical and real-time calculations of the same bar may not be 100% identical, due to technical limitations.

2.2. Anchor Period (Minutes)


- **"Anchor Period (Minutes)"**: This parameter defines the time cycle, in minutes, used to recalculate the VWAP.



For example, when **Anchor Period = 30**, the indicator will recalculate the VWAP bands every 30 minutes.



When the Anchor Period is small, the VWAP reacts quickly to price movements, making it suitable for scalping.



When the Anchor Period is larger, the VWAP reflects a broader trend and becomes more suitable for stable, higher-timeframe trading.

Increasing the Anchor Period makes the VWAP bands smoother and less noisy, while decreasing it makes the bands more responsive but more prone to noise.

2.3. VWAP Amount

- **"VWAP Amount":** Defines the number of recent VWAP layers used to construct the VWAP bands.



For example, if **VWAP Amount = 5**, the indicator will use the five most recent VWAP layers to calculate the Highest, Upper, Median, Lower, and Lowest levels.



When the VWAP Amount is increased, the price zones become more stable due to smoother data. When it is decreased, the zones react more quickly but also shift more frequently.

2.4. Trend Period

- **"Trend Period"**: defines the averaging period of price used to determine the market trend.

2.5. Trend MA Type

- **"Trend MA type"**: The moving average type (can choose from 11 popular moving-average types)

2.6. Level: Max (%)

- "Level: Max (%)": defines the highest threshold within the VWAP bands.

2.7. Level: Upper (%)

- "Level: Upper (%)": defines the threshold for the Upper plot in the VWAP bands.

2.8 Level: Median (%)

- "Level: Median (%)": defines the threshold for the Fair Value plot within the VWAP bands.

2.9. Level: Lower (%)

- "Level: Lower (%)": defines the threshold for the Lower plot in the VWAP bands.

2.10. Level: Min (%)

- "Level: Min (%)": defines the lowest threshold within the VWAP bands.

2.11. Signal Quantity Per Trend

- "Signal Quantity Per Trend": Specifies the maximum number of trade signals allowed to appear within the same support or resistance zone.




For example, if **Signal Quantity Per Trend = 4**, it means that only 4 same-direction signals are allowed to appear within a single trend.

Note: It is not recommended to set this value too high. When price repeatedly tests the same support or resistance zone, the reliability of signals generated at that zone gradually

decreases. Limiting the number of signals per trend helps prevent over-trading within a single trend.

2.12. Signal Close Threshold

- **"Signal Close Threshold"**: Defines the minimum percentage of the candle's close relative to its full range (from Low to High) for the candle to qualify as a valid signal.



- For a **Sell** signal, the candle is considered valid if its close lies within the **upper 70%** of the candle's range measured from the Low.
- For a **Buy** signal, the close must fall within the **lower 70%** of the range measured from the High.

2.13. Signal Split (Bars)

- **"Signal Split (Bars)"**: Specifies the minimum bar distance required between two consecutive signals in the same direction.



For example, in the illustration above, if **Signal Split (Bars) = 30**, it means the current Buy signal must be at least 30 bars away from the previous Buy signal.

2.14. Zone Period

- **"Zone Period"** defines the cycle used by the indicator to identify static S/R zones.

A higher value results in fewer S/R zones, as stronger price movement over a longer cycle is required for a zone to form.

Conversely, a lower value produces more frequent S/R zones.

3. Suggested settings

Parameters	
Anchor Period (Minutes)	20
VWAP Amount	7
Trend: Period	14
Trend: MA Type	EMA ▼
Level: Max (%)	80
Level: Upper (%)	60
Level: Median (%)	50
Level: Lower (%)	40
Level: Min (%)	10
Signal: Quantity Per Trend (%)	5
Signal: Close Threshold (%)	70
Signal: Split (Bars)	15

1 Minute chart

Parameters	
Anchor Period (Minutes)	60
VWAP Amount	10
Trend: Period	14
Trend: MA Type	EMA ▼
Level: Max (%)	90
Level: Upper (%)	60
Level: Median (%)	50
Level: Lower (%)	40
Level: Min (%)	20
Signal: Quantity Per Trend (%)	5
Signal: Close Threshold (%)	70
Signal: Split (Bars)	15

3 Minute chart

▼ Parameters	
Anchor Period (Minutes)	120
VWAP Amount	5
Trend: Period	14
Trend: MA Type	EMA ▼
Level: Max (%)	100
Level: Upper (%)	70
Level: Median (%)	50
Level: Lower (%)	30
Level: Min (%)	0
Signal: Quantity Per Trend (%)	5
Signal: Close Threshold (%)	70
Signal: Split (Bars)	15

5 Minute chart

▼ Parameters	
Anchor Period (Minutes)	30
VWAP Amount	5
Trend: Period	14
Trend: MA Type	EMA ▼
Level: Max (%)	80
Level: Upper (%)	60
Level: Median (%)	50
Level: Lower (%)	20
Level: Min (%)	10
Signal: Quantity Per Trend (%)	5
Signal: Close Threshold (%)	70
Signal: Split (Bars)	15

1000 Volume (Highly Recommend)

Parameters	
Anchor Period (Minutes)	3
VWAP Amount	5
Trend: Period	14
Trend: MA Type	EMA ▼
Level: Max (%)	80
Level: Upper (%)	60
Level: Median (%)	50
Level: Lower (%)	20
Level: Min (%)	10
Signal: Quantity Per Trend (%)	5
Signal: Close Threshold (%)	70
Signal: Split (Bars)	30

ninZaRenko 12/4

4. NinjaScripts Signals

You can rely on the signals below to build your own strategy:

- **Signal Trend:** 1 = bullish, -1 = bearish
- **Signal Trade:** 1 = bullish, -1 = bearish

Below is the example condition for this indicator based on the **Signal_Trade**:

If Signal_Trade equal to 1, you can enter long here.

Conversely, if Signal_Trade equal to -1, you can enter short here.

Please follow the link below to find more information about Strategy Builder.

<https://youtu.be/mtMNiOQtQE>