# Project3 Preemptive Kernel 设计文档

中国科学院大学 李云志 2017.11.13

### 1. 时钟中断与 blocking sleep 设计流程

- (1) 中断处理的一般流程
  - a) 保存被中断处理函数打断的进程的上下文
  - b) 确定中断类型
  - c) 根据中断类型跳转到相应的中断处理函数处
  - d) 处理完中断后,清中断并恢复被打断进程的上下文
  - e) 从中断处理函数返回正常任务流
- (2) 时钟中断的处理流程;如何处理 blocking sleep 的 tasks;如何处理用户态 task 和内核态 task
  - a) 时钟中断的处理流程
    - i. time elapsed 变量值增加 1000, 用于记录系统时间
    - ii. 判断当前任务所处状态,是内核态则表明是内核线程,直接执行中断返回相关操作。 如果是用户态进程,则先将其状态改为内核态后存入 ready 队列,再跳转至 scheduler 进行相关调度操作。
    - iii. 获取到新的 task 后,恢复上下文,清中断,恢复正常的任务流
  - b) 如何处理 blocking sleep 的 tasks?

当 task 调用 do\_sleep 时表明其要进入休眠模式,则根据传入的参数以及系统当前的时间 计算其 deadline,并将其加入到睡眠队列中。需要注意的是,在这地方并不是简单的加入 到睡眠队列,而是有一个排序操作。这方便我们以后的唤醒操作。

- c) 如何处理用户态 task 和内核态 task?
- 在此次任务中,时钟中断不会打断内核态的 task。所以原则上,在内核态的 task 在时钟中断到来的时候只需要进行一次保存上下文与恢复上下文。
- (3) blocking sleep 的含义,task 调用 blocking sleep 时做什么处理?什么时候唤醒 sleep 的 task? task 调用 do\_sleep 函数表明其要进行休眠。do\_sleep 函数先关闭中断,并进行睡眠时间的计算,之后将 task 加入到睡眠队列中。如上一问所述,这里加入的队列为优先队列,唤醒时间早的位于前部。之后跳转到调度器,进行调度工作。

每次任务调度时,后会进行 checking\_sleep 的操作,判断睡眠队列中的任务是否需要被唤醒。被唤醒的任务加入到 ready 队列中。

### 2. 基于优先级的调度器设计

- (1) priority-based scheduler 的设计思路
  - a) 本此实验,采用的优先级设计如下: 优先级分为 0-9 级,其中 9 级最高。
  - b) 调度器调度策略如下:

将 ready 队列中当前优先级最高的任务取出并执行。每执行一次,任务的优先级减 1.

- c) 在任务执行第一次时初始化优先级
- d) 若 ready 队列中所最高优先级的任务的优先级为负数时,初始化所有任务的优先级。

## 3. 关键函数功能

1、判断中断类型:

```
mfc0 k0, CP0_CAUSE
nop
andi k0, k0, CAUSE_IPL
clz k0, k0
xori k0, k0, 0x17
addiu k1, zero, 7
beq k0, k1, time_irq
nop
jal clear_int
nop
```

2、时钟中断处理函数:

```
time_irq:
  li
       a0, TIMER_INTERVAL
  jal reset_timer
  jal
       clear_int
        k1, time_elapsed
  addiu k1, k1, 1000
        k1, time_elapsed
  TEST_NESTED_COUNT
  bne
        k1, zero, int_done
  nop
  ENTER_CRITICAL
  lw
        k0, current_running
        k1, 1
  li
        k1, NESTED_COUNT(k0)
  SW
  jal
        put_current_running
  nop
  jal
        scheduler_entry
  nop
        k0, current_running
  lw
        zero, NESTED_COUNT(k0)
  SW
  LEAVE_CRITICAL
        int_done
  j
  nop
```

### 3. do\_sleep:

```
void do_sleep(int milliseconds){
    ASSERT(!disable_count);
    enter_critical();
    // TODO
    current_running->status = SLEEPING;
    current_running->deadline = do_gettimeofday() + milliseconds;
    sort_and_enqueue(&sleep_wait_queue, (node_t *) current_running, lte_deadline);
    scheduler_entry();
    leave_critical();
}
```

### 4. checking\_sleep:

```
void check_sleeping(){
    uint32_t now = do_gettimeofday();
    node_t *tmp;
    while(!is_empty(&sleep_wait_queue)&&((pcb_t*)peek(&sleep_wait_queue))->deadline <= now)
    {
        tmp = dequeue(&sleep_wait_queue);
        enqueue(&ready_queue,tmp);
        ((pcb_t *)tmp)->status = READY;
    }
}
```

#### 5、 自实现的优先级调度的 scheduler:

```
void scheduler(){
    ASSERT(disable_count);
    check_sleeping(); // wake up sleeping processes
    while (is_empty(&ready_queue)){
          leave_critical();
          enter critical();
          check_sleeping();
    current_running = (pcb_t *) dequeue(&ready_queue);
    pcb_t *record = current_running;
    pcb_t *temp = record;
    do{
      enqueue(&ready_queue,(node_t*)current_running);
       current_running = (pcb_t*)dequeue(&ready_queue);
       if(running_priority[current_running->pid]>running_priority[temp->pid])
        temp = current_running;
    }while(current_running!=record);
    if(running_priority[temp->pid]<0)//刷新所有的优先级
    {
        enqueue(&ready_queue,(node_t*)current_running);
        current_running = (pcb_t*)dequeue(&ready_queue);
        running_priority[current_running->pid] = original_priority[current_running->pid];
       }while(record!=current_running);
    record = current running;
    temp = record;
     do{
       enqueue(&ready_queue,(node_t*)current_running);
       current_running = (pcb_t*)dequeue(&ready_queue);
       if(running_priority[current_running->pid]>running_priority[temp->pid])
         temp = current_running;
    }while(current_running!=record);
    if (current_running!=temp){
                                   //维护队列,弹出优先级最高的任务
       //enqueue(&ready_queue,(node_t*)current_running);
      temp->node.prev->next = (node_t*)current_running;
      temp->node.next->prev = (node_t*)current_running;
       current_running->node.prev = temp->node.prev;
       current running->node.next = temp->node.next;
      current_running = temp;
    running_priority[current_running->pid]--;
    ASSERT(NULL != current_running);
    ++current_running->entry_count;
```

### 参考文献

无