

#### Module 4: Inter-VLAN Routing

**Instructor Materials** 

Switching, Routing and Wireless Essentials v7.0 (SRWE)



# 4.1 Inter-VLAN Routing Operation

### Inter-VLAN Routing Operation What is Inter-VLAN Routing?

VLANs are used to segment switched Layer 2 networks for a variety of reasons. Regardless of the reason, hosts in one VLAN cannot communicate with hosts in another VLAN unless there is a router or a Layer 3 switch to provide routing services.


Inter-VLAN routing is the process of forwarding network traffic from one VLAN to another VLAN.

There are three inter-VLAN routing options:

- Legacy Inter-VLAN routing This is a legacy solution. It does not scale well.
- Router-on-a-Stick This is an acceptable solution for a small to medium-sized network.
- Layer 3 switch using switched virtual interfaces (SVIs) This is the most scalable solution for medium to large organizations.

### Inter-VLAN Routing Operation Legacy Inter-VLAN Routing

- The first inter-VLAN routing solution relied on using a router with multiple Ethernet interfaces. Each
  router interface was connected to a switch port in different VLANs. The router interfaces served as
  the default gateways to the local hosts on the VLAN subnet.
- Legacy inter-VLAN routing using physical interfaces works, but it has a significant limitation. It is
  not reasonably scalable because routers have a limited number of physical interfaces. Requiring
  one physical router interface per VLAN quickly exhausts the physical interface capacity of a router.
- Note: This method of inter-VLAN routing is no longer implemented in switched networks and is included for explanation purposes only.





### Inter-VLAN Routing Operation Router-on-a-Stick Inter-VLAN Routing

The 'router-on-a-stick' inter-VLAN routing method overcomes the limitation of the legacy inter-VLAN routing method. It only requires one physical Ethernet interface to route traffic between multiple VLANs on a network.


- A Cisco IOS router Ethernet interface is configured as an 802.1Q trunk and connected to a trunk port on a Layer 2 switch. Specifically, the router interface is configured using subinterfaces to identify routable VLANs.
- The configured subinterfaces are software-based virtual interfaces. Each is associated with a single
  physical Ethernet interface. Subinterfaces are configured in software on a router. Each subinterface is
  independently configured with an IP address and VLAN assignment. Subinterfaces are configured for
  different subnets that correspond to their VLAN assignment. This facilitates logical routing.
- When VLAN-tagged traffic enters the router interface, it is forwarded to the VLAN subinterface. After a
  routing decision is made based on the destination IP network address, the router determines the exit
  interface for the traffic. If the exit interface is configured as an 802.1q subinterface, the data frames are
  VLAN-tagged with the new VLAN and sent back out the physical interface

**Note**: The router-on-a-stick method of inter-VLAN routing does not scale beyond 50 VLANs.

### Inter-VLAN Routing Operation Inter-VLAN Routing on a Layer 3 Switch

The modern method of performing inter-VLAN routing is to use Layer 3 switches and switched virtual interfaces (SVI). An SVI is a virtual interface that is configured on a Layer 3 switch, as shown in the figure.

**Note**: A Layer 3 switch is also called a multilayer switch as it operates at Layer 2 and Layer 3. However, in this course we use the term Layer 3 switch.



### Inter-VLAN Routing Operation Inter-VLAN Routing on a Layer 3 Switch (Cont.)

Inter-VLAN SVIs are created the same way that the management VLAN interface is configured. The SVI is created for a VLAN that exists on the switch. Although virtual, the SVI performs the same functions for the VLAN as a router interface would. Specifically, it provides Layer 3 processing for packets that are sent to or from all switch ports associated with that VLAN.


The following are advantages of using Layer 3 switches for inter-VLAN routing:

- They are much faster than router-on-a-stick because everything is hardware switched and routed.
- There is no need for external links from the switch to the router for routing.
- They are not limited to one link because Layer 2 EtherChannels can be used as trunk links between the switches to increase bandwidth.
- Latency is much lower because data does not need to leave the switch in order to be routed to a
  different network.
- They more commonly deployed in a campus LAN than routers.
- The only disadvantage is that Layer 3 switches are more expensive.

## 4.2 Router-on-a-Stick Inter-VLAN Routing

#### Router-on-a-Stick Inter-VLAN Routing Router-on-a-Stick Scenario

- In the figure, the R1 GigabitEthernet 0/0/1 interface is connected to the S1 FastEthernet 0/5 port. The S1 FastEthernet 0/1 port is connected to the S2 FastEthernet 0/1 port. These are trunk links that are required to forward traffic within and between VLANs.
- To route between VLANs, the R1 GigabitEthernet 0/0/1
  interface is logically divided into three subinterfaces, as
  shown in the table. The table also shows the three VLANs
  that will be configured on the switches.
- Assume that R1, S1, and S2 have initial basic configurations. Currently, PC1 and PC2 cannot **ping** each other because they are on separate networks. Only S1 and S2 can **ping** each other, but they but are unreachable by PC1 or PC2 because they are also on different networks.
- To enable devices to ping each other, the switches must be configured with VLANs and trunking, and the router must be configured for inter-VLAN routing.



Subinterface	VLAN	IP Address
G0/0/1.10	10	192.168.10.1/24
G0/0/1.20	20	192.168.20.1/24
G0/0/1.30	99	192.168.99.1/24



### Router-on-a-Stick Inter-VLAN Routing R1 Subinterface Configuration

The router-on-a-stick method requires you to create a subinterface for each VLAN to be routed. A subinterface is created using the **interface** *interface\_id subinterface\_id* global configuration mode command. The subinterface syntax is the physical interface followed by a period and a subinterface number. Although not required, it is customary to match the subinterface number with the VLAN number.

Each subinterface is then configured with the following two commands:

- encapsulation dot1q vlan\_id [native] This command configures the subinterface to respond to 802.1Q encapsulated traffic from the specified vlan-id. The native keyword option is only appended to set the native VLAN to something other than VLAN 1.
- **ip address** *ip-address subnet-mask* This command configures the IPv4 address of the subinterface. This address typically serves as the default gateway for the identified VLAN.

Repeat the process for each VLAN to be routed. Each router subinterface must be assigned an IP address on a unique subnet for routing to occur. When all subinterfaces have been created, enable the physical interface using the **no shutdown** interface configuration command. If the physical interface is disabled, all subinterfaces are disabled.

### Router-on-a-Stick Inter-VLAN Routing R1 Subinterface Configuration (Cont.)

In the configuration, the R1 G0/0/1 subinterfaces are configured for VLANs 10, 20, and 99.

```
Rl(config)# interface GO/O/1.10
Rl(config-subif)# Description Default Gateway for VLAN 10
R1(config-subif)# encapsulation dot10 10
R1(config-subif)# ip add 192.168.10.1 255.255.255.0
R1(config-subif)# exit
Rl(config)#
R1(config)# interface G0/0/1.20
R1(config-subif)# Description Default Gateway for VLAN 20
Rl(config-subif)# encapsulation dot10 20
Rl(config-subif)# ip add 192.168.20.1 255.255.255.0
R1(config-subif)# exit
Rl(config)#
R1(config)# interface G0/0/1.99
R1(config-subif)# Description Default Gateway for VLAN 99
R1(config-subif)# encapsulation dot10 99
R1(config-subif)# ip add 192.168.99.1 255.255.255.0
R1(config-subif)# exit
Rl(config)#
Rl(config)# interface G0/0/1
R1(config-if)# Description Trunk link to S1
Rl(config-if)# no shut
R1(config-if)# end
R1#
*Sep 15 19:08:47.015: %LINK-3-UPDOWN: Interface GigabitEthernet0/0/1, changed state to down
*Sep 15 19:08:50.071: %LINK-3-UPDOWN: Interface GigabitEthernet0/0/1, changed state to up
*Sep 15 19:08:51.071: %LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0/1,
changed state to up
R1#
```

### Router-on-a-Stick Inter-VLAN Routing Verify Connectivity Between PC1 and PC2

The router-on-a-stick configuration is complete after the switch trunk and the router subinterfaces have been configured. The configuration can be verified from the hosts, router, and switch.

From a host, verify connectivity to a host in another VLAN using the **ping** command. It is a good idea to first verify the current host IP configuration using the **ipconfig** Windows host command.

Next, use **ping** to verify connectivity with PC2 and S1, as shown in the figure.
The **ping** output successfully confirms inter-VLAN routing is operating.

```
C:\Users\PC1> ping 192.168.20.10
Pinging 192.168.20.10 with 32 bytes of data:
Reply from 192.168.20.10: bytes=32 time<1ms TTL=127
Ping statistics for 192.168.20.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss).
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
C:\Users\PC1>
C:\Users\PC1> ping 192.168.99.2
Pinging 192.168.99.2 with 32 bytes of data:
Request timed out.
Request timed out.
Reply from 192.168.99.2: bytes=32 time=2ms TTL=254
Reply from 192.168.99.2: bytes=32 time=1ms TTL=254
Ping statistics for 192.168.99.2:
    Packets: Sent = 4, Received = 2, Lost = 2 (50% loss).
Approximate round trip times in milli-seconds:
    Minimum = 1ms, Maximum = 2ms, Average = 1ms
C:\Users\PC1>
```

# 4.3 Inter-VLAN Routing using Layer 3 Switches

### Inter-VLAN Routing using Layer 3 Switches Layer 3 Switch Inter-VLAN Routing

Inter-VLAN routing using the router-on-a-stick method is simple to implement for a small to medium-sized organization. However, a large enterprise requires a faster, much more scalable method to provide inter-VLAN routing.

Enterprise campus LANs use Layer 3 switches to provide inter-VLAN routing. Layer 3 switches use hardware-based switching to achieve higher-packet processing rates than routers. Layer 3 switches are also commonly implemented in enterprise distribution layer wiring closets.


Capabilities of a Layer 3 switch include the ability to do the following:

- Route from one VLAN to another using multiple switched virtual interfaces (SVIs).
- Convert a Layer 2 switchport to a Layer 3 interface (i.e., a routed port). A routed port is similar to a physical interface on a Cisco IOS router.
- To provide inter-VLAN routing, Layer 3 switches use SVIs. SVIs are configured using the same **interface vlan** *vlan-id* command used to create the management SVI on a Layer 2 switch. A Layer 3 SVI must be created for each of the routable VLANs.



### Inter-VLAN Routing using Layer 3 Switches Layer 3 Switch Scenario


In the figure, the Layer 3 switch, D1, is connected to two hosts on different VLANs. PC1 is in VLAN 10 and PC2 is in VLAN 20, as shown. The Layer 3 switch will provide inter-VLAN routing services to the two hosts.



### Inter-VLAN Routing using Layer 3 Switches Layer 3 Switch Configuration

Complete the following steps to configure S1 with VLANs and trunking:

- Step 1. Create the VLANs. In the example, VLANs 10 and 20 are used.
- Step 2. Create the SVI VLAN interfaces. The IP address configured will serve as the default gateway for hosts in the respective VLAN.
- **Step 3**. Configure access ports. Assign the appropriate port to the required VLAN.
- Step 4. Enable IP routing. Issue the ip routing global configuration command to allow traffic to be exchanged between VLANs 10 and 20. This command must be configured to enable inter-VAN routing on a Layer 3 switch for IPv4.



### Inter-VLAN Routing using Layer 3 Switches Layer 3 Switch Inter-VLAN Routing Verification

Inter-VLAN routing using a Layer 3 switch is simpler to configure than the router-on-astick method. After the configuration is complete, the configuration can be verified by testing connectivity between the hosts.

- From a host, verify connectivity to a host in another VLAN using the ping command. It
  is a good idea to first verify the current host IP configuration using
  the ipconfig Windows host command.
- Next, verify connectivity with PC2 using the ping Windows host command.
   The successful ping output confirms inter-VLAN routing is operating.

### Inter-VLAN Routing using Layer 3 Switches Routing on a Layer 3 Switch


If VLANs are to be reachable by other Layer 3 devices, then they must be advertised using static or dynamic routing. To enable routing on a Layer 3 switch, a routed port must be configured.

A routed port is created on a Layer 3 switch by disabling the switchport feature on a Layer 2 port that is connected to another Layer 3 device. Specifically, configuring the **no switchport** interface configuration command on a Layer 2 port converts it into a Layer 3 interface. Then the interface can be configured with an IPv4 configuration to connect to a router or another Layer 3 switch.

### Inter-VLAN Routing using Layer 3 Switches Routing Scenario on a Layer 3 Switch

In the figure, the previously configured D1 Layer 3 switch is now connected to R1. R1 and D1 are both in an Open Shortest Path First (OSPF) routing protocol domain. Assume inter-VLAN has been successfully implemented on D1. The G0/0/1 interface of R1 has also been configured and enabled. Additionally, R1 is using OSPF to advertise its two networks, 10.10.10.0/24 and 10.20.20.0/24.

**Note**: OSPF routing configuration is covered in another course. In this module, OSPF configuration commands will be given to you in all activities and assessments. It is not required that you understand the configuration in order to enable OSPF routing on the Layer 3 switch.



### Inter-VLAN Routing using Layer 3 Switches Routing Configuration on a Layer 3 Switch

Complete the following steps to configure D1 to route with R1:

- **Step 1**. Configure the routed port. Use the **no switchport** command to convert the port to a routed port, then assign an IP address and subnet mask. Enable the port.
- Step 2. Enable routing. Use the **ip routing** global configuration command to enable routing.
- **Step 3**. Configure routing. Use an appropriate routing method. In this example, Single-Area OSPFv2 is configured
- Step 4. Verify routing. Use the show ip route command.
- **Step 5**. Verify connectivity. Use the **ping** command to verify reachability.

# 4.4 Troubleshoot Inter-VLAN Routing

#### Troubleshoot Inter-VLAN Routing Common Inter-VLAN Issues

There are a number of reasons why an inter-VAN configuration may not work. All are related to connectivity issues. First, check the physical layer to resolve any issues where a cable might be connected to the wrong port. If the connections are correct, then use the list in the table for other common reasons why inter-VLAN connectivity may fail.

Issue Type	How to Fix	How to Verify
Missing VLANs	•Create (or re-create) the VLAN if it does not exist. •Ensure host port is assigned to the correct VLAN.	show vlan [brief] show interfaces switchport ping
Switch Trunk Port Issues	<ul><li>Ensure trunks are configured correctly.</li><li>Ensure port is a trunk port and enabled.</li></ul>	show interface trunk show running-config
Switch Access Port Issues	<ul> <li>Assign correct VLAN to access port.</li> <li>Ensure port is an access port and enabled.</li> <li>Host is incorrectly configured in the wrong subnet.</li> </ul>	show interfaces switchport show running-config interface ipconfig
Router Configuration Issues	<ul> <li>Router subinterface IPv4 address is incorrectly configured.</li> <li>Router subinterface is assigned to the VLAN ID.</li> </ul>	show ip interface brief show interfaces

### 4.5 Module Practice and Quiz