



**FORTINET®**

# **FIREWALL IMPLEMENTATION LAB SETUP**

# TABLE OF CONTENTS

<b>1</b>	<b>Abstract</b>	<b>3</b>
<b>2</b>	<b>Introduction to Firewall?</b>	<b>5</b>
2.1	How Firewall works?	5
<b>3</b>	<b>Steps to setup Fortigate</b>	<b>7</b>
3.1	Prerequisites	7
3.2	Download FortiGate Virtual firewall	7
3.3	Configure Virtual network interfaces for FortiGate	9
3.4	<b>Deployment of FortiGate VM image in VMWare</b>	<b>11</b>
3.5	Configuring the Management Interface	14
3.6	Accessing FortiGate Firewall GUI	16
3.7	GUI Demonstration	18
<b>4</b>	<b>Implementing Firewall policies</b>	<b>22</b>
4.1	Connect Network Devices	22
4.2	Configure Network Interfaces	22
4.3	Add a Default Route	26
4.4	Create an IPV4 Firewall Policy	27
4.5	Create an IPv4 Dos Policy	30
4.6	Blocking Facebook with Web filter	34
4.7	Enable web Filter	35
4.8	Enable Default Web Filter Profile	36
4.9	Create Web Filter Security Policy	38
<b>5</b>	<b>Advance Policies</b>	<b>42</b>
5.1	Block Whole Social media using FortiGuard categories	42
5.2	Site-to-Site IPsec VPN Tunnel with two FortiGates	46
5.3	Simplifying Policies with Zone	52
<b>6</b>	<b>About Us</b>	<b>61</b>

# Abstract

In this publication, you will learn how to connect and configure a new FortiGate unit in NAT route mode to securely connect a private network to the internet.

In NAT route mode a FortiGate unit is installed as a gateway or router between two networks. In most cases it is used between private networks and the internet, this allows the Firewall to hide the IP addresses of the private network using Network Address Translation (NAT) and the various firewall Policy of FortiGate firewall as a Firewall Recipe.

# Introduction to Firewall

# Introduction to Firewall?

In the computing language, a firewall is a security software or hardware that can monitor and control network traffic, both incoming and outgoing. It establishes a kind of barrier between reliable internal and unknown external networks.

Therefore, a firewall, also known as a network firewall, is capable of preventing unauthorized access to/from private networks.

A network firewall is based on security rules to **accept**, **reject**, or **drop** specific traffic. The firewall aims to allow or deny the connection or request, depending on implemented rules.

## How Firewall works?


Basically, firewalls are divided into two parts

- Stateful: – Stateful firewalls are capable of monitoring whole network traffic, including their communication channels. These firewalls are also referred as dynamic packet filter as they filter traffic packets based on the context (it involves metadata of packets including ports and IP address belonging to that Endpoint) and state.
- Proxy: – Proxy Firewall can be Defined as, A firewall that can monitor and filter communication at the application level and protect the resources from unwanted dangerous traffic. A proxy firewall also is known as Application layer Firewall.

After some time in an inspection stateful firewall become more sophisticated and proxy Firewalls become too slow.

Today nearly all Firewalls are stateful and they are divided into two General Types.

- Host-based Firewalls
- Network Firewalls



# Steps to setup Fortigate

# Steps to setup Fortigate


## Prerequisites

To configure the virtual FortiGate Firewall on your system there are some prerequisites required for installation

- VMWare Workstation
- FortiGate Firewall VM Image
- 3 or more NIC (Network interface cards) E1000 compatible network cards
- Root privileges

## Download FortiGate Virtual firewall

First, we need to download the virtual FortiGate Firewall from the official FortiGate portal. To do this, visit [here](#), and then register or login into the account.



By creating an account or log in to the account go to Download > VM Images as shown in the image below.

The screenshot shows a browser window with the URL [www.hackingarticles.in](https://www.hackingarticles.in). The page title is "FortiCloud". The navigation bar includes "Home", "Asset", "Assistance", "Download" (which is highlighted with a red box), and "Feedback". A dropdown menu from "Download" contains "Firmware Images", "VM Images" (also highlighted with a red box), "FortiGuard Service Updates", "Firmware Image Checksums", and "HQIP Images". Below the menu, there's a banner with the text "Engineered for Remote and Secure Productivity" and a "LEARN HOW" button. The main content area is titled "Asset" and features a "Register/Activate Contracts" section with a paper airplane icon.

Further then Select Product: FortiGate > Select Platform: VMWare ESXi as shown in the image below. By default, you don't have any license associated with your virtual image so, you can go with the trial version or you can buy the license as per your requirement.

The screenshot shows the "Select Product" dropdown set to "FortiGate" and the "Select Platform" dropdown set to "VMWare ESXi". Under "FortiGate", the "6.4.3" version is selected and highlighted with a green background. The "File Information" and "Checksum" tables show two download options: one for "FGT\_VM64-v6-build1778-FORTINET.out (67.5 MB)" and another for "FGT\_VM64-v6-build1778-FORTINET.out.ovf.zip (66.96 MB)". Both download buttons are highlighted with red boxes.


After downloading the compressed FortiGate VM file you need to extract the compressed Zip file by using your favourite extractor and the extracted Zip file similarly looks like the below image

This PC > Downloads > FGT_VM64-v6-build1778-FORTINET.out.ovf				
	Name	Date modified	Type	Size
	datadrive	23-08-2010 23:02	VMDK File	70 KB
	FortiGate-VM64.hw07_vmxnet3	22-10-2020 02:32	Open Virtualizatio...	33 KB
	FortiGate-VM64.hw13	22-10-2020 02:32	Open Virtualizatio...	30 KB
	FortiGate-VM64.hw14	22-10-2020 02:32	Open Virtualizatio...	30 KB
	FortiGate-VM64.nsxt	22-10-2020 02:32	Open Virtualizatio...	14 KB
	FortiGate-VM64	22-10-2020 02:32	Open Virtualizatio...	27 KB
	FortiGate-VM64.vapp	22-10-2020 02:32	Open Virtualizatio...	44 KB
	fortios	22-10-2020 02:32	VMDK File	69,321 KB


## Configure Virtual network interfaces for FortiGate

Let's configure Virtual Network Adaptors as per your requirements.

To do this open VMware then go to Edit > Virtual Network Editor as shown in the image below



Further, then it will open another prompt that allows you to modify the network configuration. To make changes in network configuration it needs the Administrator privileges to provide Admin privileges click on change settings as shown below




Or also you can directly access the Virtual network editor app by click on Windows Start Button and search for Virtual Network Editor. If you are using Linux (i.e. Ubuntu) you can type the below command to open Virtual Network Editor.

```
sudo vmware-netcfg
```

By default, there are only two virtual network interfaces, i.e., *VMNet1* and *VMNet8*. So, click on the Add Network and make your virtual interface host only. After that, you have to provide a unique IP address of network devices to each network interface.


For example, I am going to use 192.168.200.0/24 for the *vmnet0* interface and so on...

Use Ip of your network devices or whatever as per your requirement. Similarly, you can add as much as network interfaces as you want but remember one thing all network configuration should be configured to Host-only and you can enable or disable DHCP service as per you system requirement.




# Deployment of FortiGate VM image in VMWare


Now it's time to deploy the FortiGate virtual firewall in VMWare Workstation. Just open the VMWare Workstation and go to **Files >> Open** (Ctrl+O) or go to the Home tab and select open a virtual Machine. Select the FortiGate-VM64.ovf file that you have downloaded from the official Website of FortiGate as shown below



Then after it will open another prompt of End User License Agreement accept it and move to next




On the next prompt Assign a Name for the new Virtual machine and a Storage Path then after select import as shown below




This process going to take some time, so have *patience*. After the successful completion of this process,

Now it's time to configure the Virtual Firewall resources by clicking on Edit virtual machine settings. just modify the assigned virtual network interfaces, memory, and processor by going to Edit virtual machine.



In my case, I'm giving 2GB RAM, 30 GB of Hard Disk, 1 Processor, and 6 different virtual network interfaces (VMNet2, VMNet3, VMNet4, VMNet11, VMnet11, VMnet12 to different network adaptors. Check the below image for reference.



# Configuring the Management Interface

We've just finished the deployment process of the FortiGate Firewall in the VMWare workstation. Let's configure an IP Address to the management interface. In manner to assign an IP Address to management interface firstly, we need login to the system with default credentials

**Login User:** – Admin

**Login Password:** – In this circumstance, we don't know the default password, Hit enter and change the password as shown below

```
Loading flatkc... ok
Loading /rootfs.gz...ok

Decompressing Linux... Parsing ELF... done.
Booting the kernel.

System is starting...
Serial number is FGUMEV9T3UJPII0A

FortiGate-VM64 login: admin
Password:
You are forced to change your password. Please input a new password.
New Password:
Confirm Password:
Welcome!

FortiGate-VM64 #
```

Let's check the system interfaces by running the following command

show system interface

```
FortiGate-VM64 # show system interface ←
name      Name.
fortilink static    0.0.0.0 0.0.0.0  169.254.1.1 255.255.255.0 up    disable
aggregate enable
port1   dhcp   0.0.0.0 0.0.0.0  192.168.200.128 255.255.255.0 up    disable ph
ysical enable
port2   static  0.0.0.0 0.0.0.0  0.0.0.0 0.0.0.0 up    disable physical enable
port3   static  0.0.0.0 0.0.0.0  0.0.0.0 0.0.0.0 up    disable physical enable
port4   static  0.0.0.0 0.0.0.0  0.0.0.0 0.0.0.0 up    disable physical enable
port5   static  0.0.0.0 0.0.0.0  0.0.0.0 0.0.0.0 up    disable physical enable
port6   static  0.0.0.0 0.0.0.0  0.0.0.0 0.0.0.0 up    disable physical enable
port7   static  0.0.0.0 0.0.0.0  0.0.0.0 0.0.0.0 up    disable physical enable
port8   static  0.0.0.0 0.0.0.0  0.0.0.0 0.0.0.0 up    disable physical enable
port9   static  0.0.0.0 0.0.0.0  0.0.0.0 0.0.0.0 up    disable physical enable
port10  static  0.0.0.0 0.0.0.0  0.0.0.0 0.0.0.0 up    disable physical ena
ble
--More--
```

Port 1 will be for the management interface so, assign a unique IP address to the management port and set to mode static. In this example our IP Address will 192.168.200.128/24 so, the default gateway will be 192.168.200.1. To assign IP Address to management port run the following command as shown below

```
config system interface  
edit port1  
set mode static  
set ip 192.168.200.128 255.255.255.0  
set allowaccess http https telnet ssh ping  
end
```



```
FortiGate-VM64 # config system interface ←  
FortiGate-VM64 (interface) # edit port1 ←  
FortiGate-VM64 (port1) # set mode static ←  
FortiGate-VM64 (port1) # set ip 192.168.200.128 255.255.255.0 ←  
FortiGate-VM64 (port1) # set allowaccess http https telnet ssh ping ←  
FortiGate-VM64 (port1) # end ←  
FortiGate-VM64 # _
```

Also, we can verify the make changes of system interfaces by running the following command

```
show system interface
```

```
FortiGate-VM64 # show system interface ←
config system interface
    edit "port1"
        set vdom "root"
        set ip 192.168.200.128 255.255.255.0
        set allowaccess ping https ssh http telnet
        set type physical
        set snmp-index 1
    next
    edit "port2"
        set vdom "root"
        set type physical
        set snmp-index 2
    next
    edit "port3"
        set vdom "root"
        set type physical
        set snmp-index 3
    next
    edit "port4"
        set vdom "root"
        set type physical
        set snmp-index 4
    next
--More-- _
```

## Accessing FortiGate Firewall GUI

Let's check our firewall configuration by accessing the FortiGate Firewall GUI. Before accessing the GUI first, we will check the connectivity to our Firewall using the ping utility by running the following command

```
execute ping 192.268.200.128
```

```
FortiGate-VM64 # execute ping 192.168.200.128 ←
PING 192.168.200.128 (192.168.200.128): 56 data bytes
64 bytes from 192.168.200.128: icmp_seq=0 ttl=255 time=0.0 ms
64 bytes from 192.168.200.128: icmp_seq=1 ttl=255 time=0.0 ms
64 bytes from 192.168.200.128: icmp_seq=2 ttl=255 time=0.0 ms
64 bytes from 192.168.200.128: icmp_seq=3 ttl=255 time=0.0 ms
64 bytes from 192.168.200.128: icmp_seq=4 ttl=255 time=0.0 ms

--- 192.168.200.128 ping statistics ---
5 packets transmitted, 5 packets received, 0% packet loss
round-trip min/avg/max = 0.0/0.0/0.0 ms

FortiGate-VM64 #
```


As we can see the IP Address is reachable which means it is working properly now, we will access the FortiGate Firewall GUI using its management interface IP address.

<https://192.168.200.128>

use the same login credential that we have set up on CLI


**Username:** – admin

**Password:** – 123




By logging in to the firewall it will open a setup Prompt where we need to specify the Hostname, change password upgrade firmware, and Dashboard setup

By default, this FortiGate will use the serial number/model as its hostname. To make it more identifiable set a descriptive hostname as shown below




Already we have changed the password in Firewall CLI and also, we have already downloaded the latest version of the firewall, so it automatically skips you to the last step to Dashboard setup. Select it to Optimal or Comprehensive as per your requirements



After selecting the type of Dashboard hit ok and finish the setup.

## GUI Demonstration

The GUI contains the following main menus, which provide access to configuration options for most FortiOS features:



**Dashboard:** – The dashboard displays various widgets that display important system information and allow you to configure some system options.

**Security Fabric:** – Access the physical topology, logical topology, audit, and settings of the Fortinet Security Fabric.

**FortiView:** – A collection of dashboards and logs that give insight into network traffic, showing which users are creating the most traffic, what sort of traffic it is, when the traffic occurs, and what kind of threat the traffic may pose to the network.

**Network:** – Options for networking, including configuring system interfaces and routing options.

**System:** – Configure system settings, such as administrators, FortiGuard, and certificates.

**Policy & Objects:** – Configure firewall policies, protocol options, and supporting content for policies, including schedules, firewall addresses, and traffic shapers.

**Security Profiles:** – Configure your FortiGate's security features, including Antivirus, Web Filter, and Application Control.

**VPN:** – Configure options for IPsec and SSL virtual private networks (VPNs).

**User & Device:** – Configure user accounts, groups, and authentication methods, including external authentication and single sign-on (SSO).

**WiFi & Switch Controller:** – Configure the unit to act as a wireless network controller, managing the wireless Access Point (AP) functionality of FortiWiFi and FortiAP units. On certain FortiGate models, this menu has additional features allowing for FortiSwitch units to be managed by the FortiGate.

**Log & Report:** – Configure logging and alert email as well as reports.

**Monitor:** – View a variety of monitors, including the Routing Monitor, VPN monitors for both IPsec and SSL, monitors relating to wireless networking, and more.

## Dashboard Demonstration

FortiGate dashboards can have a Network Operations Centre (NOC) or responsive layout.

- On a responsive dashboard, the number of columns is determined by the size of the screen. Widgets can only be resized horizontally, but the dashboard will fit on all screen sizes.
- On a NOC dashboard, the number of columns is explicitly set. Widgets can be resized both vertically and horizontally, but the dashboard will look best on the screen size that it is configured for.

Multiple dashboards of both types can be created, for both individual VDOMs and globally.

- Widgets are interactive; clicking or hovering over most widgets shows additional information or links to relevant pages.
- Widgets can be reorganized by clicking and dragging them around the screen.

Four dashboards are available by default: Status, Network, Security, and System Events

The Status dashboard includes the following widgets by default:

**System Information:** – The System Information widget lists information relevant to the FortiGate system, including hostname, serial number, and firmware. Clicking on the widget provides links to configure system settings and update the device firmware.

**Licenses:** – The License widget lists the status of various licenses, such as FortiCare Support and IPS. The number of used and available FortiTokens is also shown. Clicking on the widget provides a link to the FortiGuard settings page.

**Virtual Machine:** – The VM widget (shown by default in the dashboard of a FortiOS VM device) includes:

- License status and type
- vCPU allocation and usage
- RAM allocation and usage
- VMX license information (if the VM supports VMX)

Clicking on an item in the widget provides a link to the FortiGate VM License page, where license files can be uploaded.

**FortiGate Cloud:** – This widget displays the FortiGate Cloud and FortiSandbox Cloud status.

**Security Fabric:** – The Security Fabric widget displays a visual summary of the devices in the Fortinet Security Fabric.

Clicking on a product icon provides a link to a page relevancy to that product. For example, clicking the FortiAnalyzer shows a link to log settings.

**Security Rating:** – The Security Rating widget shows the security rating for your Security Fabric. It can show the current rating percentile, or historical security rating score or percentile charts.

**Administrators:** – This widget allows you to see logged-in administrators, connected administrators, and the protocols used by each. Clicking in the widget provides links to view active administrator sessions, and to open the FortiExplorer page on the App Store.

**CPU:** – This widget shows real-time CPU usage over the selected time frame. Hovering over any point on the graph displays the percentage of CPU power used at that specific time. It can be expanded to occupy the entire dashboard.

**Memory:** – This widget shows real-time memory usage over the selected time frame. Hovering over any point on the graph displays the percentage of the memory used at that specific time. It can be expanded to occupy the entire dashboard.

**Sessions:** – This widget shows the current number of sessions over the selected time frame. Hovering over any point on the graph displays the number of sessions at that specific time. It can be expanded to occupy the entire dashboard.

The Security dashboard includes the following widgets by default:

- **Top Compromised Hosts by Verdict:** – This widget lists the compromised hosts by verdict. A FortiAnalyzer is required. It can be expanded to occupy the entire dashboard.
- **Top Threats by Threat Level:** – This widget lists the top threats by threat level, from FortiView. It can be expanded to occupy the entire dashboard.
- **FortiClient Detected Vulnerabilities:** – This widget shows the number of vulnerabilities detected by FortiClient. FortiClient must be enabled. Clicking on the widget provides a link to view the information in FortiView.
- **Host Scan Summary:** – This widget lists the total number of hosts. Clicking on the widget provides links to view vulnerable devices in FortiView, FortiClient monitor, and the device inventory.
- **Top Vulnerable Endpoint Devices by Detected Vulnerabilities:** – This widget lists the top vulnerable endpoints by the detected vulnerabilities, from FortiView. It can be expanded to occupy the entire dashboard.

The System Events dashboard includes the following widgets by default:

- **Top System Events by Events:** – This widget lists the top system events, sorted by the number of events. It can be expanded to occupy the entire dashboard. Double click on an event to view the specific event log.
- **Top System Events by Level:** – This widget lists the top system events, sorted by the events' levels. It can be expanded to occupy the entire dashboard. Double click on an event to view the specific event log.

# Implementing Firewall Policies

# Implementing Firewall policies

## Connect Network Devices

First, you need to connect a physical firewall or FortiGate into your network setup. On the place of a physical firewall, we are using a Virtual FortiGate Firewall to get hands-on.

Connect the FortiGate internet facing interface usually WAN1 to your ISP supplied equipment and connect the PC to FortiGate using an internal port usually port 1 or as per your requirement.

Power on ISP equipment, firewall and the PC and they are now in the internal network.

## Configure Network Interfaces

Now you need to configure the FortiGate's Network interfaces.

**Go to network > Interfaces**

The screenshot shows the FortiGate VM64 web interface. The left sidebar has a 'Network' section with 'Interfaces' selected, indicated by a red arrow and highlighted with a red box. The main content area displays a table of network interfaces:

Name	Type	Members	IP/Netmask
fortilink	802.3ad Aggregate		Dedicated to FortiSwitch
port1	Physical Interface		192.168.200.129/255.255.255.0
port2	Physical Interface		192.168.137.138/255.255.255.0
port3	Physical Interface		192.168.237.138/255.255.255.0

and edit the internet-facing interface set the addressing mode to manual and the IP/Netmask to the public IP address provided by your ISP. Here in my case, I'm considering port2 as an internet-facing interface. Provide Administrative access as per your requirement to the network


The screenshot shows the FortiGate VM64 Ignite interface configuration page. The left sidebar navigation includes: Dashboard, Security Fabric, Network (selected), Interfaces (selected), DNS, Packet Capture, SD-WAN Zones, SD-WAN Rules, Performance SLA, Static Routes, Policy Routes, RIP, OSPF, BGP, Multicast, System, Policy & Objects, Security Profiles, VPN, User & Authentication, and Log & Report.

The main content area is titled "Edit Interface" for "port2". The "Name" field is set to "port2". The "Type" is "Physical Interface". The "VRF ID" is "0". The "Role" dropdown is set to "WAN" (highlighted with a red box). The "Estimated bandwidth" dropdown shows options: WAN (selected), LAN, DMZ, and Undefined. The "Address" section shows "Addressing mode" as "Manual" (highlighted with a red box), "IP/Netmask" as "192.168.137.138/255.255.255.0" (highlighted with a red box), and "Secondary IP address" as off. The "Administrative Access" section for IPv4 includes checkboxes for HTTPS, SSH, RADIUS Accounting, PING, SNMP, and Security Fabric Connection. It also has "Use VDOM Setting" buttons for Enable and Disable. The "Receive LLDP" and "Transmit LLDP" sections are also present. The "Traffic Shaping" section shows "Outbound shaping profile" as off. The "Miscellaneous" section includes a "Comments" field with "internal-server" and a "Status" button labeled "Enabled" (highlighted with a red box).

Then save the configuration and then similarly edit the LAN interface which may be called internal network. Set the interfaces Role to the LAN or WAN and then set the addressing mode to manual and set the IP/Netmask to the private IP address that you want to assign to the FortiGate

FortiGate VM64												
	1	3	5	7	9	11	13	15	17	19	21	23
	port2	port3	port4	port5	port6	port7	port8	port9				
	port2	Physical Interface				192.168.137.138/255.255.255.0		PING	HTTPS	SSH	SNMP	TELNET
	port3	Physical Interface				192.168.237.138/255.255.255.0		PING	HTTPS	SSH	SNMP	
	port4	Physical Interface				192.168.70.138/255.255.255.0		PING	HTTPS	SSH	SNMP	
	port5	Physical Interface				192.168.80.138/255.255.255.0		PING	HTTPS	SSH	SNMP	HTTP
	port6	Physical Interface				10.1.20.138/255.255.255.0		PING	HTTPS	SSH	SNMP	HTTP
	port7	Physical Interface				0.0.0.0/0.0.0.0						
	port8	Physical Interface				0.0.0.0/0.0.0.0						
	port9	Physical Interface				0.0.0.0/0.0.0.0						

If you need your FortiGate to provide IP addresses to devices connected to internal network enable the DHCP server and then save the configuration as shown below.



Changing the default IP of your interfaces is recommended for the security measures. But you are connected to the FortiGate through that interface the FortiGate will log you out and you must navigate to the new IP address assigned to the interface and login again.

## Add a Default Route

Now Go to Network > Static Routes and create a new Route to allow your FortiGate to reach the internet


The screenshot shows the FortiGate VM64 Ignite web interface. On the left, there's a navigation menu under the 'Network' section. The 'Static Routes' option is highlighted with a red box and has a red arrow pointing down to it from the 'Network' section. At the top right, there are buttons for 'Create New', 'Edit', 'Clone', 'Delete', and 'Search'. Below these buttons, there's a table header for 'IPv4' with columns: Destination, Gateway IP, Interface, and Status. A single entry is shown: Destination 0.0.0.0/0, Gateway IP 192.168.137.1, Interface port2, and Status Enabled.

Set destination to subnet and enter IP/Netmask of Eight Zeros. Set the Gateway to the Gateway IP provided by your ISP and the interfaces to the internet-facing interface then save the Route.

The screenshot shows the 'New Static Route' dialog box. It has fields for Destination (set to Subnet 0.0.0.0/0.0.0), Gateway Address (set to 192.168.80.1), Interface (set to port5), Administrative Distance (set to 10), Comments (internal network), and Status (Enabled). There's also an 'Advanced Options' button and an 'OK' button at the bottom, which is highlighted with a red box.

## Create an IPv4 Firewall Policy

Firewall policy designed in a manner to examine Network Traffic using policy statements to block unauthorized access while permitting authorized communication.



Go to Policy & Objects > Firewall Policy and create a new policy which allow internet traffic through the FortiGate.

The screenshot shows the FortiGate VM64 interface with the following navigation bar:

- Dashboard
- Security Fabric
- Network
- System
- Policy & Objects (highlighted with a red arrow)
- Firewall Policy (highlighted with a red box)
- IPv4 DoS Policy
- Addresses

On the right side, there is a toolbar with buttons for Create New (highlighted with a red box), Edit, Delete, Policy Lookup, and Interface Pair View (selected). Below the toolbar is a table with columns Name, Source, and Destination. A single row is shown for the Implicit policy, which has 1 rule and applies to all sources and destinations.

Name	Source	Destination
Implicit 1	Implicit Deny	all

Name the policy as "Internet-Traffic" or whatever you want. Set the incoming interface to the "Internal interface" and outgoing interface to the internet facing interface. Set the rest to allow "ALL" Traffic or you can select multiple rules by selecting the + icon and the action to "Accept" enable the "NAT" and make sure "Use Outgoing Interface Address is enabled"


**New Policy**

Name	internet access
Incoming Interface	port1
Outgoing Interface	port2
Source	all
Destination	all
Schedule	always
Service	DNS HTTP HTTPS
Action	<input checked="" type="checkbox"/> ACCEPT <input type="checkbox"/> DENY
Inspection Mode	Flow-based <input type="radio"/> Proxy-based
Firewall / Network Options	
NAT	<input checked="" type="checkbox"/>
IP Pool Configuration	<input type="checkbox"/> Use Outgoing Interface Address

**Select Entries**

- Search
- SERVICE (61)**
  - General (5)
    - \*  ALL
    - ALL\_ICMP
    - ALL\_ICMP6
    - ALL\_TCP
    - ALL\_UDP
  - Web Access (2)
    - HTTP
    - HTTPS
  - File Access (8)
    - AFS3
    - FTP
    - FTP\_GET
    - FTP\_PUT
    - NFS
    - SAMBA
    - SMB
    - TFTP
  - Email (6)
    - IMAP
    - IMAPS

Scroll down to view the logging options to Log and track internet traffic “enable Log Allowed Traffic and select All session”



After saving it you can check your saved policy is going back to a firewall policy

Firewall Policies								
Name	Source	Destination	Schedule	Action	NAT	Security Profiles	Log	Interface Pair View
internet-traffic	all	all	always	ALL	ACCEPT	Enabled	no-inspection	All
Implicit	all	all	always	ALL	DENY			Enabled


As you can see the policy successfully enabled.

## Create an IPv4 Dos Policy

Dos policy is a traffic anomaly detection feature to identify network traffic that does not fit known or common traffic patterns. Dos policies are used to apply Dos anomaly checks to network traffic based on the FortiGate interface. A common example of anomalous traffic is the Dos (Denial of Service) Attack. A denial of service occurs when an attacking system starts an abnormally large number of sessions with the target system and resultant a large number of sessions slow down or disables the target system.

### To configure IPV4 policy

- Go to Policy & Objects > IPv4 Dos Policy
- To create a new policy, select the Create New icon in the top left side of the right window.



Set the incoming interface parameter by using drop-down menu to select a single interface.  
Set the Source Address, Destination Address, and Service to “ALL”. Single or multiple options can be selected as per your requirement.

Set the parameters for various type of Traffic Anomalies.

The breakup of traffic anomalies table is divided into 2 parts.

- L3 Anomalies
- L4 Anomalies

Here is the list of Anomaly profile that includes:

#### L3 Anomalies

- ip\_src\_session
- ip\_dst\_session

New Policy

Name	Dos-protection-policy	
Incoming Interface	port1	▼
Source Address	all	x
Destination Address	all	x
Service	ALL	x

L3 Anomalies

Name	Action	Threshold
ip_src_session	Disable Block Monitor	5000
ip_dst_session	Disable Block Monitor	5000

#### L4 Anomalies

- tcp\_syn\_flood
- tcp\_port\_scan
- tcp\_src\_session
- tcp\_dst\_session
- udp\_flood
- udp\_scan
- udp\_src\_session
- udp\_dst\_session
- icmp\_flood
- icmp\_sweep
- icmp\_src\_session

- sctp\_flood
- sctp\_scan
- sctp\_src\_session
- sctp\_dst\_session

Name	Logging	Action			Threshold
		Disable	Block	Monitor	
tcp_syn_flood	<input checked="" type="checkbox"/>	Disable	Block	Monitor	2000
tcp_port_scan	<input checked="" type="checkbox"/>	Disable	Block	Monitor	1000
tcp_src_session	<input type="checkbox"/>	Disable	Block	Monitor	5000
tcp_dst_session	<input type="checkbox"/>	Disable	Block	Monitor	5000
udp_flood	<input checked="" type="checkbox"/>	Disable	Block	Monitor	2000
udp_scan	<input checked="" type="checkbox"/>	Disable	Block	Monitor	2000
udp_src_session	<input type="checkbox"/>	Disable	Block	Monitor	5000
udp_dst_session	<input type="checkbox"/>	Disable	Block	Monitor	5000
icmp_flood	<input checked="" type="checkbox"/>	Disable	Block	Monitor	250
icmp_sweep	<input type="checkbox"/>	Disable	Block	Monitor	100
icmp_src_session	<input type="checkbox"/>	Disable	Block	Monitor	300
icmp_dst_session	<input type="checkbox"/>	Disable	Block	Monitor	1000

OK Cancel

It all your choice whether or not to enable this policy and default is enabled. Here in our case, we have blocked some of the actions with the limited threshold values to check whether these policies working or not.

All Anomalies have the following parameters that can be set on Per Anomaly or Per Column Basis

- Status: – from this menu you can enable or disable the indicated profile.
- Logging: – Enable or Disable tracking and logging of the indicated profile being triggered.
- Action: – choices yours whether to pass or block traffic when it reaches the threshold limit.
- Threshold: – It is the number of anomalous packets detected before triggering the action.

And at last, select the ok button and save the policy.

Policy List					
ID	Name	Interface	Source Address	Destination Address	Service
1	Dos-protection-policy	port1	all	all	ALL

As we can see Dos-protection-Policy is successfully deployed.

Let's check these policies are truly protect the network from Dos attacks or not.

Hmm, exited

Let's do it

Fire up the Attacker Machine kali Linux and run the following command

```
hping -c 15000 -d 120 -S -w 64 -p 80 -flood --rand-source 192.168.200.128
```

where 192.168.200.128 is the management IP of FortiGate


```
(root💀 kali)-[~/home/lucifer]
# hping3 -c 15000 -d 120 -S -w 64 -p 80 --flood --rand-source 192.168.200.128
HPING 192.168.200.128 (eth0 192.168.200.128): S set, 40 headers + 120 data bytes
hping in flood mode, no replies will be shown
^@^C
--- 192.168.200.128 hping statistic ---
10816342 packets transmitted, 0 packets received, 100% packet loss
round-trip min/avg/max = 0.0/0.0/0.0 ms
[root💀 kali]-[~/home/lucifer]
#
```

As we can see it blocks whole traffic that means it works properly.

## Blocking Facebook with Web filter

In this part, we are going to explain how to use a static URL filter to block access to Facebook and its subdomain in our network.

With the help of SSL inspection, you can also ensure that Facebook and its subdomains are also blocked whenever it will be accessed through HTTPS.



## Enable web Filter

Go to **system > feature Visibility** and enable the Web Filter Feature

The screenshot shows the FortiGate VM64 interface. On the left, there's a navigation menu under the 'System' section. The 'Feature Visibility' option is highlighted with a red box and an arrow pointing to it from the text above. In the main panel, under 'Feature Visibility', the 'Web Filter' feature is shown as being enabled (green switch). Other features listed include 'Web Application Firewall' (disabled), 'Advanced Endpoint Control' (disabled), 'Allow Unnamed Policies' (disabled), 'Certificates' (enabled), 'DNS Database' (disabled), 'DoS Policy' (enabled), 'Email Collection' (enabled), and 'FortiExtender' (disabled).

Feature Visibility	
<input type="checkbox"/>	Web Application Firewall
<input checked="" type="checkbox"/>	Web Filter

Additional Features	
<input type="checkbox"/>	Advanced Endpoint Control
<input type="checkbox"/>	Allow Unnamed Policies
<input checked="" type="checkbox"/>	Certificates
<input type="checkbox"/>	DNS Database
<input checked="" type="checkbox"/>	DoS Policy
<input checked="" type="checkbox"/>	Email Collection
<input type="checkbox"/>	FortiExtender

## Enable Default Web Filter Profile


Go to **Security profiles > Web filter** and edit the default Web filter profile

The screenshot shows the FortiGate VM64 interface. On the left, there's a navigation menu with items like Dashboard, Security Fabric, Network, System, Policy & Objects, Security Profiles (which has a red arrow pointing to it), AntiVirus, Web Filter (which has a red box around it), and DNS Filter. The main content area shows a table of security profiles. One row is highlighted with a yellow background: 'WEB default' with 'Default web filtering.' in the comments. Above the table are buttons for 'Create New', 'Edit' (which is also highlighted with a red box), 'Clone', and 'Delete'. A search bar is also present.


Now go to Static URL filter, select the URL filter and then select “create”.

The screenshot shows the 'Static URL Filter' configuration page. It includes settings for 'Block invalid URLs' (disabled) and 'URL Filter' (enabled). Below these are buttons for 'Create New', 'Edit', and 'Delete'. A search bar is available. A table lists URL filters, showing one entry: 'No results'. At the bottom, there are options for 'Block malicious URLs discovered by FortiSandbox' (disabled) and 'Content Filter' (disabled).

Further then Set URL to “facebook.com”, set Type to “Wildcard”, set Action to “Block” and set status to “Enable”.



save it by selecting OK



Now you have successfully enabled web filter to block Facebook.

# Create Web Filter Security Policy

Go to **Policy & Objects > Firewall Policy** and **Create a New policy**.


The screenshot shows the FortiGate VM64 interface. The left sidebar has a red arrow pointing to the 'Policy & Objects' section, which is expanded to show 'Firewall Policy'. A red box highlights the '+ Create New' button at the top of the main content area. The main content area displays a table of firewall policies:

Name	Source	Destination	Schedule
port1 → port1 ①	internet access	all	always
port1 → port2 ①	mobile	FABRIC_DEVICE	all
Implicit ①			

Give the name to the policy “No-Facebook-Internet-Access” to make it identifiable.

Set **Incoming Interface** to the internal network and set **Outgoing Interface** to the Internet-facing interface. Set the rest to allow “**ALL**” Traffic or you can select multiple rules by selecting the + icon and the action to “**Accept**” enable the “**NAT**” and make sure “**Use Outgoing Interface Address is enabled**”


Under Security Profiles, enable “Web Filter” and select the default web filter profile.



Now we have successfully deployed the policy that block the user to visit Facebook and its subdomains. But don't forget one important thing this policy won't work until it is on the top of list of deployed policies. Confirm this by viewing policies “**By Sequence**”.

Name	From	To	Source	D...	Schedule	Service	Action	NAT	Security
internet access	port1	port1	all	all	always	DNS HTTP HTTPS	✓ ACCEPT	✓ Enabled	SSL cert
mobile	port1	port2	FABR...	all	always	DNS HTTP HTTPS	✓ ACCEPT	✓ Enabled	WEB default SSL cert
No-Facebook-i	port1	port2	all	all	always	ALL	✓ ACCEPT	✓ Enabled	WEB default SSL cert
Implicit Deny	any	any	all	all	always	ALL	✗ DENY		

To move Policy up or down, select the policy and drag it up or down as per your requirement as shown below



Name	From	To	Source	Dest	Schedule	Service	Action	NAT	Sec
No-Facebook-i	port1	port2	all	all	always	ALL	✓ ACCEPT	✓ Enabled	WEB SSL
internet access	port1	port1	all	all	always	DNS HTTP HTTPS	✓ ACCEPT	✓ Enabled	SSL
mobile	port1	port2	FABR...	all	always	DNS HTTP HTTPS	✓ ACCEPT	✓ Enabled	WEB SSL
Implicit Deny	any	any	all	all	always	ALL	✗ DENY		

Now this policy is in effect and successfully enabled.

# Advance Policies


# Advance Policies

## Block Whole Social media using FortiGuard categories

In this part, we are going to explain how to block access to social media websites using FortiGuard categories.

Must remind one thing an active license of FortiGuard web filtering service is required for using this type of function.

Web filtration with FortiGuard categories enables you to take action against a group of websites on the other hand a static URL filter is intended to block or monitor specific URL.




### Enable web Filter

Go to **system > feature Visibility** and enable the **Web Filter Feature**

## Edit Default Web Filter Profile


Go to **Security Profiles > Web Filter** and edit the Default web filter profile and make sure that “**FortiGuard category-based**” filter service is enabled.

Right-click on **General interest** FortiGuard category. scroll down to **Social networking** subcategory and select action to “**Block**” as shown below.




## Add Web Filter Profile to Internet Access Policy

Go to **Policy & objects > Firewall Policy** and create a new policy



Give the name to the policy “Blocking-social-media” to make it identifiable. Set incoming interface to internal network and outgoing interface to internet facing interface. Set the rest to allow “ALL” Traffic or you can select multiple rules by selecting the + icon and the action to “Accept” enable the “NAT” and make sure “Use Outgoing Interface Address is enabled”.

Scroll down to Security profiles enable Web Filter and select default web filter profile and save the configuration.




Now you have successfully enabled the social media blocking policy to move this policy to Top of the list to make it effective.

<a href="#">Create New</a> <a href="#">Edit</a> <a href="#">Delete</a> <a href="#">Policy Lookup</a> <input type="text"/> Search			
Interface Pair View <a href="#">By Sequence</a>			
Name	From	To	Source
Blocking-social-media	port1	wan (port2)	all
No-Facebook-internet-access	port1	wan (port2)	all
internet access	port1	port1	all
mobile	port1	wan (port2)	FABRIC_DEVICE
vpn_HQ-to-Branch_local_0	port1	HQ-to-Branch	HQ-to-Branch_local
vpn_HQ-to-Branch_remote_0	HQ-to-Branch	port1	HQ-to-Branch_remote
vpn_Branch-to-HQ_local_0	wan (port2)	Branch-to-HQ	Branch-to-HQ_local
vpn_Branch-to-HQ_remote_0	Branch-to-HQ	wan (port2)	Branch-to-HQ_remote
Implicit Deny	<input type="checkbox"/> any	<input type="checkbox"/> any	all

# Site-to-Site IPsec VPN Tunnel with two FortiGates

In this part, we are going to configure a site-to-site IPsec VPN tunnel to allow communication between two networks that are situated behind different FortiGates.


We are going to create an IPsec VPN tunnel between two FortiGates one is called HQ (Headquarter) another is called Branch.



# Configure IPsec VPN on HQ

On HQ FortiGate, GO to VPN > IPsec wizard and create a new tunnel.


In the section, VPN setup describe a VPN name to make it identifiable, set Template type to Site-to-Site, set NAT configuration to NO NAT between sites and set Remote Device type to FortiGate.




In the Authentication Section, set IP address to Public IP address of the Branch FortiGate.

After entering the IP address an interface is assigned to the outgoing interface. You can change the interface by the drop-down menu as per your requirement.


Set a secure **Pre-shared** key that is used to connect and verification for both FortiGates.




In the section of Policy and Routing set Local interface to “LAN” in my case “Port1” is dedicated to the LAN and local subnets will add automatically further then set “Remote Subnets” to the Branch network and set internet access to “None” as shown below



Review the configuration summary that you configured that shows the interfaces, firewall addresses, routes, and policies after verifying it select create an icon




After creating the VPN, you can verify the details as shown below.




## Configure IPsec VPN on a branch

On Branch FortiGate, GO to VPN > IPsec wizard and create a new tunnel.


In the section, VPN setup describes a VPN name to make it identifiable, set Template type to Site-to-Site, set NAT configuration to “NO NAT” between sites and set Remote Device type to FortiGate.




In the Authentication Section, set IP address to Public IP address of the Branch FortiGate. After entering the IP address an interface is assigned to the outgoing interface. You can change the interface by the drop-down menu as per your requirement. Set a secure **Pre-shared** key that was used on the VPN of HQ FortiGate.



Review the configuration summary that you configured that shows the interfaces, firewall addresses, routes, and policies after verifying it select create icon



After creating the VPN, you can verify the details as shown below.



You can also verify it by users of the Headquarter (HQ) can access resources on the Branch internal network and so on Vice Versa.

To test the connection, ping HQ LAN interface from the device Branch Internal network.

Or you Can also check the LOG events of VPN by going to Log & Report > Events > VPN Events and where you can see every Single logs of VPN.

The screenshot shows the FortiGate VM64 dashboard titled 'Branch-FortiGate'. The left sidebar includes links for Dashboard, Security Fabric, Network, System, Policy & Objects, Security Profiles, VPN, User & Authentication, and Log & Report (which is expanded to show Forward Traffic, Local Traffic, Sniffer Traffic, and Events). The Events section is highlighted with a red box. The main area displays a log table with columns: Date/Ti..., Level, Action, Status, Message, and VPN Tunnel. One log entry is highlighted with a yellow background and a red border: '2020/11/2...' (Level: negotiate, Status: success, Message: 'progress IPsec phase 1', VPN Tunnel: 'HQ-to-Branch').

Date/Ti...	Level	Action	Status	Message	VPN Tunnel
2020/11/2...	[progress bar]	negotiate	success	progress IPsec phase 1	HQ-to-Branch
2020/11/2...	[progress bar]	negotiate	failure	progress IPsec phase 1	Branch-to-HQ
2020/11/2...	[progress bar]	negotiate	negotiat...	IPsec phase 1 error	Branch-to-HQ
2020/11/2...	[progress bar]	negotiate	failure	progress IPsec phase 1	Branch-to-HQ
2020/11/2...	[progress bar]	negotiate	negotiat...	IPsec phase 1 error	Branch-to-HQ
2020/11/2...	[progress bar]	negotiate	failure	progress IPsec phase 1	Branch-to-HQ
2020/11/2...	[progress bar]	negotiate	negotiat...	IPsec phase 1 error	Branch-to-HQ
2020/11/2...	[progress bar]	negotiate	success	progress IPsec phase 1	Branch-to-HQ
2020/11/2...	[progress bar]	negotiate	success	progress IPsec phase 1	Branch-to-HQ
2020/11/2...	[progress bar]	negotiate	success	progress IPsec phase 1	Branch-to-HQ
2020/11/2...	[progress bar]	negotiate	failure	progress IPsec phase 1	Branch-to-HQ

# Simplifying Policies with Zone

In this Part, we're Going to Explain how to group multiple interfaces into Zone to simplify Firewall Policies.


By creating multiple VLANs we are going to add them into a zone, so that we can just use the single zone object as a source interface in our firewall policy, rather than having to reference each interface separately.

## Create VLAN Interfaces


Go to Network > interfaces and create a new interface

The screenshot shows the FortiGate VM64 interface configuration screen. The left sidebar has 'Network' selected, and 'Interfaces' is highlighted with a red box. A dropdown menu is open over the 'Create New' button, with 'Interface' selected and highlighted with a red box. The main pane displays a grid of 24 ports, with port 1 highlighted in green. Below the grid, there are tabs for 'Aggregate' (selected) and 'Physical Interface'. Under 'Aggregate', there is one entry for 'fortilink'. Under 'Physical Interface', there is one entry for 'port1'.

Enter the name for the interface VLAN10 or whatever you want, select the type to VLAN, select Interface to LAN, enter the VLAN ID, enter the VRF Id. assign the Role to LAN, set the Addressing mode to manual, enter the IP/Netmask provided by your ISP and select the Administrative Access to HTTPS, PING



Enable the DHCP server and assign the address range further then save the configuration.



Next, create another by making the same selections...

Go to Network > interfaces and create a new interface.

Enter the name for the interface VLAN20 or whatever you want, select the type to VLAN, select Interface to LAN, enter the VLAN ID, enter the VRF Id. assign the Role to LAN, set the Addressing mode to manual, enter the IP/Netmask provided by your ISP and select the Administrative Access to HTTPS, PING

New Interface

Name	VLAN20
Alias	
Type	VLAN
Interface	LAN (port4)
VLAN ID	20
VRF ID	10
Role	LAN

Address

Addressing mode	Manual
IP/Netmask	192.168.20.1/24

Create address object matching subnet

Name	VLAN20 address
Destination	192.168.20.1/24
Secondary IP address	<input type="checkbox"/>

Administrative Access

IPv4	<input checked="" type="checkbox"/> HTTPS	<input checked="" type="checkbox"/> PING	<input type="checkbox"/> FMG-Access
	<input type="checkbox"/> SSH	<input type="checkbox"/> SNMP	<input type="checkbox"/> FTM

Enable the DHCP server and assign the address range further then save the configuration.

DHCP Server

Address range	192.168.20.2-192.168.20.254
Netmask	255.255.255.0
Default gateway	Same as Interface IP
DNS server	Same as System DNS
Lease time	604800 second(s)

+ Advanced

Network

Device detection	<input checked="" type="checkbox"/>
Security mode	<input type="checkbox"/>

Traffic Shaping

Outbound shaping profile	<input type="checkbox"/>
--------------------------	--------------------------

Miscellaneous

Comments	0/255
Status	<input checked="" type="button"/> Enabled

OK  Cancel

Finally, **create a 3<sup>rd</sup> VLAN** by making the same selection

Go to Network > interfaces and create a new interface.

Enter the name for the interface VLAN30 or whatever you want, select the type to VLAN, select Interface to LAN, enter the VLAN ID, enter the VRF Id. assign the Role to LAN, set the Addressing mode to manual, enter the IP/Netmask provided by your ISP and select the Administrative Access to HTTPS, PING

New Interface

Name	VLAN30
Alias	
Type	VLAN
Interface	LAN (port4)
VLAN ID	30
VRF ID	10
Role	LAN

Address

Addressing mode	Manual
IP/Netmask	192.168.30.1/24

Create address object matching subnet

Name	VLAN30 address
Destination	192.168.30.1/24

Secondary IP address

Administrative Access

IPv4	<input checked="" type="checkbox"/> HTTPS	<input checked="" type="checkbox"/> PING	<input type="checkbox"/> FMG-Access
	<input type="checkbox"/> SSH	<input type="checkbox"/> SNMP	<input type="checkbox"/> FTM

Enable the DHCP server and assign the address range further then save the configuration.

DHCP Server

Address range	192.168.30.2-192.168.30.254
Netmask	255.255.255.0
Default gateway	Same as Interface IP
DNS server	Same as System DNS

Specify

Lease time  604800 second(s)

Advanced

Network

Device detection

Security mode

Traffic Shaping

Outbound shaping profile

Miscellaneous

Comments  0/255

Status  Enabled  Disabled

Review the Interface list to see the VLAN's that you have created


802.3ad Aggregate 1					
	fortilink	802.3ad Aggregate		Dedicated to FortiSwitch	PING Security
Physical Interface 15					
	LAN (port4)	Physical Interface		192.168.255.100/255.2...	PING HTTPS SSH SNMP +3
•	VLAN10	VLAN		192.168.10.2/255.255.2...	PING HTTPS
•	VLAN20	VLAN		192.168.20.1/255.255.2...	PING HTTPS
•	VLAN30	VLAN		192.168.30.1/255.255.2...	PING HTTPS

## Create an Interface Zone

GO to the **Network > Interfaces** and select **create new Zone**

The screenshot shows the FortiGate VM64 interface configuration. On the left, the navigation menu is open, with 'Network' selected and 'Interfaces' highlighted. A red arrow points to the 'Network' option. On the right, the main interface list shows a 6-port switch with ports 1, 3, 5 at the top and 2, 4, 6 at the bottom. A context menu is open over an interface entry, with 'Zone' highlighted. The interface entry includes fields for 'Name' (Aggregate 1), 'Type' (fortilink), and 'Status' (802.3ad Aggregate). Below the interface list, it says 'Physical Interface 15'.

Name the zone to “VLAN Zone” to make it identifiable and add the newly created VLAN’s to it as shown below.



Review the Zone list to see the VLAN’s that you have Added.

Zone 1			
VLAN Zone	Zone	VLAN10 VLAN20 VLAN30	0.0.0.0/0.0.0.0
			100

## Create a Zone Firewall Policy

Go to Policy & Objects > Firewall Policy and create a new policy that will allow any VLAN in the Zone that we have created to access the internet.

FortiGate VM64 Branch-FortiGate


Dashboard Security Fabric Network System Policy & Objects Firewall Policy IPv4 DoS Policy

Create New Edit Delete


Interface Pair View By Sequence

Name
Blocking-social-media
No-Facebook-internet-access

Assign a name to “**VLAN Zone Policy**” make it identifiable, set the **Incoming interface to your Zone** and the **outgoing interface to the internet-facing interface**. configure the rest as needed or as per your requirement.



Select the Security Profiles as per your requirements and save the configuration by selecting OK.



To make this Policy Effective move this Policy to the TOP of the List as per your environment which policy should be on Top.

Interface Pair View				
Name	From	To	Source	Dest
Blocking-social-media	port1	wan (port2)	all	all
No-Facebook-internet-access	port1	wan (port2)	all	all
internet access	port1	port1	all	all
mobile	port1	wan (port2)	FABRIC_DEVICE	all
VLAN Zone Policy	VLAN Zone	wan (port2)	all	all
vpn_HQ-to-Branch_local_0	port1	HQ-to-Branch	HQ-to-Branch_local	HQ-to
vpn_HQ-to-Branch_remote_0	HQ-to-Branch	port1	HQ-to-Branch_remote	HQ-to
vpn_Branch-to-HQ_local_0	wan (port2)	Branch-to-HQ	Branch-to-HQ_local	Branch
vpn_Branch-to-HQ_remote_0	Branch-to-HQ	wan (port2)	Branch-to-HQ_remote	Branch
Implicit Deny	any	any	all	all

Similarly, you can create as much policy as you want.

## References:

- <https://www.hackingarticles.in/firewall-lab-setup-fortigate/>
- <https://www.hackingarticles.in/implementation-of-firewall-policies-fortigate-part-1/>
- <https://www.hackingarticles.in/implementation-of-firewall-policies-fortigate-part-2/>

# About Us

# About Us

***“Simple training makes Deep Learning”***

“IGNITE” is a worldwide name in IT field. As we provide high-quality cybersecurity training and consulting services that fulfil students, government and corporate requirements.

We are working towards the vision to “Develop India as a Cyber Secured Country”. With an outreach to over eighty thousand students and over a thousand major colleges, Ignite Technologies stood out to be a trusted brand in the Education and the Information Security structure.

We provide training and education in the field of Ethical Hacking & Information Security to the students of schools and colleges along with the corporate world. The training can be provided at the client's location or even at Ignite's Training Center.

We have trained over 10,000 + individuals across the globe, ranging from students to security experts from different fields. Our trainers are acknowledged as Security Researcher by the Top Companies like - Facebook, Google, Microsoft, Adobe, Nokia, Paypal, Blackberry, AT&T and many more. Even the trained students are placed into a number of top MNC's all around the globe. Over with this, we are having International experience of training more than 400+ individuals.

The two brands, Ignite Technologies & Hacking Articles have been collaboratively working from past 10+ Years with about more than 100+ security researchers, who themselves have been recognized by several research paper publishing organizations, The Big 4 companies, Bug Bounty research programs and many more.

Along with all these things, all the major certification organizations recommend Ignite's training for its resources and guidance.

Ignite's research had been a part of number of global Institutes and colleges, and even a multitude of research papers shares Ignite's researchers in their reference.

# What We Offer

## Ethical Hacking

The Ethical Hacking course has been structured in such a way that a technical or a non-technical applicant can easily absorb its features and indulge his/her career in the field of IT security.



## Bug Bounty 2.0

A bug bounty program is a pact offered by many websites and web developers by which folks can receive appreciation and reimbursement for reporting bugs, especially those affecting to exploits and vulnerabilities.

Over with this training, an individual is thus able to determine and report bugs to the authorized before the general public is aware of them, preventing incidents of widespread abuse.



## Network Penetration Testing 2.0

The Network Penetration Testing training will build up the basic as well advance skills of an individual with the concept of Network Security & Organizational Infrastructure. Thereby this course will make the individual stand out of the crowd within just 45 days.



## Red Teaming

This training will make you think like an "Adversary" with its systematic structure & real Environment Practice that contains more than 75 practicals on Windows Server 2016 & Windows 10. This course is especially designed for the professionals to enhance their Cyber Security Skills



## CTF 2.0

The CTF 2.0 is the latest edition that provides more advance module connecting to real infrastructure organization as well as supporting other students preparing for global certification. This curriculum is very easily designed to allow a fresher or specialist to become familiar with the entire content of the course.



## Infrastructure Penetration Testing

This course is designed for Professional and provides an hands-on experience in Vulnerability Assessment Penetration Testing & Secure configuration Testing for Applications Servers, Network Deivces, Container and etc.



## Digital Forensic

Digital forensics provides a taster in the understanding of how to conduct investigations in order for business and legal audiences to correctly gather and analyze digital evidence.