A Crude Fix

June 12, 2010

Write the Godunov Flux as $[0, P, 0]^T$. Define $\mu = u_0 \frac{\Delta t}{\Delta x}$. From conservation of mass, we have

$$\rho_1 = \rho_0 - \frac{\Delta t}{\Delta x} (0 - \rho_0 u_0)$$
$$= \rho_0 (1 + \mu)$$

Conservation of momentum gives

$$\rho_1 u_1 = \rho_0 u_0 - \frac{\Delta t}{\Delta x} (P - p_0 - \rho_0 u_0^2)$$
$$= \rho_0 u_0 (1 + \mu) + \frac{\mu}{u_0} (p_0 - P)$$

and the result that

$$\rho_1 u_1^2 = \frac{1}{\rho_0 (1+\mu)} \left(\rho_0^2 u_0^2 (1+\mu)^2 + 2\rho_0 \mu (1+\mu) (p_0 - P) + \frac{\mu^2}{u_0^2} (p_0 - P)^2 \right)$$

And finally conservation of energy gives

$$\frac{p_1}{\gamma - 1} + \frac{1}{2}\rho_1 u_1^2 = \frac{p_0}{\gamma - 1} + \frac{1}{2}\rho_0 u_0^2 - \frac{\Delta t}{\Delta x} \left(0 - u_0 \left[\frac{\gamma p_0}{\gamma - 1} + \frac{1}{2}\rho_0 u_0^2 \right] \right) \\
= \frac{p_0}{\gamma - 1} + \frac{1}{2}\rho_0 u_0^2 + \mu \left[\frac{\gamma p_0}{\gamma - 1} + \frac{1}{2}\rho_0 u_0^2 \right]$$

The equation for shock speed, S, is

$$\rho_0 S^2 - \frac{\gamma - 3}{2} \rho_0 u_0 S - \frac{\gamma - 1}{2} \rho_0 u_0^2 = \gamma p_0$$

Use this to rearrange energy conservation into

$$p_{1} = p_{0} - \frac{\gamma - 1}{2}\rho_{1}u_{1}^{2} + \frac{\gamma - 1}{2}\rho_{0}u_{0}^{2}(1 + \mu) + \mu\left(\rho_{0}S^{2} - \frac{\gamma - 3}{2}\rho_{0}u_{0}S - \frac{\gamma - 1}{2}\rho_{0}u_{0}^{2}\right)$$

$$= p_{0} - \frac{\gamma - 1}{2}\rho_{1}u_{1}^{2} + \frac{\gamma - 1}{2}\rho_{0}u_{0}^{2} + \mu\rho_{0}S^{2} - \frac{\gamma - 3}{2}\mu\rho_{0}u_{0}S$$

$$= p_{0} - \frac{\gamma - 1}{2}\rho_{1}u_{1}^{2} + \mu\rho_{0}S(u_{0} + S) - \frac{\gamma - 1}{2}\mu\rho_{0}u_{0}S$$

$$= p_{0} + \mu\rho_{0}S(u_{0} + S) - \frac{\gamma - 1}{2}\left(\mu\rho_{0}u_{0}(u_{0} + S) + 2\mu(p_{0} - P) + \frac{\mu^{2}}{1 + \mu}\frac{(p_{0} - P)^{2}}{\rho_{0}u_{0}^{2}}\right)$$

To eliminate this extra term, solve the quadratic

$$\rho_0 u_0(u_0 + S) + 2(p_0 - P) + \frac{\mu}{1 + \mu} \frac{(p_0 - P)^2}{\rho_0 u_0^2} = 0$$

I get that the solution is

$$P - p_0 = \left(1 + \frac{1}{\mu}\right) \rho_0 u_0^2 \left(1 \pm \sqrt{\frac{1 - \frac{\mu S}{u_0}}{1 + \mu}}\right)$$

Since $p_e = p_0 + \rho_0 u_0(u_0 + S)$, we get that when $\mu = \mu_{\text{max}} = u_0/S \to P = p_e$. To choose the correct root, examine the momentum equation.

$$\rho_1 u_1 = \rho_0 u_0 (1 + \mu) + \frac{\mu}{u_0} (p_0 - P)$$

$$= \rho_0 u_0 (1 + \mu) - \frac{\mu}{u_0} \left(1 + \frac{1}{\mu} \right) \rho_0 u_0^2 \left(1 \pm \sqrt{\frac{1 - \frac{\mu S}{u_0}}{1 + \mu}} \right)$$

$$= \rho_0 u_0 \left((1 + \mu) - (1 + \mu) \left(1 \pm \sqrt{\frac{1 - \frac{\mu S}{u_0}}{1 + \mu}} \right) \right)$$

$$= \rho_0 u_0 (1 + \mu) \left(- \pm \sqrt{\frac{1 - \frac{\mu S}{u_0}}{1 + \mu}} \right)$$

Examining the limit as $\mu \to 0$, we get that

$$\rho_1 u_1 = -\rho_0 u_0 (\pm 1)$$

Since there should be no change in momentum if $\mu \propto \Delta t \to 0$, the correct root is the negative root.




Figure 1: CFL vs wall pressure after one timestep comparing the crude fix to pressures achieved in other ways.




Figure 2: Density and internal energy using crude pressure in wall flux on first timestep




Figure 3: Wall pressure vs wall density using crude pressure in wall flux on first timestep