CS2208 **JING XU**
ASS #5 **250942790**

PART ONE: SOURCE COED

```
            AREA a5q1, CODE, READONLY
            ENTRY
X           EQU 4                   ;define x
N           EQU 2                   ;define n

MAIN        ADR sp, STACK           ;define the stack
            MOV r0, #X              ;pass the parameter x to r0
            MOV r1, #N              ;pass the parameter n to r1
            STMFD sp!, {r0-r1}      ;push x and n parameters in the stack
            SUB sp, sp, #4          ;reserve above the parameters for return value
            BL POWER                ;call function power

            LDR r2, [sp], #12       ;load return value to r2, clean stack
            ADR r3, RESULT          ;get the address of RESULT
            STR r2, [r3]            ;store return value of POWER in RESULT address

END         B END                   ;Infinite loop to end the program

POWER       STMFD sp!, {r0-r1, fp, lr}  ;push registers to be modified, as well as fp and lr
            MOV fp, sp              ;set current frame pointer to the top of the stack
            SUB sp, sp, #4          ;allocate space in the frame for local variable y
            LDR r1, [fp, #24]       ;load parameter n passed
            CMP r1, #0              ;check if n==0
            MOVEQ r1, #1            ;if n==0, return 1
            BEQ RETURN              ;jump to RETURN

            LDR r0, [fp, #20]       ;if n isn't 0, load parameter x
            TST r1, #1              ;test last bit in n to determine if even or odd
            BNE ODD                 ;if n odd, jump to ODD
            B EVEN                  ;else, jump to EVEN

ODD         SUB r1, r1, #1          ;decrement n
            STMFD sp!, {r0-r1}      ;push x and n to stack
            SUB sp, sp, #4          ;reserve above parameters for the return value
            BL POWER                ;call function power

            LDR r1, [fp, #-16]      ;get return value from above recursive call to
POWER
            MUL r1, r0, r1          ;multiply x * previous return value to r1
            B RETURN                ;jump to RETURN

EVEN        ASR r1, #1              ;divide n by 2
            STMFD sp!, {r0-r1}      ;push x and n to stack
            SUB sp, sp, #4          ;reserve above parameters for the return value
            BL POWER                ;call power function
```

```
                LDR r0, [fp, #-16]      ;get returned value from above recursive call to
POWER
                STR r0, [fp, #-4]       ;store returned value in local variable y on the stack
                MUL r1, r0, r0          ;multiply y*y into r1

RETURN          STR r1, [fp, #16]       ;store r1 in return value address on stack
                MOV sp, fp              ;move the stack pointer to the current frame
pointer
                LDMFD sp!, {r0-r1, fp, pc}  ;restore modified registers along with fp

                SPACE 666               ;define stack space
STACK           DCD 0x00                ;location of fdstack in memory
RESULT          DCD 0x00                ;store final result

                END
```

PART TWO: STACK FRAME

Local variable y	← sp
R0	← fp
R1	
Fp	
Lr	
return value	
Parameter x	
Parameter n	

PART THREE: NUMBER OF FRAMES TO CALCULATE N POWER OF X

N=0 → 1 frame
N=1 → 2 frames
N=2 → 3 frames
N=3 → 4 frames
N=4 → 4 frames
N=5 → 5 frames
N=6 → 5 frames
N=7 → 6 frames
N=8 → 5 frames
N=9 → 6 frames
N=10 → 6 frames
N=11 → 7 frames
N=12 → 6 frames