
Operating Systems Design 8. Memory Management

Paul Krzyzanowski pxk@cs.rutgers.edu

CPU Memory Access

CPU reads instructions and reads/write data from/to memory




Functional interface:

value = read(address)

write(address, value)

Monoprogramming

- Run one program at a time
- Share memory between the program and the OS



This was the model in old MS-DOS systems

Multiprogramming

- Keep more than one process in memory
- More processes in memory improves CPU utilization



- If a process spends 20% of its time computing, then would switching among 5 processes give us 100% CPU utilization?
- Not quite. For n processes, if p = % time a process is blocked on I/O then:

probability all are blocked = p^n

- CPU is not idle for (1-pⁿ) of the time
- 5 processes: 67% utilization

How do you access memory?

Absolute code

if you know where the program gets loaded (any relocation is done at link time)

 Position independent code all addresses are relative


 Dynamically relocatable code relocated at load time

Or ... use logical addresses
 absolute code with with addresses translated at runtime

Logical addressing


Memory management unit (MMU):

Real-time, on-demand translation between *logical* and *physical* addresses



Relocatable addressing

- Base & limit
 - Physical address = logical address + base register
 - But first check that: logical address < limit</p>



Multiple Fixed Partitions

- Divide memory into predefined partitions (segments)
 - Partitions don't have to be the same size
 - For example: a few big partitions and many small ones
- New process gets queued for a partition that can hold it
- Unused memory in a partition goes unused


Variable partition multiprogramming

- Create partitions as needed
- New process gets queued
- OS tries to find a hole for it



Variable partition multiprogramming

- Create partitions as needed
- New process gets queued
- OS tries to find a hole for it




Variable partition multiprogramming

- What if a process needs more memory?
 - Always allocate some extra memory just in case
 - Find a hole big enough to relocate the process
- Combining holes
 - Memory compaction
 - Usually not done because of CPU time to move a lot of memory

Segmentation hardware

- Divide a process into segments and place each segment into a partition of memory
 - Code segment, data segment, stack segment, etc.



Allocation algorithms

- First fit: find the first hole that fits
- Best fit: find the hole that best fits the process
- Worst fit: find the largest available hole
 - Why? Maybe the remaining space will be big enough for another process. In practice, this algorithm does not work well.

Paging

- Memory management scheme
 - Physical space can be non-contiguous
 - No fragmentation problems
 - No need for compaction
- Paging is implemented by the Memory Management Unit (MMU) in the processor

Paging

Translation:

- Divide physical memory into fixed-size blocks: page frames
- A logical address is divided into blocks of the same size: pages
- All memory accesses are translated: page → page frame
- A page table maps pages to frames


Example:

- 32-bit address, 4 KB page size:
 - Top 20 bits identify the page number
 - Bottom 12 bits identify offset within the page/frame




© 2010 Paul Krzyzanowski 10/6/2010 15


Page translation



Logical vs. physical views of memory







frame

Physical Memory

Hardware Implementation

- Where do you keep the page table? In memory
- Each process gets its own virtual address space
 - Each process has its own page table
 - Change the page table by changing a page table base register
- Memory translation is now slow!
 - To read a byte of memory, we need to read the page table first
 - Each memory access is now 2x slower!

Hardware Implementation: TLB

- Cache frequently-accessed pages
 - Translation lookaside buffer (TLB)
 - Associative memory: key (page #) and value (frame #)

- TLB is on-chip & fast ... but small (64-1,024 entries)
- TLB miss: result not in the TLB
 - Need to do page table lookup in memory
- Hit ratio = % of lookups that come from the TLB

Tagged TLB

- There is only one TLB per system
- When we context switch, we switch address spaces
 - New page table
 - TLB entries belong to the old address space
- Either:
 - Flush the TLB
 - Have a Tagged TLB:
 - Address space identifier (ASID)


Protection

- An MMU can enforce memory protection
- Page table stores protection bits per frame
 - Valid/invalid: is there a frame mapped to this page?
 - Read-only
 - No execute
 - Dirty

Multilevel (Hierarchical) page tables

- Most processes use only a small part of their address space
- Keeping an entire page table is wasteful
- E.g., 32-bit system with 4KB pages: 20-bit page table
 - 1,048,576 entries in a page table

Multilevel page table



Inverted page tables

- # of pages on a system may be huge
- # of page frames will be more manageable (limited by physical memory)
- Inverted page table
 - ith entry: contains info on what is in page frame i
- Table access is no longer a simple index but a search
 - Use hashing and take advantage of associative memory

The End