Local Control of the Microcirculation

Author: Dr. Ahmed Abdelsalam
Reviewed by: Dr. Ahmed Abdelsalam

Learning Objectives

- Explain the function of arterioles as the primary site of regulation of blood flow.
- Describe the myogenic response and how it protects the capillaries from pressure changes.
- Explain the role of endothelial cells in producing vasoactive substances.
- Describe the mechanisms of metabolic control of blood flow.
- Explain the mechanisms of flow-mediated vasodilation.

Learning Resources | Glossary

Quick Refresher

Recall that the blood vessels are arranged in series and in parallel. Resistance in series is additive, while resistance in parallel is calculated using the reciprocal formula. Also, remember that the arterioles are the primary site of resistance in the circulatory system, as they have the smallest radius and the greatest ability to change their diameter.

Introduction

The body has a remarkable ability to regulate blood flow to individual tissues according to their specific needs. This process, known as local control of the microcirculation, ensures that each tissue receives the appropriate amount of blood flow to meet its metabolic demands, whether at rest or during activity. The arterioles are the primary site of this regulation, as they can dilate or constrict to alter the resistance to blood flow and, consequently, the blood flow to the capillaries.

Local control can be broadly classified into two types: intrinsic control, which is mediated by factors within the tissue itself, and extrinsic control, which is mediated by factors from outside the tissue, such as hormones and neural signals. Intrinsic control is the dominant mechanism for short-term regulation of blood flow, while extrinsic control is more important for long-term regulation and for responses to changes in overall body homeostasis.

Intrinsic control can be further divided into two main mechanisms: the myogenic response and metabolic control. The myogenic response is a direct response of the vascular smooth muscle to changes in pressure, while metabolic control is mediated by the release of vasoactive substances from the tissue in response to changes in its metabolic activity. Both of these mechanisms work together to ensure that blood flow is precisely matched to the tissue's needs.

Intrinsic control is the dominant mechanism for short-term regulation of blood flow, while extrinsic control is more important for long-term regulation and for responses to changes in overall body homeostasis.

Myogenic response is the ability of vascular smooth muscle to contract when stretched and relax when the stretch is removed. This response helps to maintain a relatively constant blood flow despite changes in blood pressure. When blood pressure increases, the arterioles are stretched, which causes the smooth muscle to contract and reduce the diameter of the vessel. This helps to prevent excessive blood flow and protect the capillaries from damage.

The myogenic response to changes in blood pressure. When pressure increases, the vessel constricts to maintain flow. When pressure decreases, the vessel dilates to maintain flow.

Clinical Correlation

Autoregulation is the ability of an organ to maintain relatively constant blood flow despite changes in perfusion pressure. It is the result of the myogenic response and metabolic control working together. Autoregulation is most effective in the brain, heart, and kidneys, which are organs that require a constant supply of blood.

What does the myogenic response help to maintain?

What is the myogenic response?

Intrinsic - Metabolic Control of Local Blood Flow (LO2)

Tissue metabolic activity is the most important factor in the local control of blood flow. When tissue activity increases, such as during exercise, the demand for oxygen and nutrients increases. To meet this demand, the arterioles in the tissue dilate, which increases blood flow. Conversely, when tissue activity decreases, the arterioles constrict, which decreases blood flow. This ensures that the blood flow is always matched to the tissue's metabolic needs.

Relationship between tissue metabolic activity and blood flow.

Several vasoactive substances are released by tissues during metabolic activity. These substances act on the vascular smooth muscle to cause vasodilation. The most important of these substances are:

- Adenosine: Adenosine is a powerful vasodilator that is released when the demand for oxygen exceeds the supply. It is a breakdown product of ATP and is also released by platelets and endothelial cells.
- Carbon dioxide (CO_2): An increase in CO_2 levels in the tissue causes vasodilation. This is because CO_2 reacts with water to form carbonic acid, which then dissociates to release hydrogen ions (H^+). The increase in H^+ concentration is a potent vasodilator.
- Potassium ions (K^+): When tissue activity increases, K^+ ions are released from the cells. This increase in extracellular K^+ concentration causes hyperpolarization of the vascular smooth muscle cells, which leads to vasodilation.
- Hydrogen ions (H^+): As mentioned above, an increase in H^+ concentration, which is caused by an increase in CO_2, is a potent vasodilator.
- Lactic acid: Lactic acid is produced during anaerobic metabolism and is a vasodilator.
- Nitric oxide (NO): Nitric oxide is released by endothelial cells in response to various stimuli, including shear stress and certain vasoactive substances. It is a potent vasodilator that plays a role in both local and systemic blood flow regulation.

Clinical Correlation

Reactive hyperemia is a temporary increase in blood flow to a tissue after a period of ischemia (reduced blood flow). It is a classic example of metabolic control of blood flow. During the ischemic period, metabolic waste products accumulate in the tissue, causing vasodilation. When blood flow is restored, the vasodilation persists for a short time, resulting in a temporary increase in blood flow.

What is the effect of nitric oxide release from endothelium cells?

What are some examples of metabolic control of arterial blood flow?

Metabolic control is a form of negative feedback. When tissue activity increases, the production of vasodilator substances increases, which causes vasodilation and increases blood flow. This increased blood flow delivers more oxygen and nutrients to the tissue and removes more waste products, which helps to restore the tissue to its normal state. When tissue activity decreases, the production of vasodilator substances decreases, which causes vasoconstriction and decreases blood flow.

Myogenic control is a form of positive feedback. When blood pressure increases, the stretch of the vascular smooth muscle causes vasoconstriction, which helps to maintain blood flow to the tissue. This is a protective mechanism that prevents damage to the capillaries from excessive pressure.

Myogenic control is a form of positive feedback. When blood pressure increases, the stretch of the vascular smooth muscle causes vasoconstriction, which helps to maintain blood flow to the tissue. This is a protective mechanism that prevents damage to the capillaries from excessive pressure.