ECG Learning: Sinus Bradycardia and Tachycardia

Author: Jeffrey Kline, MD Reviewer: Jeffrey Kline, MD

Expand All Collapse All

Estimated time: 20 minutes

Learning Objectives (4)

Review Questions (5)

After completing this brief, you will be able to:

- Describe the ECG findings indicative of sinus bradycardia and tachycardia.
- Explain how sinus bradycardia and tachycardia affect the ECG waveform.
- Discuss the clinical significance of the ventricular depolarization vector and rotation in the QRS axis.
- Apply ECG interpretation skills to recognize sinus bradycardia and tachycardia in practical scenarios.

Introduction

Jeff, can you walk people in the university clinic with episodes of lightheadedness and fatigue during my electives as we have not yet practiced after taking an extra 6 to 8 mo? Will be using anatomy for my upcoming exam and would like to review the ECG as well. Would be a great way to review and practice for my exam.

Jeff, I'll get that emailed shortly. Anatomy is a challenging skills. Remember that the ECG is a measure of the heart's electrical activity. The ECG has P-T-Q-R-S-T-U waves. Each wave represents a specific phase of the heart's electrical activity. Understanding these waves is crucial for interpreting ECGs accurately.

Review What are the P-T-Q-R-S-T-U waves?

A normal sinus rhythm (ECG) represents the normal activity of a healthy heart. In sinus rhythm, the cardiac impulse originates in the sinoatrial (SA) node and travels through the atria, causing them to contract. This is followed by the AV node, bundle of His, bundle branches, and Purkinje fibers in the ventricles. This organized electrical activity produces a predictable pattern of waveforms and intervals on the ECG that serve as the baseline for identifying abnormal rhythm disorders.

Question

Which is the correct sequence of waveforms in a normal sinus rhythm ECG?

- A. T-wave, P-wave, QRS complex
- B. QRS complex, P-wave, T-wave
- C. P-wave, QRS complex, T-wave
- D. P-wave, QRS complex, T-wave, U-wave
- E. P-wave, T-wave, QRS complex

Explanation

The correct answer is C. P-wave, QRS complex, T-wave (E). The P-wave represents the normal cardiac electrical activity (atrial depolarization). The QRS complex represents ventricular depolarization (QRS complex), and a T-wave represents ventricular repolarization (T-wave). The U-wave is not a normal component of the ECG. It is a minor deviation that is sometimes seen after the T-wave. The U-wave represents the last remnants of ventricular repolarization (U-wave). The U-wave is not always present and is not considered part of the normal ECG waveform. It is not necessary to memorize the U-wave.

What Are Key ECG Findings Indicative of Sinus Bradycardia? (CAP-)

Sinus bradycardia is characterized by a regular rhythm with a heart rate below 60 beats per minute. The primary defining feature is the slow heart rate, while the underlying electrical activity remains normal, with a consistent P-wave preceding each QRS complex.

What is the difference between sinus bradycardia and sinus arrhythmia?

Sinus bradycardia is characterized by a consistent rate below 60 beats per minute, while sinus arrhythmia involves a variable rate with fluctuations in the heart rate that are typically associated with respiration.

Figure 1. Normal sinus rhythm (NSR) with a heart rate between 60 and 100 beats per minute

Another key feature is that the P-wave remains normal (0.06 - 0.10 seconds), indicating that the impulse originates in the SA node and follows the normal conduction pathway through the atria. The PR interval (0.12 - 0.20 seconds) is also within normal limits, indicating that the impulse is conducted through the AV node at a normal speed. The QRS complex is usually narrow (0.06 - 0.10 seconds) because the impulse is conducted rapidly through the ventricles via the normal conduction pathway. Another key finding is that there is a consistent 1:1 relationship between the P-wave and QRS complex (Figure 1).

Figure 2. Sinus bradycardia with a heart rate of 50 beats per minute

What is the P-wave axis range in sinus bradycardia?

How Does Sinus Bradycardia Alter the ECG Waveform and Heart Rate? (CAR-)

Heart Rate Calculation

Heart rate calculation from a 6-s strip can be performed using several methods. The most precise method involves measuring the R-R interval (in seconds) and dividing it into 60 to obtain the heart rate. For example, if the R-R interval is 1.2 seconds (1.2 seconds = 0.2 small boxes), the heart rate would be 60 / 1.2 beats per second, which is 50 beats per minute (bpm).

Figure 3. Alternatively, the number of R-waves in a 6-s strip can be multiplied by 10 to estimate the heart rate. For example, if there are 5 R-waves in a 6-s strip, the heart rate would be approximately 50 bpm (5 x 10). This method is quicker but less precise, as it assumes a regular rhythm and may not account for variations in the R-R interval.

Figure 3. 6-s strip

Figure 4. 6-s strip with a long R-R interval

Figure 5. The 6-second strip is divided into 30 large boxes, each 0.2 seconds in duration. Count the number of R-waves and multiply by 10 to estimate the heart rate. For example, if there are 5 R-waves in the 6-second strip, the heart rate would be approximately 50 bpm (5 x 10). This method is quicker but less precise, as it assumes a regular rhythm and may not account for variations in the R-R interval.

Internal Changes during Sinus Bradycardia

While sinus bradycardia primarily affects heart rate, it can subtly affect cardiac dynamics in ECG morphology and intervals. The P-wave morphology remains consistent with normal sinus rhythm, indicating that the impulse originates from the regular SA node and travels through the atria. The P-R interval, typically measuring 0.12 - 0.20 seconds, may exhibit a slight prolongation in the PR interval due to the slower conduction through the AV node, but it usually remains within normal limits.

The QRS complex duration, typically 0.06 - 0.10 seconds, also remains consistent, as the impulse conduction through the ventricles is not significantly affected. The QT interval (typically measured from the beginning of the QRS complex to the end of the T-wave) may appear prolonged due to the slower heart rate, but it should be corrected for heart rate (QTc) to assess for any potential abnormalities.

Stepwise ECG Analysis for Sinus Bradycardia

A systematic approach to ECG interpretation for sinus bradycardia begins with heart rate calculation. If the standard 6-second strip contains 30 large boxes, each 0.2 seconds in duration, count the number of R-waves and multiply by 10 to estimate the heart rate. For example, if there are 5 R-waves in the 6-second strip, the heart rate would be approximately 50 bpm (5 x 10). This method is quicker but less precise, as it assumes a regular rhythm and may not account for variations in the R-R interval.

Step 1. Assess heart rate by measuring the R-R interval — see video for CAR- Calculate Heart Rate. If the heart rate is below 60 bpm, it indicates sinus bradycardia.

Step 2. Examine the P-wave morphology and ensure that each QRS complex is preceded by a P-wave with a consistent morphology and upright in leads I, II, and III.

Step 3. Confirm bradycardia when the calculated rate is <60 bpm, which marks the primary diagnostic criterion for sinus bradycardia.

Step 4. For borderline rates (~60 bpm), average several consecutive cycles to ensure accuracy, as variability can affect single measurements.

Step 5. Evaluate rhythm regularity to separate sinus bradycardia from arrhythmias, such as sinus arrhythmia, with slower variations in rate.

Step 6. Utilize lead measurements to determine if the rhythm is sinus bradycardia or alternative rhythms, such as atrial fibrillation, with slow ventricular response or sinus arrhythmia with intermittent slowing.

Step 7. Inspect P-waves: ensure each QRS complex is preceded by a P-wave with consistent morphology, typically upright in leads I, II, and III, to confirm sinus origin.

Step 8. Confirm rate: if the rate is <60 bpm, classify as sinus bradycardia; otherwise, rule out alternatives.

Step 9. Verify 1:1 conduction: P-waves should have consistent shape and precede each QRS complex, indicating normal AV conduction without dropped beats or variations.

Step 10. Document findings: record the calculated rate, rhythm regularity, and P-wave morphology for clinical reference and follow-up.

What is the directionality of P wave and QRS Axis? (CAR-)

As mentioned earlier, impulses that originate in the sinus node propagate from a small cluster of specialized cells on the high right atrium. The impulse then travels through the atrial muscle cells. The direction of travel dictates whether the polarity of the impulse moves toward or away from a lead. After generation of this impulse, the depolarization wave front moves in a specific direction and magnitude. The direction of travel is known as the mean electrical axis and is vital to describe the normal depolarization wave front. The mean, or vector, of a heart's thorough ventricular mass.

The mean electrical axis is described in the frontal plane. Frontal direction of the heart is the most commonly used plane to describe the mean electrical axis. The mean electrical axis is the direction from which the heart's depolarization wave front originates. The mean electrical axis is usually directed inferiorly, leftward, and anterior. The mean electrical axis is usually directed inferiorly, leftward, and anterior. Since the mean electrical axis is the net vector of the ventricular depolarization wave front, it is usually directed toward the left ventricle. Since the left ventricle is the largest mass of the heart, the mean electrical axis