Where the top of the stack is on x86 (https://eli.thegreenplace.net/2011/02/04/where-the-top-of-the-stack-is-on-x86)

February 04, 2011 at 07:24 Tags Articles (https://eli.thegreenplace.net/tag/articles), Assembly (https://eli.thegreenplace.net/tag/assembly)

I've noticed more than once that some programmers are confused about the direction in which the stack grows on x86, and what "top of the stack" and "bottom of the stack" mean. It appears that this confusion is caused by a basic mismatch in the way people are used to thinking about stacks, and in the way the stack on x86 actually behaves [1]. In this article, I intend to resolve this confusion with a few helpful diagrams.

The stack analogy

Back to the basics. The stack analogy is sometimes demonstrated to new students of computing with a stack of plates. You push a plate onto the stack and pop a plate off the stack. The top of the stack is where your next plate goes when pushing, and from where you take a plate when popping.




Hardware stacks

In computers, the stack is usually a specially treated region of memory. In the abstract sense, the analogy applies - you push data by placing it on the top of the stack, and pop data by taking it from the top of the stack. Note that this doesn't address the issue of where the top of the stack is located in memory.

The stack in x86

Herein lies the source of the confusion. Intel's x86 architecture places its stack "head down". It starts at some address and grows *down* to a lower address. Here's how it looks:




So when we say "top of the stack" on x86, we actually mean the *lowest address* in the memory area occupied by the stack. This may be unnatural for some people [2]. As long as we keep the diagram shown above firmly in mind, however, we should be OK.

While we're at it, let's see how some common idioms of x86 assembly programming map to this graphical representation.

Pushing and popping data with the stack pointer

The x86 architecture reserves a special register for working with the stack - ESP (Extended Stack Pointer). The ESP, by definition, always points to the top of the stack:



In this diagram, address 0x9080ABCC is the top of the stack. The word located in it is some "foo" and ESP contains the address 0x9080ABCC - in other words, *points to it*.


To push new data onto the stack we use the push instruction [3]. What push does is first decrement esp by 4, and then store its operand in the location esp points to. So this:

push eax

Is actually equivalent to this:

```
sub esp, 4
mov [esp], eax
```

Taking the previous diagram as the starting point, and supposing that eax held the venerable value <code>0xDEADBEEF</code>, after the <code>push</code> the stack will look as follows:




Similarly, the pop instruction takes a value off the top of stack and places it in its operand, increasing the stack pointer afterwards. In other words, this:

```
pop eax
```

Is equivalent to this:

```
mov eax, [esp] add esp, 4
```

So, again, taking the previous diagram (after the push) as a starting point, pop eax will do the following:



And the value <code>@xDEADBEEF</code> will be written into <code>eax</code>. Note that <code>@xDEADBEEF</code> also stays at address <code>@x9080ABC8</code>, since we did nothing to overwrite it yet.

Stack frames and calling conventions


When looking at assembly code generated from C, you will find a lot of interesting patterns. Perhaps the most recognizable pattern is the way parameters are passed into functions using the stack, and the way local variables are allocated on the stack [4].

I'll demonstrate this with a simple C program:

```
int foobar(int a, int b, int c)
{
    int xx = a + 2;
    int yy = b + 3;
    int zz = c + 4;
    int sum = xx + yy + zz;

    return xx * yy * zz + sum;
}
int main()
{
    return foobar(77, 88, 99);
}
```

Both the arguments passed into foobar and the local variables of that function, along with some other data, are going to be stored on the stack when foobar is called. This set of data on the stack is called a *frame* for this function. Right before the return statement, the stack frame for foobar looks like this:



The green data were pushed onto the stack by the calling function, and the blue ones by foobar itself.

Compiled with gcc into assembly as follows:

```
gcc -masm=intel -S z.c -o z.s
```

The following assembly listing is generated for foobar. I commented it heavily for easy understanding:

```
_foobar:
   ; ebp must be preserved across calls. Since
   ; this function modifies it, it must be
   ; saved.
   push
           ebp
   ; From now on, ebp points to the current stack
   ; frame of the function
   mov
           ebp, esp
   ; Make space on the stack for local variables
   sub
           esp, 16
   ; eax <-- a. eax += 2. then store eax in xx
           eax, DWORD PTR [ebp+8]
   mov
           eax, 2
   add
           DWORD PTR [ebp-4], eax
   ; eax <-- b. eax += 3. then store eax in yy
           eax, DWORD PTR [ebp+12]
   mov
   add
           eax, 3
           DWORD PTR [ebp-8], eax
   mov
   ; eax <-- c. eax += 4. then store eax in zz
           eax, DWORD PTR [ebp+16]
   mov
   add
           eax, 4
           DWORD PTR [ebp-12], eax
   mov
   ; add xx + yy + zz and store it in sum
           eax, DWORD PTR [ebp-8]
   mov
           edx, DWORD PTR [ebp-4]
   mov
           eax, [edx+eax]
   lea
   add
           eax, DWORD PTR [ebp-12]
           DWORD PTR [ebp-16], eax
   mov
   ; Compute final result into eax, which
   ; stays there until return
           eax, DWORD PTR [ebp-4]
   mov
           eax, DWORD PTR [ebp-8]
   imul
   imul
           eax, DWORD PTR [ebp-12]
           eax, DWORD PTR [ebp-16]
   ; The leave instruction here is equivalent to:
      mov esp, ebp
       pop ebp
   ; Which cleans the allocated locals and restores
```

; ebp.
;
leave
ret

Since esp keeps moving as the function executes, ebp (base pointer, also known as frame pointer in other architectures) is used as a convenient anchor relatively to which all function arguments and locals can be found. Arguments are above ebp in the stack (hence the positive offset when accessing them), while locals are below ebp in the stack.

- [1] It doesn't help that some online resources mistakenly call the top of the stack "bottom". The version presented here is the correct one of x86, since it relies on terminology defined in Intel's x86 architecture manuals.
- You may try to fix the confusion by viewing memory with its low addresses at the top and high addresses at the bottom. While this would indeed make stack movement more natural, it would also mean that increasing some memory address would take it *down* in the graphical representation, which is probably even more counter-intuitive.
- There are several instructions x86 defines in the "push family". I'm demonstrating push since it's the simplest and most generally applicable.
- This only applies to some calling conventions and architectures, of course. In others, some parameters are passed in registers.

For comments, please send me an email (mailto:eliben@gmail.com), or reach out on Twitter (https://twitter.com/elibendersky).

© 2003-2020 Eli Bendersky

♠ Back to top