
b. At top front edge stitch pocket and slacks the width of 2 inches across the top to finish for buttonhole overlap.

6. *a.* Stitch the side leg seam below the placket end, matching stitching ends of placket, and steam.


b. At the front or overlap of pocket, turn the pocket to the inside, slightly roll the seam to wrong side, baste, and stitch ⅜ inch along open edge of placket.

c. From the back placket edge, press the pocket straight out from the stitching edge.


Stitch the bag from lower placket edge down to turn and across bottom, as in Pocket i–6. Join belting to top of slacks as in Fig. 28, pp. 63, 64.




1. Right side




2. Wrong side




3. Wrong side



4. Right side




5. Wrong side




6. Right side


Figure 91 (b)



1



2



3

Figure 91 (c)

If a belt is used instead of a facing, it is attached at the top in the same manner as that of a skirt (see Fig. 28, pp. 63, 64).

The top width of the pocket is stitched to the lower edge of the facing. If a belt is used, it is stitched with the top of slacks into the lower edge of the belt.

CUFFS ON SLACKS

Figure 92.

1. Mark slack length. The slacks should not break over the instep and should hang about ¼ inch longer at the back over the heel. Turn the hem to the right side of leg along the marked length and baste along folded edge.
2. Release seam of the turned-up section until the cut edge fits smoothly around leg width.
3. Mark up from folded edge 1½ to 1¾ inches on the turned-up section, mark for the cuff width, and place basting.
4. Fold hem section down to right side along marked cuff edge and baste along top edge of cuff.
5. Fold surplus hem around the slack length up into the leg and baste along fold at bottom edge of trousers. Check cuff width for accuracy, 1¼ or 1¾ inches.
6. Turn leg wrong side out. Measure from bottom edge 1¼ inch for hem width, mark, and trim away the surplus hem. Baste hem edge to trousers but not through the cuff.
7. Catstitch hem edge to the trouser leg, using ¼-inch stitches.
8. Tack the inside seam edge of cuff to the leg seam, ⅜ inch down from the fold of the cuff. Steam cuff, remove all bastings, resteam to remove basting marks. Steam front and back length leg crease through cuff.

PLAIN HEM AT BOTTOM OF SLACKS

Figure 93.

Mark leg length, turn hem to wrong side, and baste along folded edge.

Turn leg wrong side out, measure up 1½ inches from folded edge, mark, and trim away the surplus. Closely catstitch the hem to the leg. Remove all bastings, steam the hem, then steam the length front and back crease through the hem.