### **WIKIBOOKS**

# More C++ Idioms/Empty Base Optimization

# **Contents**

# **Empty Base Optimization**

Intent

Also Known As

Motivation

Solution and Sample Code

Known Uses

Related Idioms

References

# **Empty Base Optimization**

#### Intent

Optimize storage for data members of empty class types

#### Also Known As

- EBCO: Empty Base Class Optimization
- Empty Member Optimization

#### **Motivation**

Empty classes come up from time to time in C++. C++ requires empty classes to have non-zero size to ensure object identity. For instance, an array of EmptyClass below has to have non-zero size because each object identified by the array subscript must be unique. Pointer arithmetic will fall apart if sizeof(EmptyClass) is zero. Often the size of such a class is one.

```
class EmptyClass {};
EmptyClass arr[10]; // Size of this array can't be zero.
```

When the same empty class shows up as a data member of other classes, it may consume more than a single byte. Compilers align data depending on members sizes according to architecture requirements. The padding bytes are inserted to satisfy the requirements but serve no other useful purpose. Avoiding wastage of memory is generally desirable and may be critical in certain cases: deriving structure with single member of any type from empty base or including empty member will typically make it 2x bigger because of alignment requirements.

# Solution and Sample Code

C++ makes special exemption for empty classes when they are inherited from. The compiler is allowed to flatten the inheritance hierarchy in a way that the empty base class does not consume space. For instance, in the following example, sizeof(AnInt) is 4 on 32 bit architectures and sizeof(AnotherEmpty) is 1 byte even though both of them inherit from the EmptyClass

```
class AnInt : public EmptyClass
{
   int data;
};  // size = sizeof(int)

class AnotherEmpty : public EmptyClass {};  // size = 1
```

EBCO makes use of this exemption in a **systematic** way. It may not be desirable to naively move the empty classes from member-list to base-class-list because that may expose interfaces that are otherwise hidden from the users. For instance, the following way of applying EBCO will apply the optimization but may have undesirable side-effects: The signatures of the functions (if any in E1, E2) are now visible to the users of class F00 (although they can't call them because of private inheritance).

```
class E1 {};
class E2 {};

// **** before EBCO ****

class Foo {
   E1 e1;
   E2 e2;
   int data;
}; // sizeof(Foo) = 8

// **** after EBCO ****

class Foo : private E1, private E2 {
   int data;
}; // sizeof(Foo) = 4
```

A practical way of using EBCO is to combine the empty members into a single member that flattens the storage. The following template BaseOptimization applies EBCO on its first two type parameter. The Foo class above has been rewritten to use it.

With this technique, there is no change in the inheritance relationship of the Foo class. And, because BaseOptimization declares no member functions, it also avoids the problem of accidentally overriding a function from the base classes. Note that in the approach shown above it is critical that the base classes do not conflict with each other. That is, Base1 and Base2 are part of independent hierarchies.

#### Caveat

Object identity issues do not appear to be consistent across compilers. The addresses of the empty objects may or may not be the same. For instance, consider the below.

The pointers returned by the first and second member functions may be the same on some compilers and different on others. See more discussion on <a href="StackOverflow">StackOverflow</a> (http://stackoverflow.com/questions/7694158/boost-compressed-pair-and-addresses-of-empty-objects)

#### Known Uses

boost::compressed\_pair (http://www.boost.org/doc/libs/1\_47\_0/libs/utility/compressed\_pair.htm) makes use of this technique to optimize the size of the pair.

■ A C++03 emulation of <u>unique\_ptr</u> (http://home.roadrunner.com/~hinnant/unique\_ptr03.html) also uses this idiom.

# Related Idioms

#### References

- The Empty Base Class Optimization (EBCO) (http://www.informit.com/articles/article.aspx?p=31473&seqNum=2)
- The "Empty Member" C++ Optimization (http://www.cantrip.org/emptyopt.html)
- Internals of boost::compressed\_pair (http://www.ibm.com/developerworks/aix/library/au-boostutilities/index.html)

Retrieved from "https://en.wikibooks.org/w/index.php? title=More\_C%2B%2B\_Idioms/Empty\_Base\_Optimization&oldid=3678416"

This page was last edited on 16 April 2020, at 06:38.

Text is available under the Creative Commons Attribution-ShareAlike License; additional terms may apply. By using this site, you agree to the Terms of Use and Privacy Policy.