
Tutorial 4.

- 1. In the ordinary BST, let us have an additional variable to be stored at the node, which is the height of the subtree rooted there. Thus every node x has the following attributes: left, right, value, height. Write pseudo-code for insert and delete in BST with the updation of height. Be careful with delete.
- 2. This is to ensure that you understand the analysis of the "random permutation". In Quicksort, we had said that if [a(1),a(2),...,a(n)] is a random permutation, then the probability that a(1)=i is precisely 1/n. Now, for a permutation as above, let b=a(a(1)). In other words, if a=[2,3,1,4,5] then b=3, but if a=[5,4,3,2,1] then b=1 and so on. If I were to select a random permutation, then what is the probability p(i) that b=i. Warning: p(i) is not the same for every i.
- 3. Consider the structure below. Is the tree structure AVL? If we wish to store the set 1, . . . , 22, label each node with the correct number.



- 4. Now add 23 to the set and then delete 1. Also do the same in the reverse order. Are the answers the same? When will the answers be the same?
- 5. Why is it that in insert, a single or double rotation is sufficient to balance the tree, but not in deletion?