

# 2.7.3 Packet Tracer - OSPF Multiarea Exploration - Physical Mode (Part 3)


# **Objectives**

Part 1: Evaluate Network Operation of Single Area OSPF

Part 2: Evaluate Network Operation of Multiarea OSPF

Part 3: Configure a New Area and Attach to Area 0 Through the Internet

# **Topology**



# **Background / Scenario**

## Part 1: The Beginning

Casual Recording Company, based in Sao Paulo, Brazil, provides self-serve, mini-recording studios around the city so that anyone can rent a timeslot and record their songs by themselves. CRC began with a single-area OSPF network located in one building. This idea was very popular and consequently the business has grown, causing the company to expand into a branch office in a second building at the far end of the city. They continued to use single-area OSPF. You will evaluate the impact of the expanded network.

#### Part 2: Business is Booming

The IT department in CRC decided to migrate to a multiarea OSPF network. You will evaluate the impact and benefits derived from the change to determine if it was a good decision or not.

#### **Part 3: CRC Expansion Continues**

CRC has continued to grow and will open a new branch office in Montevideo, Uruguay. You will configure the Area Border Router for the new area and physically connect the branch office network to the corporate headquarters network through the internet.

#### Instructions

# Part 3: Configure a New Area and Attach to Area 0 Through the Internet

In this part, CRC is still expanding and has decided to open another office in a Montevideo, Uruguay. The internet link between Sao Paulo and Montevideo is a submarine cable. For more information, search the internet for pictures of "fiber links between Sao Paulo and Montevideo".

## Step 1: Complete the physical cabling to connect Area 0 to Area 2.

- a. You should now see an icon for **Montevideo**. If not, adjust the scroll bars so you can see both cities and the **Internet/WAN**.
- b. Click Connections in the Bottom Toolbar, and then click Fiber cable. Click Sao Paulo and select Corporate Headquarters > HQ Wiring Closet > Rack > A1\_ABR1 > GigabitEthernet2/0. Next, click Internet/WAN > Internet/WAN Wiring Closet > Rack > WAN R1 > GigabitEthernet1/0.
- c. Select another fiber cable from the toolbar and, using the same procedure as above, click Internet/WAN > Internet/WAN Wiring Closet > Rack > WAN\_R2 > GigabitEthernet1/0. Next, click Montevideo > Montevideo Branch Office > Montevideo Branch Office Wiring Closet > Rack > A2\_ABR1 > GigabitEthernet0/0.

## Step 2: Configure OSPF on router A2\_ABR1.

A2\_ABR1 is already configured, with the exception of OSPF. In this step, you will configure the router to be an area border router connecting Area 2 to the rest of the network.

- a. Click Montevideo to enter city view. Notice there is a Branch Office building with the fiber link you just created.
- b. Click Branch Office, and then the rack icon that represents the Branch Office Wiring Closet.
- c. Click A2 ABR1, and then select the CLI tab.
- d. Enable OSPF on router A2\_ABR1 and set the router ID to 172.17.1.10

```
A2_ABR1(config)# router ospf 1
A2 ABR1(config-router)# router-id 172.17.1.10
```

e. Configure the 192.168.32.0/32 network to be in Area 2 and the 172.17.1.8/32 network to be in Area 0

```
A2_ABR1(config-router) # network 192.168.32.0 0.0.0.3 area 2
A2 ABR1(config-router) # network 172.17.1.8 0.0.0.3 area 0
```

f. Configure summarization on router A2\_ABR1 so that it will advertise the summary network 192.168.32.0/19 into Area 0.

```
A2 ABR1(config-router) # area 2 range 192.168.32.0 255.255.224.0
```

**Note**: Your completion percentage should now be 100%. If not, refer to the previous commands and correct any that are in error before moving on to the next step.

#### Step 3: View the Area 2 summarized routes in Area 1 and Area 51.

You can use the **Navigation Panel (Shift+N)** in the blue tool bar at the top to quickly navigate to the wiring closets in Sao Paulo.

a. Navigate to the **Sao Paulo HQ Wiring Closet**. Click **A1\_ABR1**, and then select the **CLI** tab. Issue the **show ip route** command. An interarea route to 192.168.32.0/19 should appear in the routing table:

```
O IA 192.168.32.0/19 [110/7] via 192.168.0.4, 02:54:00, GigabitEthernet0/0/0
```

b. Navigate to the **Sao Paulo Branch Office Wiring Closet**. Click **A2\_ABR1**, and then select the **CLI** tab. Issue the **show ip route** command. An interarea route to 192.168.32.0/19 should appear in the routing table:

```
O IA 192.168.32.0/19 [110/8] via 10.10.0.21, 02:57:38, GigabitEthernet2/0
```

## Step 4: Test connectivity from Area 51 and Area 1 to Area 2.

a. Click **A51\_PC1** > **Desktop** tab > **Command Prompt**, and then ping A2\_PC1.

```
C:\> ping 192.168.35.10

Pinging 192.168.35.10 with 32 bytes of data:

Request timed out.
Reply from 192.168.35.10: bytes=32 time<1ms TTL=120
Reply from 192.168.35.10: bytes=32 time<1ms TTL=120
Reply from 192.168.35.10: bytes=32 time<1ms TTL=120</pre>
```

b. Navigate to the **Sao Paulo HQ Wiring Closet**. Click **A1\_PC1 > Desktop** tab **> Command Prompt**, and then ping A2 PC1.

It may take a moment to receive replies.

```
C:\> ping 192.168.35.10

Pinging 192.168.35.10 with 32 bytes of data:

Reply from 192.168.35.10: bytes=32 time<1ms TTL=121
Reply from 192.168.35.10: bytes=32 time<1ms TTL=121
Reply from 192.168.35.10: bytes=32 time=3ms TTL=121
Reply from 192.168.35.10: bytes=32 time<1ms TTL=121</pre>
```

## **Reflection Question**

What are the benefits derived from using multiarea OSPF in a large multi-location company?