实验: MPLS BGP VPN 跨域

HCIE 综合实验 - MPLS BGP VPN 跨域


臧家林制作



跨域 option A 实验

基本 BGP/MPLS IP VPN 在跨域环境下的应用,ASBR 之间不需要运行 MPLS,也不需要为跨域进行特殊配置。这种方式下,两个 AS 的边界路由器 ASBR 直接相连,ASBR 同时也是各自所在自治系统的 PE。两个 ASBR 都把对端 ASBR 看作自己的CE 设备,使用 EBGP 方式向对端发布 IPv4 路由。跨域的 VP N 在 ASBR 间通过专用的接口管理自己的 VPN 路由,也称为 VRF-to-VRF;背对背。

ASBR 间有无标签不需要运行 mpls,也不需要运行 mpls ldp



如图所示,共分为 4 个 AS。PE1、P1 和 ASBR1 属于 AS100,PE2、P2 和 ASBR2 属于 AS200。CE1 和 CE2 属于同一个 VPN,CE1 通过 AS100 的 PE1 接入,CE2 通过 AS200 的 PE2接入,其分别属于 AS65001 与 AS65002。

配置思路

1.配置各接口 IP 配置 OSPF。 2.配置 MPLS/MPLS LDP。 3.配置 IBGP/MP-BGP。 4.配置 VPN 实例。 5.VPN 实例配置 EB GP。

========

1.配置各接口 IP ,配置 OSPF

R1: undo ter mo sy sys R1 user-interface console 0 idle-timeout 0 0 int loo0 ip add 1.1.1.1 32 int g0/0/0 ip add 192.168.12.1 24 int g0/0/1 ip add 192.168.17.1 24 ospf router-id 1.1.1.1 area 0 net 1.1.1.1 0.0.0.0 net 192.168.12.1 0.0.0.0 q

Sy sys R2 user-interface console 0 idle-timeout 0 0 int loo0 ip add 2.2.2.2 32 int g0/0/0 ip add 192.168.12.2 24 int g0/0/1ip add 192.168.23.2 24 ospf router-id 2.2.2.2 area 0 net 2.2.2.2 0.0.0.0 net 192.168.12.2 0.0.0.0 net 192.168.23.2 0.0.0.0 q

R3: undo ter mo sy sys R3 user-interface console 0 idle-timeout 0 0 int loo0 ip add 3.3.3.3 32 int g0/0/0 ip add 192.168.34.3 24 int g0/0/1 ip add 192.168.23.3 24 ospf router-id 3.3.3.3 area 0 net 3.3.3.3 0.0.0.0 q

R4: undo ter mo Sy sys R4 user-interface console 0 idle-timeout 0 0 int loo0 ip add 4.4.4.4 32 int g0/0/0 ip add 192.168.34.4 24 int g0/0/1ip add 192.168.45.4 24 ospf router-id 4.4.4.4 area 0 net 4.4.4.4 0.0.0.0 net 192.168.45.4 0.0.0.0 q

R5: undo ter mo

Sy sys R5 user-interface console 0 idle-timeout 0 0 int loo0 ip add 5.5.5.5 32 int g0/0/0ip add 192.168.56.5 24 int g0/0/1ip add 192.168.45.5 24 ospf router-id 5.5.5.5 area 0 net 5.5.5.5 0.0.0.0 net 192.168.45.5 0.0.0.0 net 192.168.56.5 0.0.0.0 q

R6: undo ter mo Sy sys R6 user-interface console 0 idle-timeout 0 0 int loo0 ip add 6.6.6.6 32 int g0/0/0 ip add 192.168.56.6 24 int g0/0/1ip add 192.168.68.6 24 ospf router-id 6.6.6.6 area 0 net 6.6.6.6 0.0.0.0 net 192.168.56.6 0.0.0.0 q

R7:
undo ter mo
sy
sys R7
user-interface console 0
idle-timeout 0 0
int loo0
ip add 7.7.7.7 32
int g0/0/1
ip add 192.168.17.7 24
q

R8: undo ter mo sy sys R8 user-interface console 0 idle-timeout 0 0 int loo0 ip add 8.8.8.8 32 int g0/0/1 ip add 192.168.68.8 24 q

=======

2.配置 MPLS/MPLS LDP

R1: mpls lsr-id 1.1.1.1 mpls mpls ldp int g0/0/0 mpls

```
mpls ldp
q
R2:
mpls lsr-id 2.2.2.2
mpls
mpls ldp
int g0/0/0
mpls
mpls ldp
int g0/0/1
mpls
mpls ldp
q
R3:
mpls Isr-id 3.3.3.3
mpls
mpls ldp
int g0/0/1
mpls
mpls ldp
q
R4:
mpls Isr-id 4.4.4.4
mpls
mpls ldp
int g0/0/1
mpls
mpls ldp
q
R5:
```

```
mpls lsr-id 5.5.5.5
mpls
mpls ldp
int g0/0/0
mpls
mpls ldp
int g0/0/1
mpls
mpls ldp
```

R6: mpls lsr-id 6.6.6.6 mpls mpls ldp int g0/0/0 mpls mpls ldp q

========

3.配置 IBGP/MP-BGP

进入 BGP 的 VPNv4 视图。使能 PE1 与 ASBR1 的 MP-IBGP 邻居

R1:

bgp 100 router-id 1.1.1.1 peer 3.3.3.3 as-n 100 peer 3.3.3.3 con loo0 ipv4-family vpnv4 peer 3.3.3.3 enable q R3: bgp 100 router-id 3.3.3.3 peer 1.1.1.1 as-n 100 peer 1.1.1.1 con loo0 ipv4-family vpnv4 peer 1.1.1.1 enable q

R4: bgp 200 router-id 4.4.4.4 peer 6.6.6.6 as-n 200 peer 6.6.6.6 con loo0 ipv4-family vpnv4 peer 6.6.6.6 enable q

R6: bgp 200 router-id 6.6.6.6 peer 4.4.4.4 as-n 200 peer 4.4.4.4 con loo0 ipv4-family vpnv4 peer 4.4.4.4 enable

=======

4.配置 VPN 实例

R1:

ip vpn-instance huawei route-distinguisher 100:1

vpn-target 100:1 both int g0/0/1 ip binding vpn-instance huawei ip add 192.168.17.1 24

R3:

ip vpn-instance huawei route-distinguisher 100:1 vpn-target 100:1 both int g0/0/0 ip binding vpn-instance huawei ip add 192.168.34.3 24

R4:

ip vpn-instance huawei route-distinguisher 100:1 vpn-target 100:1 both int g0/0/0 ip binding vpn-instance huawei ip add 192.168.34.4 24

R6:

ip vpn-instance huawei route-distinguisher 100:1 vpn-target 100:1 both int g0/0/1 ip binding vpn-instance huawei ip add 192.168.68.6 24 q

=======

5.VPN 实例配置 EBGP

```
R1:
bgp 100
ipv4-family vpn-instance huawei
peer 192.168.17.7 as-n 65001
q
R7:
bgp 65001
router-id 7.7.7.7
peer 192.168.17.1 as-n 100
net 7.7.7.7 32
q
R3:
bgp 100
ipv4-family vpn-instance huawei
peer 192.168.34.4 as-n 200
q
R4:
bgp 200
ipv4-family vpn-instance huawei
peer 192.168.34.3 as-n 100
q
R6:
bgp 200
ipv4-family vpn-instance huawei
peer 192.168.68.8 as-n 65002
q
R8:
```

bgp 65002 router-id 8.8.8.8 peer 192.168.68.6 as-n 200 net 8.8.8.8 32

========

检查配置结果

全部配置完成后,进行查看和检测

R1:

dis bgp vpnv4 vpn-instance huawei peer 查看 R1 R7 的 BGP 邻居关系

[R1]dis bgp vpnv4 vpn-instance huawei peer

Peer V
AS MsgRcvd MsgSent OutQ Up/Down
192.168.17.7 4 65001
3 0 00:00:41

Established

R7: dis ip routing-table 查有 8.8.8.8 的路由条目,同时使用 Ping 命令测试连通性

Destination/Mask Proto Pre Cost Flags NextHop Interface

7.7.7/32 Direct 0 0 D 127.0.0.1 LoopBack0

```
255
8.8.8/32 EBGP
                                0
                                        D
192.168.17.1
                 Gigabit0/0/1
在 R7 上进行测试 ,ping -a 7.7.7.7 8.8.8.8 ,是可以通信的
[R7]ping -a 7.7.7.7 8.8.8.8
   PING 8.8.8: 56
                       data bytes, press
CTRL C to break
       Reply from 8.8.8.8: bytes=56
Sequence=1 ttl=251 time=270 ms
       Reply from 8.8.8.8: bytes=56
Sequence=2 ttl=251 time=250 ms
      Reply from 8.8.8.8: bytes=56
Sequence=3 ttl=251 time=230 ms
       Reply from 8.8.8.8: bytes=56
Sequence=4 ttl=251 time=230 ms
       Reply from 8.8.8.8: bytes=56
Sequence=5 ttl=251 time=270 ms
=======
7.7.7.7 上如何到达 8.8.8.8
在 R7 上查看转发表,去往 8.8.8.8 的下一跳为 R1
[R7]dis fib
```

Destination/Mask Nexthop Flag TimeStamp Interface TunnelID 8.8.8.8/32 192,168,17,1 **DGHU** t[5839] GE0/0/1 0x0 192.168.17.255/32 HU 127.0.0.1 t[124] InLoop0 0x0

在 R1 上查看标签表 ,去往 8.8.8.8 下一跳为 3.3.3.3,如何到 达 3.3.3.3

[R1]dis bgp vpnv4 vpn-instance huawei routing-table label

Route Distinguisher: 100:1
Network

NextHop In/Out Label

*> 7.7.7.7

192.168.17.7 1026/NULL

*>i 8.8.8.8

3.3.3.3 NULL/1026

在 R1 上查看转发表,去往 3.3.3.3 的 tunnel ID 为 0X3 [R1] dis fib

Destination/Mask		Nexthop	Flag	
TimeStamp	Inter	face	TunnelI	:D
3.3.3/32	19	2.168.12.2	DGH	łU
t[162]	GE	0/0/0		0x3
2.2.2.2/32	192.	168.12.2	DGHU	
t[152]		GE0/0/0		
0x1				

通过 tunnel ID 为 0X3 的隧道信息可以看到,要从 g0/0/0 到 1 92.168.12.2

[R1]display tunnel-info tunnel-id 0x3
Tunnel ID:

```
0x3
Tunnel Token:
3
Type:
1sp
Destination:
3.3.3.3
Out Slot:
0
Instance ID:
Out Interface:
GigabitEthernet0/0/0
Out Label:
1025
Next Hop:
192.168.12.2
Lsp Index:
6147
R2 要去往 3.3.3.3 使用标签 1025
[R2]dis mpls lsp
FEC
                                     In/Out
Label In/Out IF
Vrf Name
2.2.2.2/32
                             3/NULL
-/-
1.1.1/32
                             NULL/3
```

-/GE0/0/0 1.1.1.1/32 -/GE0/0/0 3.3.3.3/32 -/GE0/0/1 3.3.3.3/32 -/GE0/0/1	1024/3 NULL/3 1025/3			
R3 的 lsp 路径中可以看到 8.8.8.8 的标签为 1026 ,通过 vrf hu awei 学习到的				
[R3]dis mpls lsp				
Information: BGP LSP	LSP			
FEC Label In/Out IF	In/Out			
Vrf Name 8.8.8.8/32 -/- huawei	1026/NULL			
在 R8 上可以看到 8.8.8.8 的下一跳为 R6,怎么才能到达 R6 呢				
[R4]dis bgp vpnv4 vpn-instance huawei routing-table label				

Network

```
In/Out Label
NextHop
 *>
             7.7.7.7
192.168.34.3
                         1026/NULL
 *>i
            8.8.8.8
6.6.6.6
                              NULL/1026
在 R4 上查看转发表,查看到要能过 R5,才能到达 6.6.6.6
[R4]dis fib
Destination/Mask Nexthop
                               Flag
TimeStamp Interface
                                TunnelID
6.6.6.6/32
                192,168,45,5
                                     DGHU
t[162]
              GE0/0/1
                                      0x3
5.5.5.5/32
                192.168.45.5
                                     DGHU
t[155]
              GE0/0/1
                                      0x1
R5 要去往 6.6.6.6 使用标签 1026
[R5]dis mpls lsp
FEC
                                In/Out Label
In/Out IF
Vrf Name
5.5.5.5/32
                             3/NULL
-/-
4.4.4.4/32
                             NULL/3
-/GE0/0/1
4.4.4.4/32
                             1024/3
-/GE0/0/1
6.6.6.6/32
                             NULL/3
-/GE0/0/0
6.6.6.6/32
                             1025/3
-/GE0/0/0
```

R6 的 lsp 路径中可以看到 8.8.8.8 的标签为 1026 ,通过 vrf hu awei 学习到的 [R6]dis mpls lsp LSP Information: BGP LSP FEC In/Out Label In/Out IF Vrf Name 8.8.8/32 1026/NULL -/huawei R6 通过 vrf huawei 可以看到,通过 R8 到达 8.8.8.8 的 [R6]dis bgp vpnv4 vpn-instance huawei routing-table *>i 7.7.7/32 4.4.4.4 100 65001i 100 0 *> 8.8.8.8/32 192.168.68.8 65002i 0 0