# Kubernetes 企业级高可用部署

# 景

目录	2
文档信息	3
文档约定	3
1、KUBERNETES 高可用项目介绍	3
2、项目架构设计	3
2.1、项目主机信息	3
2.2、项目架构图	4
2.3、项目实施思路	5
3、项目实施过程	6
3.1、系统初始化	6
3.2、配置部署 KEEPALIVED 服务	7
3.3、配置部署 HAPROXY 服务	10
3.4、配置部署 DOCKER 服务	13
3.5、部署 KUBELET KUBEADM KUBECTL 工具	13
3.6、部署 KUBERNETES MASTER	
3.7、安装集群网络	
3.8、添加 MASTER 节点	18
3.9、加入 KUBERNETES NODE	
3.10、测试 KUBERNETES 集群	20
4、项目总结	23

### 文档信息

文档作者	房佳亮
文档版本	Version1.0
文档版权	内部资料禁止传播
文档归类	Kubernetes 项目实战训练营
系统环境	CentOS-7.X-x86_64
作者邮箱	crushlinux@163.com
修订信息	2021-03-31
技术交流	

### 文档约定

[绿色背景]	知识重点		
[红色背景]	错误警告		
[黄色背景]	注意事项		

### 执行命令

# 1、Kubernetes 高可用项目介绍

单 master 节点的可靠性不高,并不适合实际的生产环境。Kubernetes 高可用集群是保证 Master 节点中 API Server 服务的高可用。API Server 提供了 Kubernetes 各类资源对象增删改查的唯一访问入口,是整个 Kubernetes 系统的数据总线和数据中心。采用负载均衡(Load Balance)连接多个 Master 节点可以提供稳定容器云业务。

# 2、项目架构设计

### 2.1、项目主机信息


准备 6 台虚拟机,3 台 master 节点,3 台 node 节点,保证 master 节点数为>=3 的奇数。 硬件: 2 核 CPU+、2G 内存+、硬盘 20G+

网络: 所有机器网络互通、可以访问外网


操作系统	IP 地址	角色	主机名
CentOS7-x86-64	192.168.200.111	master	k8s-master1
CentOS7-x86-64	192.168.200.112	master	k8s-master2
CentOS7-x86-64	192.168.200.113	master	k8s-master3
CentOS7-x86-64	192.168.200.114	node	k8s-node1
CentOS7-x86-64	192.168.200.115	node	k8s-node2
CentOS7-x86-64	192.168.200.116	node	k8s-node3
	192.168.200.154	VIP	master.k8s.io

## 2.2、项目架构图

多 master 节点负载均衡的 kubernetes 集群。官网给出了两种拓扑结构:堆叠 control plane node 和 external etcd node,本文基于第一种拓扑结构进行搭建。



(堆叠 control plane node)



(external etcd node)

### 2.3、项目实施思路

master 节点需要部署 etcd、apiserver、controller-manager、scheduler 这 4 种服务,其中 etcd、controller-manager、scheduler 这三种服务 kubernetes 自身已经实现了高可用,在多 master 节点的情况下,每个 master 节点都会启动这三种服务,同一时间只有一个生效。因此要实现 kubernetes 的高可用,只需要 apiserver 服务高可用。

keepalived 是一种高性能的服务器高可用或热备解决方案,可以用来防止服务器单点故障导致服务中断的问题。keepalived 使用主备模式,至少需要两台服务器才能正常工作。比如 keepalived 将三台服务器搭建成一个集群,对外提供一个唯一 IP,正常情况下只有一台服务器上可以看到这个 IP 的虚拟网卡。如果这台服务异常,那么 keepalived 会立即将 IP 移动到剩下的两台服务器中的一台上,使得 IP 可以正常使用。

haproxy 是一款提供高可用性、负载均衡以及基于 TCP(第四层)和 HTTP(第七层)应用的代理软件,支持虚拟主机,它是免费、快速并且可靠的一种解决方案。使用 haproxy 负载均衡后端的 apiserver 服务,达到 apiserver 服务高可用的目的。

本文使用的 keepalived+haproxy 方案,使用 keepalived 对外提供稳定的入口,使用 haproxy 对内均衡负载。因为 haproxy 运行在 master 节点上,当 master 节点异常后,haproxy 服务也会停止,为了避免这种情况,我们在每一台 master 节点都部署 haproxy 服务,达到 haproxy 服务高可用的目的。由于多 master 节点会出现投票竞选的问题,因此 master 节点的数据最好是单数,避免票数相同的情况。

# 3、项目实施过程

### 3.1、系统初始化

### 关闭防火墙

[root@localhost ~]# systemctl stop firewalld [root@localhost ~]# systemctl disable firewalld

#### 关闭 selinux

[root@localhost ~]# sed -i 's/enforcing/disabled/' /etc/selinux/config [root@localhost ~]# setenforce 0

### 关闭 swap

[root@localhost ~]# swapoff -a
[root@localhost ~]# sed -ri 's/.\*swap.\*/#&/' /etc/fstab

修改主机名(根据主机角色不同,做相应修改)

hostname k8s-node3 bash

### 主机名映射

[root@k8s-master1 ~]# cat >> /etc/hosts << EOF 192.168.200.111 master1.k8s.io k8s-master1 192.168.200.112 master2.k8s.io k8s-master2 192.168.200.113 master3.k8s.io k8s-master3 192.168.200.114 node1.k8s.io k8s-node1 192.168.200.115 node2.k8s.io k8s-node2 192.168.200.116 node3.k8s.io k8s-node3 192.168.200.154 master.k8s.io k8s-vip EOF

### 将桥接的 IPv4 流量传递到 iptables 的链

```
[root@k8s-master1 ~]# cat << EOF >> /etc/sysctl.conf
net.bridge.bridge-nf-call-ip6tables = 1
net.bridge.bridge-nf-call-iptables = 1
EOF
[root@k8s-master1 ~]# modprobe br_netfilter
[root@k8s-master1 ~]# sysctl -p
```

### 时间同步

### [root@k8s-master1 ~]# yum install ntpdate -y

版权所有© CRUSHLINUX 6 / 23

[root@k8s-master1 ~]# ntpdate time.windows.com

## 3.2、配置部署 keepalived 服务

安装 Keepalived (所有 master 主机)

```
[root@k8s-master1 ~]# yum install -y keepalived
```

k8s-master1 节点配置

```
[root@k8s-master1 ~]# cat > /etc/keepalived/keepalived.conf <<EOF
! Configuration File for keepalived
global_defs {
  router_id k8s
vrrp_script check_haproxy {
  script "killall -0 haproxy"
  interval 3
  weight -2
  fall 10
  rise 2
vrrp_instance VI_1 {
  state MASTER
  interface ens33
  virtual_router_id 51
  priority 100
  advert_int 1
  authentication {
    auth_type PASS
    auth_pass 1111
  }
virtual_ipaddress {
  192.168.200.154
track_script {
  check_haproxy
}
EOF
```

### k8s-master2 节点配置

```
[root@k8s-master2 ~]# cat > /etc/keepalived/keepalived.conf <<EOF
! Configuration File for keepalived
global_defs {
```

```
router_id k8s
vrrp_script check_haproxy {
  script "killall -0 haproxy"
  interval 3
  weight -2
  fall 10
  rise 2
}
vrrp_instance VI_1 {
  state BACKUP
  interface ens33
  virtual_router_id 51
  priority 90
  adver_int 1
  authentication {
    auth_type PASS
    auth_pass 1111
  }
virtual_ipaddress {
  192.168.200.154
}
track_script {
  check_haproxy
}
EOF
```

### k8s-master3 节点配置

```
[root@k8s-master3 ~]# cat > /etc/keepalived/keepalived.conf <<EOF
! Configuration File for keepalived
global_defs {
    router_id k8s
}
vrrp_script check_haproxy {
    script "killall -0 haproxy"
    interval 3
    weight -2
    fall 10
    rise 2
}
vrrp_instance VI_1 {
    state BACKUP
    interface ens33</pre>
```

```
virtual_router_id 51
priority 80
adver_int 1
authentication {
   auth_type PASS
   auth_pass 1111
}
virtual_ipaddress {
   192.168.200.154
}
track_script {
   check_haproxy
}
EOF
```

#### 启动和检查

所有 master 节点都要执行

```
[root@k8s-master1 ~]# systemctl start keepalived
[root@k8s-master1 ~]# systemctl enable keepalived
```

#### 查看启动状态

```
[root@k8s-master1 ~]# systemctl status keepalived
Created symlink from /etc/systemd/system/multi-user.target.wants/keepalived.
service to /usr/lib/systemd/system/keepalived.service.[root@k8s-master1 ~]# systemctl status
keepalived
keepalived.service - LVS and VRRP High Availability Monitor
   Loaded: loaded (/usr/lib/systemd/system/keepalived.service; enabled; vendor preset:
disabled)
   Active: active (running) since ☐ 2021-01-03 20:44:16 CST; 8s ago
 Main PID: 1670 (keepalived)
   CGroup: /system.slice/keepalived.service
             -1670 /usr/sbin/keepalived -D
             -1671 /usr/sbin/keepalived -D
               -1672 /usr/sbin/keepalived -D
1月 03 20:44:23 k8s-master1 Keepalived_vrrp[1672]: Sending gratuitous ARP on ens33 for
192.168.200.154
1月 03 20:44:23 k8s-master1 Keepalived_vrrp[1672]: Sending gratuitous ARP on ens33 for
192.168.200.154
1月 03 20:44:23 k8s-master1 Keepalived_vrrp[1672]: Sending gratuitous ARP on ens33 for
192.168.200.154
1月 03 20:44:23 k8s-master1 Keepalived_vrrp[1672]: Sending gratuitous ARP on ens33 for
192.168.200.154
```

1月 03 20:44:24 k8s-master1 Keepalived\_vrrp[1672]: Sending gratuitous ARP on ens33 for

版权所有© CRUSHLINUX

```
192.168.200.154

1月 03 20:44:24 k8s-master1 Keepalived_vrrp[1672]: VRRP_Instance(VI_1) Sending/queueing gratuitous ARPs on ens33 for 192.168.200.154

1月 03 20:44:24 k8s-master1 Keepalived_vrrp[1672]: Sending gratuitous ARP on ens33 for 192.168.200.154

1月 03 20:44:24 k8s-master1 Keepalived_vrrp[1672]: Sending gratuitous ARP on ens33 for 192.168.200.154

1月 03 20:44:24 k8s-master1 Keepalived_vrrp[1672]: Sending gratuitous ARP on ens33 for 192.168.200.154

1月 03 20:44:24 k8s-master1 Keepalived_vrrp[1672]: Sending gratuitous ARP on ens33 for 192.168.200.154
```

启动完成后在 master1 查看网络信息

### 3.3、配置部署 haproxy 服务

所有 master 主机安装 haproxy

```
[root@k8s-master1 ~]# yum install -y haproxy
```

每台 master 节点中的配置均相同,配置中声明了后端代理的每个 master 节点服务器,指定了 haproxy 的端口为 16443,因此 16443 端口为集群的入口。

```
[root@k8s-master1 ~]# cat > /etc/haproxy/haproxy.cfg << EOF
#-------
# Global settings
#-------
global
log 127.0.0.1 local2
chroot /var/lib/haproxy
pidfile /var/run/haproxy.pid
maxconn 4000
user haproxy
group haproxy
daemon
```

```
stats socket /var/lib/haproxy/stats
# common defaults that all the 'listen' and 'backend' sections will
# usr if not designated in their block
#-----
defaults
  mode
                        http
                      global
 log
 option
                      httplog
 option
                      dontlognull
 option http-server-close
                   except 127.0.0.0/8
 option forwardfor
 option
                      redispatch
                     3
 retries
 timeout http-request 10s
  timeout queue
                       10s
 timeout connect
  timeout client
                      1m
  timeout server
                       1m
  timeout http-keep-alive 10s
  timeout check
  maxconn
                            3000
# kubernetes apiserver frontend which proxys to the backends
#-----
frontend kubernetes-apiserver
  mode
                     tcp
                    *:16443
 bind
 option
                    tcplog
  default backend
                   kubernetes-apiserver
#round robin balancing between the various backends
backend kubernetes-apiserver
 mode
                      tcp
 balance
                    roundrobin
 server
                    master1.k8s.io
                                    192.168.200.111:6443 check
                    master2.k8s.io 192.168.200.112:6443 check
 server
                    master3.k8s.io 192.168.200.113:6443 check
 server
# collection haproxy statistics message
#-----
listen stats
                    *:1080
 bind
```

版权所有© CRUSHLINUX 11 / 23

stats auth admin:awesomePassword stats refresh 5s

stats realm HAProxy\ Statistics

stats uri /admin?stats

**EOF** 

### 启动和检查

所有 master 节点都要执行

[root@k8s-master1 ~]# systemctl start haproxy [root@k8s-master1 ~]# systemctl enable haproxy

### 查看启动状态

[root@k8s-master1 ~]# systemctl status haproxy

[root@k8s-master1 ~]# systemctl status haproxy

haproxy.service - HAProxy Load Balancer

Loaded: loaded (/usr/lib/systemd/system/haproxy.service; enabled; vendor preset:

disabled)

Active: active (running) since ☐ 2021-01-03 20:45:39 CST; 11s ago

Main PID: 1778 (haproxy-systemd)

CGroup: /system.slice/haproxy.service

1778 /usr/sbin/haproxy-systemd-wrapper -f /etc/haproxy/haproxy.cfg -p

/run/haproxy.pid

1779 /usr/sbin/haproxy -f /etc/haproxy/haproxy.cfg -p /run/haproxy.pid -Ds

1780 /usr/sbin/haproxy -f /etc/haproxy/haproxy.cfg -p /run/haproxy.pid -Ds

1月 03 20:45:39 k8s-master1 systemd[1]: Started HAProxy Load Balancer.

1月 03 20:45:39 k8s-master1 haproxy-systemd-wrapper[1778]: haproxy-systemd-wrapper: executing /usr/sbin/haproxy -f /etc/haproxy/haproxy.cfg -p /ru...pid -Ds

1月 03 20:45:39 k8s-master1 haproxy-systemd-wrapper[1778]: [WARNING] 002/204539

(1779): config: 'option forwardfor' ignored for frontend 'kubern...P mode.

1月 03 20:45:39 k8s-master1 haproxy-systemd-wrapper[1778]: [WARNING] 002/204539

(1779): config: 'option forwardfor' ignored for backend 'kuberne...P mode.

Hint: Some lines were ellipsized, use -I to show in full.

### 检查端口

[root@k8s	[root@k8s-master1 ~]# netstat -Intup grep haproxy							
tcp	0	0 0.0.0.0:1080	0.0.0.0:*	LISTEN				
1780/hapr	оху							
tcp	0	0 0.0.0.0:16443	0.0.0.0:*	LISTEN				
1780/hapr	оху							
udp	0	0 0.0.0.0:36433	0.0.0.0:*					
1779/hapr	оху							

### 3.4、配置部署 Docker 服务

所有主机上分别部署 Docker 环境,因为 Kubernetes 对容器的编排需要 Docker 的支持。

```
[root@k8s-master ~]# wget -O /etc/yum.repos.d/CentOS-Base.repo
http://mirrors.aliyun.com/repo/Centos-7.repo
[root@k8s-master ~]# yum install -y yum-utils device-mapper-persistent-data lvm2
```

使用 YUM 方式安装 Docker 时,推荐使用阿里的 YUM 源。

```
[root@k8s-master ~]# yum-config-manager --add-repo https://mirrors.aliyun.com/docker-ce/linux/centos/docker-ce.repo
[root@k8s-master ~]# yum clean all && yum makecache fast

[root@k8s-master ~]# yum -y install docker-ce
[root@k8s-master ~]# systemctl start docker
[root@k8s-master ~]# systemctl enable docker
```

镜像加速器 (所有主机配置)

```
[root@k8s-master ~]# cat << END > /etc/docker/daemon.json
{
         "registry-mirrors":[ "https://nyakyfun.mirror.aliyuncs.com" ]
}
END
[root@k8s-master ~]# systemctl daemon-reload
[root@k8s-master ~]# systemctl restart docker
```

### 3.5、部署 kubelet kubeadm kubectl 工具

使用 YUM 方式安装 Kubernetes 时,推荐使用阿里的 yum。 所有主机配置

版权所有© CRUSHLINUX 13 / 23

#### kubernetes.repo

安装 kubelet kubeadm kubectl

所有主机配置

[root@k8s-master  $^{\sim}$ ]# yum install -y kubelet kubeadm kubectl

[root@k8s-master ~]# systemctl enable kubelet

### 3.6、部署 Kubernetes Master

在具有 vip 的 master 上操作。此处的 vip 节点为 k8s-master1。 创建 kubeadm-config.yaml 文件

```
[root@k8s-master1 ~]# cat > kubeadm-config.yaml << EOF
apiServer:
  certSANs:
    - k8s-master1
    - k8s-master2
    - k8s-master3
    - master.k8s.io
    - 192.168.200.111
    - 192.168.200.112
    - 192.168.200.113
    - 192.168.200.154
    - 127.0.0.1
  extraArgs:
    authorization-mode: Node, RBAC
  timeoutForControlPlane: 4m0s
apiVersion: kubeadm.k8s.io/v1beta1
certificatesDir: /etc/kubernetes/pki
clusterName: kubernetes
controlPlaneEndpoint: "master.k8s.io:6443"
controllerManager: {}
  type: CoreDNS
etcd:
  local:
    dataDir: /var/lib/etcd
imageRepository: registry.aliyuncs.com/google_containers
kind: ClusterConfiguration
kubernetesVersion: v1.20.0
networking:
  dnsDomain: cluster.local
  podSubnet: 10.244.0.0/16
  serviceSubnet: 10.1.0.0/16
```

scheduler: {}
EOF

#### 查看所需镜像信息

[root@k8s-master1 ~]# kubeadm config images list --config kubeadm-config.yaml
W0103 21:00:29.765926 3145 common.go:77] your configuration file uses a deprecated
API spec: "kubeadm.k8s.io/v1beta1". Please use 'kubeadm config migrate
--old-config old.yaml --new-config new.yaml', which will write the new, similar spec using a
newer API version.
registry.aliyuncs.com/google\_containers/kube-apiserver:v1.20.0
registry.aliyuncs.com/google\_containers/kube-scheduler:v1.20.0
registry.aliyuncs.com/google\_containers/kube-proxy:v1.20.0
registry.aliyuncs.com/google\_containers/kube-proxy:v1.20.0
registry.aliyuncs.com/google\_containers/pause:3.2
registry.aliyuncs.com/google\_containers/etcd:3.4.13-0
registry.aliyuncs.com/google\_containers/coredns:1.7.0

### 上传 k8s 所需的镜像并导入(所有 master 主机)

```
[root@k8s-master1 ~]# cd master/
[root@k8s-master1 master]# ls
coredns_1.7.0.tar kube-apiserver_v1.20.0.tar kube-proxy_v1.20.0.tar
pause_3.2.tar etcd_3.4.13-0.tar kube-controller-manager_v1.20.0.tar kube-scheduler_v1.20.0.tar
[root@k8s-master1 master]# ls | while read line
do
docker load < $line
done
```

#### 使用 kubeadm 命令初始化 k8s

```
[root@k8s-master1 ~]# kubeadm init --config kubeadm-config.yaml
Your Kubernetes control-plane has initialized successfully!
To start using your cluster, you need to run the following as a regular user:
  mkdir -p $HOME/.kube
  sudo cp -i /etc/kubernetes/admin.conf $HOME/.kube/config
  \verb+sudo+ chown $(id -u):$(id -g) $HOME/.kube/config+ \\
Alternatively, if you are the root user, you can run:
  export KUBECONFIG=/etc/kubernetes/admin.conf
You should now deploy a pod network to the cluster.
Run "kubectl apply -f [podnetwork].yaml" with one of the options listed at:
  https://kubernetes.io/docs/concepts/cluster-administration/addons/
You can now join any number of control-plane nodes by copying certificate authorities
and service account keys on each node and then running the following as root:
  kubeadm join master.k8s.io:6443 --token vhqazv.c398m3ohhpl8avd0 \ 加入master时使用
    --discovery-token-ca-cert-hash sha256:40fc58440b1ea96c64816050c197b6ef0cd8ac42f687d0e54b8b2f9c392a5617 \
    --control-plane
Then you can join any number of worker nodes by running the following on each as root:
                                                                    加入node时使用
kubeadm join master.k8s.io:6443 --token vhqazv.c398m3ohhpl8avd0 \
    --discovery-token-ca-cert-hash sha256:40fc58440blea96c64816050c197b6ef0cd8ac42f687d0e54b8b2f9c392a5617
```

#### 初始化中的错误:

[ERROR FileContent--proc-sys-net-bridge-bridge-nf-call-iptables]: /proc/sys/net/bridge/bridge-nf-call-iptables contents are not set to 1

执行以下命令后重新执行初始化命令

echo "1" >/proc/sys/net/bridge/bridge-nf-call-iptables

#### 根据初始化的结果操作

```
[root@k8s-master1 ~]# mkdir -p $HOME/.kube
[root@k8s-master1 ~]# sudo cp -i /etc/kubernetes/admin.conf $HOME/.kube/config
[root@k8s-master1 ~]# sudo chown $(id -u):$(id -g) $HOME/.kube/config
```

#### 查看集群状态

注意: 出现以上错误情况,是因为/etc/kubernetes/manifests/下的 kube-controller-manager.yaml 和 kube-scheduler.yaml 设置的默认端口为 0 导致的,解决方式是注释掉对应的port 即可

修改 kube-controller-manager.yaml 文件

```
[root@k8s-master1 ~]# cat /etc/kubernetes/manifests/kube-controller-manager.yaml
apiVersion: v1
kind: Pod
metadata:
  creationTimestamp: null
  labels:
    component: kube-controller-manager
    tier: control-plane
  name: kube-controller-manager
  namespace: kube-system
spec:
  containers:
  - command:
    - kube-controller-manager
    - --allocate-node-cidrs=true
    - --authentication-kubeconfig=/etc/kubernetes/controller-manager.conf
    - --authorization-kubeconfig=/etc/kubernetes/controller-manager.conf
    - --bind-address=127.0.0.1
    - --client-ca-file=/etc/kubernetes/pki/ca.crt
    - --cluster-cidr=10.244.0.0/16
    - --cluster-name=kubernetes
    - --cluster-signing-cert-file=/etc/kubernetes/pki/ca.crt
    - --cluster-signing-key-file=/etc/kubernetes/pki/ca.key
    - --controllers=*, bootstrapsigner, tokencleaner
    - --kubeconfig=/etc/kubernetes/controller-manager.conf
    - --leader-elect=true
     - --port=0
    - --requestheader-client-ca-file=/etc/kubernetes/pki/front-proxy-ca.crt
修改 kube-scheduler.yaml 文件
```

Kubernetes 项目实战训练营 人生在勤,勤则不匮

 $[\verb|root@k8s-master1| \sim] \# \verb| cat /etc/kubernetes/manifests/kube-scheduler.yaml|$ 

apiVersion: v1
kind: Pod
metadata:

creationTimestamp: null

labels:

component: kube-scheduler
tier: control-plane
name: kube-scheduler
namespace: kube-system

spec:

containers:
 command:

- kube-scheduler

--authentication-kubeconfig=/etc/kubernetes/scheduler.conf
 --authorization-kubeconfig=/etc/kubernetes/scheduler.conf

- --bind-address=127.0.0.1

- --kubeconfig=/etc/kubernetes/scheduler.conf

--leader-elect=true

# - --port=0

image: registry.aliyuncs.com/google\_containers/kube-scheduler:v1.20.0

#### 查看集群状态

### [root@k8s-master1 ~]# kubectl get cs

Warning: v1 ComponentStatus is deprecated in v1.19+

NAME STATUS MESSAGE ERROR

controller-manager Healthy ok scheduler Healthy ok

etcd-0 Healthy {"health":"true"}

### 查看 pod 信息

[root@k8s-master1 ~]# kubectl get pods -n kube-system							
NAME	R	EADY STATUS	RESTARTS AGE				
coredns-7f89b7bc75-52kjr	0/1	Pending 0	8m30s				
coredns-7f89b7bc75-7h8js	0/1	Pending 0	8m30s				
etcd-k8s-master1	1/1	Running 0	8m38s				
kube-apiserver-k8s-master1	1/1	Running 0	8m38s				
kube-controller-manager-k8s-master1	1/1	Running 0	2m11s				
kube-proxy-s24dn	1/1	Running 0	8m31s				
kube-scheduler-k8s-master1	1/1	Running 0	119s				

### 查看节点信息

[root@k8s-master1 ~]# kubectl get nodes						
NAME	STATUS	ROLES	AG	E	VERSION	
k8s-master1	NotReady	control-plane,master	9m24s	v1.2	0.0	

17 / 23

### 3.7、安装集群网络

### 在 k8s-master1 节点执行

### [root@k8s-master1 ~]# docker load < flannel\_v0.12.0-amd64.tar

版权所有© CRUSHLINUX

#### [root@k8s-master1 ~]# kubectl apply -f kube-flannel.yml

再次查看节点信息:

[root@k8s-master1 ~]# kubectl get nodes

NAME STATUS ROLES AGE VERSION

k8s-master1 Ready control-plane,master 8m13s v1.20.1

### 3.8、添加 master 节点

在 k8s-master2 和 k8s-master3 节点创建文件夹

[root@k8s-master2 ~]# mkdir -p /etc/kubernetes/pki/etcd

[root@k8s-master3 ~]# mkdir -p /etc/kubernetes/pki/etcd

在 k8s-master1 节点执行

从 k8s-master1 复制秘钥和相关文件到 k8s-master2 和 k8s-master3

### [root@k8s-master1 ~]# scp /etc/kubernetes/admin.conf

root@192.168.200.112:/etc/kubernetes

[root@k8s-master1 ~]# scp /etc/kubernetes/admin.conf

root@192.168.200.113:/etc/kubernetes

[root@k8s-master1 ~]# scp /etc/kubernetes/pki/{ca.\*,sa.\*,front-proxy-ca.\*}

root@192.168.200.112:/etc/kubernetes/pki

[root@k8s-master1 ~]# scp /etc/kubernetes/pki/{ca.\*,sa.\*,front-proxy-ca.\*}

root@192.168.200.113:/etc/kubernetes/pki

[root@k8s-master1 ~]# scp /etc/kubernetes/pki/etcd/ca.\*

root@192.168.200.112:/etc/kubernetes/pki/etcd

[root@k8s-master1 ~]# scp /etc/kubernetes/pki/etcd/ca.\*

root@192.168.200.113:/etc/kubernetes/pki/etcd

将其他 master 节点加入集群

注意: kubeadm init 生成的 token 有效期只有 1 天, 生成不过期 token

## [root@k8s-master1 manifests]# kubeadm token create --ttl 0 --print-join-command

[root@k8s-master1 manifests]# kubeadm token list

[root@k8s-master1 -]# kubeadm token create --ttl 0 --print-join-command kubeadm join master.k8s.io:6443 --token 5zvcjk.i6r9vijc869svkke --discovery-token-ca-cert-hash sha256:40fc58440blea96c64816050c197b6ef0cd8ac42f687d0e54b8 bzf9c.392a5617
[root@k8s-master1 -]# kubeadm token list
TOKEN TIL EXPIRES USAGES DESCRIPTION EXTRA GROUPS
5zvcjk.i6r9vijc869svkke <forever> authentication,signing <none> system:bootstrappers:kube

payory.lorbysjcobsykke <forever> <never> autnentication,signing <none> add:default-node-token vhqazv.c398m3ohhpl8avd0 23h 2021-01-04T21:06:38+08:00 authentication,signing <none> bootstrappers:kubeadm:default-node-token

system:bootstrappers:kube

k8s-master2 和 k8s-master3 都需要加入

[root@k8s-master2 ~]# kubeadm join master.k8s.io:6443 --token 5zvcjk.i6r9vijc869svkke \
--discovery-token-ca-cert-hash

```
sha256:40fc58440b1ea96c64816050c197b6ef0cd8ac42f687d0e54b8b2f9c392a5617 \
--control-plane
```

[root@k8s-master2 ~]# mkdir -p \$HOME/.kube

[root@k8s-master2 ~]# sudo cp -i /etc/kubernetes/admin.conf \$HOME/.kube/config

[root@k8s-master2 ~]# sudo chown \$(id -u):\$(id -g) \$HOME/.kube/config

[root@k8s-master2 ~]# docker load < flannel\_v0.12.0-amd64.tar

[root@k8s-ma	aster1 ~]# ku	bectl get nodes				
NAME	STATUS	ROLES	AG	iE VEI	RSION	
k8s-master1	Ready	control-plane,master	19m	v1.20.0		
k8s-master2	Ready	control-plane,master	2m20s	v1.20.0		
k8s-master3	Ready	control-plane,master	95s	v1.20.0		
[root@k8s-ma	aster1 manif	ests]# kubectl get pods	all-names	spaces		
[root@k8s-mas	ter1 ~]# kub	ectl get podsall-name	spaces			
NAMESPACE	NAME		READY	STATUS	RESTARTS	AGE
kube-system	coredns-7f8	9b7bc75-52kjr	1/1	Running	0	19m
kube-system	coredns-7f8	9b7bc75-7h8js	1/1	Running	0	19m
kube-system	etcd-k8s-ma	ster1	1/1	Running	0	19m
kube-system	etcd-k8s-ma	ster2	1/1	Running	0	2m34s
kube-system	etcd-k8s-ma	ster3	1/1	Running	0	43s
kube-system	kube-apiser	ver-k8s-master1	1/1	Running	0	19m
kube-system	kube-apiser	ver-k8s-master2	1/1	Running	0	2m38s
kube-system	kube-apiser	ver-k8s-master3	1/1	Running	1	110s
kube-system	•	ller-manager-k8s-master1	1/1	Running	1	13m
kube-system		ller-manager-k8s-master2		Running	0	2m38s
kube-system		ller-manager-k8s-master3		Running	0	36s
kube-system		l-ds-amd64-nfxcc	1/1	Running	0	115s
kube-system	kube-flanne	l-ds-amd64-pb94t	1/1	Running	0	2m40s
kube-system		l-ds-amd64-x8lck	1/1	Running	0	9m31s
kube-system	kube-proxy-	gdb5l	1/1	Running	0	2m40s
kube-system	kube-proxy-	_	1/1	Running	0	19m
kube-system	kube-proxy-		1/1	Running	0	115s
kube-system		ler-k8s-master1	1/1	Running	i	12m
kube-system		ler-k8s-master2	1/1	Running	0	2m38s
			-, -		-	

# 3.9、加入 Kubernetes Node

直接在 node 节点服务器上执行 k8s-master1 初始化成功后的消息即可:

```
[root@k8s-node1 ~]# kubeadm join master.k8s.io:6443 --token 5zvcjk.i6r9vijc869svkke \
--discovery-token-ca-cert-hash
```

sha256: 40fc 58440b 1 ea 96c 64816050c 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 0e 54b8b 2f 9c 392a 5617d 197b 6e f 0cd 8ac 42f 687d 197b 6e f 0cd 8ac 42f 687d

[root@k8s-node1 ~]# docker load < flannel\_v0.12.0-amd64.tar

查看节点信息

[root@k8s-master1 ~]# kubectl get nodes						
NAME	STATUS ROI	LES	AGE	VERSION		
k8s-master1	Ready contro	ol-plane,master 2	23m \	1.20.0		

版权所有© CRUSHLINUX 19 / 23

k8s-master2	Ready	control-plane,master	6m42s	v1.20.0
k8s-master3	Ready	control-plane,master	5m57s	v1.20.0
k8s-node1	Ready	<none></none>	82s	v1.20.0
k8s-node2	Ready	<none></none>	77s	v1.20.0
k8s-node3	Ready	<none></none>	60s	v1.20.0

### 3.10、测试 Kubernetes 集群

所有 node 主机导入测试镜像

```
[root@k8s-node1 ~]# docker load < nginx-1.19.tar
[root@k8s-node1 ~]# docker tag nginx nginx:1.19.6
```

在 Kubernetes 集群中创建一个 pod,验证是否正常运行。

```
[root@k8s-master1 ~]# mkdir demo
[root@k8s-master1 ~]# cd demo
[root@k8s-master1 demo]# vim nginx-deployment.yaml
apiVersion: apps/v1
kind: Deployment
metadata:
  name: nginx-deployment
  labels:
    app: nginx
spec:
  replicas: 3
  selector:
    matchLabels:
      app: nginx
  template:
    metadata:
      labels:
         app: nginx
    spec:
      containers:
      - name: nginx
         image: nginx:1.19.6
         ports:
         - containerPort: 80
```

创建完 Deployment 的资源清单之后,使用 create 执行资源清单来创建容器。通过 get pods 可以查看到 Pod 容器资源已经自动创建完成。

```
[root@k8s-master1 demo]# kubectl create -f nginx-deployment.yaml deployment.apps/nginx-deployment created
```

[root@k8s-master1 demo]# kubectl ge	et pods			
NAME	R	EADY STAT	US	RESTARTS AGE
nginx-deployment-76ccf9dd9d-c5bjw	1/1	Running	0	10s
nginx-deployment-76ccf9dd9d-jxm9z	1/1	Running	0	10s
nginx-deployment-76ccf9dd9d-kzdfz	1/1	Running	0	<b>10</b> s
[root@k8s-master1 ~]# kubectl get po	ds -o wid	de		
NAME	R	EADY STAT	US	RESTARTS AGE IP
NODE NOMINATED NODE	READIN	ESS GATES		
nginx-deployment-76ccf9dd9d-c5bjw	1/1	Running	0	62m 10.244.4.2
k8s-node2 <none> <no< td=""><td>one&gt;</td><td></td><td></td><td></td></no<></none>	one>			
nginx-deployment-76ccf9dd9d-jxm9z	1/1	Running	0	62m 10.244.5.2
k8s-node3 <none> <no< td=""><td>one&gt;</td><td></td><td></td><td></td></no<></none>	one>			
nginx-deployment-76ccf9dd9d-kzdfz	1/1	Running	0	62m 10.244.3.2
k8s-node1 <none> <nd< td=""><td>one&gt;</td><td></td><td></td><td></td></nd<></none>	one>			

### 创建 Service 资源清单

在创建的 nginx-service 资源清单中,定义名称为 nginx-service 的 Service、标签选择器 为 app: nginx、type 为 NodePort 指明外部流量可以访问内部容器。在 ports 中定义暴露的端口库号列表,对外暴露访问的端口是 80,容器内部的端口也是 80。

```
[root@k8s-master1 demo]# vim nginx-service.yaml
kind: Service
apiVersion: v1
metadata:
  name: nginx-service
spec:
  selector:
    app: nginx
  type: NodePort
  ports:
  - protocol: TCP
    port: 80
    targetPort: 80
[root@k8s-master1 demo]# kubectl create -f nginx-service.yaml
service/nginx-service created
[root@k8s-master1 demo]# kubectl get svc
NAME
                   TYPE
                                 CLUSTER-IP
                                                  EXTERNAL-IP
                                                                  PORT(S)
                                                                                   AGE
kubernetes
                 ClusterIP
                             10.1.0.1
                                                                              38m
                                             <none>
                                                             443/TCP
                             10.1.161.204
               NodePort
                                             <none>
                                                             80:30373/TCP
nginx-service
                                                                              4s
```

通过浏览器访问 nginx: <a href="http://master.k8s.io:30373">http://master.k8s.io:30373</a> 域名或者 VIP 地址

```
[root@k8s-master1 demo]# elinks --dump http://master.k8s.io:30373

Welcome to nginx!
```

If you see this page, the nginx web server is successfully installed and working. Further configuration is required.

For online documentation and support please refer to [1]nginx.org.

Commercial support is available at [2]nginx.com.

Thank you for using nginx.


References

Visible links

1. http://nginx.org/



挂起 k8s-master1 节点,刷新页面还是能访问 nginx,说明高可用集群部署成功。



检查会发现 VIP 已经转移到 k8s-master2 节点上

[root@k8s-master2 ~]# ip a s ens33
2: ens33: <BROADCAST,MULTICAST,UP,LOWER\_UP> mtu 1500 qdisc pfifo\_fast state UP group default qlen 1000

link/ether 00:0c:29:3a:76:54 brd ff:ff:ff:ff:ff
inet 192.168.200.112/24 brd 192.168.200.255 scope global ens33
 valid\_lft forever preferred\_lft forever
inet 192.168.200.154/32 scope global ens33
 valid\_lft forever preferred\_lft forever
inet6 fe80::20c:29ff:fe3a:7654/64 scope link
 valid\_lft forever preferred\_lft forever

至此 Kubernetes 企业级高可用环境完美实现。

# 4、项目总结

- 1、集群中只要有一个 master 节点正常运行就可以正常对外提供业务服务。
- 2、如果需要在 master 节点使用 kubectl 相关的命令,必须保证至少有 2 个 master 节点正常运行才可以使用,不然会有 Unable to connect to the server: net/http: TLS handshake timeout 这样的错误。
- 3、节点故障时 pod 自动转移: 当 pod 所在的节点宕机后,根据 controller-manager 的-podeviction-timeout 配置,默认是 5 分钟,5 分钟后 k8s 会把 pod 状态设置为 unkown, 然后在其它节点启动 pod。当故障节点恢复后,k8s 会删除故障节点上面的 unkown pod。如果你想立即强制迁移,可以用 kubectl drain nodename
- 4、为了保证集群的高可用性,建议 master 节点和 node 节点至少分别部署 3 台及以上,且 master 节点应该部署基数个实例(3、5、7、9)。