[mysqld\_safe]
malloc-lib=tcmalloc

To use a specific tcmalloc library, specify its full path name. Example:

[mysqld\_safe]
malloc-lib=/opt/lib/libtcmalloc\_minimal.so

• --mysqld=prog\_name

The name of the server program (in the <code>ledir</code> directory) that you want to start. This option is needed if you use the MySQL binary distribution but have the data directory outside of the binary distribution. If <code>mysqld\_safe</code> cannot find the server, use the <code>--ledir</code> option to indicate the path name to the directory where the server is located.

This option is accepted only on the command line, not in option files. On platforms that use systemd, the value can be specified in the value of MYSQLD\_OPTS. See Section 2.5.9, "Managing MySQL Server with systemd".

• --mysqld-version=*suffix* 

This option is similar to the <code>--mysqld</code> option, but you specify only the suffix for the server program name. The base name is assumed to be <code>mysqld</code>. For example, if you use <code>--mysqld-version=debug</code>, <code>mysqld\_safe</code> starts the <code>mysqld-debug</code> program in the <code>ledir</code> directory. If the argument to <code>--mysqld-version</code> is empty, <code>mysqld\_safe</code> uses <code>mysqld</code> in the <code>ledir</code> directory.

This option is accepted only on the command line, not in option files. On platforms that use systemd, the value can be specified in the value of MYSQLD\_OPTS. See Section 2.5.9, "Managing MySQL Server with systemd".

• --nice=*priority* 

Use the nice program to set the server's scheduling priority to the given value.

• --no-defaults

Do not read any option files. If program startup fails due to reading unknown options from an option file, --no-defaults can be used to prevent them from being read. This must be the first option on the command line if it is used.

For additional information about this and other option-file options, see Section 4.2.2.3, "Command-Line Options that Affect Option-File Handling".

• --open-files-limit=count

The number of files that mysqld should be able to open. The option value is passed to ulimit -n.



Note

You must start mysqld\_safe as root for this to function properly.

• --pid-file=file\_name

The path name that mysqld should use for its process ID file.

• --plugin-dir=dir\_name

The path name of the plugin directory.