Linux网络编程: libpcap 移植及使用



錦鈊銀 ● 于 2021-06-16 17:57:48 发布 ● 1133 ★ 收藏 12

分类专栏: 网络编程 文章标签: 网络通信 socket



网络编程 专栏收录该内容

目录

参考文章:

- 一、libpcap库下载
- 二、libpcap库交叉编译安装
- 三、应用程序交叉编译
- 四、Ubuntu系统安装 libpcap (非交叉编译)
- 五、libpcap使用
- 六、开发板上测试

参考文章:

- 1. Linux下移植libpcap抓包库到arm平台
- 2. Linux 网络编程—— libpcap 详解
- 3. libpcap使用
- 4. Libpcap库编程指南—数据包捕获
- 5. libpcap函数库详细介绍

一、libpcap 库下载

- 1. http://www.tcpdump.org/
- 2. https://github.com/the-tcpdump-group/libpcap/releases

二、libpcap库交叉编译 安装

- 1. 配置交叉编译环境
- 2. 下载最新版本 libpcap-1.10.1.tar.gz,解压缩到当前目录:
 - 1 tar -xzvf ./libpcap-1.10.1.tar.gz -C ./
- 3. 配置安装目录和交叉编译环境
 - 1 ./configure --prefix=/xxx/xxx/install/ --host=arm-linux-gnueabihf
- 4. 编译
 - 1 make
- 5. 安装
 - 1 | make install

在 install/lib/ 目录下生成如下文件:











pkgconfig

libpcap.a

libpcap.so.1.10.1

版权

6. cd 进入 install 安装目录, 打包lib目录下动态库文件

```
tar -zcvf libpcap-1.10.1-install.tar.gz lib/*.so*
```

7. 将 libpcap-1.10.1-install.tar.gz 压缩包拷贝到开发板上,解压新建文件夹:/usr/local/lib/libpcap,然后解压到该文件夹中

- 1 | sudo mkdir /usr/local/lib/libpcap
- 1 sudo tar -zxf ./libpcap-1.10.1-install.tar.gz --strip-components 1 -C /usr/local/lib/libpcap
- 8. 开发板上添加库文件搜索路径

打开ld.so.conf文件

1 | sudo vi /etc/ld.so.conf.d/libc.conf

在 /etc/ld.so.conf 文件中添加库的搜索路径

1 /usr/local/lib/libpcap //根据自己的库路径添加

然后 ldconfig 生成/etc/ld.so.cache, ldconfig -v 查看

1 | sudo ldconfig

三、应用程序交叉编译

交叉编译应用程序:需要加-lpcap选项,并指定头文件及动态库路径

```
1 arm-linux-gnueabihf-gcc ./libpcap_test.c -o ./libpcap_test -lpcap -I/xxx/include/ -L/xxx/lib/
```

1. 查看头文件及动态库路径

Libpcap 安装为一个库和一组包含文件。在您的程序中使用的主要包含文件是:

1 #include <pcap.h>

要获得头文件和库文件的正确搜索路径,请使用标准pkg-config工具:

```
1 | pkg-config --libs --static --cflags libpcap
```

结果:

1 -I/usr/local/include -L/usr/local/lib -lpcap

/usr/local/此处显示的路径为默认值。configure时,可以使用 --prefix 选项指定不同的路径。

2. 编译需要添加 -lpcap 选项

```
1 gcc test.c -o test -lpcap
```

3. 基于 GNU autotools 的项目,请在以下内容中使用 configure.ac:

```
1  # Check for required libraries
2  PKG_CHECK_MODULES([libpcap], [libpcap>= 1.2])
```

并在您的 Makefile.am:

```
1  proggy_CFLAGS = $(libpcap_CFLAGS)
2  proggy_LDADD = $(libpcap_LIBS)
```

四、Ubuntu 系统安装 libpcap (非交叉编译)

1. libpcap 的安装

```
1 | sudo apt-get install libpcap-dev
```

2. 应用程序编译

```
1 | gcc libpcap_test.c -o libpcap_test -lpcap
```

五、libpcap使用

参考:

- 1. libpcap使用
- 2. Linux 网络编程—— libpcap 详解
- 3. Libpcap库编程指南—数据包捕获
- 4. libpcap函数库详细介绍

六、开发板上测试

使用 libpcap 循环捕获网络数据包 (libpcap_test.c):

```
1
                  #include <stdio.h>
   2
                  #include <pcap.h>
                  #include <arpa/inet.h>
   3
                  #include <time.h>
   4
                  #include <stdlib.h>
   5
   6
                  #define BUFSIZE 1514
   8
                  struct ether_header
   9
                                            unsigned char ether_dhost[6]; //目的mac
10
                                           unsigned char ether_shost[6]; //源mac
11
                                                                                                                                                                          //以太网类型
                                           unsigned short ether_type;
12
                  };
13
14
                  15
                  void ethernet_protocol_callback(unsigned char *argument,const struct pcap_pkthdr *packet_heaher,const unsigned char *packet_const unsigned cha
16
17
                                            unsigned char *mac_string;
18
                                            struct ether_header *ethernet_protocol;
19
                                           unsigned short ethernet_type;
                                                                                                                                                                                                         //以太网类型
20
21
                                            printf("%s\n", ctime((time_t *)&(packet_heaher->ts.tv_sec))); //转换时间
                                           ethernet_protocol = (struct ether_header *)packet_content;
24
                                           mac_string = (unsigned char *)ethernet_protocol->ether_shost;//获取源mac地址
                                           25
26
                                           mac string = (unsigned char *)ethernet protocol->ether dhost;//获取目的mac
27
                                           printf("Mac Destination Address is %02x:%02x:%02x:%02x:%02x:%02x:%02x:%02x),*(mac string+0),*(mac string+1),*(mac string+2),*(mac string+1),*(mac string+
28
29
                                            ethernet_type = ntohs(ethernet_protocol->ether_type);//获得以太网的类型
30
                                            printf("Ethernet type is :%04x\n",ethernet_type);
31
                                            switch(ethernet_type)
32
33
                                                                       case 0x0800:printf("The network layer is IP protocol\n");break;//ip
34
                                                                       case 0x0806:printf("The network layer is ARP protocol\n");break;//arp
35
                                                                       case 0x0835:printf("The network layer is RARP protocol\n");break;//rarp
                                                                       default:break;
```

```
38
39
             usleep(800*1000);
40
41
     int main(int argc, char *argv[])
42
     {
43
                                            //出错信息
             char error_content[100];
44
             pcap_t * pcap_handle;
45
             unsigned char *mac_string;
46
             unsigned short ethernet_type;
                                                            //以太网类型
47
                                                                            //接口名字
             char *net_interface = NULL;
48
             struct pcap_pkthdr protocol_header;
49
             struct ether_header *ethernet_protocol;
50
51
             //获取网络接口
52
             net_interface = pcap_lookupdev(error_content);
53
             if(NULL == net interface)
54
55
                    perror("pcap_lookupdev");
56
                     exit(-1);
57
             }
58
59
             pcap_handle = pcap_open_live(net_interface,BUFSIZE,1,0,error_content);//打开网络接口
60
61
             if(pcap_loop(pcap_handle,-1,ethernet_protocol_callback,NULL) < 0)</pre>
62
63
                     perror("pcap_loop");
64
65
66
             pcap_close(pcap_handle);
67
             return 0;
68
69
70
```

交叉编译:

1 | arm-linux-gnueabihf-gcc ./libpcap_test.c -o ./libpcap_test -lpcap -I/home/osrc/Projects/tools/libpcap/install/include/ -L/home/osrc/Projects/tools/libpcap/install/include/ -L/home/osrc/Projects/ -L/home/osrc/Projects/tools/libpcap/install/include/ -L/home/osrc/Projects/ -L/home/osrc/Pro

在开发板上运行,需要root账户权限:

1 | sudo ./libpcap_test

结果如下:

```
root@stretch-armhf:/home/qudoor# ./libpcap test
device eth0 entered promiscuous mode
Wed Jun 16 09:40:49 2021
Mac Source Address is dc:fe:18:c7:97:9f
Mac Destination Address is ff:ff:ff:ff:ff
Ethernet type is :0806
The network layer is ARP protocol
Wed Jun 16 09:40:49 2021
Mac Source Address is e4:54:e8:ac:27:65
Mac Destination Address is 33:33:00:00:00:0c
Ethernet type is :86dd
Wed Jun 16 09:40:49 2021
Mac Source Address is 9c:e3:74:91:c8:fb
Mac Destination Address is ff:ff:ff:ff:ff
The network layer is ARP protocol
Wed Jun 16 09:40:49 2021
Mac Source Address is dc:fe:18:c7:97:9f
Mac Destination Address is ff:ff:ff:ff:ff
Ethernet type is :0806
The network layer is ARP protocol
```

使用 libpcap 过滤目的端口为8080的数据包,循环捕获 (libpcap_filter_test.c);

```
1
    #include <pcap.h>
2
    #include <time.h>
    #include <stdlib.h>
3
    #include <stdio.h>
4
5
6
    * src host 192.168.1.177 //只接收源 ip 地址是 192.168.1.177 的数据包
    * dst port 80 //只接收 tcp/udp 的目的端口是 80 的数据包
    * not tcp //只接收不使用 tcp 协议的数据包
    * tcp[13] == 0x02 and (dst port 22 or dst port 23) //只接收 SYN 标志位置位且目标端口是 22 或 23 的数据包 (tcp 首部开始的第 13 个字:
    * icmp[icmptype] == icmp-echoreply or icmp[icmptype] == icmp-echo //只接收 icmp 的 ping 请求和 ping 响应的数据包
10
    * ehter dst 00:e0:09:c1:0e:82 //只接收以太网 mac 地址是 00:e0:09:c1:0e:82 的数据包
11
12
    #define PACP_FILTER
                        "dst port 8080"
13
14
    struct ether_header
15
    {
16
           unsigned char ether dhost[6]; //目的mac
17
           unsigned char ether_shost[6]; //源mac
18
                                            //以太网类型
           unsigned short ether_type;
19
    };
20
21
    void getPacket(u_char * arg, const struct pcap_pkthdr * pkthdr, const u_char * packet)
22
23
           int * id = (int *)arg;
24
           unsigned char *mac string;
25
           struct ether_header *ethernet_protocol;
26
                                                   //以太网类型
           unsigned short ethernet_type;
27
           printf("----\n");
28
29
           printf("id: %d\n", ++(*id));
30
           printf("Packet length: %d\n", pkthdr->len);
31
           printf("Number of bytes: %d\n", pkthdr->caplen);
32
           printf("Recieved time: %s", ctime((const time_t *)&pkthdr->ts.tv_sec));
33
34
           ethernet_protocol = (struct ether_header *)packet;
35
           mac_string = (unsigned char *)ethernet_protocol->ether_dhost;//获取目的mac
36
           mac_string = (unsigned char *)ethernet_protocol->ether_shost;//获取源mac地址
```

```
38
                         printf("Mac Source Address is %02x:%02x:%02x:%02x:%02x:%02x:%02x\n",*(mac_string+0),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac_string+1),*(mac
  39
  40
                         ethernet_type = ntohs(ethernet_protocol->ether_type);//获得以太网的类型
  41
                         printf("Ethernet type is :%04x\n",ethernet_type);
  42
                         switch(ethernet_type)
  43
  44
                                      case 0x0800:printf("The network layer is IP protocol\n");break;//ip
  45
                                      case 0x0806:printf("The network layer is ARP protocol\n");break;//arp
  46
                                      case 0x0835:printf("The network layer is RARP protocol\n");break;//rarp
  47
                                      default:break;
  48
                         }
  49
  50
  51
                         int i;
  52
                         for(i=0; i<pkthdr->len; ++i)
  53
                         {
  54
                                      printf(" %02x", packet[i]);
  55
                                      if((i + 1) \% 16 == 0)
  56
                                       {
  57
                                                    printf("\n");
  58
                                      }
  59
                         }
  60
  61
                         printf("\n\n");
  62
  63
  64
  65
  66
           void getOnePacket(pcap_t * device)
  67
                         struct pcap_pkthdr protocol_header;
  68
                         struct ether_header *ethernet_protocol;
  69
                         const unsigned char *p_packet_content = NULL;
                                                                                                                        // 保存接收到的数据包的起始地址
  70
                         unsigned char *p_mac_string = NULL;
                                                                                                                         // 保存mac的地址, 临时变量
  71
                         unsigned short ethernet_type = 0;
                                                                                                                         // 以太网类型
  72
                         p_packet_content = pcap_next(device,&protocol_header);
  73
  74
                         printf("-----\n");
  75
                         printf("Capture Time is :%s",ctime((const time_t *)&protocol_header.ts.tv_sec));
  76
                         printf("Packet Lenght is :%d\n",protocol_header.len);
  77
  78
  79
                         *分析以太网中的 源mac、目的mac
  80
  81
                         ethernet_protocol = (struct ether_header *)p_packet_content;
  82
                         p_mac_string = (unsigned char *)ethernet_protocol->ether_shost;//获取源mac
  83
                         84
                         p_mac_string = (unsigned char *)ethernet_protocol->ether_dhost;//获取目的mac
  85
                         printf("Mac Destination Address is %02x:%02x:%02x:%02x:%02x:%02x:%02x\n",*(p_mac_string+0),*(p_mac_string+1),*(p_mac_string+0)
  86
  87
  88
                         *获得以太网的数据包的地址,然后分析出上层网络协议的类型
  89
                         ethernet_type = ntohs(ethernet_protocol->ether_type);
  90
  91
                         printf("Ethernet type is :%04x\t",ethernet_type);
  92
                         switch(ethernet_type)
  93
  94
                                      case 0x0800:printf("The network layer is IP protocol\n");break;//ip
  95
                                      case 0x0806:printf("The network layer is ARP protocol\n");break;//arp
  96
                                      case 0x0835:printf("The network layer is RARP protocol\n");break;//rarp
  97
                                      default:printf("The network layer unknow!\n");break;
  98
  99
           }
100
101
           int main()
102
           {
103
                         char errBuf[PCAP_ERRBUF_SIZE], * devStr;
104
105
                         /* get a device */
106
                         devStr = pcap_lookupdev(errBuf);
107
108
100
```

```
2023/7/6 14:18
```

```
בטד
              if(devStr)
110
              {
111
                     printf("success: device: %s\n", devStr);
112
              }
113
              else
114
              {
115
                     printf("error: %s\n", errBuf);
116
                     exit(1);
117
              }
118
119
             /* open a device, wait until a packet arrives */
120
             pcap_t * device = pcap_open_live(devStr, 65535, 1, 1, errBuf); //设置超时时间为1ms, 超时后获取数据包的函数就会立即返回
121
122
             if(!device)
123
              {
124
                     printf("error: pcap_open_live(): %s\n", errBuf);
125
                     exit(1);
126
             }
127
128
             /* construct a filter */
129
             struct bpf_program filter;
130
             pcap_compile(device, &filter, PACP_FILTER, 1, 0);
131
             pcap_setfilter(device, &filter);
132
133
             /* wait loop forever */
134
             int id = 0;
135
             pcap_loop(device, -1, getPacket, (u_char*)&id);
136
137
             while(1)
138
139
                     getOnePacket(device);
140
141
             pcap_close(device);
142
143
             return 0;
144
      }
145
146
```

说明:

pcap_open_live 函数的 to_ms 参数指定超时时间 (毫秒) 可控制 pcap_loop 函数中的 callback 函数回调时间。