Interaction Design & Virtual Reality

Liwei chan 詹力韋
Assistant Prof.

2016.11.29

FloorProjection







When projecting,
Apply the transformation in advance.
This transformation is called an **extrinsic matrix** of a camera.
This operation is also called **homographic transformation**.

Intrinsic Matrix

http://ksimek.github.io/2013/08/13/intrinsic/

Pinhole Camera



$$K = \begin{pmatrix} f_x & s & x_0 \\ 0 & f_y & y_0 \\ 0 & 0 & 1 \end{pmatrix}$$

Focal Length, fx**,** fy
Principal Point Offset, , x0**,** y0
Axis Skew, s





With more intuitive representation

DEMO



http://ksimek.github.io/2013/08/13/intrinsic/

$$K = \begin{pmatrix} f_x & s & x_0 \\ 0 & f_y & y_0 \\ 0 & 0 & 1 \end{pmatrix}$$

$$= \underbrace{\begin{pmatrix} 1 & 0 & x_0 \\ 0 & 1 & y_0 \\ 0 & 0 & 1 \end{pmatrix}}_{\text{2D Translation}} \times \underbrace{\begin{pmatrix} f_x & 0 & 0 \\ 0 & f_y & 0 \\ 0 & 0 & 1 \end{pmatrix}}_{\text{2D Scaling}} \times \underbrace{\begin{pmatrix} 1 & s/f_x & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 1 \end{pmatrix}}_{\text{2D Shear}}$$

Extrinsic Matrix

http://ksimek.github.io/2012/08/22/extrinsic/



$$[R \mid t] = \left[\begin{array}{ccc|c} r_{1,1} & r_{1,2} & r_{1,3} & t_1 \\ r_{2,1} & r_{2,2} & r_{2,3} & t_2 \\ r_{3,1} & r_{3,2} & r_{3,3} & t_3 \end{array}\right]$$

$$\left[\begin{array}{c|c} R & t \\ \hline \mathbf{0} & 1 \end{array}\right] = \left[\begin{array}{c|c} I & t \\ \hline \mathbf{0} & 1 \end{array}\right] \times \left[\begin{array}{c|c} R & \mathbf{0} \\ \hline \mathbf{0} & 1 \end{array}\right]$$

$$= \left[\begin{array}{ccc|c} 1 & 0 & 0 & t_1 \\ 0 & 1 & 0 & t_2 \\ 0 & 0 & 1 & t_3 \\ \hline 0 & 0 & 0 & 1 \end{array}\right] \times \left[\begin{array}{ccc|c} r_{1,1} & r_{1,2} & r_{1,3} & 0 \\ r_{2,1} & r_{2,2} & r_{2,3} & 0 \\ r_{3,1} & r_{3,2} & r_{3,3} & 0 \\ \hline 0 & 0 & 0 & 1 \end{array}\right]$$

Change to a camera pose
Such that when the projector


Floor content
texture
(RenderTexture)
Floor content
camera




Floor content texture
Floor content camera
Goal is to **put/project** this texture on the **floor**.
Use mouse: adjust this keystone camera pose, such that the projected **floorContextTexture** is correct on the floor.
Physical floor projector
Keystone camera
plane
your scene
another scene

Instead of an independent
“another” scene,

we add **layer (e.g.,** FloorProjector)
to separate the scene


Floor content texture
Floor content camera
Use mouse: adjust this keystone camera pose, such that the projected floorContextTexture is correct on the floor.
Physical floor projector
Keystone camera
plane
your scene
FloorProjector Layer

STEPs for integration:

1. Import floorProject.package
2. Add Tad “CalibrationSphere”
3. Add Layer “FloorProjector”
4. Go to Edit -> Project Settings -> Players, switch to **.NET 2.0**.
5. Double check
    - FloorContentCamera: Target Display -> Display 1
    - FloorContentCamera: Target Eye -> None
    - KeystoneCamera: Target Display -> Display 2
    - KeystoneCamera: Target Eye -> None
6. **Adapt FloorContentCamera pose for your application.**


Unity Personal (64bit) - sampleFloorProjector.unity - testFloorProjection - PC, Mac & Linux Standalone <DX11>
File Edit Assets GameObject Component Tools Window Help
Center Local
Account Layers Layout
Hierarchy
Create
sampleFloorProjector
Main Camera
Directional Light
FloorContentCamera
Plane
floorProjector
floorContentPlane
KeystoneCamera
RecordPoints
[CameraRig]
Controller (right)
Camera (head)
Camera (eye)
Camera (ears)
Scene
Game
Asset Store
Shaded
2D
Gizmos
Persp
Inspector
floorProjector
Static
Tag Untagged
Layer Default
Transform
Position
Rotation
Correspondence Acquisition (Script)
Script CorrespondenceAcquisition
Texture Plane floorContentPlane
Keystone Camera KeystoneCamera (Camera
Project
Console
Create
Favorites
All Materials
All Models
All Prefabs
All Scripts
Assets
Demigiant
FloorProjection
Materials
Materials
Plugins
SteamVR
UnityVS
Assets ▸ FloorProjection ▸
Materials
Calibration
Correspond...
Correspond...
Correspond...
crosshair
DrawLine
floorConten...
grid
PointsReco...
Projection...
Recording
Rotation
RotationCo...
sampleFloo...
Serializabl...
SerializeEx...
StartTest
testNoRen...
testRender...


Unity Personal (64bit) - sampleFloorProjector.unity - testFloorProjection - PC, Mac & Linux Standalone <DX11>
File Edit Assets GameObject Component Tools Window Help
Center Local
Account Layers Layout
Hierarchy
Create
sampleFloorProjector
Main Camera
Directional Light
FloorContentCamera
scene
Plane
floorProjector
KeystoneCamera
[CameraRig]
Controller (left)
Controller (right)
Camera (head)
Camera (eye)
Camera (ears)
Scene Game Asset Store
Shaded 2D Gizmos
Persp
Camera Preview
Inspector
KeystoneCame
Static
Tag Untagged
Layer FloorProjector
Transform
Position X 0 Y 11.49 Z 0
Rotation X 90 Y 0 Z 0
Scale X 1 Y 1 Z 1
Camera
Clear Flags Solid Color
Background
Culling Mask FloorProjector
Projection Perspective
Field of View 60
Clipping Planes Near 0.3 Far 1000
Viewport Rect X 0 Y 0 W 1 H 1
Depth 0
Rendering Path Use Player Settings
Target Texture None (Render Texture)
Occlusion Culling
HDR
Stereo Separation 0.022
Target Display Display 2
Target Eye None (Main Display)
GUI Layer
Audio Listener
Add Component
Project Console
Create
Favorites
All Materials
All Models
All Prefabs
All Scripts
Assets
Demigiant
FloorProjection
Materials
Materials
Plugins
SteamVR
UnityVS
Assets ▸ FloorProjection ▸
Materials
Calibration
Correspond...
Correspond...
Correspond...
crosshair
DrawLine
floorConten...
grid
PointsReco...
Projection...
Recording
Rotation
RotationCo...
sampleFloo...
Serializabl...
SerializeEx...
StartTest
testNoRen...
testRender...


Unity Personal (64bit) - sampleFloorProjector.unity - testFloorProjection - PC, Mac & Linux Standalone <DX11>
File Edit Assets GameObject Component Tools Window Help
Hierarchy
sampleFloorProjector
Main Camera
Directional Light
FloorContentCamera
scene
floorContentPlane
RecordPoints
[CameraRig]
Controller (left)
Controller (right)
Camera (head)
Camera (eye)
Camera (ears)
Scene
Game
Asset Store
Inspector
Layer FloorProjector
Mesh Collider
Convex
Material None (Physic Material)
Mesh Plane
Mesh Renderer
Cast Shadows Off
Receive Shadows
Motion Vectors
Materials
Light Probes Off
floorContentTexture
Shader Unlit/Texture
Tiling X 1 Y 1
Offset X 0 Y 0
Select
Add Component
Set floorContentTextur (Render Texture) to floorContentPlane
Project
Console
Favorites
All Materials
All Models
All Prefabs
All Scripts
Assets
Demigiant
FloorProjection
Materials
Materials
Plugins
SteamVR
UnityVS
Assets ▸ FloorProjection ▸
Materials
Calibration
Correspond...
Correspond...
Correspond...
crosshair
DrawLine
floorConten...
grid
PointsReco...
Projection...
Recording
Rotation
RotationCo...
sampleFloo...
Serializabl...
SerializeEx...
StartTest
testNoRen...
testRender...


Unity Personal (64bit) - sampleFloorProjector.unity - testFloorProjection - PC, Mac & Linux Standalone <DX11>
File Edit Assets GameObject Component Tools Window Help
Center Local
Account Layers Layout
Hierarchy
Create All
sampleFloorProjector
Main Camera
FloorContentCamera
Plane
floorProjector
floorContentPlane
KeystoneCamera
RecordPoints
[CameraRig]
Controller (left)
Controller (right)
Camera (head)
Camera (eye)
Camera (ears)
Scene Game Asset Store
Shaded 2D Gizmos All
Persp
Camera Preview
Inspector
FloorContentCamera
Static
Tag Untagged Layer Default
Transform
Position X 0 Y 7.71 Z 0
Rotation X 90 Y 0 Z 0
Scale X 1 Y 1 Z 1
Camera
Clear Flags Skybox
Background
Culling Mask Mixed ...
Nothing
Everything
Default
TransparentFX
Ignore Raycast
Water
UI
FloorProjector
Projection
Size
Clipping Planes
Viewport Rect
X 0
W 1
Depth
Rendering Path
Target Texture
HDR
Stereo Separation 0.022
Stereo Convergence 10
Target Display Display 1
Target Eye None (Main Display)
Flare Layer
GUI Layer
Audio Listener
Add Component
Project Console
Create
Favorites
All Materials
All Models
All Prefabs
All Scripts
Assets
Demigiant
FloorProjection
Materials
Materials
Plugins
SteamVR
UnityVS
Assets ▸ FloorProjection ▸
Materials
Calibration
Correspond...
Correspond...
Correspond...
crosshair
DrawLine
floorConten...
grid
PointsReco...
Projection...
Recording
Rotation
RotationCo...
sampleFloo...
Serializabl...
SerializeEx...
StartTest
testNoRen...
testRender...


FloorContentCamera
TargetDisplay: Display 1
TargetEye: None
Unity Personal (64bit) - sampleFloorProjector.unity - testFloorProjection - PC, Mac & Linux Standalone* <DX11>
File Edit Assets GameObject Component Tools Window Help
Hierarchy
sampleFloorProjector*
Directional Light
FloorContentCamera
Plane
floorProjector
[CameraRig]
Scene
Game
Asset Store
Persp
Camera Preview
Inspector
FloorContentCamera
Static
Transform
Camera
Background
Culling Mask
Mixed ...
Projection
Orthographic
Clipping Planes
Near 0.3
Far 1000
Viewport Rect
Depth
Rendering Path
Use Player Settings
Target Texture
floorContentTexture
Occlusion Culling
HDR
Stereo Convergence 10
Target Display
Display 1
Target Eye
None (Main Display)
Flare Layer
GUI Layer
Audio Listener
Add Component
Project
Console
Favorites
All Materials
All Models
All Prefabs
All Scripts
Assets
Demigiant
FloorProjection
Materials
Materials
Plugins
SteamVR
UnityVS
Assets ▸ FloorProjection
Materials
Calibration
Correspond...
Correspond...
Correspond...
crosshair
DrawLine
floorConten...
grid
PointsReco...
Projection...
Recording
Rotation
RotationCo...
sampleFloo...
Serializabl...
SerializeEx...
StartTest
testNoRen...
testRender...


Unity Personal (64bit) - sampleFloorProjector.unity - testFloorProjection - PC, Mac & Linux Standalone <DX11>
File Edit Assets GameObject Component Tools Window Help
Center Local
Account Layers Layout
Hierarchy
Create All
sampleFloorProjector
Main Camera
Directional Light
FloorCamera
scene
floorProjector
[CameraRig]
Scene Game Asset Store
Shaded 2D
Persp
Switch to .NET 2.0
Inspector
Resolution and Presentation
Icon
Splash Image
Other Settings
Rendering
Rendering Path* Forward
Color Space* Linear
Auto Graphics API for Wir
Auto Graphics API for Mac
Auto Graphics API for Lin
Static Batching
Dynamic Batching
GPU Skinning*
Graphics Jobs (Experimer
Virtual Reality Supported
Virtual Reality SDKs
OpenVR
Single-Pass Stereo Rende
Configuration
Scripting Backend Mono2x
Disable HW Statistics
Scripting Define Symbols
Optimization
Api Compatibility Level .NET 2.0
Prebake Collision Meshes
Preload Shaders
Preloaded Assets
Vertex Compression Mixed ...
Optimize Mesh Data*
Logging*
Log Type None ScriptOnly Full
Error
Assert
Warning
Log
Exception
* Shared setting between multiple platforms.
Project Console
Clear Collapse Clear on Play Error Pause
2 28


Unity Personal (64bit) - sampleFloorProjector.unity - testFloorProjection - PC, Mac & Linux Standalone <DX11>
File Edit Assets GameObject Component Tools Window Help
Center Local
Account Layers Layout
Hierarchy
Create
sampleFloorProjector
Main Camera
Directional Light
FloorContentCamera
scene
Plane
floorProjector
floorContentPlane
KeystoneCamera
RecordPoints
[CameraRig]
Controller (left)
Controller (right)
Camera (head)
Camera (eye)
Camera (ears)
Scene
Game
Asset Store
Shaded
2D
add FloorProjector Layer
Camera Preview
Inspector
Static
Tag Untagged
Layer Default
Transform
Position
Rotation
Scale
Default
TransparentFX
Ignore Raycast
Water
UI
FloorProjector
Add Layer...
Camera
Clear Flags
Skybox
Background
Culling Mask
Mixed ...
Projection
Orthographic
Size
Clipping Planes
Far 1000
Viewport Rect
Depth
Rendering Path
Use Player Settings
Target Texture
floorContentTexture
Occlusion Culling
HDR
Stereo Separation 0.022
Stereo Convergence 10
Target Display
Display 1
Target Eye
None (Main Display)
Flare Layer
GUI Layer
Audio Listener
Add Component
Project
Console
Favorites
All Materials
All Models
All Prefabs
All Scripts
Assets
Demigiant
FloorProjection
Materials
Materials
Plugins
SteamVR
UnityVS
Assets
Demigiant
FloorProject...
Materials
Plugins
SteamVR
UnityVS


Unity Personal (64bit) - sampleFloorProjector.unity - testFloorProjection - PC, Mac & Linux Standalone <DX11>
File Edit Assets GameObject Component Tools Window Help
Hierarchy
sampleFloorProjector
Main Camera
Directional Light
FloorContentCamera
scene
Plane
floorProjector
floorContentPlane
KeystoneCamera
RecordPoints
[CameraRig]
Controller (left)
Controller (right)
Camera (head)
Camera (eye)
Camera (ears)
Scene
Game
Asset Store
add CalibrationSphere Tag
Inspector
Tag
Untagged
Respawn
Finish
EditorOnly
MainCamera
Player
GameController
CalibrationSphere
Add Tag
Add Component
Project
Console
Favorites
All Materials
All Models
All Prefabs
All Scripts
Assets
Demigiant
FloorProjection
Materials
Materials
Plugins
SteamVR
UnityVS
Assets ▸ FloorProjection
Materials
Calibration
crosshair
DrawLine
grid
Recording
Rotation
sampleFloo...
StartTest
testRender...


Vive CameraRig
Remove
FloorProjector