对流与层流

The term advection sometimes serves as a synonym同义词 for convection, but technically, convection covers the sum of transport both by diffusion and by advection. Advective transport describes the movement of some quantity via the bulk flow of a fluid (as in a river or pipeline)

代码要考虑四个方程:温度、动量、连续和advection方程解方程的顺序:动量+连续方程,层流或温度方程。

温度方程要求绝热和剪切热,他们是从速度、压力、应力、应变率中计算得到的,所以要求温度方程,先要解动量和连续方程;另一方面,动量和连续方程必须同时求解以获得速度的值,因为这两个方程中都用到了速度;层流方程需要速度场,因此要在动量和连续方程之后求解。

算法的主要步骤:

- 1)为每一个marker计算标量物理性质,黏度、密度、热导率、热产率等,并且插值,同时advected温度从标记点到欧拉节点,应用边界条件2)用压力-速度formulation解二维动量和连续方程,通过用直接方法构造和反向全局矩阵直接方法求解
- 3) 为markers定义最佳距离时间步长△tm, (typically limiting maximal displacement to 0.01-1.0 of minimal grid step) based on the velocity field computed in Step 2 (Chapter 8)
- 4) 计算剪切和绝热 heating在欧拉节点上
- 5)为温度方程定义最佳步长 \triangle t,用三个时间步长(绝对时间步长限,最佳marker displacement时间限,绝对节点温度改变限(1-20K)里最小的那个,
- 6) 用拉格朗日formulation解温度方程
- 7) 插值节点温度改变,从欧拉节点到markers并且计算新的markers温度,考虑物理频散在subgrid marker level。

8) 四阶龙格-库塔方法在空间上advection markers通过mesh根据全局 计算的速度场v;

stepl: 插值

每个marker上存储三个浮点数:两个坐标和温度场以及一个整数岩石类型,其余标量性质都可以从岩石类型中得到;欧拉点上这些性质的有效值都是从bilinear插值中得到的。注意黏度for剪切和正应力是分别插值的,考虑半个网格空间内在水平和垂直方向上的marker,温度边界条件应该用来获得节点值,在温度从marker插值后,这样减少插值误差的累计。

另一方面,从欧拉点插值到marker时,用标准的一阶精度的双线性插值,用周围四个节点值,equation8.19用来统一把速度、应力、应变率、应力、温度等属性从节点插值到marker,