CSE216 Foundations of Computer Science

Instructor: Zhoulai Fu

State University of New York, Korea

Some Ocaml details

Running a program with Ocaml Interpreter

- By convention, end your program with .ml
- Simple way to run your program is
 - ocaml your_program.ml
- Another good way is to run your program in the toplevel
 - # #use "your_prgram.ml";;
- Note: "#" after prompt, quotation marks, and the double semicolon.
- The toplevel approach gives you a chance to get the types.

We will not need to use "ocamic" for now

- Interpreter "ocaml" translates the source code into machine language one line at a time, and then executes that line before moving on to the next one.
- Compiler "ocamlc" reads the source code of a program and translates it into machine language all at once.
- Use Interpreter for quick testing.
- Use compiler for production.

Double semicolon

- In general, not necessary in your Ocaml code, except
- Use it in Ocaml directives like #use "file.ml";;

Single semicolon

- Semicolon is an expression separator, not a statement terminator
- Syntax for expression: e1; e2;...; e_n;
- **Type of** e1...e_{n-1} need to be of type unit. The type of the e_n is the type of the expression

Single semicolon example

This code

```
let foo x y =
  print_endline "Now I'll add up two numbers";
  print_endline "Yes, seriously";
  x + y
```

is semantically equivalent to

```
let foo x y =
   let _ = print_endline "Now I'll add up two numbers" in
   let _ = print_endline "Yes, seriously" in
   x + y
```

Single semicolon example (2)

- In "if-then-else", we need begin...end to enclose e1;...
 e_n; to avoid unexpected parsing
- begin...end is a more readable alternative to parentheses

Shadowing is not mutation

Some uses of top level let bindings may look like mutation, but they actually aren't.

```
let x = 10
let x = x + 10
let () = Printf.printf "%d\n" x
```

In this example, the x in the printf expression is 20. Did we redefine x for the whole program?

```
let x = 10
let print_old_x () = Printf.printf "%d\n" x

let x = x + 10
let () = Printf.printf "%d\n" x (* prints 20 *)
let () = print_old_x () (* prints 10 *)
```

let _ = ... and let () = ...

- Both are definitions
- Syntax for let definitions is let pattern = expression
- Therefore, let(x,y,z)=(4,5,6) makes sense
- _ is a pattern for anything, or wildcard; () is a pattern for the single element of unit type
- The two are used to enforce evaluation
- Use let () = ... instead of let _ = ... if what follows is of type unit

Ocaml debug 1 — typing

- Always fix typing errors first
- You can add your own types to make sure the your implementation corresponds to your thought

```
# let avg x y: float = (x+y)/2;;
Error: This expression has type float but an expression was expected of type int
```

Ocam debug 2 — assert

```
# let avg x y = x +. y /.2.;;
val avg : float -> float -> float = <fun>
# assert (avg 2.0 3.0 = 2.5) ;;
Exception: Assert_failure ("//toplevel//", 1,0).
```

Ocaml debug 3 — print

• **Print statements.** Insert a *print statement* to ascertain the value of a variable. Suppose you want to know what the value of **x** is in the following function:

```
let inc x =
  x+1
```

Just add the line below to print that value:

```
let inc x =
  let () = print_int(x) in (* added *)
  x+1
```

Ocaml debug 4— trace

```
# let rec fact x = if x = 1 then 1 else x * fact (x-1)
  ;;
val fact : int -> int = <fun>
# fact 5
-: int = 120
# #trace fact;;
fact is now traced.
# fact 5;;
fact <-- 5
fact <-- 4
fact <-- 3
fact <-- 2
fact <-- 1
fact --> 1
fact --> 2
fact --> 6
fact --> 24
fact --> 120
-: int = 120
```