UCSB, Physics 129AL, Computational Physics Lecture notes, Week 2

Zihang Wang (UCSB), zihangwang@ucsb.edu January 14, 2025

Contents

0.0.1	Embedding	1
0.0.2	Geodesic	•
0.0.3	parallel transport	4
0.0.4	Tensors	Ę

0.0.1 Embedding

The distinction between intrinsic and extrinsic properties of surfaces is fundamental in differential geometry and has significant implications in various fields. Intrinsic properties, such as Gaussian curvature, depend solely on measurements made within the surface and are invariant under isometric deformations (transformations of surfaces that preserve the lengths of curves on the surface). In contrast, extrinsic properties, like mean curvature, rely on how the surface is embedded in a higher dimensional space, or the **ambient space**.

This is particular useful if we want to study interactions between embedded object and environment (such as electric fields outside of a solid sphere). In numerical calculations, it is usually used to calculate surface dynamics of fields where interactions (as the field is 3D) are important. Let's consider example, a line in \mathbb{R} with length L. We embed it in \mathbb{R}^n . Regardless how the line is bended, the length of the line remains the same. Therefore, distance between two points on the line is the intrinsic. On the other hand, the degrees of freedom allows the line to move around and bend (isometries are transformations that preserve the distance between points on the manifold). The curvature induced is extrinsic. This has great implications in graphics. Let's say you want to project a wall paper to a cup, cylinder. What can you do? You need to find a isometry that preserves the distance between any given two points. You can only do that without "connecting the back", locally isometric to a plane. What about a sphere? You can't find a continuous bijective mapping between them with a continuous inverse. This defines the concept of topology.

The first fundamental form describes the intrinsic property of the embedded surface within an ambient space,

$$I = ds^{2} = \left[\frac{\partial \mathbf{r}}{\partial u} \cdot \frac{\partial \mathbf{r}}{\partial v}\right] du dv = g_{ij} du dv, \tag{1}$$

where g_{ij} are the components of the surface metric.

We should note that the inner product used here is the metric of the ambient space. Explicitly, for a surface parameterized by coordinates $\mathbf{r}(u, v)$, it becomes, $ds^2 = (\partial_u \mathbf{r})^2 du^2 + 2(\partial_u \mathbf{r}) \cdot (\partial_v \mathbf{r}) du dv + (\partial_v \mathbf{r})^2 dv^2$. This can be written in a matrix form,

$$I = \begin{pmatrix} du & dv \end{pmatrix} \begin{pmatrix} (\partial_u \mathbf{r})^2 & (\partial_u \mathbf{r}) \cdot (\partial_v \mathbf{r}) \\ (\partial_u \mathbf{r}) \cdot (\partial_v \mathbf{r}) & (\partial_v \mathbf{r})^2 \end{pmatrix} \begin{pmatrix} du \\ dv \end{pmatrix}, \tag{2}$$

where you should note that the change in the metric from a (0,2) tensor to a (1,1) tensor, that takes one vector and one covector.

On the other hand, let's consider the surface variation $\delta \mathbf{r}(u, v)$ with respect to a unit normal direction with strength g, namely the deformed surface,

$$\mathbf{R}(u, v, g) = \mathbf{r}(u, v) \pm g\mathbf{N}(u, v). \tag{3}$$

The first fundamental form of this deformed surface is given by,

$$dS^{2} = (\partial_{u}\mathbf{R})^{2}du^{2} + 2(\partial_{u}\mathbf{R}) \cdot (\partial_{v}\mathbf{r})dudv + (\partial_{v}\mathbf{R})^{2}dv^{2}$$

$$\approx ds^{2} \pm 2g[(\partial_{u}\mathbf{r})(\partial_{u}\mathbf{N})du^{2} + (\partial_{v}\mathbf{r})(\partial_{v}\mathbf{N})dv^{2} + (\partial_{u}\mathbf{r})(\partial_{v}\mathbf{N})dudv + (\partial_{v}\mathbf{r})(\partial_{u}\mathbf{N})dudv]$$

$$= ds^{2} \pm 2gII,$$
(4)

such that,

$$\frac{dS^2 - ds^2}{2a} = II = [(\partial_u^2 \mathbf{r}) \cdot \mathbf{N} du^2 + (\partial_v^2 \mathbf{r}) \cdot \mathbf{N} dv^2 + 2(\partial_u \partial_v \mathbf{r}) \cdot \mathbf{n} du dv],$$
 (5)

where we use the fact that $\partial_v \mathbf{r} \cdot \mathbf{n} = 0$. II is the second fundamental form that captures the variation with respect to local orthogonal deformations. It is a measure of the extrinsic property of the embedded surface,

$$II = d\mathbf{N}(u, v) \cdot [\partial_u \mathbf{r} du + \partial_v \mathbf{r} dv] = [\partial_u \mathbf{N} du + \partial_v \mathbf{N} dv] \cdot [\partial_u \mathbf{r} du + \partial_v \mathbf{r} dv], \quad (6)$$

The inner product used here is the metric of the ambient space.

$$II = \begin{pmatrix} du & dv \end{pmatrix} \begin{pmatrix} (\partial_u^2 \mathbf{r}) \cdot \mathbf{N} & (\partial_u \partial_v \mathbf{r}) \cdot \mathbf{N} \\ (\partial_u \partial_v \mathbf{r}) \cdot \mathbf{N} & (\partial_v^2 \mathbf{r}) \cdot \mathbf{N} \end{pmatrix} \begin{pmatrix} du \\ dv. \end{pmatrix}$$
(7)

The second fundamental form describes how the surface normal varies in a neighborhood, which has an alternative form.

 \mathcal{S} is the **shape operator** (Weingarten Map), defined via the ratio of the following form,

$$S(u,v) = \begin{pmatrix} (\partial_u \mathbf{r})^2 & (\partial_u \mathbf{r}) \cdot (\partial_v \mathbf{r}) \\ (\partial_u \mathbf{r}) \cdot (\partial_v \mathbf{r}) & (\partial_v \mathbf{r})^2 \end{pmatrix}^{-1} \begin{pmatrix} (\partial_u^2 \mathbf{r}) \cdot \mathbf{N} & (\partial_u \partial_v \mathbf{r}) \cdot \mathbf{N} \\ (\partial_u \partial_v \mathbf{r}) \cdot \mathbf{N} & (\partial_v^2 \mathbf{r}) \cdot \mathbf{N}. \end{pmatrix}$$
(8)

The **principle curvatures** at (u, v) are the eigenvalues of the shape operator and the principal directions are the eigenvectors.

The **Gaussian curvature** K is the product of the principal curvatures, or the determinant of the shape operator.

The **mean curvature** H is the average of the principal curvatures, or the trace of the shape operator.

These forms are crucial in differential geometry and have important applications in general relativity and other areas of theoretical physics, and mesh generations.

0.0.2 Geodesic

Let's say there is a curve $\gamma(t)$ (vector), parameterized by t on a surface S. We want to know paths with extrema distance between two end points t_0, t_1 . It is called **geodesic** if at every point in between, the acceleration $\partial_t^2 \gamma(t)$ is either zero or parallel to its unit normal. In other words, the transport is at constant speed along geodesics $\partial_t(\partial_t \gamma(t))^2 = \partial_t^2 \gamma(t) \cdot \partial_t \gamma(t) = 0$. Let's consider the arc length functional,

$$E[\gamma(t)] = \int \sqrt{ds^2} = \int \sqrt{g_{ij}dx^idx^j} = \int dt \sqrt{g_{ij}\frac{dx^i}{dt}\frac{dx^j}{dt}} = \int_{t_0}^{t_1} dt \sqrt{g_{ij}[\gamma(t)][\partial_t\gamma(t)]^i[\partial_t\gamma(t)]^j}$$
(9)

To find the geodesics, we look for critical points of $E[\gamma]$ under small variations of the curve. Consider a variation of the curve $\gamma(t)$:

$$\gamma^{\mu}(t,\epsilon) = \gamma^{\mu}(t) + \epsilon \eta^{\mu}(t),$$

where, $\eta^{\mu}(t)$ is the variation of the μ component, and ϵ is a small parameter. The first variation of $E[\gamma^{\mu}]$ is:

$$\delta E[\gamma^{\mu}] = \frac{d}{d\epsilon} \Big|_{\epsilon=0} E[\gamma^{\mu}(t,\epsilon)].$$

Expanding $E[\gamma]$ under variation:

$$E[\gamma^{\mu}(t,\epsilon)] = \int_{t_0}^{t_1} g_{ij}[\gamma(t) + \epsilon \eta(t)] \left(\frac{d(\gamma^i + \epsilon \eta^i)}{dt} \right) \left(\frac{d(\gamma^j + \epsilon \eta^j)}{dt} \right) dt.$$
 (10)

Differentiating with respect to ϵ and evaluating at $\epsilon = 0$:

$$E[\gamma(t,\epsilon)] = E[\gamma(t)] + \int_{t_1}^{t_2} \frac{\partial g_{ij}}{\partial [\gamma^g - \epsilon \eta^g]} \eta^g \frac{d\gamma^i}{dt} \frac{d\gamma^j}{dt} dt + 2 \int_{t_1}^{t_2} g_{ij} \frac{d\gamma^i}{dt} \frac{d\eta^j}{dt} + \mathcal{O}(\epsilon)$$

$$\delta E[\gamma(t,0)] = \int_{t_1}^{t_2} \frac{\partial g_{ij}}{\partial \gamma^g} \frac{d\gamma^i}{dt} \frac{d\gamma^j}{dt} \eta^g dt - 2 \int_{t_1}^{t_2} g_{ij} \frac{d^2\gamma^i}{dt^2} \eta^j + \mathcal{O}(\epsilon)$$
(11)

where the second line we use the integration by parts. Since for any η^{j} , this equation must hold, we have,

$$\frac{\partial g_{ij}}{\partial \gamma^g} \frac{d\gamma^i}{dt} \frac{d\gamma^j}{dt} - 2g_{ij} \frac{d^2 \gamma^i}{dt^2} = 0 \tag{12}$$

Since we can change index,

$$-\frac{1}{2}g^{ij}\left[\frac{\partial g_{uj}}{\partial \gamma^g}\frac{d\gamma^v}{dt}\frac{d\gamma^j}{dt}\right] + \frac{d^2\gamma^i}{dt^2} = 0$$
 (13)

the geodesic equation becomes,

$$\frac{d^2\gamma^i}{dt^2} + \Gamma^i_{uj} \frac{d\gamma^u}{dt} \frac{d\gamma^j}{dt} = 0,$$

and it describes the paths that minimize "an energy functional", which correspond to the shortest (or extrema) paths between two points on the manifold. We will talk more when we working with classical phase space evolutions.

0.0.3 parallel transport

Metric compatibility ensures the inner product remain consistent when **parallel transported** to different parts of the region. For example, let's move vectors along a curve $\gamma(t)$ such that the vector **n** does not change with time,

$$\frac{\partial}{\partial t}\mathbf{n} = \frac{\partial \gamma}{\partial t} \cdot \frac{\partial}{\partial \gamma}\mathbf{n} = \frac{\partial \gamma^{j}}{\partial t} [\partial_{j}n^{i} + n^{k}\Gamma^{i}_{jk}]\hat{\mathbf{e}}_{\mathbf{i}} = [\frac{\partial n^{i}}{\partial t} + n^{k}\Gamma^{i}_{jk}\frac{\partial \gamma^{j}}{\partial t}]\hat{\mathbf{e}}_{\mathbf{i}} = 0.$$
 (14)

The equation for parallel transport is then given by,

$$\frac{\partial n^i}{\partial t} + n^k \Gamma^i_{jk} \frac{\partial \gamma^j}{\partial t} = 0, \tag{15}$$

and you should note that $\mathbf{V} = \frac{\partial \gamma^j}{\partial t}$ is the velocity. Sometimes, you might see people use the notation with directional derivative along the tangent vector \mathbf{V} ,

$$\nabla_V \mathbf{n} = \mathbf{V} \cdot (\nabla_i n^i) \hat{\mathbf{e}}_i = 0. \tag{16}$$

Let's consider what happens when parallel transporting a vector \mathbf{n} on the unit sphere. We have two natural parameters, $\phi(t)$, $\theta(t)$ with the standard parametrization t. Non-zero Christoffel Symbols on the sphere are given by,

$$\Gamma^{\theta}_{\phi\phi} = -\sin\theta\cos\theta, \quad \Gamma^{\phi}_{\theta\phi} = \Gamma^{\phi}_{\phi\theta} = \frac{\cos\theta}{\sin\theta} = \cot\theta$$
(17)

Let's first consider the transport of a vector from the north pole $[r=1,\phi=0,\theta=0]$ to the equator at $[r=1,\phi=0,\theta=\frac{\pi}{2}]$ following the unit-speed parametrization,

$$\gamma(t) = 0 + t\hat{\mathbf{e}}_{\theta}(t) = \gamma(\theta). \tag{18}$$

the curve is unit-speed since $|d\gamma(t)/dt| = 1$ (**noted the norm**, not the vector), and you are following a curve that is in the tangent direction of the unit sphere. The may look strange, and let's write it in the Cartesian coordinate,

$$\gamma(\theta) = \hat{\mathbf{e}}_r = \sin\theta\cos\phi\,\hat{\mathbf{x}} + \sin\theta\sin\phi\,\hat{\mathbf{y}} + \cos\theta\,\hat{\mathbf{z}} = \sin\theta\,\hat{\mathbf{x}} + \cos\theta\,\hat{\mathbf{z}},\tag{19}$$

since $\phi = 0$. As θ goes $0 \to \frac{\pi}{2}$, this describes the trace from the north pole to the equator in Cartesian coordinates.

Let's start with a vector near the north pole (initial condition),

$$\mathbf{n}(t=0) = \mathbf{n}_0,\tag{20}$$

and we want to transport it to the equator. Let's look at the geodesic equations,

$$\partial_{\phi} n^{i} + n^{k} \Gamma^{i}_{\phi k} \frac{\partial \gamma^{\phi}}{\partial t} = 0,$$

$$\partial_{\theta} n^{i} + n^{k} \Gamma^{i}_{\theta k} \frac{\partial \gamma^{\theta}}{\partial t} = 0.$$
(21)

We write the non-zero terms explicitly,

$$\partial_{\phi} n^{\phi} + n^{\theta} \Gamma^{\phi}_{\phi\theta} \frac{\partial \gamma^{\phi}}{\partial t} = \partial_{\phi} n^{\phi} + n^{\theta} \cot \theta \frac{\partial \gamma^{\phi}}{\partial t} = 0$$

$$\partial_{\phi} n^{\theta} + n^{\phi} \Gamma^{\theta}_{\phi\phi} \frac{\partial \gamma^{\phi}}{\partial t} = \partial_{\phi} n^{\theta} - \sin \theta \cos \theta n^{\phi} \frac{\partial \gamma^{\phi}}{\partial t} = 0$$

$$\partial_{\theta} n^{\phi} + n^{\phi} \Gamma^{\phi}_{\theta\phi} \frac{\partial \gamma^{\theta}}{\partial t} = \partial_{\theta} n^{\phi} + n^{\phi} \cot \theta \frac{\partial \gamma^{\theta}}{\partial t} = 0.$$
(22)

The unit-speed condition $\frac{\partial \gamma^{\theta}}{\partial t} = 1$ gives,

$$\partial_{\theta} n^{\phi} + n^{\phi} \cot \theta = 0, \tag{23}$$

with solution,

$$n^{\phi}(\theta) = \frac{n_{\phi}(\theta_0)}{\sin(\theta)} \tag{24}$$

You might find problematic at $\theta = 0$, and $\hat{\mathbf{e}}_{\phi}$ is undefined. It is one reason that when transport vectors, we avoid at the exact $\theta = 0$ point for the unit-speed parametrization if there are non-zero ϕ components. When at $\pi/2$, it seems like they will have the same component, but this does not mean that the overall direction of the vector is unchanged due to the basis dependent.

If $\mathbf{n}_0 = \hat{\mathbf{e}}_{\theta}$, the term $n^{\phi}(\theta) = 0$ for all θ . This is a part of the **geodesics**: it parallel transports its own tangent vector.

0.0.4 Tensors

In a given coordinate system with basis vectors $\{e_i\}$ and dual basis vectors $\{\omega^i\}$, a tensor is mutilinear map that expressed as:

$$\mathcal{T} = T_{j_1 j_2 \cdots j_p}^{i_1 i_2 \cdots i_q} e_{i_1} \otimes e_{i_2} \otimes \cdots \otimes \omega^{j_1} \otimes \omega^{j_2} \otimes \cdots,$$
 (25)

where $T_{j_1j_2\cdots j_p}^{i_1i_2\cdots i_q}$ is the tensor component, and

- Upper indices (i_1, i_2, \ldots) denote contravariant components.
- Lower indices $(j_1, j_2, ...)$ denote covariant components.

In physics, it is common to write a tensor as a sum of tensor products between m vector spaces $v \in V \otimes V \otimes V \otimes \cdots$ and/or n dual spaces $\omega \in V^* \otimes V^* \otimes V^* \otimes \cdots$,

$$\mathcal{T} = \sum_{i} v^{i} \otimes \omega_{i}. \tag{26}$$

For example, the simplest case is the density matrix,

$$\rho = \sum_{i} |\phi_{i}\rangle \langle \psi_{j}| = \sum_{i} U^{\dagger} |\phi'_{i}\rangle \langle \psi'_{j}| U, \qquad (27)$$

which transforms in their respective spaces.