



12-05-2020

https://youtu.be/j7GrSo7XFdQ

User Administration

Root – Administrator – super user

- Root user has highest level of access
- Root user cannot be renamed
- Never share root password
- Don't put password in chats or text messages
- Root user access to Company Data

Creat a user

[root@zmpt01 ~]# useradd terminator

The file /etc/passwd gets updated

terminator:x:1000:1000::/home/terminator:/bin/bash

User	Check for password	User id –UID	Group id – GID	User info text	User home	Shell type
Terminator	х	1000	1000	CONC	/home/terminator	/bin/bash

[root@zmpt01 ~]# id terminator

uid=1000(terminator) gid=1000(terminator) groups=1000(terminator)

UID – User Id	GID – user primary group	Group User is part of
uid=1000(terminator)	gid=1000(terminator)	groups=1000(terminator)

[root@zmpt01 ~]# id 1000

uid=1000(terminator) gid=1000(terminator) groups=1000(terminator)

Switching to regular user from root



[root@zmpt01 ~]# su terminator [terminator@zmpt01 root]\$ whoami

Terminator

Set the user password

[root@zmpt01 ~]# passwd terminator

Changing password for user terminator.

New password:

BAD PASSWORD: The password fails the dictionary check - it is based on a dictionary word

Retype new password:

passwd: all authentication tokens updated successfully.

Note: root user don't have follow password restrictions, any password will be allowed

Set password as user termination

[terminator@zmpt01 ~]\$ passwd

Changing password for user terminator.

Changing password for terminator.

(current) UNIX password:

New password:

BAD PASSWORD: The password is too similar to the old one

New password:

BAD PASSWORD: The password fails the dictionary check - it is based on a dictionary word

New password:

Retype new password:

passwd: all authentication tokens updated successfully.

Password file - Shadow file

[root@zmpt01 ~]# vi /etc/shadow

terminator:\$6\$pF2bCs4Z\$Yifb7T/yi5uUkGm9lSpGRWxWPrXR.hwYEqbQkxOQ7npyTJpoTtjVcWfxutdD0W4233i791Ud3Zt7Ec5t1/69C.:18601:0:99999:7:::

User	Password	Dec 31 1969	Grace Period	Expiration date from last update	Warning days
terminator	\$6\$pF2bCs4Z	18601	0	60	7

Group file

[root@zmpt01 ~]# vi /etc/group



terminator:x:1000:

Group Name	Check for password	Group id - GID
Terminator	X	1000

Where is all the setting defined for users, groups and passwords?

[root@zmpt01 ~]# vi /etc/login.defs

PASS_MAX_DAYS 60 PASS_MIN_DAYS 0 PASS_MIN_LEN 5 PASS_WARN_AGE 7

UID_MIN 3000 UID_MAX 60000

GID_MIN 4000 GID_MAX 60000

[root@zmpt01 ~]# useradd xmen [root@zmpt01 ~]# id xmen

uid=3000(xmen) gid=4000(xmen) groups=4000(xmen)

Assigning same password as a another user

[root@zmpt01 ~]# vi /etc/shadow

terminator<mark>:\$6\$87Fs/vJF\$EHqhBznCvyU5w4d3XsL6tfsaB7Q3WcDnf8xVB0.NwO</mark>

bSnBZo/Sw6KTG.qpBfvwvo.AkOajFd.PiKjuE1IAytQ.:18601:0:99999:7:::

xmen<mark>:\$6\$87Fs/vJF\$EHqhBznCvyU</mark>

5w4d3XsL6tfsaB7Q3WcDnf8xVB0.NwO

bSnBZo/Sw6KTG.qpBfvwvo.AkOajFd.PiKjuE1IAytQ.:18601:0:60:1:::

login as: xmen



xmen@192.168.56.250's password:

Last login: Sat Dec 5 14:57:51 2020 from 192.168.56.1

Create user manually

Copy the existing line and paste in new line

[root@zmpt01 ~]# vi /etc/passwd spiderman:x:5005:6005::/home/spiderman:/bin/bash

Create group manually

spiderman:x:6005:

Create password maually

[root@zmpt01 ~]# vi /etc/passwd

spiderman:\$6\$87Fs/vJF\$EHqhBznCvyU5w4d3XsL6tfsaB7Q3WcDnf8xVB0. NwObSnBZo/Sw6KTG.qpBfvwvo.AkOajFd.PiKjuE1IAytQ.:18601:0:60:7:::

Create user home directory manually

[root@zmpt01 home]# mkdir spiderman

Change the permissions for spiderman home directory

[root@zmpt01 home]# chown spiderman:spiderman spiderman [root@zmpt01 home]# chown 5005:6005 spiderman

Change the permissions either user the name or the id's

[root@zmpt01 home]# ls -ls

total 0

0 drwxr-xr-x. 2 spiderman spiderman 6 Dec 5 15:16 spiderman

Login to user spiderman

spiderman@192.168.56.250's password:

Last login: Sat Dec 5 15:15:37 2020 from 192.168.56.1

-bash-4.2\$ pwd



/home/spiderman

.bashrc - .bash_profile - .bash_history are missing

-bash-4.2\$ cp /etc/skel/.bash* .

-bash-4.2\$ Is -la

total 12

drwxr-xr-x. 2 spiderman spiderman 62 Dec 5 15:26.

drwxr-xr-x. 5 root root 53 Dec 5 15:16 ..

-rw-r--r-. 1 spiderman spiderman 18 Dec 5 15:26 .bash_log out -rw-r--r-. 1 spiderman spiderman 193 Dec 5 15:26 .bash_pro file

-rw-r--r-. 1 spiderman spiderman 231 Dec 5 15:26 .bashrc

Difference between root user and regular user

[root@zmpt01 ~]# < --- # root user

[spiderman@zmpt01 ~]\$ < --- \$ regular user

SuDO access

SuDO = Super User DO

Super user access – but not full root access.

- It allows regular user to perform taks wich requires admin access

User without SuDO access

[terminator@zmpt01 ~]\$ yum install firefox -y

Loaded plugins: fastestmirror

You need to be root to perform this command.

[terminator@zmpt01 ~]\$

Informational

[root@zmpt01 ~]# visudo

Allows people in group wheel to run all commands

%wheel ALL=(ALL) ALL

< --- making sure wheel group is not

commented out

Grant Access to SuDO



[root@zmpt01 ~]# usermod -aG wheel terminator [root@zmpt01 ~]# id terminator uid=1000(terminator) gid=1000(terminator), 10(wheel)

usermod -aG wheel terminator

Command	Adding to group	Groupd name/ id	User name/ user id	
	-a add			
	-G secondary group			
Usermod	-aG	Wheel	Terminator	

Run sudo commands

[terminator@zmpt01 ~]\$ sudo yum install firefox -y [sudo] password for terminator:

Successfully completed Complete!

Switch to root

[terminator@zmpt01 $^$]\$ sudo su - Last login: Sat Nov 28 17:01:34 EST 2020 from 192.168.56.1 on pts/0

[root@zmpt01~]#