OS_review2-1

Assign	
≔ tag	homework
≡ 姓名	
■ 学号	

3.关于调度

- 由于本次的任务不存在进程之间的互相抢占,故调度只发生在如下两种情况
 - 。 内核线程主动调度
 - 。 进程自己放弃
- 现阶段动用调度时,进程都是处在running态,那么在进行调度时,直接将之转变为ready态,放在ready queue里即可
 - 。 把下一个进程从ready queue里移出来
 - 。 改变进程状态
 - 。 换掉正在运行的线程
 - 。 把上一个线程放到ready queue里
 - 。 上下文切换
 - 保存上文
 - 恢复上文

```
void do_scheduler(void)
{
    if (!list_empty(&ready_queue)){
        pcb_t *next_running = outputqueue(&ready_queue);
        pcb_t *temp = current_running;
        if(current_running->status == TASK_RUNNING){
            inputqueue(&ready_queue, current_running);
            current_running->status = TASK_READY;
    }
    next_running->status = TASK_RUNNING;
    current_running = next_running;
    process_id = current_running->pid;
    switch_to(temp, next_running);
}
```

}

4.关于锁

- 向 OS 申请锁
 - 。 没被占用则直接访问,访问结束后释放锁,进程进入ready queue
 - 。 被占用则加入该锁的阻塞队列,等待锁被释放后访问,进程进入ready queue

```
void do_mutex_lock_init(mutex_lock_t *lock)
    init_head(&lock->block_queue);
    lock->lock.status = UNLOCKED;
}
void do_mutex_lock_acquire(mutex_lock_t *lock)
    if(lock->lock.status == LOCKED)
        do_block(current_running, &lock->block_queue);
    else
        lock->lock.status = LOCKED;
}
void do_mutex_lock_release(mutex_lock_t *lock)
    if(list_empty(&lock->block_queue))
        lock->lock.status = UNLOCKED;
    else{
        do_unblock(&lock->block_queue);
}
```

csr寄存器

问题:

- time.c函数的一些,比如获取时间
- reflush的含义

关于risc-v系统调用的约定

- 系统调用号传入 [a7]
- 系统调用参数传入 🔞 至 🔠

- 未使用的参数设置为 •
- 返回值在 🔞 中返回

关于中断:

首先是在用户态:

- 系统调用(ecall) (软中断)
- 始终中断(硬中断)

其后进入内核态

• 进入方式为,中断触发,CPU跳转至stvec存的地址

```
ENTRY(exception_handler_entry)
    SAVE_CONTEXT

csrw CSR_SSCRATCH, x0

/* Load the global pointer */
    .option push
    .option norelax
la gp, __global_pointer$
    .option pop

/* TODO: load ret_from_exception into $ra
    * so that we can return to ret_from_exception
    * when interrupt_help complete.
    */

/* TODO: call interrupt_helper
    * note: don't forget to pass parameters for it.
    */

ENDPROC(exception_handler_entry)
```

• 问题:csrw CSR_SSCRATCH, x0

可以注意到其先保存上下文

```
.macro SAVE_CONTEXT
  .local _restore_kernel_tpsp
  .local _save_context
/*
  * If coming from userspace, preserve the user thread pointer and load
  * the kernel thread pointer. If we came from the kernel, sscratch
  * will contain 0, and we should continue on the current TP.
  */
csrrw tp, CSR_SSCRATCH, tp
```

```
bnez tp, _save_context
_restore_kernel_tpsp:
 csrr tp, CSR_SSCRATCH
  sd sp, PCB_KERNEL_SP(tp)
_save_context:
  sd sp, PCB_USER_SP(tp)
  ld sp, PCB_KERNEL_SP(tp)
  addi sp, sp, -(OFFSET_SIZE)
  ^{\prime *} TODO: save all general purpose registers here! ^{*}/
  sd ra, OFFSET_REG_RA(sp)
  sd gp, OFFSET_REG_GP(sp)
  sd t0, OFFSET_REG_T0(sp)
  sd t1, OFFSET_REG_T1(sp)
  sd t2, OFFSET_REG_T2(sp)
  sd s0, OFFSET_REG_S0(sp)
  sd s1, OFFSET_REG_S1(sp)
  sd a0, OFFSET_REG_A0(sp)
  sd a1, OFFSET_REG_A1(sp)
  sd a2, OFFSET_REG_A2(sp)
  sd a3, OFFSET_REG_A3(sp)
  sd a4, OFFSET_REG_A4(sp)
  sd a5, OFFSET_REG_A5(sp)
  sd a6, OFFSET_REG_A6(sp)
  sd a7, OFFSET_REG_A7(sp)
  sd s2, OFFSET_REG_S2(sp)
  sd s3, OFFSET_REG_S3(sp)
  sd s4, OFFSET_REG_S4(sp)
  sd s5, OFFSET_REG_S5(sp)
  sd s6, OFFSET_REG_S6(sp)
  sd s7, OFFSET_REG_S7(sp)
  sd s8, OFFSET_REG_S8(sp)
  sd s9, OFFSET_REG_S9(sp)
  sd s10, OFFSET_REG_S10(sp)
  sd s11, OFFSET_REG_S11(sp)
  sd t3, OFFSET_REG_T3(sp)
  sd t4, OFFSET_REG_T4(sp)
  sd t5, OFFSET_REG_T5(sp)
  sd t6, OFFSET_REG_T6(sp)
   * Disable user-mode memory access as it should only be set in the
   * actual user copy routines.
   * Disable the FPU to detect illegal usage of floating point in kernel
   * space.
   */
  li t0, SR_SUM | SR_FS
  /* TODO: save sstatus, sepc, stval, scause and sscratch on user stack */
.endm
```

之后则调用irp helper确定中断类型,其后处理

```
void interrupt_helper(regs_context_t *regs, uint64_t stval, uint64_t cause)
{
    // TODO interrupt handler.
    // call corresponding handler by the value of `cause`
}
```

• 问题:stval的作用以及table的作用

再之后则调用中断返回程序,恢复上下文并返回(sret)

关于系统调用

• user无法直接使用内核态的函数,所以需要封装好后提供一个接口给user

```
void sys_yield()
{
   invoke_syscall(SYSCALL_YIELD , IGNORE, IGNORE, IGNORE);
}
```

• invoke_syscall 涉及到的参数传递,可以注意 handle_syscall 的写法,他也同时实现了内核态向用户态的信息传递(返回值写入中断帧的 a0 寄 存器中。这样在恢复现场时,返回值自然就被恢复到 a0 寄存器中)

```
ENTRY(invoke_syscall)
  /* TODO: */
  mv a7, a0
  mv a0, a1
  mv a1, a2
  mv a2, a3
  ecall
  jr ra
ENDPROC(invoke_syscall)
```

```
static void init_syscall(void)
{
    // initialize system call table.
    syscall[SYSCALL_SLEEP] = &do_sleep;
    syscall[SYSCALL_YIELD] = &do_scheduler;
    syscall[SYSCALL_WRITE] = &screen_write;
    syscall[SYSCALL_CURSOR] = &screen_move_cursor;
    syscall[SYSCALL_REFLUSH] = &screen_reflush;
    syscall[SYSCALL_GET_TIMEBASE] = &get_time_base;
    syscall[SYSCALL_GET_TICK] = &get_ticks;
}
```

(感觉这个函数有点花)

关于用户栈和内核栈

主要作用就是隔离用户和内核,保证安全

- 用户态的信息保存在内核
- 在系统调用/中断处理完时恢复过去,系统调用还涉及到通信,已经说了