Nginx 安装手册

1 nginx 安装环境

nginx 是 C 语言开发,建议在 linux 上运行,本教程使用 Centos6.5 作为安装环境。

■ gcc

安装 nginx 需要先将官网下载的源码进行编译,编译依赖 gcc 环境,如果没有 gcc 环境, 需要安装 gcc: yum install gcc-c++

■ PCRE

PCRE(Perl Compatible Regular Expressions)是一个 Perl 库,包括 perl 兼容的正则表达式库。nginx 的 http 模块使用 pcre 来解析正则表达式,所以需要在 linux 上安装 pcre 库。

yum install -y pcre pcre-devel

注: pcre-devel 是使用 pcre 开发的一个二次开发库。nginx 也需要此库。

■ zlib

zlib 库提供了很多种压缩和解压缩的方式, nginx 使用 zlib 对 http 包的内容进行 gzip, 所以需要在 linux 上安装 zlib 库。

yum install -y zlib zlib-devel

openssl

OpenSSL 是一个强大的安全套接字层密码库,囊括主要的密码算法、常用的密钥和证书 封装管理功能及 SSL 协议,并提供丰富的应用程序供测试或其它目的使用。

nginx 不仅支持 http 协议,还支持 https(即在 ssl 协议上传输 http),所以需要在 linux 安装 openssl 库。

yum install -y openssl openssl-devel

2编译安装

将 nginx-1.8.0.tar.gz 拷贝至 linux 服务器。

解压:

tar -zxvf nginx-1.8.0.tar.gz cd nginx-1.8.0

1 configure

./configure --help 查询详细参数(参考本教程附录部分: nginx 编译参数)

注意:上边将临时文件目录指定为/var/temp/nginx,需要在/var 下创建 temp 及 nginx 目录

参数设置如下:

```
./configure \
```

- --prefix=/usr/local/nginx \
- --pid-path=/var/run/nginx/nginx.pid \
- --lock-path=/var/lock/nginx.lock \
- --error-log-path=/var/log/nginx/error.log \
- --http-log-path=/var/log/nginx/access.log \
- --with-http_gzip_static_module \
- --http-client-body-temp-path=/var/temp/nginx/client \
- --http-proxy-temp-path=/var/temp/nginx/proxy \
- --http-fastcgi-temp-path=/var/temp/nginx/fastcgi \
- --http-uwsgi-temp-path=/var/temp/nginx/uwsgi \
- --http-scgi-temp-path=/var/temp/nginx/scgi

#注意: 上边将临时文件目录指定为/var/temp/nginx,需要在/var 下创建 temp 及 nginx 目录

2、编译安装

make

make install

安装成功查看安装目录:

```
[root@server01 nginx-1.8.0]# cd ../nginx
[root@server01 nginx]# ]]
总用量 12
drwxr-xr-x. 2 root root 4096 5月 10 19:54 conf
drwxr-xr-x. 2 root root 4096 5月 10 19:54 html
drwxr-xr-x. 2 root root 4096 5月 10 19:54 sbin
```

3 启动 nginx

cd /usr/local/nginx/sbin/
./nginx

查询 nginx 进程:

```
[root@server01 sbin]# ps aux|grep nginx root 15098 0.0 0.0 3568 528 ? Ss 20:15 0:00 nginx: master process ./nginx nobody 15099 0.0 0.0 3768 884 ? S 20:15 0:00 nginx: worker process
```

15098 是 nginx 主进程的进程 id, 15099 是 nginx 工作进程的进程 id

注意:执行./nginx 启动 nginx,这里可以-c 指定加载的 nginx 配置文件,如下:

./nginx -c /usr/local/nginx/conf/nginx.conf

如果不指定-c, nginx 在启动时默认加载 conf/nginx.conf 文件,此文件的地址也可以在编译 安装 nginx 时指定./configure 的参数(--conf-path= 指向配置文件(nginx.conf))

4 停止 nginx

方式 1, 快速停止:

cd /usr/local/nginx/sbin

./nginx -s stop

此方式相当于先查出 nginx 进程 id 再使用 kill 命令强制杀掉进程。

方式 2, 完整停止(建议使用):

cd /usr/local/nginx/sbin

./nginx -s quit

此方式停止步骤是待 nginx 进程处理任务完毕进行停止。

5 重启 nginx

方式 1, 先停止再启动 (建议使用):

对 nginx 进行重启相当于先停止 nginx 再启动 nginx, 即先执行停止命令再执行启动命令。如下:

./nginx -s quit

./nginx

方式 2, 重新加载配置文件:

当 nginx 的配置文件 nginx.conf 修改后,要想让配置生效需要重启 nginx,使用-s reload 不用 先停止 nginx 再启动 nginx 即可将配置信息在 nginx 中生效,如下:

./nginx -s reload

6 测试

nginx 安装成功,启动 nginx,即可访问虚拟机上的 nginx:



Welcome to nginx!

If you see this page, the nginx web server is successfully installed and working. Further configuration is required.

For online documentation and support please refer to <u>nginx.org</u>. Commercial support is available at <u>nginx.com</u>.

Thank you for using nginx.

到这说明 nginx 上安装成功。

7 开机自启动 nginx

7.1编写 shell 脚本

这里使用的是编写 shell 脚本的方式来处理

vi /etc/init.d/nginx (输入下面的代码)

```
#!/bin/bash
# nginx Startup script for the Nginx HTTP Server
# it is v.0.0.2 version.
# chkconfig: - 85 15
# description: Nginx is a high-performance web and proxy server.
                  It has a lot of features, but it's not for everyone.
# processname: nginx
# pidfile: /var/run/nginx.pid
# config: /usr/local/nginx/conf/nginx.conf
nginxd=/usr/local/nginx/sbin/nginx
nginx_config=/usr/local/nginx/conf/nginx.conf
nginx_pid=/var/run/nginx.pid
RETVAL=0
prog="nginx"
# Source function library.
./etc/rc.d/init.d/functions
# Source networking configuration.
./etc/sysconfig/network
# Check that networking is up.
```

```
[ ${NETWORKING} = "no" ] && exit 0
[-x $nginxd] || exit 0
# Start nginx daemons functions.
start() {
if [ -e $nginx_pid ];then
   echo "nginx already running...."
   exit 1
fi
   echo -n $"Starting $prog: "
   daemon $nginxd -c ${nginx_config}
   RETVAL=$?
   echo
   [$RETVAL = 0] && touch /var/lock/subsys/nginx
   return $RETVAL
# Stop nginx daemons functions.
stop() {
         echo -n $"Stopping $prog: "
         killproc $nginxd
         RETVAL=$?
         echo
         [$RETVAL = 0] && rm -f /var/lock/subsys/nginx /var/run/nginx.pid
# reload nginx service functions.
reload() {
     echo -n $"Reloading $prog: "
     #kill -HUP `cat ${nginx_pid}`
     killproc $nginxd -HUP
     RETVAL=$?
     echo
# See how we were called.
case "$1" in
start)
         start
stop)
         stop
         ;;
reload)
         reload
         ;;
restart)
         stop
```

```
start
;;
status)

status $prog
RETVAL=$?
;;

*)

echo $"Usage: $prog {start|stop|restart|reload|status|help}"
exit 1
esac
exit $RETVAL
```

:wq 保存并退出

7.2设置文件的访问权限

chmod a+x /etc/init.d/nginx (a+x ==> all user can execute 所有用户可执行)

这样在控制台就很容易的操作 nginx 了:查看 Nginx 当前状态、启动 Nginx、停止 Nginx、重启 Nginx…

```
[root@DevelopServer nginx-0.8.54] # /etc/init.d/nginx status
nginx is stopped
[root@DevelopServer nginx-0.8.54] # /etc/init.d/nginx start
Starting nginx:
                                                            [ OK ]
[root@DevelopServer nginx-0.8.54] # /etc/init.d/nginx stop
                                                            [ OK ]
Stopping nginx:
[root@DevelopServer nginx-0.8.54] # /etc/init.d/nginx restart
Stopping nginx:
                                                            [FAILED]
Starting nginx:
                                                              OK ]
[root@DevelopServer nginx-0.8.54]# /etc/init.d/nginx stop
Stopping nginx:
                                                               OK ]
[root@DevelopServer nginx-0.8.54]# /etc/init.d/nginx restart
                                                            [FAILED]
Stopping nginx:
Starting nginx:
                                                            [ OK ]
[root@DevelopServer nginx-0.8.54]#
```

如果修改了 nginx 的配置文件 nginx.conf,也可以使用上面的命令重新加载新的配置文件并运行,可以将此命令加入到 rc.local 文件中,这样开机的时候 nginx 就默认启动了

7.3加入到 rc. local 文件中

vi /etc/rc.local

加入一行 /etc/init.d/nginx start 保存并退出,下次重启会生效。