

# RUST FOR RUSTACEANS

IDIOMATIC PROGRAMMING FOR  
EXPERIENCED DEVELOPERS

JON GJENGSET



## **NO STARCH PRESS EARLY ACCESS PROGRAM: FEEDBACK WELCOME!**

Welcome to the Early Access edition of the as yet unpublished *Rust for Rustaceans* by Jon Gjengset! As a prepublication title, this book may be incomplete and some chapters may not have been proofread.

Our goal is always to make the best books possible, and we look forward to hearing your thoughts. If you have any comments or questions, email us at [earlyaccess@nostarch.com](mailto:earlyaccess@nostarch.com). If you have specific feedback for us, please include the page number, book title, and edition date in your note, and we'll be sure to review it. We appreciate your help and support!

We'll email you as new chapters become available. In the meantime, enjoy!

# **RUST FOR RUSTACEANS**

## **JON GJENGSET**

Early Access edition, 5/27/21

Copyright © 2022 by Jon Gjengset.

ISBN 13: 978-1-7185-0185-0 (print)

ISBN 13: 978-1-7185-0186-7 (ebook)

Publisher: William Pollock

Production Manager and Editor: Rachel Monaghan

Developmental Editor: Liz Chadwick

Cover and Interior Design: Octopod Studios

Cover Illustrator: James L. Barry

Technical Reviewer: David Tolnay

Copyeditor: Rachel Head

Compositor: Maureen Forys, Happenstance Type-O-Rama

Proofreader: Sadie Barry

No Starch Press and the No Starch Press logo are registered trademarks of No Starch Press, Inc. Other product and company names mentioned herein may be the trademarks of their respective owners. Rather than use a trademark symbol with every occurrence of a trademarked name, we are using the names only in an editorial fashion and to the benefit of the trademark owner, with no intention of infringement of the trademark.

All rights reserved. No part of this work may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying, recording, or by any information storage or retrieval system, without the prior written permission of the copyright owner and the publisher.

The information in this book is distributed on an “As Is” basis, without warranty. While every precaution has been taken in the preparation of this work, neither the author nor No Starch Press, Inc. shall have any liability to any person or entity with respect to any loss or damage caused or alleged to be caused directly or indirectly by the information contained in it.

# CONTENTS

Introduction

Chapter 1: Rust Programming Mindset

Chapter 2: Foundations

Chapter 3: Types and Traits

Chapter 4: Designing Interfaces

Chapter 5: Error Handling

Chapter 6: Project Structure

Chapter 7: Testing

Chapter 8: Macros

Chapter 9: Asynchronous Programming

Chapter 10: Unsafe Rust

Chapter 11: Concurrency

Chapter 12: Foreign Function Interface

Chapter 13: no\_std

Chapter 14: Interacting with Large Projects

Chapter 15: Putting It Together

Index

The chapters in **red** are included in this Early Access PDF.

# 2

## FOUNDATIONS



As you dive into the more advanced corners of Rust, it's important that you ensure you have a solid understanding of the fundamentals. In Rust, as in any programming language, the precise meaning of various keywords and concepts becomes important as you begin to use the language in more sophisticated ways. In this chapter, we'll walk through many of Rust's primitives and try to define more clearly what they mean, how they work, and why they are exactly the way that they are. Specifically, we'll look at how variables and values differ, how they are represented in memory, and the different memory regions a program has. We'll then discuss some of the subtleties of ownership, borrowing, and lifetimes that you'll need to have a handle on before you continue with the book.

You can read this chapter from top to bottom if you wish, or you can use it as a reference to brush up on the concepts that you feel less sure about. I recommend that you move on only when you feel completely

comfortable with the content of this chapter, as misconceptions about how these primitives work will quickly get in the way of understanding the more advanced topics, or lead to you using them incorrectly.

## Talking About Memory

Not all memory is created equal. In most programming environments, your programs have access to a stack, a heap, registers, text segments, memory-mapped registers, memory-mapped files, and perhaps nonvolatile RAM. Which one you choose to use in a particular situation has implications for what you can store there, how long it remains accessible, and what mechanisms you use to access it. The exact details of these memory regions vary between platforms and are beyond the scope of this book, but some are so important to how you reason about Rust code that they are worth covering here.

### Memory Terminology

Before we dive into regions of memory, you first need to know about the difference between values, variables, and pointers. A *value* in Rust is the combination of a type and an element of that type's domain of values. A value can be turned into a sequence of bytes using its type's *representation*, but on its own you can think of a value more like what you, the programmer, meant." For example, the number 6 in the type `u8` is an instance of the mathematical integer 6, and its in-memory representation is the byte `0x06`. Similarly, the `str` "Hello world" is a value in the domain of all strings whose representation is its UTF-8 encoding. A value's meaning is independent of the location where those bytes are stored.

A value is stored in a *place*, which is the Rust terminology for "a location that can hold a value." This place can be on the stack, on the heap, or in a number of other locations. The most common place to store a value is a *variable*, which is a named value slot on the stack.

A *pointer* is a value that holds the address of a region of memory, so the pointer points to a place. A pointer can be dereferenced to access the value stored in the memory location it points to. We can store the same pointer in more than one variable and therefore have multiple variables that indirectly refer to the same location in memory and thus the same underlying value.

Consider the code in Listing 2-1 that illustrates these three elements.

---

```
let x = 42;
let y = 43;
let var1 = &x;
let mut var2 = &x;
❶ var2 = &y;
```

---

Listing 2-1: Values, variables, and pointers

Here, there are four distinct values: 42 (an `i32`), 43 (an `i32`), the address of `x` (a pointer), and the address of `y` (a pointer). There are also four variables: `x`, `y`, `var1`, and `var2`. The latter two variables both hold values of the pointer type, because references are pointers. While `var1` and `var2` store the same value initially, they store separate, independent copies of that value; when we change the value stored in `var2` ❶, the value in `var1` does not change. In particular, the `=` operator stores the value of the right-hand side expression in the place named by the left-hand side.

An interesting example of where the distinction between variables, values, and pointers becomes important is in a statement such as:

---

```
let string = "Hello world";
```

---

Even though we assign a string value to the variable `string`, the *actual* value of the variable is a pointer to the first character in the string value "Hello world", and not the string value itself. At this point you might say, "But hang on, where is the string value stored, then? Where does the pointer point?" If so, you have a keen eye—we'll get to that in a second.

## Variables in Depth

The definition of a variable I gave earlier is broad and unlikely to be all that useful in and of itself. As you encounter more complex code, you'll need a more accurate mental model to help you reason through what the programs are really doing. There are many such models that we can make use of. Describing them all in detail would take up several chapters and is beyond the scope of this book, but broadly speaking, they can be divided into two categories: high-level models and low-level models. High-level models are useful when thinking about code at the level of lifetimes and borrows, while low-level models are good for when you are reasoning about unsafe code and raw pointers. The models for variables described in the following two sections will suffice for most of the material in this book.

### High-Level Model

In the high-level model, we don't think of variables as places that hold bytes. Instead, we think of them just as names given to values as they are instantiated, moved, and used throughout a program. When you assign a value to a variable, that value is from then on named by that variable. When a variable is later accessed, you can imagine drawing a line from the previous access of that variable to the new access, which establishes a dependency relationship between the two accesses. If the value in a variable is moved, no lines can be drawn from it anymore.

In this model, a variable exists only so long as it holds a legal value; you cannot draw lines from a variable whose value is uninitialized or has been moved, so effectively it isn't there. Using this model, your entire program

consists of many of these dependency lines, often called *flows*, each one tracing the lifetime of a particular instance of a value. Flows can fork and merge when there are branches, with each split tracing a distinct lifetime for that value. The compiler can check that at any given point in your program, all flows that can exist in parallel with each other are compatible. For example, there cannot be two parallel flows with mutable access to a value. Nor can there be a flow that borrows a value while there is no flow that owns the value. Listing 2-2 shows examples of both of these cases.

---

```
let mut x;
// this access would be illegal, nowhere to draw the flow from:
// assert_eq!(x, 42);
❶ x = 42;
// this is okay, can draw a flow from the value assigned above:
❷ let y = &x;
// this establishes a second, mutable flow from x:
❸ x = 43;
// this continues the flow from y, which in turn draws from x:
❹ assert_eq!(*y, 42);
```

---

*Listing 2-2: Illegal flows that the borrow checker will catch*

First, we cannot use `x` before it is initialized, because we have nowhere to draw the flow from. Only when we assign a value to `x` can we draw flows from it. This code has two flows: one exclusive (`&mut`) flow from ❶ to ❸, and one shared (`&`) flow from ❶ through ❷ to ❹. The borrow checker inspects every vertex of every flow and checks that no other incompatible flows exist concurrently. In this case, when the borrow checker inspects the exclusive flow at ❸, it sees the shared flow that terminates at ❹. Since you cannot have an exclusive and a shared use of a value at the same time, the borrow checker (correctly) rejects the code. Notice that if ❹ was not there, this code would compile fine! The shared flow would terminate at ❷, and when the exclusive flow is checked at ❸, no conflicting flows would exist.

If a new variable is declared with the same name as a previous one, they are still considered distinct variables. This is called *shadowing*—the later variable “shadows” the former by the same name. The two variables coexist, though subsequent code no longer has a way to name the earlier one. This model matches roughly how the compiler, and the borrow checker in particular, reasons about your program, and is actually used internally in the compiler to produce efficient code.

## Low-Level Model

Variables name memory locations that may or may not hold legal values. You can think of a variable as a “value slot.” When you assign to it, the slot is filled, and its old value (if it had one) is dropped and replaced. When you access it, the compiler checks that the slot isn’t empty, as that would mean the variable is uninitialized or its value has been moved. A pointer to a variable refers to the variable’s backing memory and can be dereferenced to get at its value. For example, in the statement `let x: usize`, the variable `x` is a



name for a region of memory on the stack that has room for a value the size of a `usize`, though it does not have a well-defined value (its slot is empty). If you assign a value to that variable, such as with `x = 6`, that region of memory will then hold the bits representing the value 6. `&x` does not change when you assign to `x`. If you declare multiple variables with the same name, they still end up with different memory backing them. This model matches the memory model used by C and C++, and many other low-level languages, and is useful for when you need to reason explicitly about memory.

#### NOTE

*In this example, we ignore CPU registers and treat them as an optimization. In reality, the compiler may use a register to back a variable instead of a region of memory if no memory address is needed for that variable.*

You may find that one of these matches your previous model better than the other, but I urge you to try to wrap your head around both of them. They are both equally valid, and both are simplifications, like any useful mental model has to be. If you are able to consider a piece of code from both of these perspectives, you will find it much easier to work through complicated code segments and understand why they do or do not compile and work as you expect.

## Memory Regions

Now that you have a grip on how we refer to memory, we need to talk about what memory actually is. There are many different regions of memory, and perhaps surprisingly, not all of them are stored in the DRAM of your computer. Which part of memory you use has a significant impact on how you write your code. The three most important regions for the purposes of writing Rust code are the stack, the heap, and static memory.

### The Stack

The *stack* is a segment of memory that your program uses as scratch space for function calls. Each time a function is called, a contiguous chunk of memory called a *frame* is allocated at the top of the stack. Near the bottom of the stack is the frame for the `main` function, and as functions call other functions, additional frames are pushed onto the stack. A function's frame contains all the variables within that function, along with any arguments the function takes. When the function returns, its stack frame is reclaimed.

The bytes that make up the values of the function's local variables are not immediately wiped, but it's not safe to access them as they may have been overwritten by a subsequent function call whose frame overlaps with the reclaimed one. And even if they haven't been overwritten, they may contain values that are illegal to use, such as ones that were moved when the function returned.

Stack frames, and crucially the fact that they eventually disappear, are very closely tied to the notion of lifetimes in Rust. Any variable stored in a

frame on the stack cannot be accessed after that frame goes away, so any reference to it must have a lifetime that is at most as long as the lifetime of the frame.

## The Heap

The *heap* is a pool of memory that isn't tied to the current call stack of the program. Values in heap memory live until they are explicitly deallocated. This is useful when you want a value to live beyond the lifetime of the current function's frame. If that value is the function's return value, the calling function can leave some space on its stack for the called function to write that value into before it returns. But if you want to, say, send that value to a different thread with which the current thread may share no stack frames at all, you can store it on the heap.

The heap allow you to explicitly allocate contiguous segments of memory. When you do so, you get a pointer to the start of that segment of memory. That memory segment is reserved for you until you later deallocate it; this process is often referred to as *freeing*, after the name of the corresponding function in the C standard library. Since allocations from the heap do not go away when a function returns, you can allocate memory for a value in one place, pass the pointer to it to another thread, and have that thread safely continue to operate on that value. Or, phrased differently, when you heap-allocate memory, the resulting pointer has an unconstrained lifetime—its lifetime is however long your program keeps it alive.

The primary mechanism for interacting with the heap in Rust is the `Box` type. When you write `Box::new(value)`, the value is placed on the heap, and what you are given back (the `Box<T>`) is a pointer to that value on the heap. When the `Box` is eventually dropped, that memory is freed.

If you forget to deallocate heap memory, it will stick around forever, and your application will eventually eat up all the memory on your machine. This is called *leaking memory* and is usually something you want to avoid. However, there are some cases where you explicitly want to leak memory. For example, say you have a read-only configuration that the entire program should be able to access. You can allocate that on the heap and explicitly leak it with `Box::leak` to get a 'static reference to it.

## Static Memory

*Static memory* is really a catch-all term for several closely related regions located in the file your program is compiled into. These regions are automatically loaded into your program's memory when that program is executed. Values in static memory live for the entire execution of your program. Your program's static memory contains the program's binary code, which is usually mapped as read-only. As your program executes, it walks through the binary code in the text segment instruction by instruction and jumps around whenever a function is called. Static memory also holds the memory for variables you declare with the `static` keyword, as well as certain constant values in your code, like strings.

The special lifetime `'static`, which gets its name from the static memory region, marks a reference as being valid for “as long as static memory is around,” which is until the program shuts down. Since a static variable’s memory is allocated when the program starts, a reference to a variable in static memory is, by definition, `'static`, as it is not deallocated until the program shuts down. The inverse is not true—there can be `'static` references that do not point to static memory—but the name is still appropriate: once you create a reference with a static lifetime, whatever it points to might as well be in static memory as far as the rest of the program is concerned, as it can be used for however long your program wishes.

You will encounter the `'static` lifetime much more often than you will encounter truly static memory (through the `static` keyword, for example) when working with Rust. This is because `'static` often shows up in trait bounds on type parameters. A bound like `T: 'static` indicates that the type parameter `T` is able to live for however long we keep it around for, up to and including the remaining execution of the program. Essentially, this bound requires that `T` is owned and self-sufficient, either in that it does not borrow other (non-static) values or that anything it does borrow is also `'static` and thus will stick around until the end of the program. A good example of `'static` as a bound is the `std::thread::spawn` function that creates a new thread, which requires that the closure you pass it is `'static`. Since the new thread may outlive the current thread, the new thread cannot refer to anything stored on the old thread’s stack. The new thread can refer only to values that will live for its entire lifetime, which may be for the remaining duration of the program.

#### NOTE

*You may wonder how `const` differs from `static`. The `const` keyword declares the following item as constant. Constant items can be completely computed at compile time, and any code that refers to them is replaced with the constant’s computed value during compilation. A constant has no memory or other storage associated with it (it is not a place). You can think of constant as a convenient name for a particular value.*

## Ownership

Rust’s memory model centers on the idea that all values have a single *owner*—that is, exactly one location (usually a scope) is responsible for ultimately deallocating each value. This is enforced through the borrow checker. If the value is moved, such as by assigning it to a new variable, pushing it to a vector, or placing it on the heap, the ownership of the value moves from the old location to the new one. At that point, you can no longer access the value through variables that flow from the original owner, even though the bits that make up the value are technically still there. Instead, you must access the moved value through variables that refer to its new location.

Some types are rebels and do not follow this rule. If a value’s type implements the special `Copy` trait, the value is not considered to have moved even if it is reassigned to a new memory location. Instead, the value is *copied*, and

both the old and new locations remain accessible. Essentially, another identical instance of that same value is constructed at the destination of the move. Most primitive types in Rust, such as the integer and floating-point types, are Copy. To be Copy, it must be possible to duplicate the type's values simply by copying their bits. This eliminates all types that *contain* non-Copy types as well as any type that owns a resource it must deallocate when the value is dropped.

To see why, consider what would happen if a type like Box were Copy. If we executed `box2 = box1`, then `box1` and `box2` would both believe that they owned the heap memory allocated for the box, and they would both attempt to free it when they went out of scope. Freeing the memory twice could have catastrophic consequences.

When a value's owner no longer has use for it, it is the owner's responsibility to do any necessary cleanup for that value by *dropping* it. In Rust, dropping happens automatically when the variable that holds the value is no longer in scope. Types usually recursively drop values they contain, so dropping a variable of a complex type may result in many values being dropped. Because of Rust's discrete ownership requirement, we cannot accidentally drop the same value multiple times. A variable that holds a reference to another value does not own that other value, so the value isn't dropped when the variable drops.

The code in Listing 2-3 gives a quick summary of the rules around ownership, move and copy semantics, and dropping.

---

```

let x1 = 42;
let y1 = Box::new(84);
{ // starts a new scope
❶ let z = (x1, y1);
    // z goes out of scope, and is dropped;
    // it in turn drops the values from x1 and y1
❷ }
    // x1's value is Copy, so it was not moved into z
❸ let x2 = x1;
    // y1's value is not Copy, so it was moved into z
❹ // let y2 = y1;
```

---

*Listing 2-3: Moving and copying semantics*

We start out with two values, the number 42 and a Box (a heap-allocated value) containing the number 84. The former is Copy, whereas the latter is not. When we place `x1` and `y1` into the tuple `z` ❶, `x1` is *copied* into `z`, whereas `y1` is *moved* into `z`. At this point, `x1` continues to be accessible and can be used again ❸. On the other hand, `y1` is rendered inaccessible once its value has been moved ❹, and any attempt to access it would incur a compiler error. When `z` goes out of scope ❷, the tuple value it contains is dropped, and this in turn drops the value copied from `x1` and the one moved from `y1`. When the Box from `y1` is dropped, it also deallocates the heap memory used to store `y1`'s value.

## DROP ORDER

Rust automatically drops values when they go out of scope, such as `x1` and `x2` in the inner scope in Listing 2-3. The rules for the order in which to drop are fairly simple: variables (including function arguments) are dropped in reverse order, and nested values are dropped in source-code order.

This might sound weird at first—why the discrepancy? If we look at it closely, though, it makes a lot of sense. Say you write a function that declares a string and then inserts a reference to that string into a new hash table. When the function returns, the hash table must be dropped first; if the string were dropped first, the hash table would then hold an invalid reference! In general, later variables may contain references to earlier values, whereas the inverse cannot happen due to Rust’s lifetime rules. And for that reason, Rust drops variables in reverse order.

Now, we could have the same behavior for nested values, like the values in a tuple, array, or struct, but that would likely surprise users. If you constructed an array that contained two values, it’d seem odd if the last element of the array were dropped first. The same applies to tuples and structs, where the most intuitive behavior is for the first tuple element or field to be dropped first, then the second, and so on. Unlike for variables, there is no need to reverse the drop order in this case, since Rust doesn’t (currently) allow self-references in a single value. So, Rust goes with the intuitive option.

## Borrowing and Lifetimes

Rust allows the owner of a value to lend out that value to others, without giving up ownership, through references. *References* are pointers that come with an additional contract for how they can be used, such as whether the reference provides exclusive access to the referenced value, or whether the referenced value may also have other references point to it.

### Shared References

A shared reference, `&T`, is, as the name implies, a pointer that may be shared. Any number of other references may exist to the same value, and each shared reference is *Copy*, so you can trivially make more of them. Values behind shared references are not mutable; you cannot modify or reassign the value a shared reference points to, nor can you cast a shared reference to a mutable one.

The Rust compiler is allowed to assume that the value a shared reference points to *will not change* while that reference lives. For example, if the Rust compiler sees that the value behind a shared reference is read multiple times in a function, it is within its rights to read it only once and reuse that value. More concretely, the assertion in Listing 2-4 should never fail.

---

```
fn cache(input: &i32, sum: &mut i32) {
    *sum = *input + *input;
    assert_eq!(*sum, 2 * *input);
}
```

---

*Listing 2-4: Rust assumes that shared references are immutable.*

Whether or not the compiler chooses to apply a given optimization is more or less irrelevant. The compiler heuristics change over time, so you generally want to code against what the compiler is allowed to do rather than what it actually does in a particular case at a particular moment in time.

## Mutable References

The alternative to a shared reference is a mutable reference: `&mut T`. With mutable references, the Rust compiler is again allowed to make full use of the contract that the reference comes with: the compiler assumes that there are no other threads accessing the target value, whether through a shared reference or a mutable one. In other words, it assumes that the mutable reference is *exclusive*. This enables some interesting optimizations that are not readily available in other languages. Take, for example, the code in Listing 2-5.

---

```
fn noalias(input: &i32, output: &mut i32) {
    if *input == 1 {
❶      *output = 2;
    }
    if *input != 1 {
❷      *output = 3;
    }
}
```

---

*Listing 2-5: Rust assumes that mutable references are exclusive.*

In Rust, the compiler can assume that `input` and `output` do not point to the same memory. Therefore, the reassignment of `output` at ❶ cannot affect the check at ❷, and the entire function can be compiled as a single if-else block. If the compiler could not rely on the exclusive mutability contract, that optimization would be invalid, since an `input` of 1 could then result in an `output` of 3 in a case like `noalias(&x, &mut x)`.

A mutable reference lets you mutate only the memory location that the reference points to. Whether you can mutate values that lie beyond the immediate reference depends on the methods provided by the type that lies between. This may be easier to understand with an example, so consider Listing 2-6.

---

```
let x = 42;
let mut y = &x; // y is of type &i32
let z = &mut y; // z is of type &mut &i32
```

---

*Listing 2-6: Mutability applies only to the immediately referenced memory.*

In this example, you are able to change the value of the pointer `y` to a different value (that is, a different pointer) by making it reference a different variable, but you cannot change the value that is pointed to (that is, the value of `x`). Similarly, you can change the pointer value of `y` through `z`, but you cannot change `z` itself to hold a different reference.

The primary difference between owning a value and having a mutable reference to it is that the owner is responsible for dropping the value when it is no longer necessary. Apart from that, you can do anything through a mutable reference that you can if you own the value, with one caveat: if you move the value behind the mutable reference, then you must leave another value in its place. If you did not, the owner would still think it needed to drop the value, but there would be no value for it to drop!

Listing 2-7 gives an example of the ways in which you can move the value behind a mutable reference.

---

```
fn replace_with_84(s: &mut Box<i32>) {
    // this is not okay, as *s would be empty:
    ❶ // let was = *s;
    // but this is:
    ❷ let was = std::mem::take(s);
    // so is this:
    ❸ *s = was;
    // we can exchange values behind &mut:
    let mut r = Box::new(84);
    ❹ std::mem::swap(s, &mut r);
    assert_ne!(*r, 84);
}
let mut s = Box::new(42);
replace_with_84(&mut s);
❺
```

---

*Listing 2-7: Access through a mutable reference must leave a value behind.*

I've added commented-out lines that represent illegal operations. You cannot simply move the value out ❶ since the caller would still think they owned that value and would free it again at ❺, leading to a double free. If you just want to leave some valid value behind, `std::mem::take` ❷ is a good candidate. It is equivalent to `std::mem::replace(&mut value, Default::default());` it moves value out from behind the mutable reference but leaves a new, default value for the type in its place. The default is a separate, owned value, so it is safe for the caller to drop it when the scope ends at ❺.

Alternatively, if you don't need the old value behind the reference, you can overwrite it with a value that you already own ❸, leaving it to the caller to drop the value later. When you do this, the value that used to be behind the mutable reference is dropped immediately.

Finally, if you have two mutable references, you can swap their values without owning either of them ❹, since both references will end up with a legal owned value for their owners to eventually free.

## Interior Mutability

Some types provide *interior mutability*, meaning they allow you to mutate a value through a shared reference. These types usually rely on additional mechanisms (like atomic CPU instructions) or invariants to provide safe mutability without relying on the semantics of exclusive references. These normally fall into two categories: those that let you get a mutable reference through a shared reference, and those that just let you mutate through a shared reference.

The first category consists of types like `Mutex` and `RefCell`, which contain safety mechanisms to ensure that, for any value they give a mutable reference to, only one mutable reference (and no shared references) can exist at a time. Under the hood, these types (and those like them) all rely on a type called `UnsafeCell`, whose name should immediately make you hesitate to use it. We will cover `UnsafeCell` in more detail in [Chapter 10](#), but for now you should know that it is the *only* correct way to mutate through a shared reference.

Other categories of types that provide interior mutability are those that do not give out a mutable reference to the inner value but instead just give you methods for manipulating that value in place. The atomic integer types in `std::sync::atomic` and the `std::cell::Cell` type fall into this category. You cannot get a reference directly to the `usize` or `i32` behind such a type, but you can read and replace its value at a given point in time.

### NOTE

*The `Cell` type in the standard library is an interesting example of safe interior mutability through invariants. It is not shareable across threads and never gives out a reference to the value contained in the `Cell`. Instead, the methods all either replace the value entirely or return a copy of the contained value. Since no references can exist to the inner value, it is always okay to move it. And since `Cell` isn't shareable across threads, the inner value will never be concurrently mutated even though mutation happens through a shared reference.*

## Lifetimes

If you're reading this book, you're probably already familiar with the concept of lifetimes, likely through repeated notices from the compiler about lifetime rules violations. That level of understanding will serve you well for the majority of Rust code you will write, but as we dive deeper into the more complex parts of Rust, you will need a more rigorous mental model to work with.

Newer Rust developers are often taught to think of lifetimes as corresponding to scopes: a lifetime begins when you take a reference to some variable and ends when that variable is moved or goes out of scope. That's often correct, and usually useful, but the reality is a little more complex. A *lifetime* is really a name for a region of code that some reference must be valid for. While a lifetime will frequently coincide with a scope, it does not have to, as we will see later in this section.



## Lifetimes and the Borrow Checker

At the heart of Rust lifetimes is the *borrow checker*. Whenever a reference with some lifetime 'a is used, the borrow checker checks that 'a is still *alive*. It does this by tracing the path back to where 'a starts—where the reference was taken—from the point of use and checking that there are no conflicting uses along that path. This ensures that the reference still points to a value that it is safe to access. This is similar to the high-level “data flow” mental model we discussed earlier in the chapter; the compiler checks that the flow of the reference we are accessing does not conflict with any other parallel flows.

Listing 2-8 shows a simple code example with lifetime annotations for the reference to x.

---

```

let mut x = Box::new(42);
❶ let r = &x;                // 'a
  if rand() > 0.5 {
❷   *x = 84;
  } else {
❸   println!("{}", r);    // 'a
  }
❹
```

---

*Listing 2-8: Lifetimes do not need to be contiguous.*

The lifetime starts at ❶ when we take a reference to x. In the first branch ❷, we then immediately try to modify x by changing its value to 84, which requires a `&mut x`. The borrow checker takes out a mutable reference to x and immediately checks its use. It finds no conflicting uses between when the reference was taken and when it was used, so it accepts the code. This may come as a surprise if you are used to thinking about lifetimes as scopes, since r is still in scope at ❷ (it goes out of scope at ❹). But the borrow checker is smart enough to realize that r is never used later if this branch is taken, and therefore it is fine for x to be mutably accessed here. Or, phrased differently, the lifetime created at ❶ does not extend into this branch: there is no flow from r beyond ❷, and therefore there are no conflicting flows. The borrow checker then finds the use of r in the print statement at ❸. It walks the path back to ❶ and finds no conflicting uses (❷ is not on that path), so it accepts this use as well.

If we were to add another use of r at ❹ in Listing 2-8, the code would no longer compile. The lifetime 'a would then last from ❶ all the way until ❹ (the last use of r), and when the borrow checker checked our new use of r, it would discover a conflicting use at ❷.

Lifetimes can get quite convoluted. In Listing 2-9 you can see an example of a lifetime that has *holes*, where it’s intermittently invalid between where it starts and where it ultimately ends.

---

```

let mut x = Box::new(42);
❶ let mut z = &x;            // 'a
  for i in 0..100 {
```

---

```

❷ println!("{}", z);    // 'a
❸ x = Box::new(i);
❹ z = &x;                // 'a
}
println!("{}", z);    // 'a

```

---

*Listing 2-9: Lifetimes can have holes.*

The lifetime starts at ❶ when we take a reference to `x`. We then move out of `x` at ❸, which ends the lifetime `'a` because it is no longer valid. The borrow checker accepts this move by considering `'a` ended at ❷, which leaves no conflicting flows from `x` at ❸. Then, we restart the lifetime by updating the reference in `z` ❹. Regardless of whether the code now loops back around to ❷ or continues to the final print statement, both of those uses now have a valid value to flow from, and there are no conflicting flows, so the borrow checker accepts the code!

Again, this aligns perfectly with the data-flow model of memory we discussed earlier. When `x` is moved, `z` stops existing. When we reassign `z` later, we are creating an entirely new variable that exists only from that point forward. With that model in mind, this example is not weird.

## Generic Lifetimes

Occasionally you need to store references within your own types. Those references need to have a lifetime so that the borrow checker can check their validity when they are used in the various methods on that type. This is especially true if you want a method on your type to return a reference that outlives the reference to `self`.

Rust allows you to make a type definition generic over one or more lifetimes, just like it allows you to make it generic over types. *The Rust Programming Language* by Steve Klabnik and Carol Nichols (No Starch Press, 2018) covers this topic in some detail, so I won't reiterate the basics here. But as you write more complex types of this nature, there are two subtleties around the interaction between such types and lifetimes that you should be aware of.

First, if your type also implements `Drop`, then dropping your type counts as a use of any lifetime or type your type is generic over. Essentially, when an instance of your type is dropped, the borrow checker will check that it's still legal to use any of your type's generic lifetimes before dropping it. This is necessary in case your drop code *does* use any of those references. If your type does not implement `Drop`, dropping the type does *not* count as a use, and users are free to invalidate any references stored in your type as long as they do not use it any more, like we saw in Listing 2-7. We'll talk more about these rules around dropping in [Chapter 10](#).

Second, while a type can be generic over multiple lifetimes, making it so often only serves to unnecessarily complicate your type signature. Usually, a type being generic over a single lifetime is fine, and the compiler will use the shorter of the lifetimes for any references inserted into your type as that one lifetime. You should only really use multiple generic

lifetime parameters if you have a type that contains multiple references, and its methods return references that should be tied to the lifetime of only *one* of those references.

Consider the type in Listing 2-10, which gives you an iterator over parts of a string separated by a particular other string.

---

```
struct StrSplit<'s, 'p> {
    delimiter: &'p str,
    document: &'s str,
}
impl<'s, 'p> Iterator for StrSplit<'s, 'p> {
    type Output = &'s str;
    fn next(&self) -> Option<Self::Output> {
        todo!()
    }
}
fn str_before(s: &str, c: char) -> Option<&str> {
    StrSplit { document: s, delimiter: &c.to_string() }.next()
}
```

---

*Listing 2-10: A type that needs to be generic over multiple lifetimes*

When you construct this type, you have to give the `delimiter` and `document` to search, both of which are references to string values. When you ask for the next string, you get a reference into the document. Consider what would happen if you used a single lifetime in this type. The values yielded by the iterator would be tied to the lifetime of the `document` *and* the `delimiter`. This would make `str_before` impossible to write: the return type would have a lifetime associated with a variable local to the function—the `String` produced by `to_string`—and the borrow checker would reject the code.

## Lifetime Variance

Variance is a concept that programmers are often exposed to but rarely know the name of because it's mostly invisible. At a glance, variance describes what types are subtypes of other types and when a subtype can be used in place of a supertype (and vice versa). Broadly speaking, a type `A` is a subtype of another type `B` if `A` is at least as useful as `B`. Variance is the reason why, in Java, you can pass a `Turtle` to a function that accepts an `Animal` if `Turtle` is a subtype of `Animal`, or why, in Rust, you can pass a `&'static str` to a function that accepts a `&'a str`.

While variance usually hides out of sight, it comes up often enough that we need to have a working knowledge of it. `Turtle` is a subtype of `Animal` because a `Turtle` is more “useful” than some unspecified `Animal`—a `Turtle` can do anything an `Animal` can do, and likely more. Similarly, `'static` is a subtype of `'a` because a `'static` lives at least as long as any `'a` and so is more useful. Or, more generally, if `'b: 'a` (`'b` outlives `'a`), then `'b` is a subtype of `'a`. This is obviously not the formal definition, but it gets close enough to be of practical use.

All types have a variance, which defines what other similar types can be used in that type's place. There are three kinds of variance: covariant,

invariant, and contravariant. A type is *covariant* if you can just use a subtype in place of the type. For example, if a variable is of type `&'a T`, you can provide a value of type `&'static T` to it, because `&'a T` is covariant in `'a`. `&'a T` is also covariant in `T`, so you can pass a `&Vec<&'static str>` to a function that takes `&Vec<&'a str>`.

Some types are *invariant*, which means that you must provide exactly the given type. `&mut T` is an example of this—if a function takes a `&mut Vec<&'a str>`, you cannot pass it a `&mut Vec<&'static str>`. That is, `&mut T` is invariant in `T`. If you could, the function could put a short-lived string inside the `Vec`, which the caller would then continue using, thinking that it were a `Vec<&'static str>` and thus that the contained string were `'static`! Any type that provides mutability is generally invariant for the same reason—for example, `Cell<T>` is invariant in `T`.

The last category, *contravariance*, comes up for function arguments. Function types are more useful if they're okay with their arguments being *less* useful. This is clearer if you contrast the variance of the argument types on their own with their variance when used as function arguments:

---

```
let x: &'static str; // more useful, lives longer
let x: &'a      str; // less useful, lives shorter

fn take_func1(&'static str) // stricter, so less useful
fn take_func2(&'a str)      // less strict, more useful
```

---

This flipped relationship indicates that `Fn(T)` is contravariant in `T`.

So why do you need to learn about variance when it comes to lifetimes? Variance becomes relevant when you consider how generic lifetime parameters interact with the borrow checker. Consider a type like the one shown in Listing 2-11, which uses multiple lifetimes in a single field.

---

```
struct MutStr<'a, 'b> {
    s: &'a mut &'b str
}
let mut s = "hello";
❶ *MutStr { s: &mut s }.s = "world";
println!("{}", s);
```

---

*Listing 2-11: A type that needs to be generic over multiple lifetimes*

At first glance, using two lifetimes here seems unnecessary—we have no methods that need to differentiate between a borrow of different parts of the structure, as we did with `StrSplit` in Listing 2-10. But if you replace the two lifetimes here with a single `'a`, the code no longer compiles! And it's all because of variance.

At ❶, the compiler must determine what lifetime the lifetime parameter(s) should be set to. If there are two lifetimes, `'a` is set to the to-be-determined lifetime of the borrow of `s`, and `'b` is set to `'static` since that's the lifetime of the provided string `"hello"`. If there is just one lifetime `'a`, the compiler infers that that lifetime must be `'static`.

When we later attempt to access the string reference `s` through a shared reference to print it, the compiler tries to shorten the mutable borrow of `s` used by `MutStr` to allow the shared borrow of `s`.

In the two-lifetime case, `'a` simply ends just before the `println`, and `'b` stays the same. In the single-lifetime case, on the other hand, we run into issues. The compiler wants to shorten the borrow of `s`, but to do so, it would also have to shorten the borrow of the `str`. While `&'static str` can in general be shortened to any `&'a str` (`&'a T` is covariant in `'a`), here it's behind a `&mut T`, which is invariant in `T`. Invariance requires that the relevant type is never replaced with a sub- or supertype, so the compiler's attempt to shorten the borrow fails, and it reports that the list is still mutably borrowed. Ouch!

Because of the reduced flexibility imposed by invariance, you want to ensure that your types remain covariant (or contravariant where appropriate) over as many of their generic parameters as possible. If that requires introducing additional lifetime arguments, you need to carefully weigh the cognitive cost of adding another parameter against the ergonomic cost of invariance.

## Summary

The aim of this chapter has been to establish a solid, shared foundation that we can build on in the chapters to come. By now, I hope you feel that you have a firm grasp on Rust's memory and ownership model, and that those errors you may have gotten from the borrow checker seem less mysterious. You might have known bits and pieces of what we covered here already, but hopefully the chapter has given you a more holistic image of how it all fits together. In the next chapter, we will do something similar for types. We'll go over how types are represented in memory, see how generics and traits produce running code, and take a look at some of the special type and trait constructs Rust offers for more advanced use cases.



# 3

## TYPES



Now that the fundamentals are out of the way, we'll look at Rust's type system. We'll skip past the basics covered in *The Rust*

*Programming Language* and instead dive head-first into how different types are laid out in memory, the ins and outs of traits and trait bounds, existential types, and the rules for using types across crate boundaries.

### Types in Memory

Every Rust value has a type. Types serve many purposes in Rust, as we'll see in this chapter, but one of their most fundamental roles is to tell you how to interpret bits of memory. For example, the sequence of bits `0b10111101` (written in hexadecimal notation as `0xBD`) does not mean anything in and of itself until you assign it a type. When interpreted under the type `u8`, that sequence

of bits is the number 189. When interpreted under the type `i8`, it is `-67`. When you define your own types, it's the compiler's job to determine where each part of the defined type goes in the in-memory representation for that type. Where does each field of your struct appear in the sequence of bits? Where is the discriminant for your enum stored? It's important to understand how this process works as you begin to write more advanced Rust code, because these details affect both the correctness and the performance of your code.

## Alignment

Before we talk about how a type's in-memory representation is determined, we first need to discuss the notion of *alignment*, which dictates where the bytes for a type can be stored. Once a type's representation has been determined, you might think you can take any arbitrary memory location and interpret the bytes stored there as that type. While that is true in a theoretical sense, in practice the hardware also constrains where a given type can be placed. The most obvious example of this is that pointers point to *bytes*, not *bits*. If you placed a value of type `T` starting at bit 4 of your computer's memory, you would have no way to refer to its location; you can create a pointer pointing only to byte 0 or byte 1 (bit 8). For this reason, all values, no matter their type, must start at a byte boundary. We say that all values must be at least *byte-aligned*—they must be placed at an address that is a multiple of 8 bits.

Some values have more stringent alignment rules than just being byte-aligned. In the CPU and the memory system, memory is often accessed in blocks larger than a single byte. For example, on a 64-bit CPU, most values are accessed in chunks of 8 bytes (64 bits), with each operation starting at an 8-byte-aligned address. This is referred to as the CPU's *word size*. The CPU then uses some cleverness to handle reading and writing smaller values, or values that span the boundaries of these chunks.

Where possible, you want to ensure that the hardware can operate in its “native” alignment. To see why, consider what happens if you try to read an `i64` that starts in the middle of an 8-byte block (that is, the pointer to it is not 8-byte-aligned). The hardware will have to do two reads—one from the second half of the first block to get to the start of the `i64`, and one from the first half of the second block to read the rest of the `i64`—and then splice the results together. This is not very efficient. Since the operation is spread across multiple accesses to the underlying memory, you may also end up with strange results if the memory you're reading from is concurrently written to by a different thread. You might read the first 4 bytes before the other thread's write has happened and the second 4 bytes after, resulting in a corrupted value.

Operations on data that is not aligned are referred to as *misaligned accesses* and can lead to poor performance and bad concurrency problems. For this reason, many CPU operations require, or strongly prefer, that their arguments are *naturally aligned*. A naturally aligned value is one whose alignment matches its size. So, for example, for an 8-byte load, the provided address would need to be 8-byte-aligned.

Since aligned accesses are generally faster and provide stronger consistency semantics, the compiler tries to take advantage of them where



possible. It does this by giving every type an alignment that’s computed based on the types that it contains. Built-in values are usually aligned to their size, so a `u8` is byte-aligned, a `u16` is 2-byte-aligned, a `u32` is 4-byte-aligned, and a `u64` is 8-byte-aligned. Complex types—types that contain other types—are typically assigned the largest alignment of any type they contain. For example, a type that contains a `u8`, a `u16`, and a `u32` will be 4-byte-aligned because of the `u32`.

## Layout

Now that you know about alignment, we can explore how the compiler decides on the in-memory representation, known as the *layout*, of a type. By default, as you’ll see shortly, the Rust compiler gives very few guarantees about how it lays out types, which makes for a poor starting point for understanding the underlying principles. Luckily, Rust provides a `repr` attribute you can add to your type definitions to request a particular in-memory representation for that type. The most common one you will see, if you see one at all, is `repr(C)`. As the name suggests, it lays out the type in a way that is compatible with how a C or C++ compiler would lay out the same type. This is helpful when writing Rust code that interfaces with other languages using the foreign-function interface, which we’ll talk about in [Chapter 12](#), as Rust will generate a layout that matches the expectations of the other language’s compiler. Since the C layout is predictable and not subject to change, `repr(C)` is also useful in unsafe contexts if you’re working with raw pointers into the type, or if you need to cast between two different types that you know have the same fields. And, of course, it is perfect for taking our first steps into layout algorithms.

### NOTE

*Another useful representation is `repr(transparent)`, which can be used only on types with a single field and which guarantees that the layout of the outer type is exactly the same as that of the inner type. This comes in handy in combination with the “newtype” pattern, where you may want to operate on the in-memory representations of some `struct A` and `struct NewA(A)` as if they were the same. Without `repr(transparent)`, the Rust compiler does not guarantee that they will have the same layout.*

So, let’s look how the compiler would lay out a particular type with `repr(C)`: the `Foo` type in Listing 3-1. How do you think the compiler would lay this out in memory?

---

```
#[repr(C)]
struct Foo {
    tiny: bool,
    normal: u32,
    small: u8,
    long: u64,
    short: u16,
}
```

---

Listing 3-1: Alignment affects layout.

First the compiler sees the field `tiny`, whose logical size is 1 bit (true or false). But since the CPU and memory operate in terms of bytes, `tiny` is given 1 byte in the in-memory representation. Next, `normal` is a 4-byte type, so we want it to be 4-byte-aligned. But even if `Foo` is aligned, the 1 byte we allocated to `tiny` is going to make `normal` miss its alignment. To rectify this, the compiler inserts 3 bytes of *padding*—bytes with an indeterminate value that are ignored in user code—into the in-memory representation between `tiny` and `normal`. No values go into the padding, but it does take up space.

For the next field, `small`, alignment is simple: it's a 1-byte value, and the current byte offset into the struct is  $1 + 3 + 4 = 8$ . This is already byte-aligned, so `small` can go immediately after `normal`. With `long` we have a problem again, though. We are now  $1 + 3 + 4 + 1 = 9$  bytes into `Foo`. If `Foo` is aligned, then `long` is not 8-byte-aligned the way we want it to be, so we must insert another 7 bytes of padding to make `long` aligned again. This also conveniently ensures the 2-byte alignment we need for the last field, `short`, bringing the total to 26 bytes. Now that we've gone through all the fields, we also need to determine the alignment of `Foo` itself. The rule here is to use the largest alignment of any of `Foo`'s fields, which will be 8 bytes because of `long`. So, to ensure that `Foo` remains aligned if placed in, say, an array, the compiler then adds a final 6 bytes of padding to make `Foo`'s size a multiple of its alignment at 32 bytes.

Now we are ready to shed the C legacy and consider what would happen to the layout if we did not use `repr(C)` in Listing 3-1. One of the primary limitations of the C representation is that it requires that we place all fields in the same order that they appear in the original struct definition. The default Rust representation `repr(Rust)` removes that limitation, along with a couple of other lesser restrictions, such as deterministic field ordering for types that happen to have the same fields. That is, even two different types that share all the same fields, of the same type, in the same order, are not guaranteed to be laid out the same when using the default Rust layout!

Since we're now allowed to reorder the fields, we can place them in decreasing order of size. This means we no longer need the padding between `Foo`'s fields; the fields themselves are used to achieve the necessary alignment! `Foo` is now just the size of its fields: only 16 bytes. This is one of the reasons why Rust by default does not give many guarantees about how a type is laid out in memory: by giving the compiler more leeway to rearrange things, we can produce more efficient code.

It turns out there's also a third way to lay out a type, and that is to tell the compiler that we do not want any padding between our fields. In doing so, we're saying that we are willing to take the performance hit of using misaligned accesses. The most common use case for this is when the impact of every additional byte of memory can be felt, such as if you have a lot of instances of the type, if you have very limited memory, or if you're sending the in-memory representation over a lower-bandwidth medium like a network connection. To opt in to this behavior, you can annotate your type with `#[repr(packed)]`. Keep in mind that this may lead to much slower code, and in extreme cases, this can cause your program to crash if you try to perform operations that the CPU supports only on aligned arguments.

Sometimes, you want to give a particular field or type a larger alignment than it technically requires. You can do that using the attribute `#[repr(align(n))]`. A common use case for this is to ensure that different values stored contiguously in memory (like in an array) end up in different cache lines on the CPU. That way, you avoid *false sharing*, which can cause huge performance degradations in concurrent programs. False sharing occurs when two different CPUs access different values that happen to share a cache line; while they can theoretically operate in parallel, they both end up contending to update the same single entry in the cache. We'll talk about concurrency in much greater detail in [Chapter 11](#).

## Complex Types

You might be curious about how the compiler represents other Rust types in memory. Here's a quick reference:

**Tuple** Represented like a struct with fields of the same type as the tuple values in the same order.

**Array** Represented as a contiguous sequence of the contained type with no padding between the elements.

**Union** Layout is chosen independently for each variant. Alignment is the maximum across all the variants.

**Enumeration** Same as union, but with one additional hidden shared field that stores the enum variant discriminant. The discriminant is the value the code uses to determine which of the enum variants a given value holds. The size of the discriminant field depends on the number of variants.

## Dynamically Sized Types and Fat Pointers

You may have come across the marker trait `Sized` in various odd corners of the Rust documentation and in error messages. Usually, it comes up because the compiler wants you to provide a type that is `Sized`, but you (apparently) did not. Most types in Rust implement `Sized` automatically—that is, they have a size that's known at compile time—but two common types do not: trait objects and slices. If you have, for example, a `dyn Iterator` or a `[u8]`, those do not have a well-defined size. Their size depends on some information that is known only when the program runs and not at compile time, which is why they are called *dynamically sized types (DSTs)*. Nobody knows ahead of time whether the `dyn Iterator` your function received is this 200-byte struct or that 8-byte struct. This presents a problem: often the compiler must know the size of something in order to produce valid code, such as how much space to allocate to a tuple of type `(i32, dyn Iterator, [u8], i32)` or what offset to use if your code tries to access the fourth field. But if the type isn't `Sized`, that information isn't available.

The compiler requires types to be `Sized` nearly everywhere. Struct fields, function arguments, return values, variable types, and array types must all be `Sized`. This restriction is so common that every single type bound you

write includes `T: Sized` unless you explicitly opt out of it with `T: ?Sized` (the `?` means “may not be”). But this is pretty unhelpful if you have a DST and want to do something with it, like if you really want your function to accept a trait object or a slice as an argument.

The solution to this is to place them behind a *fat pointer*. A fat pointer is just like a normal pointer, but it includes an extra word-sized field that gives the additional information about that pointer that the compiler needs to generate reasonable code for working with the pointer. When you take a reference to a DST, the compiler automatically constructs a fat pointer for you. For a slice, the extra information is simply the length of the slice. For a trait object—well, we’ll get to that later. And crucially, that fat pointer *is* `Sized`. Specifically, it is twice the size of a `usize` (the size of a word on the target platform): one `usize` for holding the pointer, and one `usize` for holding the extra information needed to “complete” the type.

#### NOTE

*Box and Arc also support storing fat pointers, which is why they both support `T: ?Sized`.*

## Traits and Trait Bounds

Traits are a key piece of Rust’s type system—they are the glue that allows types to interoperate even though they don’t know about each other at the time they are defined. *The Rust Programming Language* does a great job of covering how to define and use traits, so I won’t go over that here. Instead, we’re going to take a look at some of the more technical aspects of traits: how they’re implemented, restrictions you have to adhere to, and some more esoteric uses of traits.

### Compilation and Dispatch

By now, you’ve probably written a decent amount of generic code in Rust. You’ve used generic type parameters on types and methods, and maybe even a few trait bounds here and there. But have you ever wondered what actually happens to generic code when you compile it, or what happens when you call a trait method on a `dyn Trait`?

When you write a type or function that is generic over `T`, you’re really telling the compiler to make a copy of that type or function for each type `T`. When you construct a `Vec<i32>` or a `HashMap<String, bool>`, the compiler essentially copy-pastes the generic type and all its implementation blocks and replaces all instances of each generic parameter with the concrete type you provided. It makes a full copy of the `Vec` type with every `T` replaced with `i32`, and a full copy of the `HashMap` type with every `K` replaced with `String` and every `V` with `bool`.

#### NOTE

*In reality, the compiler does not actually do a full copy-paste. It copies only parts of the code that you use, so if you never call `find` on a `Vec<i32>`, the code for `find` won’t be copied and compiled.*

The same thing applies to generic functions. Consider the code in Listing 3-2, which shows a generic method.

---

```
impl String {
    pub fn contains(&self, p: impl Pattern) -> bool {
        p.is_contained_in(self)
    }
}
```

---

*Listing 3-2: A generic method using static dispatch*

A copy of this method is made for every distinct pattern type (recall that `impl Trait` is shorthand for `<T: Trait>`). We need a different copy of the function body for each `impl Pattern` type because we need to know the address of the `is_contained_in` function to call it. The CPU needs to be told where to jump to and continue execution. For any *given* pattern, the compiler knows that that address is the address of the place where that pattern type implements that trait method. But there is no one address we could use for *any* type, so we need to have one copy for each type, each with its own address to jump to. This is referred to as *static dispatch*, since for any given copy of the method, the address we are “dispatching to” is known statically.

#### NOTE

*You may have noticed that the word “static” is a little overloaded in this context. Static is generally used to refer to anything that is known at compile time, or can be treated as though it were, since it can then be written into static memory, as we discussed in [Chapter 2](#).*

This process of going from a generic type to many non-generic types is called *monomorphization*, and it’s part of the reason generic Rust code usually performs just as well as non-generic code. By the time the compiler starts optimizing your code, it’s as if no generics were there at all! Each instance is optimized separately and with all of the types known. As a result, the code is just as efficient as if the `is_contained_in` method of the pattern that is passed in were called directly without any traits present. The compiler has full knowledge of the types involved and can even inline the implementation of `is_contained_in` if it wishes.

Monomorphization also comes at a cost: all those instantiations of your type need to be compiled separately, which can increase compile time if the compiler cannot optimize them away. Each monomorphized function also results in its own chunk of machine code, which can make your program larger. And because instructions aren’t shared between different instantiations of a generic type’s methods, the CPU’s instruction cache is also less effective as it now needs to hold multiple copies of effectively the same instructions.

## NON-GENERIC INNER FUNCTIONS

Often, much of the code in a generic method is not type-dependent. Consider, for example, the implementation of `HashMap::insert`. The code to compute the hash of the supplied key depends on the key type of the map, but the code to walk the buckets of the map to find the insertion point may not. In cases like this, it would be more efficient to share the generated machine code for the non-generic parts of the method across monomorphizations, and only generate distinct copies where this is actually needed.

One pattern you can use for cases like this is to declare a non-generic helper function inside the generic method that performs the shared operations. This leaves only the type-dependent code for the compiler to copy-paste for you while allowing the helper function to be shared.

Making the function an inner function comes with the added benefit that you do not pollute your module with a single-purpose function. You can instead declare such a helper function outside the method instead; just be careful that you don't make it a method under a generic `impl` block, as then it will still be monomorphized.

The alternative to static dispatch is *dynamic dispatch*, which enables code to call a trait method on a generic type without knowing what that type is. I said earlier that the reason we needed multiple instances of the method in Listing 3-2 was that otherwise your program wouldn't know what address to jump to in order to call the trait method `is_contained_in` on the given pattern. Well, with dynamic dispatch, the caller simply tells you. If you replace `impl` Pattern with `&dyn` Pattern, you tell the caller that they must give *two* pieces of information for this argument: the address of the pattern *and* the address of the `is_contained_in` method. In practice, the caller gives us a pointer to a chunk of memory called a virtual method table, or *vtable*, that holds the address of the implementation of *all* the trait's methods for the type in question, one of which is `is_contained_in`. When the code inside the method wants to call a trait method on the provided pattern, it looks up the address of that pattern's implementation of `is_contained_in` in the vtable and then calls the function at that address. This allows us to use the same function body regardless of what type the caller wants to use.

### NOTE

*Every vtable also contains information about the concrete type's layout and alignment since that information is always needed to work with a type. If you want an example of what an explicit vtable looks like, take a look at the `std::task::RawWakerVTable` type.*

You'll notice that when we opted in to dynamic dispatch using the `dyn` keyword, we had to place an `&` in front of it. The reason is that we no longer know at compile time the size of the pattern type that the caller passes in, so we don't know how much space to set aside for it. In other words, `dyn Trait` is

`!Sized`, where the `!` means not. To make it `Sized` so we can take it as an argument, we place it behind a pointer (which we know the size of). Since we also need to pass along the table of method addresses, this pointer becomes a fat pointer, where the extra word holds the pointer to the vtable. You can use any type that is able to hold a fat pointer for dynamic dispatch, such as `&mut`, `Box`, and `Arc`. Listing 3-3 shows the dynamic dispatch equivalent of Listing 3-2.

---

```
impl String {
    pub fn contains(&self, p: &dyn Pattern) -> bool {
        p.is_contained_in(&*self)
    }
}
```

---

*Listing 3-3: A generic method using dynamic dispatch*

The combination of a type that implements a trait and its vtable is known as a *trait object*. Most traits can be turned into trait objects, but not all. For example, the `Clone` trait, whose `clone` method returns `Self`, cannot be turned into a trait object. If we accept a `dyn Clone` trait object and then call `clone` on it, the compiler won't know what type to return. Or, consider the `Extend` trait from the standard library, which has a method `extend` that is generic over the type of the provided iterator (so there may be many instances of it). If you were to call a method that took a `dyn Extend`, there would be no single address for `extend` to place in the trait object's vtable; there would have to be one entry for every type `extend` might ever be called with. These are examples of traits that are not *object-safe* and therefore may not be turned into trait objects. To be object-safe, none of a trait's methods can be generic or use the `Self` type. Furthermore, the trait cannot have any static methods (that is, methods whose first argument does not dereference to `Self`), since it would be impossible to know which instance of the method to call. It is not clear, for example, what code `FromIterator::from_iter(&[0])` should execute.

When reading about trait objects, you may see mentions of the trait bound `Self: Sized`. Such a bound implies that `Self` is not being used through a trait object (since it would then be `!Sized`). You can place that bound on a trait to require that the trait never use dynamic dispatch, or you can place it on a specific method to make that method unavailable when the trait is accessed through a trait object. Methods with a `where Self: Sized` bound are exempted when checking if a trait is object-safe.

Dynamic dispatch cuts compile times, since it's no longer necessary to compile multiple copies of types and methods, and it can improve the efficiency of your CPU instruction cache. However, it also prevents the compiler from optimizing for the specific types that are used. With dynamic dispatch, all the compiler can do for `find` in Listing 3-2 is insert a call to the function through the vtable—it can no longer perform any additional optimizations as it does not know what code will sit on the other side of that function call. Furthermore, every method call on a trait object requires a lookup in the vtable, which adds a small amount of overhead over calling the method directly.



When you're given the choice between static and dynamic dispatch, there is rarely a clear-cut right answer. Broadly speaking, though, you'll want to use static dispatch in your libraries and dynamic dispatch in your binaries. In a library, you want to allow your users to decide what kind of dispatch is best for them, since you don't know what their needs are. If you use dynamic dispatch, they're forced to do the same, whereas if you use static dispatch, they can choose whether to use dynamic dispatch or not. In a binary, on the other hand, you're writing the final code, so there are no needs to consider except those of the code you are writing. Dynamic dispatch often allows you to write cleaner code that leaves out generic parameters and will compile more quickly, all at a (usually) marginal performance cost, so it's usually the better choice for binaries.

## ***Generic Traits***

Rust traits can be generic in one of two ways: with generic type parameters like `trait Foo<T>` or with associated types like `trait Foo { type Bar; }`. The difference between these is not immediately apparent, but luckily the rule of thumb is quite simple: use an associated type if you expect only one implementation of the trait for a given type, and use a generic type parameter otherwise.

The rationale for this is that associated types are often significantly easier to work with, but will not allow multiple implementations. So, more simply put, the advice is really just to use associated types whenever you can.

With a generic trait, users must always specify all the generic parameters and repeat any bounds on those parameters. This can quickly get messy and hard to maintain. If you add a generic parameter to a trait, all users of that trait must also be updated to reflect the change. And since multiple implementations of a trait may exist for a given type, the compiler may have a hard time deciding which instance of the trait you meant to use, leading to awful disambiguating function calls like `FromIterator::<u32>::from_iter`. But the upside is that you can implement the trait multiple times for the same type—for example, you can implement `PartialEq` against multiple right-hand side types for your type, or you can implement both `FromIterator<T>` and `FromIterator<&T>` where `T: Clone`, precisely because of the flexibility that generic traits provide.

With associated types, on the other hand, the compiler needs to know only the type that implements the trait, and all the associated types follow (since there is only one implementation). This means the bounds can all live in the trait itself and do not need to be repeated on use. In turn, this allows the trait to add further associated types without affecting its users. And because the type dictates all the associated types of the trait, you never have to disambiguate with the unified function calling syntax shown in the previous paragraph. However, you cannot implement `Deref` against multiple `Target` types, nor can you implement `Iterator` with multiple different `Item` types.

## ***Coherence and the Orphan Rule***

Rust has some fairly strict rules about where you can implement traits and what types you can implement them on. These rules exist to preserve the



*coherence* property: for any given type and method, there is only ever one correct choice for which implementation of the method to use for that type. To see why this is important, consider what would happen if I could write my own implementation of the `Display` trait for the `bool` type from the standard library. Now, for any code that tries to print a `bool` value and includes my crate, the compiler won't know whether to pick the implementation I wrote or the one from the standard library. Neither choice is correct or better than the other, and the compiler obviously cannot choose randomly. The same issue occurs if the standard library is not involved at all, but we instead have two crates that depend on each other, and they both implement a trait for some shared type. The coherence property ensures that the compiler never ends up in these situations and never has to make these choices: there will always be exactly one obvious choice.

A facile way to uphold coherence would be to ensure only the crate that defines a trait can write implementations for that trait; if no one else can implement the trait, then there can be no conflicting implementations elsewhere. However, this is too restrictive in practice and would essentially make traits useless, as there would be no way to implement traits like `std::fmt::Debug` and `serde::Serialize` for your own types, unless you got your own type included into the defining crate. The opposite extreme, saying that you can implement traits for only your own types, solves that problem but introduces another: a crate that defines a trait now cannot provide implementations of that trait for types in the standard library or in other popular crates! Ideally, we would like to find some set of rules that balances the desire for downstream crates to implement upstream traits for their own types against the desire for upstream crates to be able to add implementations of their own traits without breaking downstream code.

#### NOTE

*Upstream refers to something your code depends on, and downstream refers to something that depends on your code. Often, these terms are used in the direct sense of crate dependencies, but they can also be used to refer to authoritative forks of a codebase—if you do a fork of the Rust compiler, the official Rust compiler is your “upstream.”*

In Rust, the rule that establishes that balance is the *orphan rule*. Simply stated, the orphan rule says that you can implement a trait for a type only if the trait *or* the type is local to your crate. So, you can implement `Debug` for your own type, and you can implement `MyNeatTrait` for `bool`, but you cannot implement `Debug` for `bool`. If you try, your code will not compile, and the compiler will tell you that there are conflicting implementations.

This gets you pretty far; it allows you to implement your own traits for third-party types and to implement third-party traits for your own types. However, the orphan rule is not the end of the story. There are a number of additional implications, caveats, and exceptions to it that you should be aware of.

## Blanket Implementations

The orphan rule allows you to implement traits over a range of types with code like `impl<T> MyTrait for T` where `T`: and so on. This is a *blanket implementation*—it is not limited to just one particular type but instead applies to a wide range of types. Only the crate that defines a trait is allowed to write a blanket implementation, and adding a blanket implementation to an existing trait is considered a breaking change. If it were not, a downstream crate that contained `impl MyTrait for Foo` could suddenly stop compiling just because you update the crate that defines `MyTrait` with an error about a conflicting implementation.

## Fundamental Types

Some types are so essential that it's necessary to allow anyone to implement traits on them, even if this seemingly violates the orphan rule. These types are marked with the `#[fundamental]` attribute and currently include `&`, `&mut`, and `Box`. For the purposes of the orphan rule, fundamental types may as well not exist—they are effectively erased before the orphan rule is checked in order to allow you to, for example, implement `IntoIterator` for `&MyType`. With just the orphan rule, this implementation would not be permitted since it implements a foreign trait for a foreign type—`IntoIterator` and `&` both come from the standard library. Adding a blanket implementation over a fundamental type is also considered a breaking change.

## Covered Implementations

There are some limited cases where we want to allow implementing a foreign trait for a foreign type, which the orphan rule does not normally allow. The simplest example of this is when you want to write something like `impl From<MyType> for Vec<i32>`. Here, the `From` trait is foreign, as is the `Vec` type, yet there is no danger of violating coherence. This is because a conflicting implementation could be added only through a blanket implementation in the standard library (the standard library cannot otherwise name `MyType`), which is a breaking change anyway.

To allow these kinds of implementations, the orphan rule includes a narrow exemption that permits implementing foreign traits for foreign types under a very specific set of circumstances. Specifically, a given `impl<P1..=Pn> ForeignTrait<T1..=Tn> for T0` is allowed only if at least one `Ti` is a local type and no `T` before the first such `Ti` is one of the generic types `P1..=Pn`. Generic type parameters (`Ps`) are allowed to appear in `T0..Ti` as long as they are *covered* by some intermediate type. A `T` is covered if it appears as a type parameter to some other type (like `Vec<T>`), but not if it stands on its own (just `T`) or just appears behind a fundamental type like `&T`. So, all the implementations in Listing 3-4 are valid.

---

```
impl<T> From<T> for MyType
impl<T> From<T> for MyType<T>
impl<T> From<MyType> for Vec<T>
impl<T> ForeignTrait<MyType, T> for Vec<T>
```

---

Listing 3-4: Valid implementations of foreign traits for foreign types

However, the implementations in Listing 3-5 are invalid.

---

```
impl<T> ForeignTrait for T
impl<T> From<T> for T
impl<T> From<Vec<T>> for T
impl<T> From<MyType<T>> for T
impl<T> From<T> for Vec<T>
impl<T> ForeignTrait<T, MyType> for Vec<T>
```

---

*Listing 3-5: Invalid implementations of foreign traits for foreign types*

This relaxation of the orphan rule complicates the rules for what constitutes a breaking change when you add a new implementation for an existing trait. In particular, adding a new implementation to an existing trait is non-breaking only if it contains at least one *new* local type, and that new local type satisfies the rules for the exemption described earlier. Adding any other new implementation is a breaking change.

#### NOTE

*Note that `impl<T> ForeignTrait<LocalType, T> for ForeignType` is valid, but `impl<T> ForeignTrait<T, LocalType> for ForeignType` is not! This may seem arbitrary, but without this rule, you could write `impl<T> ForeignTrait<T, LocalType> for ForeignType`, and another crate could write `impl<T> ForeignTrait<TheirType, T> for ForeignType`, and a conflict would arise only when the two crates were brought together. Instead of disallowing this pattern altogether, the orphan rule requires that your local type come before the type parameter, which breaks the tie and ensures that if both crates uphold coherence in isolation, they also uphold it when combined.*

## Trait Bounds

The standard library is flush with trait bounds, whether it's that the keys in a `HashMap` must implement `Hash + Eq` or that the function given to `thread::spawn` must be `FnOnce + Send + 'static`. When you write generic code yourself, it will almost certainly include trait bounds, as otherwise your code cannot do much with the type it is generic over. As you write more elaborate generic implementations, you'll find that you also need more fidelity from your trait bounds, so let's look at some of the ways to achieve that.

First and foremost, trait bounds do not have to be of the form `T: Trait` where `T` is some type your implementation or type is generic over. The bounds can be arbitrary type restrictions and do not even need to include generic parameters, types of arguments, or local types. You can write a trait bound like `where String: Clone`, even though `String: Clone` is always true and contains no local types. You can also write `where io::Error: From<MyError<T>>`; your generic type parameters do not need to appear only on the left-hand side. This not only allows you to express more intricate bounds but also can save you from needlessly repeating bounds. For example, if your method wants to construct a `HashMap<K, V, S>` whose keys are some generic type `T` and whose value is a `usize`, instead of writing the bounds out like `where T: Hash + Eq, S: BuildHasher + Default`, you could write `where HashMap<T, usize, S>: FromIterator`. This saves you from looking up the exact bounds requirements

for the methods you end up using and more clearly communicates the “true” requirement of your code. As you can see, it can also significantly reduce the complexity of your bounds if the bounds on the underlying trait methods you want to call are complex.

### DERIVE TRAIT

While `#[derive(Trait)]` is extremely convenient, in the context of trait bounds, you should be aware of one subtlety around how it is often implemented. Many `#[derive(Trait)]` expansions desugar into `impl Trait for Foo<T> where T: Trait`. This is often what you want, but not always. For example, consider what happens if we try to derive `Clone` this way for `Foo<T>` and `Foo` contains an `Arc<T>`. `Arc` implements `Clone` *regardless* of whether `T` implements `Clone`, but due to the derived bounds, `Foo` will implement `Clone` only if `T` does! This isn’t usually too big of an issue, but it does add a bound where one isn’t needed. If we rename the type to `Shared`, the problem may become a little clearer. Imagine how confused a user that has a `Shared<NotClone>` will be when the compiler tells them that they cannot clone it! At the time of writing, this is how `#[derive(Clone)]` as provided by the standard library works, though this may change in the future.

Sometimes, you want bounds on associated types of types you’re generic over. As an example, consider the iterator method `flatten`, which takes an iterator that produces items that in turn implement `Iterator` and produces an iterator of the items of those inner iterators. The type it produces, `Flatten`, is generic over `I`, which is the type of the outer iterator. `Flatten` implements `Iterator` if `I` implements `Iterator` *and* the items yielded by `I` themselves implement `IntoIterator`. To enable you to write bounds like this, Rust lets you refer to associated types of a type using the syntax `Type::AssocType`. For example, we can refer to `I`’s `Item` type using `I::Item`. If a type has multiple associated types by the same name, such as if the trait that provides the associated type is itself generic (and therefore there are many implementations), you can disambiguate with the syntax `<Type as Trait>::AssocType`. Using this, you can write bounds not only for the outer iterator type but also for the item type of that outer iterator.

In code that uses generics extensively, you may find that you need to write a bound that talks about references to a type. This is normally fine, as you’ll tend to also have a generic lifetime parameter that you can use as the lifetime for these references. In some cases, however, you want the bound to say “this reference implements this trait for any lifetime.” This is exceedingly rare—at the time of writing, the standard library uses it in just three places—but it does happen. This type of bound is known as a *higher-ranked trait bound*, and it’s particularly useful in association with the `Fn` traits. For example, imagine you want to be generic over a function that takes a reference to a `T` and returns a reference to *inside* that `T`. If you write `F: Fn(&T) ->`

&U, you need to provide a lifetime for those references, but you really want to say “any lifetime as long as the output is the same as the input.” Using a higher-ranked lifetime, you can write `F: for<'a> Fn(&'a T) -> &'a U` to say that for *any* lifetime 'a, the bound must hold. The Rust compiler is smart enough to automatically add the `for` when you write `Fn` bounds with references like this, which is part of why you so rarely need the explicit form, but it is worth knowing about.

To bring all of this together, consider the code in Listing 3-6, which can be used to implement `Debug` for any type that can be iterated over and whose elements are `Debug`.

---

```
impl Debug for AnyIterable
where for<'a> &'a Self: IntoIterator,
    for<'a> <&'a Self as IntoIterator>::Item: Debug {
    fn fmt(&self, f: &mut Formatter) -> Result<(), Error> {
        f.debug_list().entries(self).finish()
    }
}
```

---

*Listing 3-6: An excessively generic implementation of `Debug` for any iterable collection*

You could copy-paste this implementation for pretty much any collection type and it would “just work.” Of course, you may want a smarter debug implementation, but this illustrates the power of trait bounds quite well.

## Marker Traits

Usually, we use traits to denote functionality that multiple types can support; a `Hash` type can be hashed by calling `hash`, a `Clone` type can be cloned by calling `clone`, and a `Debug` type can be formatted for debugging by calling `fmt`. But not all traits are functional in this way. Some traits, called *marker traits*, instead indicate a property of the implementing type. Marker traits have no methods or associated types and serve just to tell you that a particular type can or cannot be used in a certain way. For example, if a type implements the `Send` marker trait, it is safe to send across thread boundaries. If it does not implement this marker trait, it isn’t safe to send. There are no methods associated with this behavior; it’s just a fact about the type. The standard library has a number of these in the `std::marker` module, including `Send`, `Sync`, `Copy`, `Sized`, and `Unpin`. Most of these (all except `Copy`) are also *auto-traits*; the compiler automatically implements them for types unless the type contains something that does not implement the marker trait.

Marker traits serve an important purpose in Rust: they allow you to write bounds that capture semantic requirements not directly expressed in the code. There is no call to `send` in code that requires that a type is `Send`. Instead, the code *assumes* that the given type is fine to use in a separate thread, and without marker traits the compiler would have no way of checking that assumption. It would be up to the programmer to remember the assumption and read the code very carefully, which we all know is not something we’d like to rely on. That path is riddled with data races, segfaults, and other runtime issues.

Similar to marker traits are *marker types*. These are unit types (like `struct MyMarker;`) that hold no data and have no methods. Marker types are useful for, well, marking a type as being in a particular state. They come in handy when you want to make it impossible for a user to misuse an API. For example, consider a type like `SshConnection`, which may or may not have been authenticated yet. You could add a generic type argument to `SshConnection` and then create two marker types: `Unauthenticated` and `Authenticated`. When the user first connects, they get `SshConnection<Unauthenticated>`. In its `impl` block, you provide only a single method: `connect`. `connect` returns a `SshConnection<Authenticated>`, and it's only in that `impl` block that you provide the remaining methods for running commands and such. We will look at this pattern further in [Chapter 4](#).

## Existential Types

In Rust you very rarely have to specify the types of variables you declare in the body of a function or the types of generic arguments to methods that you call. This is because of *type inference*, where the compiler decides what type to use based on what type the code the type appears in evaluates to. The compiler will usually infer types only for variables and for the arguments (and return types) of closures; top-level definitions like functions, types, traits, and trait implementation blocks all require that you explicitly name all types. There are a couple of reasons for this, but the primary one is that type inference is much easier when you have at least some known points to start the inference from. However, it's not always easy, or even possible, to fully name a type! For example, if you return a closure from a function, or an `async` block from a trait method, its type does not have a name that you can type into your code.

To handle situations like this, Rust supports *existential types*. Chances are, you have already seen existential types in action. All functions marked as `async fn` or with a return type of `impl Trait` have an existential return type: the signature does not give the true type of the return value, just a hint that the function returns *some* type that implements some set of traits that the caller can rely on. And crucially, the caller can only rely on the return type implementing those traits, and nothing else.

### NOTE

*Technically, it isn't strictly true that the caller relies on the return type and nothing else. The compiler will also propagate auto-traits like `Send` and `Sync` through `impl Trait` in return position. We'll look at this more in the next chapter.*

This behavior is what gives existential types their name: we are asserting that there exists some concrete type that matches the signature, and we leave it up to the compiler to find what that type is. The compiler will usually then go figure that out by applying type inference on the body of the function.

Not all instances of `impl Trait` use existential types. If you use `impl Trait` in argument position for a function, it's really just shorthand for an unnamed generic parameter to that function. For example, `fn foo(s: impl ToString)` is mostly just syntax sugar for `fn foo<S: ToString>(s: S)`.

Existential types come in handy particularly when you implement traits that have associated types. For example, imagine you're implementing the `IntoIterator` trait. It has an associated type `IntoIter` that holds the type of the iterator that the type in question can be turned into. With existential types, you do not need to define a separate iterator type to use for `IntoIter`. Instead, you can give the associated type as `impl Iterator<Item = Self::Item>` and just write an expression inside the `fn into_iter(self)` that evaluates to an `Iterator`, such as by using `maps` and `filters` over some existing iterator type.

Existential types also provide a feature beyond mere convenience: they allow you to perform zero-cost type erasure. Instead of exporting helper types just because they appear in a public signature somewhere—iterators and futures are common examples of this—you can use existential types to hide the underlying concrete type. Users of your interface are shown only the traits that the relevant type implements, while the concrete type is left as an implementation detail. Not only does this simplify the interface, but it also enables you to change that implementation as you wish without breaking downstream code in the future.

## Summary

This chapter has provided a thorough review of the Rust type system. We've looked both at how the compiler manifests types in memory and how it reasons about the types themselves. This is important background material for writing unsafe code, complex application interfaces, and asynchronous code in later chapters. You'll also find that much of the type reasoning from this chapter plays into how you design Rust code interfaces, which we'll cover in the next chapter.





# 4

## DESIGNING INTERFACES



Every project, no matter how large or small, has an API. In fact, it usually has several. Some of these are user-facing, like an HTTP endpoint or a command line interface, and some are developer-facing, like a library's public interface. On top of these, Rust crates also have a number of internal interfaces: every type, trait, and module boundary has its own miniature API that the rest of your code interfaces with. As your codebase grows in size and complexity, you'll find it worthwhile to invest some thought and care into how you design even the internal APIs to make the experience of using and maintaining the code over time as pleasant as possible.

In this chapter we'll look at some of the most important considerations for writing idiomatic interfaces in Rust, whether the users of those interfaces are your own code or other developers using your library. These essentially boil down to four principles: your interfaces should be *unsurprising*, *flexible*, *obvious*, and *constrained*. I'll discuss each of these principles in turn, to provide some guidance for writing reliable and usable interfaces.

I highly recommend taking a look at the Rust API Guidelines (<https://rust-lang.github.io/api-guidelines/>) after you’ve read this chapter. There’s an excellent checklist you can follow, with a detailed run-through of each recommendation. Many of the recommendations in this chapter are also checked by the `cargo clippy` tool, which you should start running on your code if you aren’t already. I also encourage you to read through Rust RFC 1105 (<https://rust-lang.github.io/rfcs/1105-api-evolution.html>) and the chapter of *The Cargo Book* on SemVer compatibility (<https://doc.rust-lang.org/cargo/reference/semver.html>), which cover what is and is not a breaking change in Rust.

## Unsurprising

The Principle of Least Surprise, otherwise known as the Law of Least Astonishment, comes up a lot in software engineering, and it holds true for Rust interfaces as well. Where possible, your interfaces should be intuitive enough that if the user has to guess, they usually guess correctly. Of course, not everything about your application is going to be immediately intuitive in this way, but anything that *can* be unsurprising should be. The core idea here is to stick close to things the user is likely to already know so that they don’t have to relearn concepts in a different way than they’re used to. That way you can save their brain power for figuring out the things that are actually specific to your interface.

There are a variety of ways you can make your interfaces predictable. Here, we’ll look at how you can use naming, common traits, and ergonomic trait tricks to help the user out.

### ***Naming Practices***

A user of your interface will encounter it first through its names; they will immediately start to infer things from the names of types, methods, variables, fields, and libraries they come across. If your interface reuses names for things—say, methods and types—from other (perhaps common) interfaces, the user will know they can make certain assumptions about your methods and types. A method called `iter` probably takes `&self`, and probably gives you an iterator. A method called `into_inner` probably takes `self` and likely returns some kind of wrapped type. A type called `SomethingError` probably implements `std::error::Error` and appears in various `Results`. By reusing common names for the same purpose, you make it easier for the user to guess what things do and allow them to more easily understand the things that are different about your interface.

A corollary to this is that things that share a name *should* in fact work the same way. Otherwise—for example, if your `iter` method takes `self`, or if your `SomethingError` type does not implement `Error`—the user will likely write incorrect code based on how they expect the interface to work. They will be surprised and frustrated and will have to spend time digging into how your interface differs from their expectations. When we can save the user this kind of friction, we should.

## Common Traits for Types

Users in Rust will also make the major assumption that everything in the interface “just works.” They expect to be able to print any type with `{:?}` and send anything and everything to another thread, and they expect that every type is `Clone`. Where possible, we should again avoid surprising the user and eagerly implement most of the standard traits even if we do not need them immediately.

Because of the coherence rules discussed in [Chapter 3](#), the compiler will not allow users to implement these traits when they need them. Users aren’t allowed to implement a foreign trait (like `Clone`) for a foreign type like one from your interface. They would instead need to wrap your interface type in their own type, and even then it may be quite difficult to write a reasonable implementation without access to the type’s internals.

First among these standard traits is the `Debug` trait. Nearly every type can, and should, implement `Debug`, even if it only prints the type’s name. Using `#[derive(Debug)]` is often the best way to implement the `Debug` trait in your interface, but keep in mind that all derived traits automatically add the same bound for any generic parameters. You could also simply write your own implementation by leveraging the various `debug_` helpers on `fmt::Formatter`.

Tied in close second are the Rust auto-traits `Send` and `Sync` (and, to a lesser extent, `Unpin`). If a type does not implement one of these traits, it should be for a very good reason. A type that is not `Send` can’t be placed in a `Mutex` and can’t be used even transitively in an application that contains a thread pool. A type that is not `Sync` can’t be shared through an `Arc` or placed in a static variable. Users have come to expect that types *just work* in these contexts, especially in the asynchronous world where nearly everything runs on a thread pool, and will become frustrated if you don’t ensure that your types implement these traits. If your types cannot implement them, make sure that fact, and the reason why, is well documented!

The next set of nearly universal traits you should implement is `Clone` and `Default`. These traits can be derived or implemented easily and make sense to implement for most types. If your type cannot implement these traits, make sure to call it out in your documentation, as users will usually expect to be able to easily create more (and new) instances of types as they see fit. If they cannot, they will be surprised.

One step further down in the hierarchy of expected traits is the comparison traits: `PartialEq`, `PartialOrd`, `Hash`, `Eq`, and `Ord`. The `PartialEq` trait is particularly desirable, because users will at some point inevitably have two instances of your type that they wish to compare with `==` or `assert_eq!`. Even if your type would compare equal for only the same instance of the type, it’s worth implementing `PartialEq` to enable your users to use `assert_eq!`.

`PartialOrd` and `Hash` are more specialized, and may not apply quite as broadly, but where possible you will want to implement them too. This is especially true for types a user might use as the key in a map, or a type they may deduplicate using any of the `std::collection` set types, since they tend to require these bounds. `Eq` and `Ord` come with additional semantic requirements on the implementing type’s comparison operations beyond those of `PartialEq` and `PartialOrd`. These are well documented in the documentation

for those traits, and you should implement them *only* if you're sure those semantics actually apply to your type.

Finally, for most types, it makes sense to implement the `serde` crate's `Serialize` and `Deserialize` traits. These can be easily derived, and the `serde_derive` crate even comes with mechanisms for overwriting the serialization for just one field or enum variant. Since `serde` is a third-party crate, you may not wish to add a required dependency on it. Most libraries therefore choose to provide a `serde` feature that adds support for `serde` only when the user opts into it.

You might be wondering why I haven't included the derivable trait `Copy` in this section. There are two things that set `Copy` apart from the other traits mentioned. The first is that users do not generally expect types to be `Copy`; quite to the contrary, they tend to expect that if they want two copies of something, they have to call `clone`. `Copy` changes the semantics of moving a value of the given type, which might surprise the user. This ties in to the second observation: it is very easy for a type to *stop* being `Copy`, because `Copy` types are highly restricted. A type that starts out simple can easily end up having to hold a `String`, or some other non-`Copy` type. Should that happen, and you have to remove the `Copy` implementation, that's a backward incompatible change. It is much rarer that you will have to remove a `Clone` implementation, so that's a less onerous promise to make.

## Ergonomic Trait Implementations

Rust does not automatically implement traits for references to types that implement traits. To phrase this a different way, you cannot generally call `fn foo<T: Trait>(t: T)` with a `&Bar`, even if `Bar: Trait`. This is because `Trait` may contain methods that take `&mut self` or `self`, which obviously cannot be called on `&Bar`. Nonetheless, this behavior might be very surprising to a user who sees that `Trait` has only `&self` methods!

For this reason, when you define a new trait, you'll usually want to provide blanket implementations as appropriate for that trait for `&T` where `T: Trait`, `&mut T` where `T: Trait`, and `Box<T>` where `T: Trait`. You may be able to implement only some of these depending on what receivers the methods of `Trait` have. Many of the traits in the standard library have similar implementations, precisely because that leads to fewer surprises for the user.

Iterators are another case where you'll often want to specifically add trait implementations on references to a type. For any type that can be iterated over, consider implementing `IntoIterator` for both `&MyType` and `&mut MyType` where applicable. This makes for loops work with borrowed instances of your type as well out of the box, just like users would expect.

## Wrapper Types

Rust does not have object inheritance in the classical sense. However, the `Deref` trait and its cousin `AsRef` both provide something a little like inheritance. These traits allow you to have a value of type `T` and call methods on some type `U` by calling them directly on the `T`-typed value if `T: Deref<Target = U>`. This feels like magic to the user, and is generally great.

If you provide a relatively transparent wrapper type (like `Arc`), there's a good chance you'll want to implement `Deref` so that users can call methods on the inner type by just using the `.` operator. If accessing the inner type does not require any complex or potentially slow logic, you should also consider implementing `AsRef`, which allows users to easily use a `&WrapperType` as an `&InnerType`. For most wrapper types, you will also want to implement `From<InnerType>` and `Into<InnerType>` where possible so that your users can easily add or remove your wrapping.

You may also have come across the `Borrow` trait, which feels very similar to `Deref` and `AsRef` but is really a bit of a different beast. Specifically, `Borrow` is tailored for a much narrower use case: allowing the caller to supply any one of multiple essentially identical variants of the same type. It could, perhaps, have been called `Equivalent` instead. For example, for a `HashSet<String>`, `Borrow` allows the caller to supply either a `&str` or a `&String`. While the same could have been achieved with `AsRef`, that would not be safe without `Borrow`'s additional requirement that the target type implements `Hash`, `Eq`, and `Ord` exactly the same as the implementing type. `Borrow` also has a blanket implementation of `Borrow<T>` for `T`, `&T`, and `&mut T`, which makes it convenient to use in trait bounds to accept either owned or referenced values of a given type. In general, `Borrow` is intended only for when your type is essentially equivalent to another type, whereas `Deref` and `AsRef` are intended to be implemented more widely for anything your type can “act as.”

### DEREF AND INHERENT METHODS

The magic around the dot operator and `Deref` can get confusing and surprising when there are methods on `T` that take `self`. For example, given a value `t: T`, it is not clear whether `t.frobnicate()` frobnicates the `T` or the underlying `U`!

For this reason, types that allow you to transparently call methods on some inner type that isn't known in advance should avoid inherent methods. It's fine for `Vec` to have a `push` method even though it dereferences to a slice, since you know that slices won't get a `push` method any time soon. But if your type dereferences to a user-controlled type, any inherent method you add may also exist on that user-controlled type, and thus cause issues. In these cases, favor static methods of the form `fn frobnicate(t: T)`. That way, `t.frobnicate()` always calls `U::frobnicate`, and `T::frobnicate(t)` can be used to frobnicate the `T` itself. There are many examples of this pattern in the standard library, with the smart pointer types like `Arc` and `Box` being prime examples: to clone an `Arc`, you use `Arc::clone(&myarc)`, not `myarc.clone()` (which would clone the inner type).

## Flexible

Every piece of code you write includes, implicitly or explicitly, a contract. The contract consists of a set of requirements and a set of promises. The

requirements are restrictions on how the code can be used, while the promises are guarantees about how the code can be used. When designing a new interface, you want to think carefully about this contract. A good rule of thumb is to avoid imposing unnecessary restrictions and to only make promises you can keep. Adding restrictions or removing promises usually requires a major semantic version change and is likely to break code elsewhere. Relaxing restrictions or giving additional promises, on the other hand, is usually backward compatible.

In Rust, restrictions usually come in the form of trait bounds and argument types, and promises come in the form of trait implementations and return types. For example, compare the three function signatures in Listing 4-1.

---

```
fn frobnicate1(s: String) -> String
fn frobnicate2(s: &str) -> Cow<'_, str>
fn frobnicate3(s: impl AsRef<str>) -> impl AsRef<str>
```

---

*Listing 4-1: Similar function signatures with different contracts*

These three function signatures all take a string and return a string, but they do so under very different contracts.

The first function requires the caller to own the string in the form of the `String` type, and it promises that it will return an owned `String`. Since the contract requires the caller to allocate and requires us to return an owned `String`, we cannot later make this function allocation-free in a backward compatible way.

The second function relaxes the contract: the caller can provide any reference to a string, so the user no longer needs to allocate or give up ownership of a `String`. It also promises to give back a `std::borrow::Cow`, meaning it can return either a string reference or an owned `String`, depending on whether it needs to own the string. The promise here is that the function will always return a `Cow`, which means that we cannot, say, change it to use some other optimized string representation later. The caller must also specifically provide a `&str`, so if they have, say, a pre-existing `String` of their own, they must dereference it to a `&str` to call our function.

The third function lifts these restrictions. It requires only that the user pass in a type that can produce a reference to a string, and it promises only that the return value can produce a reference to a string.

None of these function signatures is *better* than the others. If you need ownership of a string in the function, you can use the first argument type to avoid an extra string copy. If you want to allow the caller to take advantage of the case where an owned string was allocated and returned, the second function with a return type of `Cow` may be a good choice. Instead, what I want you to take away from this is that you should think carefully about what contract your interface binds you to, because changing it after the fact can be disruptive.

In the remainder of this section I give examples of interface design decisions that often come up, and their implications for your interface contract.

## Generic Arguments

One obvious requirement your interface must place on users is what types they must provide to your code. If your function explicitly takes a `Foo`, the user must own and give you a `Foo`. There is no way around it. In most cases it pays off to use generics rather than concrete types, to allow the caller to pass any type that conforms to what your function actually needs, rather than only a particular type. Changing `&str` in Listing 4-1 to `impl AsRef<str>` is an example of this kind of relaxing. One way to go about relaxing requirements this way is to start with the argument fully generic with no bounds, and then just follow the compiler errors to discover what bounds you need to add.

However, if taken to the extreme, this approach would make every argument to every function its own generic type, which would be both hard to read and hard to understand. There are no hard-and-fast rules for exactly when you should or should not make a given parameter generic, so use your best judgment. A good rule of thumb is to make an argument generic if you can think of other types a user might reasonably and frequently want to use instead of the concrete type you started with.

You may remember from [Chapter 3](#) that generic code is duplicated for every combination of types ever used with the generic code through monomorphization. With that in mind, the idea of making lots of arguments generic might make you worried about overly enlarging your binaries. In [Chapter 3](#) we also discussed how you can use dynamic dispatch to mitigate this at a (usually) negligible performance cost, and that applies here too. For arguments that you take by reference anyway (recall that `dyn Trait` is not `Sized`, and that you need a fat pointer to use them), you can easily replace your generic argument with one that uses dynamic dispatch. For instance, instead of `impl AsRef<str>`, you could take `&dyn AsRef<str>`.

Before you go running to do that, though, there are a few things you should consider. First, you are making this choice on behalf of your users, who cannot opt out of dynamic dispatch. If you know that the code you're applying dynamic dispatch to will never be performance-sensitive, that may be fine. But if a user comes along who wants to use your library in their high-performance application, dynamic dispatch in a function that is called in a hot loop may be a deal breaker. Second, at the time of writing, using dynamic dispatch will work only when you have a simple trait bound like `T: AsRef<str>` or `impl AsRef<str>`. For more complex bounds, Rust does not know how to construct a dynamic dispatch vtable, so you cannot take, say, `&dyn Hash + Eq`. And finally, remember that with generics, the caller can always choose dynamic dispatch themselves by passing in a trait object. The reverse is not true: if you take a trait object, that is what the caller must provide.

It may be tempting to start your interfaces off with concrete types and then turn them generic over time. This can work, but keep in mind that such changes are not necessarily backward compatible. To see why, imagine that you change a function from `fn foo(v: &Vec<usize>)` to `fn foo(v: impl AsRef<[usize]>)`. While every `&Vec<usize>` implements `AsRef<[usize]>`, type

inference can still cause issues for users. Consider what happens if the caller invokes `foo` with `foo(&iter.collect())`. In the original version, the compiler could determine that it should collect into a `Vec`, but now it just knows that it needs to collect into some type that implements `AsRef<[usize]>`. And there could be multiple such types, so with this change, the caller's code will no longer compile!

## Object Safety

When you define a new trait, whether or not that trait is object-safe (see the end of “Compilation and Dispatch” on [page XX](#) in [Chapter 3](#)) is an unwritten part of the trait's contract. If the trait is object-safe, users can treat different types that implement your trait as a single common type using `dyn Trait`. If it isn't, the compiler will disallow `dyn Trait` for that trait. You should prefer your traits to be object-safe even if that comes at a slight cost to the ergonomics of using them (such as taking `impl AsRef<str> over &str`), since object safety enables new ways to use your traits. If your trait must have a generic method, consider whether its generic parameters can be on the trait itself or if its generic arguments can also use dynamic dispatch to preserve the object safety of the trait. Alternatively, you can add a `where Self: Sized` trait bound to that method, which makes it possible to call the method only with a concrete instance of the trait (and not through `dyn Trait`). You can see examples of this pattern in the `Iterator` and `Read` traits, which are object-safe but provide some additional convenience methods on concrete instances.

There is no single answer to the question of how many sacrifices you should be willing to make to preserve object safety. My recommendation is that you consider how your trait will be used, and whether it makes sense for users to want to use it as a trait object. If you think it's likely that users will want to use many different instances of your trait together, you should work harder to provide object safety than if you don't think that use case makes much sense. For example, dynamic dispatch would not be useful for the `FromIterator` trait because its one method does not take `self`, so you wouldn't be able to construct a trait object in the first place. Similarly, `std::io::Seek` is fairly useless as a trait object on its own, because the only thing you would be able to do with such a trait object is `seek`, without being able to read or write.

### DROP TRAIT OBJECTS

You might think that the `Drop` trait is also useless as a trait object, since all you can do with `Drop` as a trait object is to drop it. But it turns out there are some libraries that specifically just want to be able to drop arbitrary types. For example, a library that offers deferred dropping of values, such as for concurrent garbage collection or just deferred cleanup, cares only that the values can



be dropped, and nothing else. Interestingly enough, the story of Drop doesn't end there; since Rust needs to be able to drop trait objects too, every vtable contains the drop method. Effectively, every dyn Trait is also a dyn Drop.

Remember that object safety is a part of your public interface! If you modify a trait in an otherwise backward compatible way, such as by adding a method with a default implementation, but it makes the trait not object-safe, you need to bump your major semantic version number.

### ***Borrowed vs. Owned***

For nearly every function, trait, and type you define in Rust, you must decide whether it should own, or just hold a reference to, its data. Whatever decision you make will have far-reaching implications for the ergonomics and performance of your interface. Luckily, these decisions very often make themselves.

If the code you write needs ownership of the data, such as to call methods that take `self` or to move the data to another thread, it must store the owned data. When your code must own data, it should generally also make the caller provide owned data, rather than taking values by reference and cloning them. This leaves the caller in control of allocation, and it is upfront about the cost of using the interface in question.

On the other hand, if your code doesn't need to own the data, it should operate on references instead. One common exception to this rule is with small types like `i32`, `bool`, or `f64`, which are just as cheap to store and copy directly as to store through references. Be wary of assuming this holds true for all Copy types, though; `[u8; 8192]` is Copy, but it would be expensive to store and copy it all over the place.

Of course, in the real world, things are often less clear-cut. Sometimes, you don't know in advance whether your code will need to own the data or not. For example, `String::from_utf8_lossy` needs to take ownership of the byte sequence that is passed to it only if it contains invalid UTF-8 sequences. In this case, the `Cow` type is your friend: it lets you operate on references if the data allows, and it lets you produce an owned value if necessary.

Other times, reference lifetimes complicate the interface so much that it becomes a pain to use. If your users are struggling to get code to compile on top of your interface, that's a sign that you may want to (even unnecessarily) take ownership of certain pieces of data. If you do this, start with data that is cheap to clone or is not

part of anything performance-sensitive before you decide to heap-allocate what might be a huge chunk of bytes.

## Fallible and Blocking Destructors

Types centered on I/O often need to perform cleanup when they're dropped. This may include flushing writes to disk, closing files, or gracefully terminating connections to remote hosts. The natural place to perform this cleanup is in the type's `Drop` implementation. Unfortunately, once a value is dropped, we no longer have a way to communicate errors to the user except by panicking. A similar problem arises in asynchronous code, where we wish to finish up when there is work pending. By the time `drop` is called, the executor may be shutting down, and we have no way to do more work. We could try to start another executor, but that comes with its own host of problems, such as blocking in asynchronous code, as we will see in [Chapter 9](#).

There is no perfect solution to these problems, and no matter what we do, some applications will inevitably fall back to our `Drop` implementation. For that reason, we need to provide best-effort cleanup through `Drop`. If cleanup errors, at least we tried—we swallow the error and move on. If an executor is still available, we might spawn a future to do cleanup, but if it never gets to run, we did what we could.

However, we ought to provide a better alternative for users who wish to leave no loose threads. We can do this by providing an explicit destructor. This usually takes the form of a method that takes ownership of `self` and exposes any errors (using `-> Result<_, _>`) or asynchrony (using `async fn`) that are inherent to the destruction. A careful user can then use that method to gracefully tear down any associated resources.

### NOTE

*Make sure you highlight the explicit destructor in your documentation!*

As always, there's a trade-off. The moment you add an explicit destructor, you will run into two issues. First, since your type implements `Drop`, you can no longer move out of any of that type's fields in the destructor. This is because `Drop::drop` will still be called after your explicit destructor runs, and it takes `&mut self`, which requires that no part of `self` has been moved. Second, `drop` takes `&mut self`, not `self`, so your `Drop` implementation cannot simply call your explicit destructor and ignore its result (because it doesn't own `self`). There are a couple of ways around these problems, none of which are perfect.

The first is to make your top-level type a newtype wrapper around an `Option`, which in turn holds some inner type that holds all of the type's fields. You can then use `Option::take` in both destructors, and call the inner type's explicit destructor only if the inner type has not already been taken. Since the inner type does not implement `Drop`, you can take ownership of all the fields there. The downside of this approach is that all the methods you wish to provide on the top-level type must now include code to get through the `Option` (which you know is always `Some` since `drop` has not yet been called) to the fields on the inner type.

The second workaround is to make each of your fields *takeable*. You can “take” an `Option` by replacing it with `None` (which is what `Option::take` does), but you can do this with many other types as well. For example, you can take a `Vec` or `HashMap` by simply replacing them with their cheap-to-construct default values—`std::mem::take` is your friend here. This approach works great if your types have sane “empty” values but gets tedious if you must wrap nearly every field in an `Option` and then modify every access of those fields with a matching `unwrap`.

The third option is to hold the data inside the `ManuallyDrop` type, which dereferences to the inner type, so there’s no need for `unwraps`. You can also use `ManuallyDrop::take` in `drop` to take ownership at destruction time. The primary downside of this approach is that `ManuallyDrop::take` is unsafe. There are no safety mechanisms in place to ensure that you don’t try to use the value inside the `ManuallyDrop` after you’ve called `take` or that you don’t call `take` multiple times. If you do, your program will silently exhibit undefined behavior, and bad things will happen.

Ultimately, you should choose whichever of these approaches fits your application best. I would err on the side of going with the second option, and switching to the others only if you find yourself in a sea of `Options`. The `ManuallyDrop` solution is excellent if the code is simple enough that you can easily check the safety of your code, and you are confident in your ability to do so.

## Obvious

While some users may be familiar with aspects of the implementation that underpins your interface, they are unlikely to understand all of its rules and limitations. They won’t know that it’s never okay to call `foo` after calling `bar`, or that it’s only safe to call the unsafe method `baz` when the moon is at a 47-degree angle and no one has sneezed in the past 18 seconds. Only if the interface makes it clear that something strange is going on will they reach for the documentation or carefully read type signatures. It’s therefore critical for you to make it as easy as possible for users to understand your interface and as hard as possible for them to use it incorrectly. The two primary techniques at your disposal for this are your documentation and the type system, so let’s look at each of those in turn.

### NOTE

*You can also take advantage of naming to suggest to the user when there’s more to an interface than meets the eye. If a user sees a method named `dangerous`, chances are they will read its documentation.*

## Documentation

The first step to making your interfaces transparent is to write good documentation. I could write an entire book dedicated to how to write documentation, but let’s focus on Rust-specific advice here.

First, clearly document any cases where your code may do something unexpected, or where it relies on the user doing something beyond what’s dictated by the type signature. Panics are a good example of both of

these circumstances: if your code can panic, document that fact, along with the circumstances it might panic under. Similarly, if your code might return an error, document the cases in which it does. For unsafe functions, document what the caller must guarantee in order for the call to be safe.

Second, include end-to-end usage examples for your code on a crate and module level. These are more important than examples for specific types or methods, since they give the user a feel for how everything fits together. With a decent high-level understanding of the interface's structure, the developer may soon realize what particular methods and types do and where they should be used. End-to-end examples also give the user a starting point for customizing their usage, and they can, and often will, copy-paste the example and then modify it to suit their needs. This kind of "learning by doing" tends to work better than having them try to piece something together from the components.

#### NOTE

*Very method-specific examples that show that, yes, the `len` method indeed returns the length are unlikely to tell the user anything new about your code.*

Third, organize your documentation. Having all your types, traits, and functions in a single top-level module makes it difficult for the user to get a sense of where to start. Take advantage of modules to group together semantically related items. Then, use intra-documentation links to interlink items. If the documentation on type A talks about trait B, then it should link to that trait right there. If you make it easy for the user to explore your interface, they are less likely to miss important connections or dependencies. Also consider marking parts of your interface that are not intended to be public but are needed for legacy reasons with `#[doc(hidden)]`, so that they do not clutter up your documentation.

And finally, enrich your documentation wherever possible. Link to external resources that explain concepts, data structures, algorithms, or other aspects of your interface that may have good explanations elsewhere. RFCs, blog posts, and whitepapers are great for this, if any are relevant. Use `#[doc(cfg(...))]` to highlight items that are available only under certain configurations so the user quickly realizes why some method that's listed in the documentation isn't available. Use `#[doc(alias = "...")]` to make types and methods discoverable under other names that users may search for them by. In the top-level documentation, point the user to commonly used modules, features, types, traits, and methods.

## Type System Guidance

The type system is an excellent tool to ensure that your interfaces are obvious, self-documenting, and misuse-resistant. You have several techniques at your disposal that can make your interfaces very hard to misuse, and thus, make it more likely that they will be used correctly.

The first of these is *semantic typing*, in which you add types to represent the *meaning* of a value, not just its primitive type. The classic example here is for Booleans: if your function takes three `bool` arguments, chances

are some user will mess up the order of the values and realize it only after something has gone terribly wrong. If, on the other hand, it takes three arguments of distinct two-variant enum types, the user cannot get the order wrong without the compiler yelling at them: if they attempt to pass `DryRun::Yes` to the `overwrite` argument, that will simply not work, nor will passing `Overwrite::No` as the `dry_run` argument. You can apply semantic typing beyond Booleans as well. For example, a newtype around a numeric type may provide a unit for the contained value, or it could constrain raw pointer arguments to only those that have been returned by another method.

A closely related technique is to use zero-sized types to indicate that a particular fact is true about an instance of a type. Consider, for instance, a type called `Rocket` that represents the state of a real rocket. Some operations (methods) on `Rocket` should be available no matter what state the rocket is in, but some make sense only in particular situations. It is, for example, impossible to launch a rocket if it has already been launched. Similarly, it should probably not be possible to separate the fuel tank if the rocket has not yet launched. We could model these as enum variants, but then all the methods would be available at every stage, and we'd need to introduce possible panics.

Instead, as shown in Listing 4-2, we can introduce a generic parameter on `Rocket`, `Stage`, and use it to restrict what methods are available when.

---

```

❶ struct Grounded;
   struct Launched;
   // and so on
   struct Rocket<Stage = Grounded> {
❷   stage: std::marker::PhantomData<Stage>,
   }

❸ impl Default for Rocket<Grounded> {}
   impl Rocket<Grounded> {
       pub fn launch(self) -> Rocket<Launched> { }
   }
❹ impl Rocket<Launched> {
       pub fn accelerate(&mut self) { }
       pub fn decelerate(&mut self) { }
   }

❺ impl<Stage> Rocket<Stage> {
       pub fn color(&self) -> Color { }
       pub fn weight(&self) -> Kilograms { }
   }

```

---

*Listing 4-2: Using marker types to restrict implementations*

We introduce unit types to represent each stage the rocket can be in

- ❶. We don't actually need to store the stage—only the meta-information it provides—so we store it behind a `PhantomData`
- ❷ to guarantee that it is eliminated at compile time. Then, we write implementation blocks for `Rocket` only when it holds a particular type parameter. You can construct a rocket only

on the ground (for now), and you can launch it only from the ground ❸. Only when the rocket has been launched can you control its velocity ❹. There are some things you can always do with the rocket, no matter what state it is in, and those we place in a generic implementation block ❺. You'll notice that with the interface designed this way, it's simply not possible for the user to call a method at the wrong time—we have encoded the usage rules in the types themselves, and made illegal states *unrepresentable*.

This notion extends to many other domains as well; if your function ignores a pointer argument unless a given Boolean argument is true, it's better to combine the two arguments instead. With an enum type with one variant for false (and no pointer) and one variant for true that holds a pointer, neither the caller nor the implementer can misunderstand the relationship between the two. This is a powerful idea that I highly encourage you to make use of.

Another small but useful tool in making interfaces obvious is the `#[must_use]` annotation. Add it to any type, trait, or function, and the compiler will issue a warning if the user's code receives an element of that type or trait, or calls that function, and does not explicitly handle it. You may already have seen this in the context of `Result`: if a function returns a `Result` and you do not assign its return value somewhere, you get a compiler warning. Be careful not to overuse this annotation, though—add it only if the user is very likely to make a mistake if they are not using the return value.

## Constrained

Over time, some user will depend on every property of your interface, whether bug or feature. This is especially true for publicly available libraries where you have no control over your users. As a result, you should think carefully before you make user-visible changes. Whether you're adding a new type, field, method, or trait implementation or changing an existing one, you want to make sure that the change will not break existing users' code, and that you are planning to keep that change around for a while. Frequent backward incompatible changes (major version increases in semantic versioning) are sure to draw the ire of your users.

Many backward incompatible changes are obvious, like renaming a public type or removing a public method, but some are subtler and tie in deeply with the way Rust works. Here, we'll cover some of the thornier subtle changes and how to plan for them. You'll see that you need to balance some of these against how flexible you want your interface to be—sometimes, something's got to give.

### **Type Modifications**

Removing or renaming a public type will almost certainly break some user's code. To counter this, you'll want to take advantage of Rust's visibility modifiers, like `pub(crate)` and `pub(in path)`, whenever possible. The fewer public types you have, the more freedom you have to change things later without breaking existing code.

User code can depend on your types in more ways than just by name, though. Consider the public type in Listing 4-3 and the given use of that code.

---

```
// in your interface
pub struct Unit;
// in user code
let u = lib::Unit;
```

---

*Listing 4-3: An innocent-looking public type*

Now consider what happens if you add a private field to `Unit`. Even though the field you add is private, the change will still break the user’s code, because the constructor they relied on has disappeared. Similarly, consider the code and use in Listing 4-4.

---

```
// in your interface
pub struct Unit { pub field: bool };
// in user code
fn is_true(u: lib::Unit) -> bool {
    matches!(u, Unit { field: true })
}
```

---

*Listing 4-4: User code accessing a single public field*

Here, too, adding a private field to `Unit` will break user code, this time because Rust’s exhaustive pattern match checking logic is able to see parts of the interface that the user cannot see. It recognizes that there are more fields, even though the user code cannot access them, and rejects the user’s pattern as incomplete. A similar issue arises if we turn a tuple struct into a regular struct with named fields: even if the fields themselves are exactly the same, any old patterns will no longer be valid for the new type definition.

Rust provides the `#[non_exhaustive]` attribute to help mitigate these issues. You can add it to any type definition, and the compiler will disallow the use of implicit constructors (like `lib::Unit { field1: true }`) and non-exhaustive pattern matches (that is, patterns without a trailing `, ..`) on that type. This is a great attribute to add if you suspect that you’re likely to modify a particular type in the future. It does constrain user code though, such as by taking away users’ ability to rely on exhaustive pattern matches, so avoid adding it if you think a given type is likely to remain stable.

## ***Trait Implementations***

As you’ll recall from [Chapter 3](#), Rust’s coherence rules disallow multiple implementations of a given trait for a given type. Since we do not know what implementations downstream code may have added, adding a blanket implementation of an existing trait is generally a breaking change. The same holds true for implementing a foreign trait for an existing type, or an existing trait for a foreign type—in both cases, the owner of the foreign

trait or type may simultaneously add a conflicting implementation, so this must be a breaking change.

Removing a trait implementation is a breaking change, but implementing traits for a *new* type is never a problem, since no crate can have implementations that conflict with that type.

Perhaps counterintuitively, you also want to be careful about implementing *any* trait for an existing type. To see why, consider the code in Listing 4-5.

---

```
// crate1 1.0
pub struct Unit;
pub trait Foo1 { fn foo(&self) }
// note that Foo1 is not implemented for Unit

// crate2; depends on crate1 1.0
use crate1::{Unit, Foo1};
trait Foo2 { fn foo(&self) }
impl Foo2 for Unit { .. }
fn main() {
    Unit.foo();
}
```

---

*Listing 4-5: Implementing a trait for an existing type may cause problems.*

If you add `impl Foo1 for Unit` to `crate1` without marking it a breaking change, the downstream code will suddenly stop compiling since the call to `foo` is now ambiguous. This can even apply to implementations of *new* public traits, if the downstream crate uses wildcard imports (`use crate1::*`). You will particularly want to keep this in mind if you provide a `prelude` module that you instruct users to use wildcard imports for.

Most changes to existing traits are also breaking changes, such as changing a method signature or adding a new method. Changing a method signature breaks all implementations, and probably many uses, of the trait, whereas adding a new method “just” breaks all implementations. Adding a new method with a default implementation is fine though, since existing implementations will continue to apply.

I say “generally” and “most” here, because as interface authors, we have a tool available to us that lets us skirt some of these rules: *sealed traits*. A sealed trait is one that can be used only, and not implemented, by other crates. This immediately makes a number of breaking changes non-breaking. For example, you can add a new method to a sealed trait, since you know there are no implementations outside of the current crate to consider. Similarly, you can implement a sealed trait for new foreign types, since you know the foreign crate that defined that type cannot have added a conflicting implementation.

Sealed traits are most commonly used for *derived* traits—traits that provide blanket implementations for types that implement particular other traits. You should seal a trait only if it does not make sense for a foreign



crate to implement your trait; it severely restricts the usefulness of the trait, since downstream crates will no longer be able to implement it for their own types.

Listing 4-6 shows how to seal a trait and how to then still add implementations for it in the defining crate.

---

```
pub trait CanUseCannotImplement: sealed::Sealed ❶ { .. }
mod sealed {
    pub trait Sealed {}
    ❷ impl<T> Sealed for T where T: TraitBounds {}
}
impl<T> CanUseCannotImplement for T where T: TraitBounds {}
```

---

*Listing 4-6: How to seal a trait and add implementations for it*

The trick is to add a private, empty trait as a supertrait of the trait you wish to seal ❶. Since the supertrait is in a private module, other crates cannot reach it and thus cannot implement it. The sealed trait requires the underlying type to implement `Sealed`, so only the types that we explicitly allow ❷ are able to ultimately implement the trait.

#### NOTE

*If you do seal a trait this way, make sure you document that fact so that users do not get frustrated trying to implement the trait themselves!*

## Hidden Contracts

Sometimes, changes you make to one part of your code affect the contract elsewhere in your interface in subtle ways. The two primary ways this happens are through re-exports and auto-traits.

### Re-Exports

If any part of your interface exposes foreign types, then any change to one of those foreign types is *also* a change to your interface. For example, consider what happens if you move to a new major version of a dependency and expose a type from that dependency as, say, an iterator type in your interface. A user that depends on your interface may also depend directly on that dependency and expect that the type your interface provides is the same as the one by the same name in that dependency. But if you change the major version of your dependency, that is no longer true even though the *name* of the type is the same. Listing 4-7 shows an example of this.

---

```
// your crate: bestiter
pub fn iter<T>() -> itercrate::Empty<T> { .. }
// their crate
struct EmptyIterator { it: itercrate::Empty<>() }
EmptyIterator { it: bestiter::iter() }
```

---

*Listing 4-7: Re-exports make foreign crates part of your interface contract.*

If your crate moves from `itercrate 1.0` to `itercrate 2.0` but otherwise does not change, the code in this listing will no longer compile. Even though no types have changed, the compiler believes (correctly) that `itercrate1.0::Empty` and `itercrate2.0::Empty` are *different* types. Therefore, you cannot assign the latter to the former, making this a breaking change in your interface.

To mitigate issues like this, it's often best to wrap foreign types using the `newtype` pattern, and then expose only the parts of the foreign type that you think are useful. In many cases, you can avoid the `newtype` wrapper altogether by using `impl Trait` to provide only the very minimal contract to the caller. By promising less, you make fewer changes breaking.

### THE SEMVER TRICK

The `itercrate` example may have rubbed you the wrong way. If the `Empty` type did not change, then why does the compiler not allow anything that uses it to keep working, regardless of whether the code is using version 1.0 or 2.0 of it? The answer is . . . complicated. It boils down to the fact that the Rust compiler does not assume that just because two types have the same fields, they are the same. To take a simple example of this, imagine that `itercrate 2.0` added a `#[derive(Copy)]` for `Empty`. Now, the type suddenly has different move semantics depending on whether you are using 1.0 or 2.0! And code written with one in mind won't work with the other.

This problem tends to crop up in large, widely used libraries, where over time, breaking changes are likely to have to happen *somewhere* in the crate. Unfortunately, semantic versioning happens at the crate level, not the type level, so a breaking change anywhere is a breaking change everywhere.

But all is not lost. A few years ago, David Tolnay (the author of `serde`, among a vast number of other Rust contributions) came up with a neat trick to handle exactly this kind of situation. He called it “the semver trick.” The idea is simple: if some type `T` stays the same across a breaking change (from 1.0 to 2.0, say), then after releasing 2.0, you can release a new 1.0 *minor* version that depends on 2.0 and replaces `T` with a re-export of `T` from 2.0.

By doing this, you're ensuring that there is in fact only a single type `T` across both major versions. This, in turn, means that any crate that depends on 1.0 will be able to use a `T` from 2.0, and vice versa. And because this happens only for types you *explicitly* opt into with this trick, changes that were in fact breaking will continue to be.

### Auto-Traits

Rust has a handful of traits that are automatically implemented for every type depending on what that type contains. The most relevant of these for this discussion are `Send` and `Sync`, though the `Unpin`, `Sized`, and `UnwindSafe`

traits have similar issues. By their very nature, these add a hidden promise made by nearly every type in your interface. These traits even propagate through otherwise type-erased types like `impl Trait`.

Implementations for these traits are (generally) automatically added by the compiler, but that also means that they are *not* automatically added if they no longer apply. So, if you have a public type `A` that contains a private type `B`, and you change `B` so that it is no longer `Send`, then `A` is now *also* not `Send`. That is a breaking change!

These changes can be hard to keep track of and are often not discovered until a user of your interface complains that their code no longer works. To catch these cases before they happen, it's good practice to include some simple tests in your test suite that check that all your types implement these traits the way you expect. Listing 4-8 gives an example of what such a test might look like.

---

```
fn is_normal<T: Sized + Send + Sync + Unpin>() {}
#[test]
fn normal_types() {
    is_normal::<MyType>();
}
```

---

*Listing 4-8: Testing that a type implements a set of traits*

Notice that this test does not run any code, but simply tests that the code compiles. If `MyType` no longer implements `Sync`, the test code will not compile, and you will know that the change you just made broke the auto-trait implementation.

### HIDING ITEMS FROM DOCUMENTATION

The `#[doc(hidden)]` attribute lets you hide a public item from your documentation without making it inaccessible to code that happens to know it is there. This is often used to expose methods and types that are needed by macros, but not by user code. How such hidden items interact with your interface contract is a matter of some debate. In general, items marked as `#[doc(hidden)]` are only considered part of your contract insofar as their public effects; for example, if user code may end up containing a hidden type, then whether that type is `Send` or not is part of the contract, whereas its name is not. Hidden inherent methods and hidden trait methods on sealed traits are not generally part of your interface contract, though you should make sure to state this clearly in the documentation for those methods. And yes, hidden items should still be documented!

## Summary

In this chapter we've explored the many facets of designing a Rust interface, whether it's intended for external use or just as an abstraction boundary between the different modules within your crate. We covered a lot of specific pitfalls and tricks, but ultimately, the high-level principles are what should guide your thinking: your interfaces should be unsurprising, flexible, obvious, and constrained. In the next chapter, we will dig into how to represent and handle errors in Rust code.

# 5

## ERROR HANDLING



For all but the simplest programs, you will have methods that can fail. In this chapter, we'll look at different ways to represent, handle, and propagate those failures and the advantages and drawbacks of each. We'll start by exploring different ways to represent errors, including enumeration and erasure, and then examine some special error cases that require a different representation technique. Next, we'll look at various ways of handling errors and the future of error handling.

It's worth noting that best practices for error handling in Rust are still an active topic of conversation, and at the time of writing, the ecosystem has not yet settled on a single, unified approach. This chapter will therefore focus on the underlying principles and techniques rather than recommending specific crates or patterns.

## Representing Errors

When you write code that can fail, the most important question to ask yourself is how your users will interact with any errors returned. Will users need to know exactly which error happened and the minutiae about what went wrong, or will they simply log that an error occurred and move on as best they can? To understand this, we have to look at whether the nature of the error is likely to affect what the caller does in response to its occurrence. This in turn will dictate how we represent different errors.

You have two main options for representing errors: enumeration and erasure. That is, you can either have your error type *enumerate* the possible error conditions so that the caller can distinguish them, or you can just provide the caller with a single, *opaque* error. Let's discuss these two options in turn.

### Enumeration

For our example, we'll use a library function that copies bytes from some input stream into some output stream, much like `std::io::copy`. The user provides you with two streams, one to read from and one to write to, and you copy the bytes from one to the other. During this process, it's entirely possible for either stream to fail, at which point the copy has to stop and return an error to the user. Here, the user will likely want to know whether it was the input stream or the output stream that failed. For example, in a web server, if an error occurs on the input stream while streaming a file to a client, it might be because a disk was ejected, whereas if the output stream errors, maybe the client just disconnected. The latter may be an error the server should ignore, since copies to new connections can still complete, whereas the former may require that the whole server be shut down!

This is a case where we want to enumerate the errors. The user needs to be able to distinguish between the different error cases so that they can respond appropriately, so we use an `enum` named `CopyError`, with each variant representing a separate underlying cause for the error, like in Listing 5-1.

---

```
pub enum CopyError {
    In(std::io::Error),
    Out(std::io::Error),
}
```

---

*Listing 5-1: An enumerated error type*

Each variant also includes the error that was encountered to provide the caller with as much information about what went wrong as possible.

When making your own error type, you need to take a number of steps to make the error type play nicely with the rest of the Rust ecosystem. First, your error type should implement the `std::error::Error` trait, which provides callers with common methods for introspecting error types. The main method of interest is `Error::source`, which provides a mechanism to find the underlying cause of an error. This is most commonly used to print a backtrace that displays a trace all the way back to the error's root cause. For our `CopyError` type,

the implementation of `source` is straightforward: we match on `self` and extract and return the inner `std::io::Error`.

Second, your type should implement both `Display` and `Debug` so that callers can meaningfully print your error. This is required if you implement the `Error` trait. In general, your implementation of `Display` should give a one-line description of what went wrong that can easily be folded into other error messages. The display format should be lowercase and without trailing punctuation so that it fits nicely into other, larger error reports. `Debug` should provide a more descriptive error including auxiliary information that may be useful in tracking down the cause of the error, such as port numbers, request identifiers, source code location, and the like.

#### NOTE

*In older Rust code, you may see references to the `Error::description` method, but this has been deprecated in favor of `Display`.*

Third, your type should, if possible, implement both `Send` and `Sync` so that users are able to share the error across thread boundaries. If your error type is not thread-safe, you will find that it's almost impossible to use your crate in a multithreaded context. Error types that implement `Send` and `Sync` are also much easier to use with the very common `std::io::Error` type, which is able to wrap errors that implement `Error`, `Send`, and `Sync`. Of course, not all error types can reasonably be `Send` and `Sync`, such as if they're tied to particular thread-local resources, and that's okay. You're probably not sending those errors across thread boundaries either. However, it's something to be aware of before you go placing `Rc<String>` and `RefCell<bool>` types in your errors.

Finally, where possible, your error type should be `'static`. The most immediate benefit of this is that it allows the caller to more easily propagate your error up the call stack without running into lifetime issues. It also enables your error type to be used more easily with type-erased error types, as we'll see shortly.

## Opaque Errors

Now let's consider a different example: an image decoding library. You give the library a bunch of bytes to decode, and it gives you access to various image manipulation methods. If the decoding fails, the user needs to be able to figure out how to resolve the issue, and so must understand the cause. But is it important whether the cause is the size field in the image header being invalid, or the compression algorithm failing to decompress a block? Probably not—the application can't meaningfully recover from either situation, even if it knows the exact cause. In cases like this, you as the library author may instead want to provide a single, opaque error type. This also makes your library a little nicer to use, because there is only one error type in use everywhere. This error type should implement `Send`, `Debug`, and `Display`, and should probably also implement `Error`, but beyond that, the caller doesn't need to know anything more. You might internally represent more fine-grained error states, but there is no need to expose those to the users of the library. Doing so would only serve to unnecessarily increase the size and complexity of your API.

Exactly what your opaque error type should be is mostly up to you. It could just be a type with all private fields that exposes only limited methods for displaying and introspecting the error, or it could be a severely type-erased error type like `Box<dyn Error + Send + Sync + 'static>`, which reveals nothing more than the fact that it is an error and does not generally let your users introspect at all. Deciding how far to go down the route of type erasure is mostly a matter of whether there is anything interesting about the error beyond its description. With `Box<dyn Error>`, you leave your users with little option but to bubble up your error. That might be fine if it truly has no information of value to present to the user—for example, if it’s just a dynamic error message or is one of a large number of unrelated errors from deeper inside your program. But if the error has some interesting facets to it, such as a line number or a status code, you may want to expose that through a concrete but opaque type instead.

#### NOTE

*In general, the community consensus is that errors should be rare and therefore should not add much cost to the “happy path.” For that reason, errors are often placed behind a pointer type, such as a `Box` or `Arc`. This way, they’re unlikely to add much to the size of the overall `Result` type they’re contained within.*

One benefit of using type-erased errors is that it allows you to easily combine errors from different sources without having to introduce additional error types. That is, type-erased errors often *compose* nicely. If you write a function whose return type is `Box<dyn Error + ...>`, then you can use `?` almost indiscriminately inside that function, on all sorts of different errors, and they will all be turned into that one common error type.

The `'static` bound on `Box<dyn Error + Send + Sync + 'static>` is worth spending a bit more time on in the context of erasure. I mentioned in the previous section that it’s useful for letting the caller propagate the error without worrying about the lifetime bounds of the method that failed, but it serves an even bigger purpose: access to downcasting. *Downcasting* is the process of taking an item of one type and casting it to a more specific type. This is one of the few cases where Rust gives you access to type information at runtime; it’s a limited case of the more general type reflection that dynamic languages often provide. In the context of errors, downcasting allows a user to turn a `dyn Error` into a concrete underlying error type when that `dyn Error` was originally of that type. For example, the user may want to take a particular action if the error they received was a `std::io::Error` of kind `std::io::ErrorKind::WouldBlock`, but they would not take that same action in any other case. If the user gets a `dyn Error`, they can use `Error::downcast_ref` to try to downcast the error into a `std::io::Error`. The `downcast_ref` method returns an `Option`, which tells the user whether or not the downcast succeeded. And here is the key observation: `downcast_ref` works only if the argument is `'static`. If we return an opaque `Error` that’s not `'static`, we take away the user’s ability to do this kind of error introspection should they wish.

There’s some disagreement in the ecosystem about whether a library’s type-erased errors (or more generally, its type-erased types) are part of



its public and stable API. That is, if the method `foo` in your library returns `lib::MyError` as a `Box<dyn Error>`, would changing `foo` to return a different error type be a breaking change? The type signature hasn't changed, but users may have written code that assumes that they can use `downcast` to turn that error back into `lib::MyError`. My opinion on this matter is that you chose to return `Box<dyn Error>` (and not `lib::MyError`) for a reason, and unless explicitly documented, that does not guarantee anything in particular about downcasting.

You may wonder how `Error::downcast_ref` can be safe. That is, how does it know whether a provided `dyn Error` argument is indeed of the given type `T`? The standard library even has a trait called `Any` that is implemented for *any* type, and which implements `downcast_ref` for `dyn Any`—how can that be okay? The answer lies in the compiler-supported type `std::any::TypeId`, which allows you to get a unique identifier for any type. The `Error` trait has a hidden provided method called `type_id`, whose default implementation is to return `TypeId::of::<Self>()`. Similarly, `Any` has a blanket implementation of `impl Any for T`, and in that implementation, its `type_id` returns the same. In the context of these `impl` blocks, the concrete type of `Self` is known, so this `type_id` is the type identifier of the real type. That provides all the information `downcast_ref` needs. `downcast_ref` calls `self.type_id`, which forwards through the vtable for dynamically sized types (see [Chapter 3](#)) to the implementation for the underlying type and compares that to the type identifier of the provided `downcast` type. If they match, then the type behind the `dyn Error` or `dyn Any` really is `T`, and it is safe to cast from a reference to one to a reference to the other.

## Special Error Cases

Some functions are fallible but cannot return any meaningful error if they fail. Conceptually, these functions have a return type of `Result<T, ()>`. In some codebases, you may see this represented as `Option<T>` instead. While both are legitimate choices for the return type for such a function, they convey different semantic meanings, and you should usually avoid “simplifying” a `Result<T, ()>` to `Option<T>`. An `Err()` indicates that an operation failed and should be retried, reported, or otherwise handled exceptionally. `None`, on the other hand, conveys only that the function has nothing to return; it is usually not considered an exceptional case or something that should be handled. You can see this in the `#[must_use]` annotation on the `Result` type—when you get a `Result`, the language expects that it is important to handle both cases, whereas with an `Option`, neither case actually needs to be handled.

### NOTE

*You should also keep in mind that `()` does not implement the `Error` trait. This means that it cannot be type-erased into `Box<dyn Error>` and can be a bit of a pain to use with `?`. For this reason, it is often better to define your own unit struct type, implement `Error` for it, and use that as the error instead of `()` in these cases.*

Some functions, like those that start a continuously running server loop, only ever return errors; unless an error occurs, they run forever. Other functions never error but need to return a `Result` nonetheless, for example, to match a trait signature. For functions like these, Rust provides the *never type*, written with the `!` syntax. The never type represents a value that can never be generated. You cannot construct an instance of this type yourself—the only way to make one is by entering an infinite loop or panicking, or through a handful of other special operations that the compiler knows never return. With `Result`, when you have an `Ok` or `Err` that you know will never be used, you can set it to the `!` type. If you write a function that returns `Result<T, !>`, you will be unable to ever return `Err`, since the only way to do so is to enter code that will never return. Because the compiler knows that any variant with a `!` will never be produced, it can also optimize your code with that in mind, such as by not generating the panic code for an `unwrap` on `Result<T, !>`. And when you pattern match, the compiler knows that any variant that contains a `!` does not even need to be listed. Pretty neat!

One last curious error case is the error type `std::thread::Result`. Here's its definition:

---

```
type Result<T> = Result<T, Box<dyn Any + Send + 'static>>;
```

---

The error type is type-erased, but it's not erased into a `dyn Error` as we've seen so far. Instead, it is a `dyn Any`, which guarantees only that the error is *some* type, and nothing more . . . which is not much of a guarantee at all. The reason for this curious-looking error type is that the error variant of `std::thread::Result` is produced only in response to a panic; specifically, if you try to join a thread that has panicked. In that case, it's not clear that there's much the joining thread can do other than either ignore the error or panic itself using `unwrap`. In essence, the error type is “a panic” and the value is “whatever argument was passed to `panic!`,” which can truly be any type (even though it's usually a formatted string).

## Handling Errors

Rust's `?` operator acts as a shorthand for *unwrap or return early*, for working easily with errors. But it also has a few other tricks up its sleeve that are worth knowing about. First, `?` performs type conversion through the `From` trait. In a function that returns `Result<T, E>`, you can use `?` on any `Result<T, X>` where `E: From<X>`. This is the feature that makes error erasure through `Box<dyn Error>` so appealing; you can just use `?` everywhere and not worry about the particular error type, and it will usually “just work.”

### FROM AND INTO

The standard library has many conversion traits, but two of the core ones are `From` and `Into`. It might strike you as odd to have two: if we have `From`, why

do we need `Into`, and vice versa? There are a couple of reasons, but let's start with the historical one: it wouldn't have been possible to have just one in the early days of Rust due to the coherence rules discussed in [Chapter 3](#). Or, more specifically, what the coherence rules used to be.

Suppose you want to implement two-way conversion between some local type you have defined in your crate and some type in the standard library. You can write `impl<T> From<Vec<T>> for MyType<T>` and `impl<T> Into<Vec<T>> for MyType<T>` easily enough, but if you only had `From` or `Into`, you would have to write `impl<T> From<MyType<T>> for Vec<T>` or `impl<T> Into<MyType<T>> for Vec<T>`. However, the compiler used to reject those implementations! Only since Rust 1.41.0, when the exception for covered types was added to the coherence rules, are they legal. Before that change, it was necessary to have both traits. And since much Rust code was written before Rust 1.41.0, neither trait can be removed now.

Beyond that historical fact, however, there are also good ergonomic reasons to have both of these traits, even if we could start from scratch today. It is often significantly easier to use one or the other in different situations. For example, if you're writing a method that takes a type that can be turned into a `Foo`, would you rather write `fn(impl Into<Foo>)` or `fn<T>(T)` where `Foo: From<T>?` And conversely, to turn a string into a syntax identifier, would you rather write `Ident::from("foo")` or `<_ as Into<Ident>>::into("foo")`? Both of these traits have their uses, and we're better off having them both.

Given that we do have both, you may wonder which you should use in your code today. The answer, it turns out, is pretty simple: implement `From`, and use `Into` in bounds. The reason is that `Into` has a blanket implementation for any `T` that implements `From`, so regardless of whether a type explicitly implements `From` or `Into`, it implements `Into`!

Of course, as simple things frequently go, the story doesn't quite end there. Since the compiler often has to "go through" the blanket implementation when `Into` is used as a bound, the reasoning for whether a type implements `Into` is more complicated than whether it implements `From`. And in some cases, the compiler is not quite smart enough to figure that puzzle out. For this reason, the `?` operator at the time of writing uses `From`, not `Into`. Most of the time that doesn't make a difference, because most types implement `From`, but it does mean that error types from old libraries that implement `Into` instead may not work with `?`. As the compiler gets smarter, `?` will likely be "upgraded" to use `Into`, at which point that problem will go away, but it's what we have for now.

The second aspect of `?` to be aware of is that this operator is really just syntax sugar for a trait tentatively called `Try`. At the time of writing, the `Try` trait has not yet been stabilized, but by the time you read this, it's likely that it, or something very similar, will have been settled on. Since the details haven't all been figured out yet, I'll give you only an outline of how `Try` works, rather than the full method signatures. At its heart, `Try` defines a wrapper type whose state is either one where further computation is useful

(the happy path), or one where it is not. Some of you will correctly think of monads, though we won't explore that connection here. For example, in the case of `Result<T, E>`, if you have an `Ok(t)`, you can continue on the happy path by unwrapping the `t`. If you have an `Err(e)`, on the other hand, you want to stop executing and produce the error value immediately, since further computation is not possible as you don't have the `t`.

What's interesting about `Try` is that it applies to more types than just `Result`. An `Option<T>`, for example, follows the same pattern—if you have a `Some(t)`, you can continue on the happy path, whereas if you have a `None`, you want to yield `None` instead of continuing. This pattern extends to more complex types, like `Poll<Result<T, E>>`, whose happy path type is `Poll<T>`, which makes `?` apply in far more cases than you might expect. When `Try` stabilizes, we may see `?` start to work with all sorts of types to make our happy path code nicer.

The `?` operator is already usable in fallible functions, in doctests, and in `fn main`. To reach its full potential, though, we also need a way to scope this error handling. For example, consider the function in Listing 5-2.

---

```
fn do_the_thing() -> Result<(), Error> {
    let thing = Thing::setup()?;
    // .. code that uses thing and ? ..
    thing.cleanup();
    Ok(())
}
```

---

*Listing 5-2: A multi-step fallible function using the `?` operator*

This won't quite work as expected. Any `?` between `setup` and `cleanup` will cause an early return from the entire function, which would skip the `cleanup` code! This is the problem *try blocks* are intended to solve. A try block acts pretty much like a single-iteration loop, where `?` uses `break` instead of `return`, and the final expression of the block has an implicit `break`. We can now fix the code in Listing 5-2 to always do `cleanup`, as shown in Listing 5-3.

---

```
fn do_the_thing() -> Result<(), Error> {
    let thing = Thing::setup()?;
    let r = try {
        // .. code that uses thing and ? ..
    };
    thing.cleanup();
    r
}
```

---

*Listing 5-3: A multi-step fallible function that always cleans up after itself*

Try blocks are also not stable at the time of writing, but there is enough of a consensus on their usefulness that they're likely to land in a form similar to that described here.

## Summary

This chapter covered the two primary ways to construct error types in Rust: enumeration and erasure. We looked at when you may want to use each one and the advantages and drawbacks of each. We also took a look at some of the behind-the-scenes aspects of the `?` operator and considered how `?` may become even more useful going forward. In the next chapter, we'll take a step back from the code and look at how you *structure* a Rust project. We'll look at feature flags, dependency management, and versioning as well as how to manage more complex crates using workspaces and subcrates. See you on the next page!



# 6

## PROJECT STRUCTURE



This chapter provides some ideas for structuring your Rust projects. For simple projects, the structure set up by `cargo new` is likely to be something you think little about. You

may add some modules to split up the code, and some dependencies for additional functionality, but that's about it. However, as a project grows in size and complexity, you'll find that you need to go beyond that. Maybe the compilation time for your crate is getting out of hand, or you need conditional dependencies, or you need a better strategy for continuous integration. In this chapter, we will look at some of the tools that the Rust language, and Cargo in particular, provide that make it easier to manage such things.

### Features

*Features* are Rust's primary tool for customizing projects. At its core, a feature is just a build flag that crates can pass to their dependencies in order to add optional functionality. Features carry no semantic meaning in and of themselves—instead, *you* choose what a feature means for *your* crate.

Generally, we use features in three ways: to enable optional dependencies, to conditionally include additional components of a crate, and to augment the behavior of the code. Note that all of these uses are *additive*; features can add to the functionality of the crate, but they shouldn't generally do things like remove modules or replace types or function signatures. This stems from the principle that if a developer makes a simple change to their *Cargo.toml*, such as adding a new dependency or enabling a feature, that shouldn't make their crate stop compiling. If a crate has mutually exclusive features, that principle quickly falls by the wayside—if crate A depends on one feature of crate C, and crate B on another mutually exclusive feature of C, adding a dependency on crate B would then break crate A! For that reason, we generally follow the principle that if crate A compiles against crate C with some set of features, it should also compile if all features are enabled on crate C.

Cargo leans into this principle quite hard. For example, if two crates (A and B) both depend on crate C, but they each enable different features on C, Cargo will compile crate C only once, with *all* the features that either A or B requires. That is, it'll take the union of the requested features for C across A and B. Because of this, it's generally hard to add mutually exclusive features to Rust crates; chances are that some two dependents will depend on the crate with different features, and if those features are mutually exclusive, the downstream crate will fail to build.

#### NOTE

*I highly recommend that you configure your continuous integration infrastructure to check that your crate compiles for any combination of its features. One tool that helps you do this is *cargo-hack*, which you can find at <https://github.com/taiki-e/cargo-hack>.*

## Defining and Including Features

Features are defined in *Cargo.toml*. Listing 6-1 shows an example of a crate named `foo` with a simple feature that enables the optional dependency `syn`.

---

```
[package]
name = "foo"
...
[features]
derive = ["syn"]

[dependencies]
syn = { version = "1", optional = true }
```

---

*Listing 6-1: A feature that enables an optional dependency*

When Cargo compiles this crate, it will not compile the `syn` crate by default, which reduces compile time (often significantly). The `syn` crate will be compiled only if a downstream crate needs to use the APIs enabled by the `derive` feature and explicitly opts in to it. Listing 6-2 shows how such a downstream crate `bar` would enable the `derive` feature, and thus include the `syn` dependency.

---

```
[package]
name = "bar"
...
```

---



```
[dependencies]
foo = { version = "1", features = ["derive"] }
```

---

*Listing 6-2: Enabling a feature of a dependency*

Some features are used so frequently that it makes more sense to have a crate opt out of them rather than in to them. To support this, Cargo allows you to define a set of default features for a crate. And similarly, it allows you to opt out of the default features of a dependency. Listing 6-3 shows how `foo` can make its `derive` feature enabled by default, while also opting out of some of `syn`'s default features and instead enabling only the ones it needs for the `derive` feature.

---

```
[package]
name = "foo"
...
[features]
derive = ["syn"]
default = ["derive"]

[dependencies.syn]
version = "1"
default-features = false
features = ["derive", "parsing", "printing"]
optional = true
```

---

*Listing 6-3: Adding and opting out of default features, and thus optional dependencies*

Here, if a crate depends on `foo` and does not explicitly opt out of the default features, it will also compile `foo`'s `syn` dependency. In turn, `syn` will be built with only the three listed features, and no others. Opting out of default features this way, and opting in to only what you need, is a great way to cut down on your compile times!

### OPTIONAL DEPENDENCIES AS FEATURES

When you define a feature, the list that follows the equal sign is itself a list of features. This might, at first, sound a little odd—in Listing 6-3, `syn` is a dependency, not a feature. It turns out that Cargo makes every optional dependency a feature with the same name as the dependency. You'll see this if you try to add a feature with the same name as an optional dependency; Cargo won't allow it. Support for a different namespace for features and dependencies is in the works in Cargo, but has not been stabilized at the time of writing. In the meantime, if you want to have a feature named after a dependency, you can rename the dependency using `package = ""` to avoid the name collision. The list of features that a feature enables can also include features of dependencies. For example, you can write `derive = ["syn/derive"]` to have your `derive` feature enable the `derive` feature of the `syn` dependency.

## Using Features in Your Crate

When using features, you need to make sure your code uses a dependency only if it is available. And if your feature enables a particular component, you need to make sure that if the feature isn't enabled, the component is not included.

You achieve this using *conditional compilation*, which lets you use annotations to give conditions under which a particular piece of code should or should not be compiled. Conditional compilation is primarily expressed using the `#[cfg]` attribute. There is also the closely related `cfg!` macro, which lets you change runtime behavior based on similar conditions. You can do all sorts of neat things with conditional compilation, as we'll see later in this chapter, but the most basic form is `#[cfg(feature = "some-feature")]`, which makes it so that the next “thing” in the source code is compiled only if the `some-feature` feature is enabled. Similarly, `if cfg!(feature = "some-feature")` is equivalent to `if true` only if the `derive` feature is enabled (and `if false` otherwise).

The `#[cfg]` attribute is used more often than the `cfg!` macro, because the macro modifies runtime behavior based on the feature, which can make it difficult to ensure that features are additive. You can place `#[cfg]` in front of certain Rust *items*—such as functions and type definitions, `impl` blocks, modules, and `use` statements—as well as on certain other constructs like struct fields, function arguments, and statements. `#[cfg]` cannot go just anywhere, though; where it can appear is carefully restricted by the Rust language team so that conditional compilation can't cause situations that are too strange and hard to debug.

Remember that modifying certain public parts of your API may inadvertently make a feature nonadditive, which in turn may make it impossible for some users to compile your crate. You can often use the rules for backward compatible changes as a rule of thumb here—for example, if you make an enum variant or a public struct field conditional upon a feature, then that type must also be annotated with `#[non_exhaustive]`. Otherwise, a dependent crate that does not have the feature enabled may no longer compile if the feature is added due to some second crate in the dependency tree.

### NOTE

*If you're writing a large crate where you expect that your users will need only a subset of the functionality, you should consider making it so that larger components (usually modules) are guarded by features. That way, users can opt in to, and pay the compilation cost of, only the parts they really need.*

## Workspaces

Crates play many roles in Rust—they are the vertices in the dependency graph, the boundaries for trait coherence, and the scopes for compilation features. Because of this, each crate is managed as a single compilation

unit; the Rust compiler treats a crate more or less as one big source file compiled as one chunk that is ultimately turned into a single binary output (either a binary or a library).

While this simplifies many aspects of the compiler, it also means that large crates can be painful to work with. If you change a unit test, a comment, or a type in one part of your application, the compiler must re-evaluate the entire crate to determine what, if anything, changed. Internally, the compiler implements a number of mechanisms to speed up this process, like incremental recompilation and parallel code generation, but ultimately the size of your crate is a big factor in how long your project takes to compile.

For this reason, as your project grows, you may want to split it into multiple crates that internally depend on one another. Cargo has just the feature you need to make this convenient: workspaces. A *workspace* is a collection of crates (often called *subcrates*) that are tied together by a top-level *Cargo.toml* file like the one shown in Listing 6-4.

---

```
[workspace]
members = [
  "foo",
  "bar/one",
  "bar/two",
]
```

---

*Listing 6-4: A workspace Cargo.toml*

The `members` array is a list of directories that each contain a crate in the workspace. Those crates all have their own *Cargo.toml* files in their own subdirectories, but they share a single *Cargo.lock* file and a single output directory. The crate names don't need to match the entry in `members`. It is common, but not required, that crates in a workspace share a name prefix, usually chosen as the name of the “main” crate. For example, in the `tokio` crate, the members are called `tokio`, `tokio-test`, `tokio-macros`, and so on.

Perhaps the most important feature of workspaces is that you can interact with all of the workspace's members by invoking `cargo` in the root of the workspace. Want to check that they all compile? `cargo check` will check them all. Want to run all your tests? `cargo test` will test them all. It's not quite as convenient as having everything in one crate, so don't go splitting everything into minuscule crates, but it's a pretty good approximation.

#### NOTE

*Cargo commands will generally do the “right thing” in a workspace. If you ever need to disambiguate, such as if two workspace crates both have a binary by the same name, use the `-p` flag (for package). If you are in the subdirectory for a particular workspace crate, you can pass `--workspace` to perform the command for the entire workspace instead.*

Once you have a workspace-level *Cargo.toml* with the array of workspace members, you can set your crates to depend on one another using path dependencies, as shown in Listing 6-5.

---

```
# bar/two/Cargo.toml
[dependencies]
one = { path = "../one" }
# bar/one/Cargo.toml
[dependencies]
foo = { path = "../../foo" }
```

---

*Listing 6-5: Intercrate dependencies among workspace crates*

Now if you make a change to the crate in *bar/two*, then only that crate is re-compiled, since *foo* and *bar/one* did not change. It may even be faster to compile your project from scratch, since the compiler does not need to evaluate your entire project source for optimization opportunities.

### SPECIFYING INTRA-WORKSPACE DEPENDENCIES

The most obvious way to specify that one crate in a workspace depends on another is to use the path specifier, as shown in Listing 6-5. However, if your individual subcrates are intended for public consumption, you may want to use *version* specifiers instead.

Say you have a crate that depends on a Git version of the *one* crate from the *bar* workspace in Listing 6-5 with `one = { git = ". . ." }`, and a released version of *foo* (also from *bar*) with `foo = "1.0.0"`. Cargo will dutifully fetch the *one* Git repository, which holds the entire *bar* workspace, and see that *one* in turn depends on *foo*, located at `../../foo` inside the workspace. But Cargo doesn't know that the released version `foo = "1.0.0"` and the *foo* in the Git repository are the same crate! It considers them two separate dependencies that just happen to have the same name.

You may already see where this is going. If you try to use any type from *foo* (1.0.0) with an API from *one* that accepts a type from *foo*, the compiler will reject the code. Even though the types have the same name, the compiler can't know that they are the same underlying type. And the user will be thoroughly confused, since the compiler will say something like "expected `foo::Type`, got `foo::Type`."

The best way to mitigate this problem is to use path dependencies between subcrates only if they depend on unpublished changes. As long as *one* works with *foo* 1.0.0, it should list `foo = "1.0.0"` in its dependencies. Only if you make a change to *foo* that *one* needs should you change *one* to use a path dependency. And once you release a new version of *foo* that *one* can depend on, you should remove the path dependency again.

This approach also has its shortcomings. Now if you change *foo* and then run the tests for *one*, you'll see that *one* will be tested using the old *foo*, which may not be what you expected. You'll probably want to configure your continuous integration infrastructure to test each subcrate both with the latest released versions of the other subcrates and with all of them configured to use path dependencies.

## Project Configuration

Running `cargo new` sets you up with a minimal *Cargo.toml* that has the crate's name, its version number, some author information, and an empty list of dependencies. That will take you pretty far, but as your project matures, there are a number of useful things you may want to add to your *Cargo.toml*.

### Crate Metadata

The first and most obvious thing to add to your *Cargo.toml* is all the metadata directives that Cargo supports. In addition to obvious fields like `description` and `homepage`, it can be useful to include information such as the path to a *README* for the crate (`readme`), the default binary to run with `cargo run` (`default-run`), and additional keywords and categories to help *crates.io* categorize your crate.

For crates with a more convoluted project layout, it's also useful to set the `include` and `exclude` metadata fields. These dictate which files should be included and published in your package. By default, Cargo includes all files in a crate's directory except any listed in your `.gitignore` file, but this may not be what you want if you also have large test fixtures, unrelated scripts, or other auxiliary data in the same directory that you *do* want under version control. As their names suggest, `include` and `exclude` allow you to include only a specific set of files or exclude files matching a given set of patterns, respectively.

#### NOTE

*If you have a crate that should never be published, or should be published only to certain alternative registries (that is, not to *crates.io*), you can set the `publish` directive to `false` or to a list of allowed registries.*

The list of metadata directives you can use continues to grow, so make sure to periodically check in on the Manifest Format page of the Cargo reference (<https://doc.rust-lang.org/cargo/reference/manifest.html>).

### Build Configuration

*Cargo.toml* can also give you control over how Cargo builds your crate. The most obvious tool for this is the `build` parameter, which allows you to write a completely custom build program for your crate (we'll revisit this in [Chapter 12](#)). However, Cargo also provides two smaller, but very useful, mechanisms that we'll explore here: patches and profiles.

#### [patch]

The `[patch]` section of *Cargo.toml* allows you to specify a different source for a dependency that you can use temporarily, no matter where in your dependencies the patched dependency appears. This is invaluable when you need to compile your crate against a modified version of some transitive dependency to test a bug fix, a performance improvement, or a new minor release you're about to publish. Listing 6-6 shows an example of how you might temporarily use a variant of a set of dependencies.

---

```
[patch.crates-io]
# use a local (presumably modified) source
regex = { path = "/home/jon/regex" }
# use a modification on a git branch
serde = { git = "https://github.com/serde-rs/serde.git", branch = "faster" }
# patch a git dependency
[patch.'https://github.com/jonhoo/project.git']
project = { path = "/home/jon/project" }
```

---

*Listing 6-6: Overriding dependency sources in `Cargo.toml` using `[patch]`*

Even if you patch a dependency, Cargo takes care to check the crate versions so that you don't accidentally end up patching the wrong major version of a crate. If you for some reason transitively depend on multiple major versions of the same crate, you can patch each one by giving them distinct identifiers, as shown in Listing 6-7.

---

```
[patch.crates-io]
nom4 = { path = "/home/jon/nom4", package = "nom" }
nom5 = { path = "/home/jon/nom5", package = "nom" }
```

---

*Listing 6-7: Overriding multiple versions of the same crate in `Cargo.toml` using `[patch]`*

Cargo will look at the *Cargo.toml* inside each path, realize that `/nom4` contains major version 4 and that `/nom5` contains major version 5, and patch the two versions appropriately. The `package` keyword tells Cargo to look for a crate by the name `nom` in both cases instead of using the dependency identifiers (the part on the left) as it does by default. You can use `package` this way in your regular dependencies as well to rename a dependency!

Keep in mind that patches are not taken into account in the package that's uploaded when you publish a crate. A crate that depends on your crate will use only its own `[patch]` section (which may be empty), not that of your crate!

## CRATES VS. PACKAGES

You may wonder what the difference between a package and a crate is. These two terms are often used interchangeably in informal contexts, but they also have specific definitions that vary depending on whether you're talking about the Rust compiler, Cargo, *crates.io*, or something else. I personally think of a crate as a Rust module hierarchy starting at a root `.rs` file (one where you can use crate-level attributes like `#![feature]`)—usually something like *lib.rs* or *main.rs*. In contrast, a package is a collection of crates and metadata, so essentially all that's described by a *Cargo.toml* file. That may include a library crate, multiple binary crates, some integration test crates, and maybe even multiple workspace members that themselves have *Cargo.toml* files.

**[profile]**

The `[profile]` section lets you pass additional options to the Rust compiler in order to change the way it compiles your crate. These options fall primarily into three categories: performance options, debugging options, and options that change code behavior in user-defined ways. They all have different defaults depending on whether you are compiling in debug mode or in release mode (other modes also exist).

The three primary performance options are `opt-level`, `codegen-units`, and `lto`. The `opt-level` option tweaks runtime performance by telling the compiler how aggressively to optimize your program (0 is “not at all,” 3 is “as much as you can”). The higher the setting, the more optimized your code will be, which *may* make it run faster. Extra optimization comes at the cost of higher compile times, though, which is why optimizations are generally enabled only for release builds.

**NOTE**

*You can also set `opt-level` to "s" to optimize for binary size, which may be important on embedded platforms.*

You can also set `opt-level` to "s" to optimize for binary size, which may be important on embedded platforms.

The `codegen-units` option is about compile-time performance. It tells the compiler how many independent compilation tasks (*code generation units*) it is allowed to split the compilation of a single crate into. The more pieces a large crate’s compilation is split into, the faster it will compile, since more threads can help compile the crate in parallel. Unfortunately, to achieve this speedup, the threads need to work more or less independently, which means code optimization suffers. Imagine, for example, that the segment of a crate compiling in one thread could benefit from inlining some code in a different segment—since the two segments are independent, that inlining can’t happen! This setting, then, is a trade-off between compile-time performance and runtime performance. By default, Rust uses an effectively unbounded number of codegen units in debug mode (basically, “compile as fast as you can”) and a smaller number (16 at the time of writing) in release mode.

The `lto` setting toggles *link-time optimization (LTO)*, which enables the compiler (or the linker, if you want to get technical about it) to jointly optimize bits of your program, known as *compilation units*, that were originally compiled separately. The exact details of LTO are beyond the scope of this book, but the basic idea is that the output from each compilation unit includes information about the code that went into that unit. After all the units have been compiled, the linker makes another pass over all of the units and uses that additional information to optimize the combined compiled code. This extra pass adds to the compile time but recovers most of the runtime performance that may have been lost due to splitting the compilation into smaller parts. In particular, LTO can offer significant performance boosts to performance-sensitive programs that might benefit from cross-crate optimization. Beware, though, that cross-crate LTO can add a lot to your compile time.

Rust performs LTO across all the codegen units within each crate by default in an attempt to make up for the lost optimizations caused by using

many codegen units. Since the LTO is performed only within each crate, rather than across crates, this extra pass isn't too onerous, and the added compile time should be lower than the amount of time saved by using a lot of codegen units. Rust also offers a technique known as *thin LTO*, which allows the LTO pass to be mostly parallelized, at the cost of missing some optimizations a “full” LTO pass would have found.

#### NOTE

*LTO can be used to optimize across foreign function interface boundaries in many cases, too. See the `linker-plugin-lto` `rustc` flag for more details.*

The `[profile]` section also supports flags that aid in debugging, such as `debug`, `debug-assertions`, and `overflow-checks`. The `debug` flag tells the compiler to include debug symbols in the compiled binary. This increases the binary size, but it means that you get function names and such, rather than just instruction addresses, in backtraces and profiles. The `debug-assertions` flag enables the `debug_assert!` macro and other related debug code that isn't compiled otherwise (through `cfg(debug_assertions)`). Such code may make your program run slower, but it makes it easier to catch questionable behavior at runtime. The `overflow-checks` flag, as the name implies, enables overflow checks on integer operations. This slows them down (notice a trend here?) but can help you catch tricky bugs early on. By default, these are all enabled in debug mode and disabled in release mode.

#### `[profile.*.panic]`

The `[profile]` section has another flag that deserves its own subsection: `panic`. This option dictates what happens when code in your program calls `panic!`, either directly or indirectly through something like `unwrap`. You can set `panic` to either `unwind` (the default on most platforms) or `abort`. We'll talk more about panics and unwinding in [Chapter 10](#), but I'll give a quick summary here.

Normally in Rust, when your program panics, the thread that panicked starts *unwinding* its stack. You can think of unwinding as forcibly returning recursively from the current function all the way to the bottom of that thread's stack. That is, if `main` called `foo`, `foo` called `bar`, and `bar` called `baz`, a panic in `baz` would forcibly return from `baz`, then `bar`, then `foo`, and finally from `main`, resulting in the program exiting. A thread that unwinds will drop all values on the stack normally, which gives the values a chance to clean up resources, report errors, and so on. This gives the running system a chance to exit gracefully even in the case of a panic.

When a thread panics and unwinds, other threads continue running unaffected. Only when (and if) the thread that ran `main` exits does the program terminate. That is, the panic is generally isolated to the thread in which the panic occurred.

This means unwinding is a double-edged sword; the program is limping along with some failed components, which may cause all sorts of strange behaviors. For example, imagine a thread that panics halfway through updating the state in a `Mutex`. Any thread that subsequently acquires that `Mutex` must now be prepared to handle the fact that the state may be in a partially updated, inconsistent state. For this reason, some synchronization primitives



(like `Mutex`) will remember if a panic occurred when they were last accessed and communicate that to any thread that tries to access the primitive subsequently. If a thread encounters such a state, it will normally also panic, which leads to a cascade that eventually terminates the entire program. But that is arguably better than continuing to run with corrupted state!

The bookkeeping needed to support unwinding is not free, and it often requires special support by the compiler and the target platform. For example, many embedded platforms cannot unwind the stack efficiently at all. Rust therefore supports a different panic mode: `abort` ensures the whole program simply exits immediately when a panic occurs. In this mode, no threads get to do any cleanup. This may seem severe, and it is, but it ensures that the program is never running in a half-working state and that errors are made visible immediately.

### WARNING

*The panic setting is global—if you set it to `abort`, all your dependencies are also compiled with `abort`.*

You may have noticed that when a thread panics, it tends to print a *backtrace*: the trail of function calls that led to where the panic occurred. This is also a form of unwinding, though it is separate from the unwinding panic behavior discussed here. You can have backtraces even with `panic=abort` by passing `-Cforce-unwind-tables` to `rustc`, which makes `rustc` include the information necessary to walk back up the stack while still terminating the program on a panic.

## PROFILE OVERRIDES

You can set profile options for just a particular dependency, or a particular profile, using *profile overrides*. For example, Listing 6-8 shows how to enable aggressive optimizations for the `serde` crate and moderate optimizations for all other crates in debug mode, using the `[profile.<profile-name>.package.<crate-name>]` syntax.

```
[profile.dev.package.serde]
opt-level = 3
[profile.dev.package."*"]
opt-level = 2
```

*Listing 6-8: Overriding profile options for a specific dependency or for a specific mode*

This kind of optimization override can be handy if some dependency would be prohibitively slow in debug mode (such as decompression or video encoding), and you need it optimized so that your test suite won't take several days to complete. You can also specify global profile defaults using a `[profile.dev]` (or similar) section in the Cargo configuration file in `~/.cargo/config`.

When you set optimization parameters for a specific dependency, keep in mind that the parameters apply only to the code compiled as part of that crate;

*(continued)*

if `serde` in this example has a generic method or type that you use in your crate, the code of that method or type will be monomorphized and optimized in *your* crate, and *your* crate's profile settings will apply, not those in the profile override for `serde`.

## Conditional Compilation

Most Rust code you write is universal—it'll work the same regardless of what CPU or operating system it runs on. But sometimes you'll have to do something special to get the code to work on Windows, on ARM chips, or when compiled against a particular platform application binary interface (ABI). Or maybe you want to write an optimized version of a particular function when a given CPU instruction is available, or disable some slow but uninteresting setup code when running in a continuous integration (CI) environment. To cater to cases like these, Rust provides mechanisms for *conditional compilation*, in which a particular segment of code is compiled only if certain conditions are true of the compilation environment.

We denote conditional compilation with the `cfg` keyword that you saw in “Using Features in Your Crate” on [page XX](#). It usually appears in the form of the `#[cfg(condition)]` attribute, which says to compile the next item only if `condition` is true. Rust also has `#[cfg_attr(condition, attribute)]`, which is compiled as `#[attribute]` if `condition` holds and is a no-op otherwise. You can also evaluate a `cfg` condition as a Boolean expression using the `cfg!(condition)` macro.

Every `cfg` construct takes a single condition made up of options, like `feature = "some-feature"`, and the combinators `all`, `any`, and `not`, which do what you would probably expect. Options are either simple names, like `unix`, or key/value pairs like those used by feature conditions.

There are a number of interesting options you can make compilation dependent on. Let's go through them, from most common to least common:

### Feature options

You've already seen examples of these. Feature options take the form `feature = "name-of-feature"` and are considered true if the named feature is enabled. You can check for multiple features in a single condition using the combinators. For example, `any(feature = "f1", feature = "f2")` is true if either feature `f1` or feature `f2` is enabled.

### Operating system options

These use key/value syntax with the key `target_os` and values like `windows`, `macos`, and `linux`. You can also specify a family of operating systems using `target_family`, which takes the value `windows` or `unix`. These are common enough that they have received their own named short forms, so you can use `cfg(windows)` and `cfg(unix)` directly. For example, if you wanted a particular code segment to be compiled only on macOS and Windows, you would write: `#[cfg(any(windows, target_os = "macos"))]`.

## Context options

These let you tailor code to a particular compilation context. The most common of these is the `test` option, which is true only when the crate is being compiled under the test profile. Keep in mind that `test` is set only for the crate that is being tested, not for any of its dependencies. This also means that `test` is not set in your crate when running integration tests; it's the integration tests that are compiled under the test profile, whereas your actual crate is compiled normally (that is, without test set). The same applies to the `doc` and `doctest` options, which are set only when building documentation or compiling doctests, respectively. There's also the `debug_assertions` option, which is set in debug mode by default.

## Tool options

Some tools, like `clippy` and `Miri`, set custom options (more on that later) that let you customize compilation when run under these tools. Usually, these options are named after the tool in question. For example, if you want a particular compute-intensive test not to run under `Miri`, you can give it the attribute `#[cfg_attr(miri, ignore)]`.

## Architecture options

These let you compile based on the CPU instruction set the compiler is targeting. You can specify a particular architecture with `target_arch`, which takes values like `x86`, `mips`, and `aarch64`, or you can specify a particular platform feature with `target_feature`, which takes values like `avx` or `sse2`. For very low-level code, you may also find the `target_endian` and `target_pointer_width` options useful.

## Compiler options

These let you adapt your code to the platform ABI it is compiled against and are available through `target_env` with values like `gnu`, `msvc`, and `musl`. For historical reasons, this value is often empty, especially on GNU platforms. You normally need this option only if you need to interface directly with the environment ABI, such as when linking against an ABI-specific symbol name using `#[link]`.

While `cfg` conditions are usually used to customize code, some can also be used to customize dependencies. For example, the dependency `winnr` usually makes sense only on Windows, and the `nix` crate is probably only useful on Unix-based platforms. Listing 6-9 gives an example of how you can use `cfg` conditions for this:

---

```
[target.'cfg(windows)'.dependencies]
winnr = "0.7"
[target.'cfg(unix)'.dependencies]
nix = "0.17"
```

---

*Listing 6-9: Conditional dependencies*

Here, we specify that `wirrt` version 0.7 should be considered a dependency only under `cfg(windows)` (so, on Windows), and `nix` version 0.17 only under `cfg(unix)` (so, on Linux, macOS, and other Unix-based platforms). One thing to keep in mind is that the `[dependencies]` section is evaluated very early in the build process, when only certain `cfg` options are available. In particular, feature and context options are not yet available at this point, so you cannot use this syntax to pull in dependencies based on features and contexts. You can, however, use any `cfg` that depends only on the target specification or architecture, as well as any options explicitly set by tools that call into `rustc` (like `cfg(miri)`).

#### NOTE

*While we're on the topic of dependency specifications, I highly recommend that you set up your CI infrastructure to perform basic auditing of your dependencies using tools like `cargo-deny` and `cargo-audit`. These tools will detect cases where you transitively depend on multiple major versions of a given dependency, where you depend on crates that are unmaintained or have known security vulnerabilities, or where you use licenses that you may want to avoid. Using such a tool is a great way to raise the quality of your codebase in an automated way!*

It's also quite simple to add your own custom conditional compilation options. You just have to make sure that `--cfg=myoption` is passed to `rustc` when `rustc` compiles your crate. The easiest way to do this is to add your `--cfg` to the `RUSTFLAGS` environment variable. This can come in handy in CI, where you may want to customize your test suite depending on whether it's being run on CI or on a dev machine: add `--cfg=ci` to `RUSTFLAGS` in your CI setup, and then use `cfg(ci)` and `cfg(not(ci))` in your code. Options set this way are also available in `Cargo.toml` dependencies.

## Versioning

All Rust crates are versioned and are expected to follow Cargo's implementation of semantic versioning. *Semantic versioning* dictates the rules for what kinds of changes require what kinds of version increases and for which versions are considered compatible, and in what ways. The RFC 1105 standard itself is well worth reading (it's not horribly technical), but to summarize, it differentiates between three kinds of changes: breaking changes, which require a major version change; additions, which require a minor version change; and bug fixes, which require only a patch version change. RFC 1105 does a decent job of outlining what constitutes a breaking change in Rust, and we've touched on some aspects of it elsewhere in this book.

I won't go into detail here about the exact semantics of the different types of changes. Instead, I want to highlight some less straightforward ways version numbers come up in the Rust ecosystem, which you need to keep in mind when deciding how to version your own crates.

## Minimum Supported Rust Version

The first Rust-ism is the *minimum supported Rust version (MSRV)*. There is much debate in the Rust community about what policy projects should adhere to when it comes to their MSRV and versioning, and there's no truly good answer. The core of the problem is that some Rust users are limited to using older versions of Rust, often in an enterprise setting where they have little choice. If we constantly take advantage of newly stabilized APIs, those users will not be able to compile the latest versions of our crates and will be left behind.

There are two techniques crate authors can use to make life a little easier for users in this position. The first is to establish an MSRV policy promising that new versions of a crate will always compile with any stable release from the last *X* months. The exact number varies, but 6 or 12 months is common. With Rust's six-week release cycle, that corresponds to the latest four or eight stable releases, respectively. Any new code introduced to the project must compile with the MSRV compiler (usually checked by CI) or be held until the MSRV policy allows it to be merged as is. This can sometimes be a pain, as it means these crates cannot take advantage of the latest and greatest the language has to offer, but it will make life easier for your users.

The second technique is to make sure to increase the minor version number of your crate any time that the MSRV changes. So, if you release version 2.7.0 of your crate and that increases your MSRV from Rust 1.44 to Rust 1.45, then a project that is stuck on 1.44 and that depends on your crate can use the dependency version specifier `version = "2, <2.7"` to keep the project working until it can move on to Rust 1.45. It's important that you increment the minor version, not just the patch version, so that you can still issue critical security fixes for the previous MSRV release by doing another patch release if necessary.

Some projects take their MSRV support so seriously that they consider an MSRV change a breaking change and increment the major version number. This means that downstream projects will explicitly have to opt in to an MSRV change, rather than opting out—but it also means that users who do not have such strict MSRV requirements will not see future bug fixes without updating their dependencies, which may require *them* to issue a breaking change as well. As I said, none of these solutions are without drawbacks.

Enforcing an MSRV in the Rust ecosystem today is challenging. Only a small subset of crates provide any MSRV guarantees, and even if your dependencies do, you will need to constantly monitor them to know when they increase their MSRV. When they do, you'll need to do a new release of your crate with the restricted version bounds mentioned previously to make sure your MSRV doesn't also change. This may in turn force you to forego security and performance updates made to your dependencies, as you'll have to continue using older versions until your MSRV policy permits updating. And that decision also carries over to your dependents. There have been proposals to build MSRV checking into Cargo itself, but nothing workable has been stabilized as of this writing.

## Minimal Dependency Versions

When you first add a dependency, it's not always clear what version specifier you should give that dependency. Programmers commonly choose the latest version, or just the current major version, but chances are that both of those choices are wrong. By “wrong,” I don't mean that your crate won't compile, but rather that making that choice may cause strife for users of your crate down the line. Let's look at why each of these cases is problematic.

First, consider the case where you add a dependency on `hugs = "1.7.3"`, the latest published version. Now imagine that a developer somewhere depends on your crate, but they also depend on some other crate, `foo`, that itself depends on `hugs`. Further imagine that the author of `foo` is really careful about their MSRV policy, so they depend on `hugs = "1, <1.6"`. Here, you'll run into trouble. When Cargo sees `hugs = "1.7.3"`, it considers only versions  $\geq 1.7$ . But then it sees that `foo`'s dependency on `hugs` requires  $<1.6$ , so it gives up and reports that there is no version of `hugs` compatible with all the requirements.

### NOTE

*In practice, there are a number of reasons why a crate may explicitly not want a newer version of a dependency. The most common ones are to enforce MSRV, to meet enterprise auditing requirements (the newer version will contain code that hasn't been audited), and to ensure reproducible builds where only the exact listed version is used.*

This is unfortunate, as it could well be that your crate compiles fine with, say, `hugs 1.5.6`. Maybe it even compiles fine with *any* `1.x` version! But by using the latest version number, you are telling Cargo to consider only versions at or beyond that minor version. Is the solution to use `hugs = "1"` instead, then? No, that's not quite right either. It could be that your code truly does depend on something that was added only in `hugs 1.6`, so while `1.6.2` would be fine, `1.5.6` would not be. You wouldn't notice this if you were only ever compiling your crate in situations where a newer version ends up getting used, but if some crate in the dependency graph specifies `hugs = "1, <1.5"`, your crate would not compile!

The right strategy is to list the earliest version that has all the things your crate depends on and to make sure that this remains the case even as you add new code to your crate. But how do you establish that beyond trawling the changelogs, or through trial and error? Your best bet is to use Cargo's unstable `-Z minimal-versions` flag, which makes your crate use the minimum acceptable version for all dependencies, rather than the maximum. Then, set all your dependencies to just the latest major version number, try to compile, and add a minor version to any dependencies that don't. Rinse and repeat until everything compiles fine, and you now have your minimum version requirements!

It's worth noting that, like with MSRV, minimal version checking faces an ecosystem adoption problem. While you may have set all your version specifiers correctly, the projects you depend on may not have. This makes the Cargo minimal versions flag hard to use in practice (and is why it's still unstable). If you depend on `foo`, and `foo` depends on `bar` with a specifier of `bar = "1"` when it actually requires `bar = "1.4"`, Cargo will report that it failed to compile `foo` no matter how you list `foo` because the `-Z` flag tells it

to always prefer minimal versions. You can work around this by listing *bar* directly in *your* dependencies with the appropriate version requirement, but these workarounds can be painful to set up and maintain. You may end up listing a large number of dependencies that are only really pulled in through your transitive dependencies, and you'll have to keep that list up to date as time goes on.

**NOTE**

*One current proposal is to present a flag that favors minimal versions for the current crate but maximal ones for dependencies, which seems quite promising.*

## Changelogs

For all but the most trivial crates, I highly recommend keeping a changelog. There is little more frustrating than seeing that a dependency has received a major version bump and then having to dig through the Git logs to figure out what changed and how to update your code. I recommend that you do not just dump your Git logs into a file named *changelog*, but instead keep a manual changelog. It is much more likely to be useful.

A simple but good format for changelogs is the Keep a Changelog format documented at <https://keepachangelog.com/>.

## Unreleased Versions

Rust considers version numbers even when the source of a dependency is a directory or a Git repository. This means that semantic versioning is important even when you have not yet published a release to *crates.io*; it matters what version is listed in your *Cargo.toml* between releases. The semantic versioning standard does not dictate how to handle this case, but I'll provide a workflow that works decently well without being too onerous.

After you've published a release, immediately update the version number in your *Cargo.toml* to the next patch version with a suffix like *-alpha.1*. If you just released 2.0.3, make the new version 2.0.4-alpha.1. If you just released an alpha, increment the alpha number instead.

As you make changes to the code between releases, keep an eye out for additive or breaking changes. If one happens, and the corresponding version number has not changed since the last release, increment it. For example, if the last released version is 2.0.3, the current version is 2.0.4-alpha.2, and you make an additive change, make the version with the change 2.1.0-alpha.1. If you made a breaking change, it becomes 3.0.0-alpha.1 instead. If the corresponding version increase has already been made, just increment the alpha number.

When you make a release, remove the suffix (unless you want to do a prerelease), then publish, and start from the top.

This process is effective because it makes two common workflows work much better. First, imagine that a developer depends on major version 2 of your crate, but they need a feature that's currently available only in Git. Then you commit a breaking change. If you don't increase the major version at the same time, their code will suddenly fail in unexpected ways,

either by failing to compile or as a result of weird runtime issues. If you follow the procedure laid out here, they'll instead be notified by Cargo that a breaking change has occurred, and they'll have to either resolve that or pin a specific commit.

Next, imagine that a developer needs a feature they just contributed to your crate, but which isn't part of any released version of your crate yet. They've used your crate behind a Git dependency for a while, so other developers on their project already have older checkouts of your crate's repository. If you do not increment the major version number in Git, this developer has no way to communicate that their project now relies on the feature that was just merged. If they push their change, their fellow developers will find that the project no longer compiles, since Cargo will reuse the old checkout. If, on the other hand, the developer can increment the minor version number for the Git dependency, then Cargo will realize that the old checkout is outdated.

This workflow is by no means perfect. It doesn't provide a good way to communicate multiple minor or major changes between releases, and you still need to do a bit of work to keep track of the versions. However, it does address two of the most common issues Rust developers run into when they work against Git dependencies, and even if you make multiple such changes between releases, this workflow will still catch many of the issues.

If you're not too worried about small or consecutive version numbers in releases, you can improve this suggested workflow by simply always incrementing the appropriate part of the version number. Be aware, though, that depending on how frequently you make such changes, this may make your version numbers quite large!

## Summary

In this chapter, we've looked at a number of mechanisms for configuring, organizing, and publishing crates, for both your own benefit and that of others. We've also gone over some common gotchas when working with dependencies and features in Cargo that now hopefully won't catch you out in the future. In the next chapter we'll turn to testing and dig into how you go beyond Rust's simple `#[test]` functions that we know and love.



# 7

## TESTING



In this chapter, we'll look at the various ways in which you can extend Rust's testing capabilities and what other kinds of testing you may want to add into your testing mix. Rust comes with a number of built-in testing facilities that are well covered in *The Rust Programming Language*, represented primarily by the `#[test]` attribute and the `tests/` directory. These will serve you well across a wide range of applications and scales and are often all you need when you are getting started with a project. However, as the codebase develops and your testing needs grow more elaborate, you may need to go beyond just tagging `#[test]` onto individual functions.

This chapter is divided into two main sections. The first part covers Rust testing mechanisms, like the standard testing harness and conditional testing code. The second looks at other ways to evaluate the correctness of your Rust code, such as benchmarking, linting, and fuzzing.

## Rust Testing Mechanisms

To understand the various testing mechanisms Rust provides, you must first understand how Rust builds and runs tests. When you run `cargo test --lib`, the only special thing Cargo does is pass the `--test` flag to `rustc`. This flag tells `rustc` to produce a test binary that runs all the unit tests, rather than just compiling the crate’s library or binary. Behind the scenes, `--test` has two primary effects. First, it enables `cfg(test)` so that you can conditionally include testing code (more on that in a bit). Second, it makes the compiler generate a *test harness*: a carefully generated main function that invokes each `#[test]` function in your program when it’s run.

### The Test Harness

The compiler generates the test harness main function through a mix of procedural macros, which we’ll discuss in greater depth in [Chapter 8](#), and a light sprinkling of magic. Essentially, the harness transforms every function annotated by `#[test]` into a test *descriptor*—this is the procedural macro part. It then exposes the path of each of the descriptors to the generated main function—this is the magic part. The descriptor includes information like the test’s name, any additional options it has set (like `#[should_panic]`), and so on. At its core, the test harness iterates over the tests in the crate, runs them, captures their results, and prints the results. So, it also includes logic to parse command line arguments (for things like `--test-threads=1`), capture test output, run the listed tests in parallel, and collect test results.

As of this writing, Rust developers are working on making the magic part of test harness generation a publicly available API so that developers can build their own test harnesses. This work is still at the experimental stage, but the proposal aligns fairly closely with the model as it exists today. Part of the magic that needs to be figured out is how to ensure that `#[test]` functions are available to the generated main function even if they are inside private submodules.

Integration tests (the tests in `tests/`) follow the same process as unit tests, with the one exception that they are each compiled as their own separate crate, meaning they can access only the main crate’s public interface and are run against the main crate compiled without `#[cfg(test)]`. A test harness is generated for each file in `tests/`. Test harnesses are not generated for files in subdirectories under `tests/` to allow you to have shared submodules for your tests.

#### NOTE

*If you explicitly want a test harness for a file in a subdirectory, you can opt in to that by calling the file `main.rs`.*

Rust does not require that you use the default test harness. You can instead opt out of it and implement your own `main` method that represents the test runner by setting `harness = false` for a given integration test in *Cargo.toml*, as shown in Listing 7-1. The `main` method that you define will then be invoked to run the test.

---

```
[[test]]
name = "custom"
path = "tests/custom.rs"
harness = false
```

---

*Listing 7-1: Opting out of the standard test harness*

Without the test harness, none of the magic around `#[test]` happens. Instead, you're expected to write your own `main` function to run the testing code you want to execute. Essentially, you're writing a normal Rust binary that just happens to be run by `cargo test`. That binary is responsible for handling all the things that the default harness normally does (if you want to support them), such as command line flags. The harness property is set separately for each integration test, so you can have one test file that uses the standard harness and one that does not.

### ARGUMENTS TO THE DEFAULT TEST HARNESS

The default test harness supports a number of command line arguments to configure how the tests are run. These aren't passed to `cargo test` directly but rather to the test binary that Cargo compiles and runs for you when you run `cargo test`. To access that set of flags, pass `--` to `cargo test`, followed by the arguments to the test binary. For example, to see the help text for the test binary, you'd run `cargo test -- --help`.

A number of handy configuration options are available through these command line arguments. The `--nocapture` flag disables the output capturing that normally happens when you run Rust tests. This is useful if you want to observe a test's output in real time rather than all at once after the test has failed. You can use the `--test-threads` option to limit how many tests run concurrently, which is helpful if you have a test that hangs or segfaults and you want to figure out which one it is by running the tests sequentially. There's also a `--skip` option for skipping tests that match a certain pattern, `--ignored` to run tests that would normally be ignored (such as those that require an external program to be running), and `--list` to just list all the available tests.

Keep in mind that these arguments are all implemented by the default test harness, so if you disable it (with `harness = false`), you'll have to implement the ones you need yourself in your `main` function!

Integration tests without a harness are primarily useful for benchmarks, as we'll see later, but they also come in handy when you want to run tests that don't fit the standard "one function, one test" model. For example, you'll frequently see harnessless tests used with fuzzers, model checkers, and tests that require a custom global setup (like under WebAssembly or when working with custom targets).

## **`#[cfg(test)]`**

When Rust builds code for testing, it sets the compiler configuration flag `test`, which you can then use with conditional compilation to have code that is compiled out unless it is specifically being tested. On the surface, this may seem odd: don't you want to test exactly the same code that's going into production? You do, but having code exclusively available when testing allows you to write better, more thorough tests, in a few ways.

### **MOCKING**

When writing tests, you often want tight control over the code you're testing as well as any other types that your code may interact with. For example, if you are testing a network client, you probably do not want to run your unit tests over a real network but instead want to directly control what bytes are emitted by the "network" and when. Or, if you're testing a data structure, you want your test to use types that allow you to control what each method returns on each invocation. You may also want to gather metrics such as how often a given method was called or whether a given byte sequence was emitted.

These "fake" types and implementations are known as *mocks*, and they are a key feature of any extensive unit test suite. While you can often do the work needed to get this kind of control manually, it's nicer to have a library take care of most of the nitty-gritty details for you. This is where automated mocking comes into play. A mocking library will have facilities for generating types (including functions) with particular properties or signatures, as well as mechanisms to control and introspect those generated items during a test execution.

Mocking in Rust generally happens through generics—as long as your program, data structure, framework, or tool is generic over anything you might want to mock (or takes a trait object), you can use a mocking library to generate conforming types that will instantiate those generic parameters. You then write your unit tests by instantiating your generic constructs with the generated mock types, and you're off to the races!

In situations where generics are inconvenient or inappropriate, such as if you want to avoid making a particular aspect of your type generic to users, you can instead encapsulate the state and behavior you want to mock in a dedicated struct. You would then generate a mocked version of that struct and its methods and use conditional compilation to use either the real or mocked implementation depending on `cfg(test)` or a test-only feature like `cfg(feature = "test_mock_foo")`.

At the moment, there isn't a single mocking library, or even a single mocking approach, that has emerged as the One True Answer in the Rust community. The most extensive and thorough mocking library I know of is the `mockall` crate, but that is still under active development, and there are many other contenders.

## Test-Only APIs

First, having test-only code allows you to expose additional methods, fields, and types to your (unit) tests so the tests can check not only that the public API behaves correctly, but also that the internal state is correct. For example, consider the `HashMap` type from `hashbrown`, the crate that implements the standard library `HashMap`. The `HashMap` type is really just a wrapper around a `RawTable` type, which is what implements most of the hash table logic. Suppose that after doing a `HashMap::insert` on an empty map, you want to check that a single bucket in the map is nonempty, as shown in Listing 7-2.

---

```
#[test]
fn insert_just_one() {
    let mut m = HashMap::new();
    m.insert(42, ());
    let full = m.table.buckets.iter().filterBucket::is_full.count();
    assert_eq!(full, 1);
}
```

---

*Listing 7-2: A test that accesses inaccessible internal state and thus does not compile*

This code will not compile as written, because while the test code can access the private `table` field of `HashMap`, it cannot access the also private `buckets` field of `RawTable`, as `RawTable` lives in a different module. We could fix this by making the `buckets` field visibility `pub(crate)`, but we really don't want `HashMap` to be able to touch buckets in general, as it could accidentally corrupt the internal state of the `RawTable`. Even making buckets available as read-only could be problematic, as new code in `HashMap` may then start depending on the internal state of `RawTable`, making future modifications more difficult.

The solution is to use `#[cfg(test)]`. We can add a method to `RawTable` that allows access to buckets only while testing, as shown in Listing 7-3, and thereby avoid adding footguns for the rest of the code. The code from Listing 7-2 can then be updated to call `buckets()` instead of accessing the private `buckets` field.

---

```
impl RawTable {
    #[cfg(test)]
    pub(crate) fn buckets(&self) -> &[Bucket] {
        &self.buckets
    }
}
```

---

*Listing 7-3: Using `#[cfg(test)]` to make internal state accessible in the testing context*

## Bookkeeping for Test Assertions

The second benefit of having code that exists only during testing is that you can augment the program to perform additional runtime bookkeeping that can then be inspected by tests. For example, imagine you're writing your own version of the `BufWriter` type from the standard library. When testing it, you want to make sure that `BufWriter` does not issue system calls

unnecessarily. The most obvious way to do so is to have the `BufWriter` keep track of how many times it has invoked `write` on the underlying `Write`. However, in production this information isn't important, and keeping track of it introduces (marginal) performance and memory overhead. With `#[cfg(test)]`, you can have the bookkeeping happen only when testing, as shown in Listing 7-4.

---

```
struct BufWriter<T> {
    #[cfg(test)]
    write_through: usize,
    // other fields...
}

impl<T: Write> Write for BufWriter<T> {
    fn write(&mut self, buf: &[u8]) -> Result<usize> {
        // ...
        if self.full() {
            #[cfg(test)]
            self.write_through += 1;
            let n = self.inner.write(&self.buffer[..])?;
            // ...
        }
    }
}
```

---

*Listing 7-4: Using `#[cfg(test)]` to limit bookkeeping to the testing context*

Keep in mind that `test` is set only for the crate that is being compiled as a test. For unit tests, this is the crate being tested, as you would expect. For integration tests, however, it is the integration test binary being compiled as a test—the crate you are testing is just compiled as a library and so will not have `test` set.

## Doctests

Rust code snippets in documentation comments are automatically run as test cases. These are commonly referred to as *doctests*. Because doctests appear in the public documentation of your crate, and users are likely to mimic what they contain, they are run as integration tests. This means that the doctests don't have access to private fields and methods, and `test` is not set on the main crate's code. Each doctest is compiled as its own dedicated crate and is run in isolation, just as if the user had copy-pasted the doctest into their own program.

Behind the scenes, the compiler performs some preprocessing on doctests to make them more concise. Most importantly, it automatically adds an `fn main` around your code. This allows doctests to focus only on the important bits that the user is likely to care about, like the parts that actually use types and methods from your library, without including unnecessary boilerplate.

You can opt out of this auto-wrapping by defining your own `fn main` in the doctest. You may want to do this, for example, if you want to write an

asynchronous main function using something like `#[tokio::main] async fn main`, or if you want to add additional modules to the doctest.

To use the `?` operator in your doctest, you don't normally have to use a custom main function as `rustdoc` includes some heuristics to set the return type to `Result<(), impl Debug>` if your code looks like it makes use of `?` (for example, if it ends with `Ok(())`). If type inference gives you a hard time about the error type for the function, you can disambiguate it by changing the last line of the doctest to be explicitly typed, like this: `Ok:<(), T>()`.

Doctests have a number of additional features that come in handy as you write documentation for more complex interfaces. The first is the ability to hide individual lines. If you prefix a line of a doctest with a `#`, that line is included when the doctest is compiled and run, but it is not included in the code snippet generated in the documentation. This lets you easily hide details that are not important to the current example, such as implementing traits for dummy types or generating values. It is also useful if you wish to present a sequence of examples without showing the same leading code each time. Listing 7-5 gives an example of what a doctest with hidden lines might look like.

---

```

/// Completely frobnifies a number through I/O.
///
/// In this first example we hide the value generation.
/// ```
/// # let unfrobnified_number = 0;
/// # let already_frobnified = 1;
/// assert!(frobnify(unfrobnified_number).is_ok());
/// assert!(frobnify(already_frobnified).is_err());
/// ```
///
/// Here's an example that uses ? on multiple types
/// and thus needs to declare the concrete error type,
/// but we don't want to distract the user with that.
/// We also hide the use that brings the function into scope.
/// ```
/// # use mylib::frobnify;
/// frobnify("0".parse())?;
/// # Ok:<(), anyhow::Error>()
/// ```
///
/// You could even replace an entire block of code completely,
/// though use this _very_ sparingly:
/// ```
/// # /*
/// let i = ...;
/// # */
/// # let i = 42;
/// frobnify(i)?;
/// ```
fn frobnify(i: usize) -> std::io::Result<()> {

```

---

*Listing 7-5: Hiding lines in a doctest with `#`*

**NOTE**

*Use this feature with care; it can be frustrating to users if they copy-paste an example and then it doesn't work because of required steps that you've hidden.*

Much like `#[test]` functions, doctests also support attributes that modify how the doctest is run. These attributes go immediately after the triple-backtick used to denote a code block, and multiple attributes can be separated by commas.

Like with test functions, you can specify the `should_panic` attribute to indicate that the code in a particular doctest should panic when run, or ignore to check the code segment only if cargo test is run with the `--ignored` flag. You can also use the `no_run` attribute to indicate that a given doctest should compile but should not be run.

The attribute `compile_fail` tells rustdoc that the code in the documentation example should not compile. This indicates to the user that a particular use is not possible and serves as a useful test to remind you to update the documentation should the relevant aspect of your library change. You can also use this attribute to check that certain static properties hold for your types. Listing 7-6 shows an example of how you can use `compile_fail` to check that a given type does not implement `Send`, which may be necessary to uphold safety guarantees in unsafe code.

---

```
```compile_fail
# struct MyNonSendType(std::rc::Rc<()>);
fn is_send<T: Send>() {}
is_send::<MyNonSendType>();
```
```

---

*Listing 7-6: Testing that code fails to compile with `compile_fail`*

`compile_fail` is a fairly crude tool in that it gives no indication of *why* the code does not compile. For example, if code doesn't compile because of a missing semicolon, a `compile_fail` test will appear to have been successful. For that reason, you'll usually want to add the attribute only after you have made sure that the test indeed fails to compile with the expected error. If you need more fine-grained tests for compilation errors, such as when developing macros, take a look at the `trybuild` crate.

## Additional Testing Tools

There's a lot more to testing than just running test functions and seeing that they produce the expected result. A thorough survey of testing techniques, methodologies, and tools is outside the scope of this book, but there are some key Rust-specific pieces that you should know about as you expand your testing repertoire.

### *Linting*

You may not consider a linter's checks to be tests, but in Rust they often can be. The Rust linter *clippy* categorizes a number of its lints as *correctness*



*lints*. These lints catch code patterns that compile but are almost certainly bugs. Some examples are `a = b; b = a`, which fails to swap `a` and `b`; `std::mem::forget(t)`, where `t` is a reference; and `for x in y.next()`, which will iterate only over the first element in `y`. If you are not running clippy as part of your CI pipeline already, you probably should be.

Clippy comes with a number of other lints that, while usually helpful, may be more opinionated than you'd prefer. For example, the `type_complexity` lint, which is on by default, issues a warning if you use a particularly involved type in your program, like `Rc<Vec<Vec<Box<(u32, u32, u32, u32)>>>>`. While that warning encourages you to write code that is easier to read, you may find it too pedantic to be broadly useful. If some part of your code erroneously triggers a particular lint, or you just want to allow a specific instance of it, you can opt out of the lint just for that piece of code with `#[allow(clippy::name_of_lint)]`.

The Rust compiler also comes with its own set of lints in the form of warnings, though these are usually more directed toward writing idiomatic code than checking for correctness. Instead, correctness lints in the compiler are simply treated as errors (take a look at `rustc -W help` for a list).

#### NOTE

*Not all compiler warnings are enabled by default. Those disabled by default are usually still being refined, or are more about style than content. A good example of this is the “idiomatic Rust 2018 edition” lint, which you can enable with `#![warn(rust_2018_idioms)]`. When this lint is enabled, the compiler will tell you if you're failing to take advantage of changes brought by the Rust 2018 edition. Some other lints that you may want to get into the habit of enabling when you start a new project are `missing_docs` and `missing_debug_implementations`, which warn you if you've forgotten to document any public items in your crate or add `Debug` implementations for any public types, respectively.*

## Test Generation

Writing a good test suite is a lot of work. And even when you do that work, the tests you write test only the particular set of behaviors you were considering at the time you wrote them. Luckily, you can take advantage of a number of test generation techniques to develop better and more thorough tests. These generate input for you to use to check your application's correctness. Many such tools exist, each with their own strengths and weaknesses, so here I'll cover only the main strategies used by these tools: fuzzing and property testing.

### Fuzzing

Entire books have been written about fuzzing, but at a high level the idea is simple: generate random inputs to your program and see if it crashes. If the program crashes, that's a bug. For example, if you're writing a URL parsing library, you can fuzz-test your program by systematically generating random strings and throwing them at the parsing function until it panics. Done

naively, this would take a while to yield results: if the fuzzer starts with a, then b, then c, and so on, it will take it a long time to generate a tricky URL like `http://[:]`. In practice, modern fuzzers use code coverage metrics to explore different paths in your code, which lets them reach higher degrees of coverage faster than if the inputs were truly chosen at random.

Fuzzers are great at finding strange corner cases that your code doesn't handle correctly. They require little setup on your part: you just point the fuzzer at a function that takes a “fuzzable” input, and off it goes. For example, Listing 7-7 shows an example of how you might fuzz-test a URL parser.

---

```
libfuzzer_sys::fuzz_target!(|data: &[u8]| {
    if let Ok(s) = std::str::from_utf8(data) {
        let _ = url::Url::parse(s);
    }
});
```

---

*Listing 7-7: Fuzzing a URL parser with libfuzzer*

The fuzzer will generate semi-random inputs to the closure, and any that form valid UTF-8 strings will be passed to the parser. Notice that the code here doesn't check whether the parsing succeeds or fails—instead, it's looking for cases where the parser panics or otherwise crashes due to internal invariants that are violated.

The fuzzer keeps running until you terminate it, so most fuzzing tools come with a built-in mechanism to stop after a certain number of test cases have been explored. If your input isn't a trivially fuzzable type—something like a hash table—you can usually use a crate like `arbitrary` to turn the byte string that the fuzzer generates into a more complex Rust type. It feels like magic, but under the hood it's actually implemented in a very straightforward fashion. The crate defines an `Arbitrary` trait with a single method, `arbitrary`, that constructs the implementing type from a source of random bytes. Primitive types like `u32` or `bool` read the necessary number of bytes from that input to construct a valid instance of themselves, whereas more complex types like `HashMap` or `BTreeSet` produce one number from the input to dictate their length and then call `Arbitrary` that number of times on their inner types. There's even an attribute, `#[derive(Arbitrary)]`, that implements `Arbitrary` by just calling `arbitrary` on each contained type! To explore fuzzing further, I recommend starting with `cargo-fuzz`.

## Property-Based Testing

Sometimes you want to check not only that your program doesn't crash but also that it does what it's expected to do. It's great that your `add` function didn't panic, but if it tells you that the result of `add(1, 4)` is 68, it's probably still wrong. This is where *property-based testing* comes into play; you describe a number of properties your code should uphold, and then the property testing framework generates inputs and checks that those properties indeed hold.

A common way to use property-based testing is to first write a simple but naive version of the code you want to test that you are confident is correct. Then, for a given input, you give that input to both the code you want to test and the simplified but naive version. If the result or output of the two implementations is the same, your code is good—that is the correctness property you’re looking for—but if it’s not, you’ve likely found a bug. You can also use property-based testing to check for properties not directly related to correctness, such as whether operations take strictly less time for one implementation than another. The common principle is that you want any difference in outcome between the real and test versions to be informative and actionable so that every failure allows you to make improvements. The naive implementation might be one from the standard library that you’re trying to replace or augment (like `std::collections::VecDeque`), or it might be a simpler version of an algorithm that you’re trying to optimize (like naive versus optimized matrix multiplication).

If this approach of generating inputs until some condition is met sounds a lot like fuzzing, that’s because it is—smarter people than I have argued that fuzzing is “just” property-based testing where the property you’re testing for is “it doesn’t crash.”

One downside of property-based testing is that it relies more heavily on the provided descriptions of the inputs. Whereas fuzzing will keep trying all possible inputs, property testing tends to be guided by developer annotations like “a number between 0 and 64” or “a string that contains three commas.” This allows property testing to more quickly reach cases that fuzzers may take a long time to encounter randomly, but it does require manual work and may miss important but niche buggy inputs. As fuzzers and property testers grow closer, however, fuzzers are starting to gain this kind of constraint-based searching capability as well.

If you’re curious about property-based test generation, I recommend starting with the `proptest` crate.

### TESTING SEQUENCES OF OPERATIONS

Since fuzzers and property testers allow you to generate arbitrary Rust types, you aren’t limited to testing a single function call in your crate. For example, say you want to test that some type `Foo` behaves correctly if you perform a particular sequence of operations on it. You could define an enum `Operation` that lists operations, and make your test function take a `Vec<Operation>`. Then you could instantiate a `Foo` and perform each operation on that `Foo`, one after the other. Most testers have support for minimizing inputs, so they will even search for the smallest sequence of operations that still violates a property if a property-violating input is found!

## Test Augmentation

Let's say you have a magnificent test suite all set up, and your code passes all the tests. It's glorious. But then, one day, one of the normally reliable tests inexplicably fails or crashes with a segmentation fault. There are two common reasons for these kinds of nondeterministic test failures: race conditions, where your test might fail only if two operations occur on different threads in a particular order, and undefined behavior in unsafe code, such as if some unsafe code reads a particular value out of uninitialized memory.

Catching these kinds of bugs with normal tests can be difficult—often you don't have sufficient low-level control over thread scheduling, memory layout and content, or other random-ish system factors to write a reliable test. You could run each test many times in a loop, but even that may not catch the error if the bad case is sufficiently rare or unlikely. Luckily, there are tools that can help augment your tests to make catching these kinds of bugs much easier.

The first of these is the amazing tool *Miri*, an interpreter for Rust's *mid-level intermediate representation* (*MIR*). *MIR* is an internal, simplified representation of Rust that helps the compiler find optimizations and check properties without having to consider all of the syntax sugar of Rust itself. Running your tests through *Miri* is as simple as running `cargo miri test`. *Miri* *interprets* your code rather than compiling and running it like a normal binary, which makes the tests run a decent amount slower. But in return, *Miri* can keep track of the entire program state as each line of your code executes. This allows *Miri* to detect and report if your program ever exhibits certain types of undefined behavior, such as uninitialized memory reads, uses of values after they've been dropped, or out-of-bounds pointer accesses. Rather than having these operations yield strange program behaviors that may only sometimes result in observable test failures (like crashes), *Miri* detects them when they happen and tells you immediately.

For example, consider the very unsound code in Listing 7-8, which creates two exclusive references to a value.

---

```
let mut x = 42;
let x: *mut i32 = &mut x;
let (x1, x2) = unsafe { (&mut *x, &mut *x) };
println!("{}", x1, x2);
```

---

Listing 7-8: Wildly unsafe code that *Miri* detects is incorrect

At the time of writing, if you run this code through *Miri*, you get an error that points out exactly what's wrong:

---

```
error: Undefined Behavior: trying to reborrow for Unique at alloc1383, but
parent tag <2772> does not have an appropriate item in the borrow stack
--> src/main.rs:4:6
|
4 | let (x1, x2) = unsafe { (&mut *x, &mut *x) };
|   ^^ trying to reborrow for Unique at alloc1383, but parent tag <2772>
does not have an appropriate item in the borrow stack
```

---

**NOTE**

*Miri is still under development, and its error messages aren't always the easiest to understand. This is a problem that's being actively worked on, so by the time you read this, the error output may have already gotten much better!*

Another tool worth looking at is *Loom*, a clever library that tries to ensure your tests are run with every relevant interleaving of concurrent operations. At a high level, Loom keeps track of all cross-thread synchronization points and runs your tests over and over, adjusting the order in which threads proceed from those synchronization points each time. So, if thread A and thread B both take the same `Mutex`, Loom will ensure that the test runs once with A taking it first and once with B taking it first. Loom also keeps track of atomic accesses, memory orderings, and accesses to `UnsafeCell` (which we'll discuss in [Chapter 10](#)) and checks that threads do not access them inappropriately. If a test fails, Loom can give you an exact rundown of which threads executed in what order so you can determine how the crash happened.

## Performance Testing

Writing performance tests is difficult because it is often hard to accurately model a workload that reflects real-world usage of your crate. But having such tests is important; if your code suddenly runs 100 times slower, that really should be considered a bug, yet without a performance test you may not spot the regression. If your code runs 100 times *faster*, that might also indicate that something is off. Both of these are good reasons to have automated performance tests as part of your CI—if performance changes drastically in either direction, you should know about it.

Unlike with functional testing, performance tests do not have a common, well-defined output. A functional test will either succeed or fail, whereas a performance test may give you a throughput number, a latency profile, a number of processed samples, or any other metric that might be relevant to the application in question. Also, a performance test may require running a function in a loop a few hundred thousand times, or it might take hours running across a distributed network of multicore boxes. For that reason, it is difficult to speak about how to write performance tests in a general sense. Instead, in this section, we'll look at some of the issues you may encounter when writing performance tests in Rust and how to mitigate them. Three particularly common pitfalls that are often overlooked are performance variance, compiler optimizations, and I/O overhead. Let's explore each of these in turn.

### Performance Variance

Performance can vary for a huge variety of reasons, and many factors affect how fast a particular sequence of machine instructions run. Some are obvious, like the CPU and memory clock speed, or how loaded the machine otherwise is, but many are much more subtle. For example, your kernel version may change paging performance, the length of your username might change the

layout of memory, and the temperature in the room might cause the CPU to clock down. Ultimately, it is highly unlikely that if you run a benchmark twice, you'll get the same result. In fact, you may observe significant variance, even if you are using the same hardware. Or, viewed from another perspective, your code may have gotten slower or faster, but the effect may be invisible due to differences in the benchmarking environment.

There are no perfect ways to eliminate all variance in your performance results, unless you happen to be able to run benchmarks repeatedly on a highly diverse fleet of machines. Even so, it's important to try to handle this measurement variance as best we can to extract a signal from the noisy measurements benchmarks give us. In practice, our best friend in combating variance is to run each benchmark many times and then look at the *distribution* of measurements rather than just a single one. Rust has tools that can help with this. For example, rather than ask “How long did this function take to run on average?” crates like `hdrhistogram` enable us to look at statistics like “What range of runtime covers 95% of the samples we observed?” To be even more rigorous, we can use techniques like null hypothesis testing from statistics to build some confidence that a measured difference indeed corresponds to a true change and is not just noise.

A lecture on statistical hypothesis testing is beyond the scope of this book, but luckily much of this work has already been done by others. The criterion crate, for instance, does all of this and more for you. All you have to do is give it a function that it can call to run one iteration of your benchmark, and it will run it the appropriate number of times to be fairly sure that the result is reliable. It then produces a benchmark report, which includes a summary of the results, analysis of outliers, and even graphical representations of trends over time. Of course, it can't eliminate the effects of just testing on a particular configuration of hardware, but it at least categorizes the noise that is measurable across executions.

## Compiler Optimizations

Compilers these days are really clever. They eliminate dead code, compute complex expressions at compile time, unroll loops, and perform other dark magic to squeeze every drop of performance out of our code. Normally this is great, but when we're trying to measure how fast a particular piece of code is, the compiler's smartness can give us invalid results. For example, take the code to benchmark `Vec::push` in Listing 7-9.

---

```
let mut vs = Vec::with_capacity(4);
let start = std::time::Instant::now();
for i in 0..4 {
    vs.push(i);
}
println!("took {:?}", start.elapsed());
```

---

*Listing 7-9: A suspiciously fast performance benchmark*

If you were to look at the assembly output of this code compiled in release mode using something like the excellent *godbolt.org* or *cargo-asm*, you’d immediately notice that something was wrong: the calls to `Vec::with_capacity` and `Vec::push`, and indeed the whole `for` loop, are nowhere to be seen. They have been optimized out completely. The compiler realized that nothing in the code actually required the vector operations to be performed and eliminated them as dead code. Of course, the compiler is completely within its rights to do so, but for benchmarking purposes, this is not particularly helpful.

To avoid these kinds of optimizations for benchmarking, the standard library provides `std::hint::black_box`. This function has been the topic of much debate and confusion and is still pending stabilization at the time of writing, but is so useful it’s worth discussing here nonetheless. At its core, it’s simply an identity function (one that takes `x` and returns `x`) that tells the compiler to assume that the argument to the function is used in arbitrary (legal) ways. It does not prevent the compiler from applying optimizations to the input argument, nor does it prevent the compiler from optimizing how the return value is used. Instead, it encourages the compiler to actually compute the argument to the function (under the assumption that it will be used) and to store that result somewhere accessible to the CPU such that `black_box` could be called with the computed value. The compiler is free to, say, compute the input argument at compile time, but it should still inject the result into the program.

This function is all we need for many, though admittedly not all, of our benchmarking needs. For example, we can annotate Listing 7-9 so that the vector accesses are no longer optimized out, as shown in Listing 7-10.

---

```
let mut vs = Vec::with_capacity(4);
let start = std::time::Instant::now();
for i in 0..4 {
    black_box(vs.as_ptr());
    vs.push(i);
    black_box(vs.as_ptr());
}
println!("took {:?}", start.elapsed());
```

---

*Listing 7-10: A corrected version of Listing 7-9*

We’ve told the compiler to assume that `vs` is used in arbitrary ways on each iteration of the loop, both before and after the calls to `push`. This forces the compiler to perform each `push` in order, without merging or otherwise optimizing consecutive calls, since it has to assume that “arbitrary stuff that cannot be optimized out” (that’s the `black_box` part) may happen to `vs` between each call.

Note that we used `vs.as_ptr()` and not, say, `&vs`. That’s because of the caveat that the compiler should assume `black_box` can perform any *legal* operation on its argument. It is not legal to mutate the `Vec` through a shared reference, so if we used `black_box(&vs)`, the compiler might notice that `vs` will not change between iterations of the loop and implement optimizations based on that observation!

## I/O Overhead Measurement

When writing benchmarks, it's easy to accidentally measure the wrong thing. For example, we often want to get information in real time about how far along the benchmark is. To do that, we might write code like that in Listing 7-11, intended to measure how fast `my_function` runs:

---

```
let start = std::time::Instant::now();
for i in 0..1_000_000 {
    println!("iteration {}", i);
    my_function();
}
println!("took {:?}", start.elapsed());
```

---

*Listing 7-11: What are we really benchmarking here?*

This may look like it achieves the goal, but in reality, it does not actually measure how fast `my_function` is. Instead, this loop is most likely to tell us how long it takes to print a million numbers. The `println!` in the body of the loop does a lot of work behind the scenes: it turns a binary integer into decimal digits for printing, locks standard output, writes out a sequence of UTF-8 code points using at least one system call, and then releases the standard output lock. Not only that, but the system call might block if your terminal is slow to print out the input it receives. That's a lot of cycles! And the time it takes to call `my_function` might pale in comparison.

A similar thing happens when your benchmark uses random numbers. If you run `my_function(rand::random())` in a loop, you may well be mostly measuring the time it takes to generate a million random numbers. The story is the same for getting the current time, reading a configuration file, or starting a new thread—these things all take a long time, relatively speaking, and may end up overshadowing the time you actually wanted to measure.

Luckily, this particular issue is often easy to work around once you are aware of it. Make sure that the body of your benchmarking loop contains almost nothing but the particular code you want to measure. All other code should run either before the benchmark begins or outside of the measured part of the benchmark. If you're using `criterion`, take a look at the different timing loops it provides—they're all there to cater to benchmarking cases that require different measurement strategies!

## Summary

In this chapter, we explored the built-in testing capabilities that Rust offers in great detail. We also looked at a number of testing facilities and techniques that are useful when testing Rust code. This is the last chapter that focuses on higher-level aspects of intermediate Rust use in this book. Starting with the next chapter on declarative and procedural macros, we will be focusing much more on Rust code. See you on the next page!



# 8

## MACROS



Macros are, in essence, a tool for making the compiler write code for you. You give the compiler a formula for generating code given some input parameters, and the compiler replaces every invocation of the macro with the result of running through the formula. You can think of macros as automatic code substitution where you get to define the rules for the substitution.

Rust's macros come in many different shapes and sizes to make it easy to implement many different forms of code generation. The two primary types are *declarative* macros and *procedural* macros, and we will explore both of them in this chapter. We'll also look at some of the ways macros can come in handy in your everyday coding, and some of the pitfalls that arise with more advanced use. Some familiarity with macros is assumed, so before reading this chapter I recommend that you read the chapter on macros in the Rust language reference (<https://doc.rust-lang.org/reference/macros.html>).

Programmers coming from C-based languages may be used to the unholy land of C and C++ where you can use `#define` to change each `true` to `false`, or to remove all occurrences of the `else` keyword. If that’s the case for you, you’ll need to disassociate macros from a feeling of doing something “bad.” Macros in Rust are far from the Wild West of C macros. They follow (mostly) well-defined rules, and are fairly misuse-resistant.

## Declarative Macros

Declarative macros are those defined using the `macro_rules!` syntax, which lets you conveniently define function-like macros without having to resort to writing a dedicated crate for the purpose (as you do with procedural macros). Once you’ve defined a declarative macro, you can invoke it using the name of the macro followed by an exclamation mark. I like to think of this kind of macro as a sort of compiler-assisted search and replace: it does the job for many regular, well-structured transformation tasks, and for eliminating repetitive boilerplate. In your experience with Rust up until this point, most of the macros you have recognized as macros are likely to have been declarative macros. Note, however, that not all function-like macros are declarative macros; `macro_rules!` itself is one example of this, and `format_args!` is another. The `!` suffix merely indicates to the compiler that the macro invocation will be replaced with different source code at compile time.

### NOTE

*Since Rust’s parser specifically recognizes and parses macro invocations annotated with `!`, you can only use them in places where the parser allows them. They work in most places you’d expect, like in expression position or in an `impl` block, but not everywhere. For example, you cannot (at the time of writing) invoke a function-like macro where an identifier or match arm is expected.*

It may not be immediately obvious why declarative macros are called declarative. After all, don’t you “declare” everything in your program? In this context, *declarative* refers to the fact that you don’t say how the macro’s inputs should be translated into the output, just that you want the output to look like A when the input is B. You declare that it shall be so, and the compiler figures out all the parsing rewiring that has to happen to make your declaration reality. This makes declarative macros concise and expressive, though it also has a tendency to make them rather cryptic since you have a limited language to express your declarations in.

### When to Use Them

Declarative macros are primarily useful when you find yourself writing the same code over and over, and you’d like to, well, not do that. They’re best suited for fairly mechanical replacements—if you’re aiming to do fancy code transformations or lots of code generation, procedural macros are likely a better fit.

I most frequently make use of declarative macros in cases where I find myself writing repetitive and structurally similar code, such as in tests and

trait implementations. For tests, I often want to run the same test multiple times but with slightly different configurations. I might have something like what is shown in Listing 8-1.

---

```
fn test_inner<T>(init: T, frobnify: bool) { ... }
#[test]
fn test_u8_frobnified() {
    test_inner(u8, true);
}
// ...
#[test]
fn test_i128_not_frobnified() {
    test_inner(i128, false);
}
```

---

*Listing 8-1: Repetitive testing code*

While this works, it's too verbose, too repetitive, and too prone to manual error. With macros we can do much better, as shown in Listing 8-2.

---

```
macro_rules! test_battery {
    ($($t:ty as $name:ident),*) => {
        $(
            mod $name {
                #[test]
                fn frobnified() { test_inner::<$t>(1, true) }
                #[test]
                fn unfrobnified() { test_inner::<$t>(1, false) }
            }
        )*
    }
}
test_battery! {
    u8 as u8_tests,
    // ...
    i128 as i128_tests
};
```

---

*Listing 8-2: Making a macro repeat for you*

This macro expands each comma-separated directive into its own module that then contains two tests, one that calls `test_inner` with `true`, and one with `false`. While the macro definition isn't trivial, it makes adding more tests much easier. Each type is one line in the `test_battery!` invocation, and the macro will take care of generating tests for both `true` and `false` arguments. We could also have it generate tests for different values for `init`. We've now significantly reduced the likelihood that we'll forget to test a particular configuration!

The story for trait implementations is similar. If you define your own trait, you'll often want to implement that trait for a number of types in the standard library, even if those implementations are trivial. Let's imagine you invented the `Clone` trait and want to implement it for all the `Copy` types

in the standard library. Instead of manually writing out an implementation for each one, you can use a macro like the one in Listing 8-3.

---

```
macro_rules! clone_from_copy {
    ($($t:ty),*) => {
        $(impl Clone for $t {
            fn clone(&self) -> Self { *self }
        })*
    }
}
clone_from_copy![bool, f32, f64, u8, i8, /* ... */];
```

---

*Listing 8-3: Using a macro to implement a trait for many similar types in one fell swoop*

Here, we generate an implementation of `Clone` for each provided type whose body just uses `*` to Copy out of `&self`. You may wonder why we don't add a blanket implementation of `Clone` for `T` where `T: Copy`. We could do that, but a big reason not to is that it would force types in other crates to also use that same implementation of `Clone` for their own types that happen to be `Copy`. There is an experimental compiler feature called *specialization* that could offer a workaround, but at the time of writing the stabilization of that feature that is still some way off. So, for the time being, we're better off enumerating the types specifically. This pattern also extends beyond simple forwarding implementations: you could easily adapt the example in Listing 8-3 to implement an `AddOne` trait to all integer types, for example!

#### NOTE

*If you ever find yourself wondering if you should use generics or a declarative macro, you should use generics. Generics are generally more ergonomic than macros, and integrate much better with other constructs in the language. If you want a rule of thumb: if your code changes based on type, use generics; otherwise, use macros.*

## How They Work

Every programming language has a *grammar* that dictates how the individual characters that make up the source code can be turned into *tokens*. Tokens are the lowest-level building blocks of a language, such as numbers, punctuation characters, string and character literals, and identifiers; at this level, there's no distinction between language keywords and variable names. For example, the text `(value + 4)` would be represented by the five-token sequence `(, value, +, 4, )` in Rust-like grammar. The process of turning text into tokens also provides a layer of abstraction between the rest of the compiler and the gnarly low-level details of parsing text. For example, in the token representation there is no notion of whitespace, and `/*"foo"*/` and `/*foo*/` have distinct representations (the former is no token, the latter is a string literal token with the content `/*foo*/`).

Once the source code has been turned into a sequence of tokens, the compiler walks that sequence and assigns syntactic meaning to the tokens. For example, `()`-delimited tokens make up a group, `!` tokens denote macro invocations, and so on. This is the process of *parsing*, which ultimately produces an abstract syntax tree (AST) that describes the structure represented by the

source code. As an example, consider the expression `let x = || 4`, which consists of the sequence of tokens `let` (keyword), `x` (identifier), `=` (punctuation), 2 instances of `|` (punctuation), and `4` (literal). When the compiler turns that into a syntax tree, it represents it as a *statement* whose *pattern* is the *identifier* `x`, and whose right-hand side *expression* is a *closure* that has an empty *argument list* and a *literal expression* of the *integer literal* `4` as its body. Notice how the syntax tree representation is much richer than the token sequence, since it assigns syntactic meaning to the token combinations following the language’s grammar.

Rust macros dictate the syntax tree that a given sequence of tokens gets turned into—when the compiler encounters a macro invocation during parsing, it has to evaluate the macro to determine the replacement tokens, which will ultimately become the syntax tree for the macro invocation. At this point, however, the compiler is still parsing the tokens and might not be in a position to evaluate a macro yet, since all it has done is parse the tokens of the macro definition. Instead, then, the compiler defers the parsing of anything contained within the delimiters of a macro invocation, and remembers the input token sequence. When the compiler is ready to evaluate the indicated macro, it evaluates the macro over the token sequence, parses the tokens it yields, and substitutes the resulting syntax tree into the tree where the macro invocation was.

Technically, the compiler does do a little bit of parsing for the input to a macro. Specifically, it parses out basic things like string literals and delimited groups, and so produces a sequence of token *trees* rather than just tokens. For example, the code `x - (a.b + 4)` parses as a sequence of three token trees. The first token tree is a single token that is the identifier `x`, the second is a single token that is the punctuation character `-`, and the third is a group (using parentheses as the delimiter) which itself consists of a sequence of five token trees: `a` (an identifier), `.` (punctuation), `b` (another identifier), `+` (another punctuation token), and `4` (a literal). This means that the input to a macro does not necessarily have to be valid Rust, but it must consist of code that the Rust compiler can parse. For example, you couldn’t write `for <- x` in Rust outside of a macro invocation, but inside of a macro invocation you can, as long as the macro produces valid syntax. On the other hand, you cannot pass `{` to a macro due to the lack of a closing brace.

Declarative macros always generate valid Rust as output. You cannot have a macro generate, say, the first half of a function invocation or an `if` without the block that follows it. Concretely, a declarative macro must generate an expression (basically anything that you can assign to a variable), a statement such as `let x = 1;`, an item like a trait definition or `impl` block, and a type or a `match` pattern. This makes Rust macros fairly resistant to misuse: you simply cannot write a declarative macro that generates invalid Rust code, because the macro definition itself would not compile!

That’s really all there is to declarative macros at a high level—when the compiler encounters a macro invocation, it passes the tokens contained within the invocation delimiters to the macro, parses the resulting token stream, and replaces the macro invocation with the resulting AST.

## Writing Declarative Macros

An exhaustive explanation of all the syntax that declarative macros supports is outside the scope of this book. However, we'll cover the basics as there are some oddities that are worth pointing out.

Declarative macros consist of two main parts: *matchers* and *transcribers*. A given macro can have many matchers, and each matcher has an associated transcriber. When the compiler finds a macro invocation, it walks the macro's matchers from first to last, and when it finds a matcher that matches the tokens in the invocation, it substitutes the invocation by walking the tokens of the corresponding transcriber. Listing 8-4 shows how the different parts of a declarative macro rule fit together.

---

```
macro_rules! /* macro name */ {
  /* 1st matcher */ => { /* 1st transcriber */ };
  /* 2nd matcher */ => { /* 2nd transcriber */ };
}
```

---

Listing 8-4: Declarative macro definition components

### Matchers

You can think of a macro matcher as a token tree that the compiler tries to twist and bend in predefined ways to match the input token tree it was given at the invocation site. As an example, consider a macro with the matcher `$a:ident + $b:expr`. That matcher will match any identifier (`:ident`) followed by a plus sign followed by any Rust expression (`:expr`). If the macro is invoked with `x + 3 * 5`, the compiler notices that the matcher matches if it sets `$a = x` and `$b = 3 * 5`. Even though `*` never appears in the matcher, the compiler realizes that `3 * 5` is a valid expression, and that it can therefore be matched with `$b:expr`, which accepts anything that is an expression (the `:expr` part).

Matchers can get pretty hairy, but they have huge expressive power, much like regular expressions. For a not-too-hairy example, this matcher accepts a sequence `$(...)` of one or more `(+)` comma-separated `(,)` key/value pairs given in `key => value` format:

---

```
$( $key:expr => $value:expr ), +
```

---

And, crucially, code that invokes a macro with this matcher can give an arbitrarily complex expression for the key or value—the magic of matchers will make sure that the key and value expressions are partitioned appropriately.

Macro rules support a wide variety of *fragment types*; you've already seen `:ident` for identifiers and `:expr` for expressions, but there is also `:ty` for types, and even `:tt` for any single token tree! You can find a full list of the fragment types in Chapter 3 of the Rust language reference (<https://doc.rust-lang.org/reference/macros-by-example.html>). These, plus the mechanism for matching a pattern repeatedly `$(...)`, enable you to match most straightforward code patterns. If, however, you find that it is difficult to express the pattern you want with a matcher, you may want to try a procedural macro instead,

where you don't need to follow the strict syntax `macro_rules!` requires. We'll look at these in more detail later in the chapter.

## Transcribers

Once the compiler has matched a declarative macro matcher, it generates code using the matcher's associated transcriber. The variables defined by a macro matcher are called *metavariables*, and the compiler substitutes any occurrence of each metavariable in the transcriber (like `$key` in the example in the previous section) with the input that matches that part of the matcher. If you have repetition in the matcher (like `$(...)+` in that same example), you can use the same syntax in the transcriber and it will be repeated once for each match in the input, with each expansion holding the appropriate substitution for each metavariable for that iteration. For example, for the `$key` and `$value` matcher, we could write the following transcriber to generate an `insert` call into some `map` for each `$key/$value` pair that was matched:

---

```
$(map.insert($key, $value;))+
```

---

Notice that here we want a semicolon for each repetition, not just to delimit the repetition, so we place the semicolon inside the repetition parentheses. You must use a metavariable in each repetition in the transcriber so that the compiler knows which repetition in the matcher to use (in case there is more than one).

## Hygiene

You may have heard it said that Rust macros are *hygienic*, and perhaps that being hygienic makes them safer or nicer to work with, without necessarily understanding what that means. When we say Rust macros are hygienic, we mean that a declarative macro (generally) cannot affect variables that aren't explicitly passed to it. A trivial example is that if you declare a variable with the name `foo`, and then call a macro that also defines a variable named `foo`, the macro's `foo` is by default not visible at the call site (the place where the macro is called from). Similarly, macros cannot access variables defined at the call site (even `self`) unless they are explicitly passed in.

You can, most of the time, think of macro identifiers as existing in their own namespace that is separate from that of the code they expand into. For an example, take a look at the code in Listing 8-5, which has a macro that tries (and fails) to shadow a variable at the call site.

---

```
macro_rules! let_foo {
  ($x:expr) => {
    let foo = $x;
  }
}
let foo = 1;
let_foo!(2);
// expands to let foo = 2;
assert_eq!(foo, 1);
```

---

*Listing 8-5: Macros exist in their own little universes. Mostly.*

After the compiler expands `let_foo!(2)`, it looks like the `assert` should fail. However, the `foo` from the original code and the one generated by the macro exist in different universes, and have no relationship to one another beyond that they happen to share a human-readable name. In fact, the compiler will complain that the `let foo` in the macro is an unused variable. This hygiene is very helpful in making macros easier to debug—you don’t have to worry about accidentally shadowing or overwriting variables in the macro caller just because you happened to choose the same variable names!

This hygienic separation does not apply beyond variable identifiers, however. Declarative macros do share a namespace for types, modules, and functions with the call site. This means your macro can define new functions that can be called in the invoking scope, add new implementations to a type defined elsewhere (and not passed in), introduce a new module that can then be accessed where the macro was invoked, and so on. This is by design—if macros could not affect the broader code like this, it would be much more cumbersome to use them to generate types, trait implementations, and functions, which is where they come in most handy.

The lack of hygiene for types in macros is particularly important when writing a macro you want to export from your crate. For the macro to truly be reusable, you cannot assume anything about what types will be in scope at the caller. Maybe the code that calls your macro has a `mod std {}` defined, or has imported its own `Result` type. To be on the safe side, make sure you use fully specified types like `::core::option::Option` or `::alloc::boxed::Box`. Avoid using `::std` paths if you can so that the macro will continue to work in `no_std` crates. If you specifically need to refer to something in the crate that defines the macro, use the special metavariable `$crate`.

You can explicitly choose to share identifiers between a macro and its caller if you specifically want the macro to affect a variable in the caller’s scope. The key is to remember where the identifier originated, because that’s the namespace the identifier will be tied to. If you put `let foo = 1;` in a macro, the identifier `foo` originates in the macro and will never be available to the identifier namespace at the caller. If, on the other hand, the macro takes `$foo:ident` as an argument and then writes `let $foo = 1;`, when the caller invokes the macro with `!(foo)` the identifier will have originated in the caller and will therefore refer to `foo` in the caller’s scope.

The identifier does not have to be quite so explicitly passed, either; any identifier that appears in code that originates outside the macro will refer to the identifier in the caller’s scope. In the example in Listing 8-6 the variable identifier appears in an `:expr`, but nonetheless affects the variable in the caller’s scope.

---

```
macro_rules! please_set {
    ($i:ident, $x:expr) => {
        $i = $x;
    }
}
```



```
let mut x = 1;
please_set!(x, x + 1);
assert_eq!(x, 2);
```

---

*Listing 8-6: Giving macros access to identifiers at the call site*

We could have used `= $i + 1` in the macro instead, but we could not have used `= x + 1`, as the name `x` is not available in the macro's definition scope.

One last note on declarative macros and scoping: unlike pretty much everything else in Rust, declarative macros only exist in the source code after they are declared. If you try to use a macro that you define further down in the file, this will not work! This applies globally to your project; if you declare a macro in one module and want to use it in another, the module you declare the macro in must appear earlier in the crate, not later. Concretely, if `foo` and `bar` are modules at the root of a crate, and `foo` declares a macro that `bar` wants to use, then `mod foo` must appear before `mod bar` in *lib.rs*!

#### NOTE

*There is one exception to this odd scoping of macros (formally called textual scoping), and that is if you mark the macro with `#[macro_export]`. That annotation effectively hoists the macro to the root of the crate and marks it as `pub`, so that it can then be used anywhere in your crate or by your crate's dependents.*

## Procedural Macros

You can think of a procedural macro as a combination of a parser and code generation, where you write the glue code in between. At a high level, with procedural macros, the compiler gathers up the sequence of input tokens to the macro and runs your program to figure out what tokens to replace them with.

Procedural macros are so called because you define *how* to generate code given some input tokens, rather than just writing out what code gets generated. There are very few smarts involved on the compiler's side—as far as it is aware the procedural macro is more or less a source code preprocessor that may perform arbitrary code replacement. The requirement that your input can be parsed as a stream of Rust tokens still holds, but that's about it!

### Types of Procedural Macros

Procedural macros come in three different flavors, each specialized to a particular common use case:

- Function-like macros, like the ones that `macro_rules!` generates
- Derive macros, like `#[derive(Serialize)]`
- Attribute macros, like `#[test]`

All three types use the same underlying mechanism: the compiler provides your macro with a sequence of tokens, and it expects you to produce

a sequence of tokens in return that are (probably) related to the input tree. However, they differ in how the macro is invoked and how its output is handled. We'll cover each one briefly next.

### Function-Like Macros

The function-like macro is the simplest form of procedural macro. Like a declarative macro, it simply replaces the macro code at the call site with the code that the procedural macro returns. However, unlike with declarative macros, all the guard rails are off: these macros (like all procedural macros) are not required to be hygienic and will not protect you from interacting with identifiers in the surrounding code at the call site. Instead, your macros are expected to explicitly call out which identifiers should overlap with the surrounding code (using `Span::call_site`) and which should be treated as private to the macro (using `Span::mixed_site`, which we'll discuss later).

### Attribute Macros

The attribute macro also replaces the item that the attribute is assigned to wholesale, but this one takes two inputs: the token tree that appears in the attribute (minus the attribute's name) and the token tree of the entire item it is attached to, including any other attributes that item may have. Attribute macros allow you to easily write a procedural macro that transforms an item, such as by adding a prelude or epilogue to a function definition (like `#[test]` does) or modifying the fields of a struct.

### Derive Macros

The derive macro is slightly different from the other two in that it adds to, rather than replaces, the target of the macro. Even though this limitation may seem severe, derive macros were one of the original motivating factors behind the creation of procedural macros. Specifically, the well-known `serde` crate needed derive macros to be able to implement its now-well-known `#[derive(Serialize, Deserialize)]` magic.

Derive macros are arguably the simplest of the procedural macros, since they have such a rigid form: you can only append items after the annotated item; you can't replace the annotated item, and you cannot have the derivation take arguments. Derive macros do allow you to define *helper attributes*—attributes that can be placed inside the annotated type to give clues to the derive macro (like `#[serde(skip)]`)—but these function mostly like markers, and are not independent macros.

### The Cost of Procedural Macros

Before we talk about when each of the different procedural macro types is appropriate, it's worth discussing why you may want to think twice before you reach for a procedural macro—namely, increased compile time.

Procedural macros can significantly increase compile times for two main reasons. The first is that they tend to bring with them some pretty

heavy dependencies. For example, the `syn` crate, which provides a parser for Rust token streams that makes the experience of writing procedural macros much easier, can take tens of seconds to compile with all features enabled. This can (and should) be mitigated by disabling features you do not need, and compiling your procedural macros in debug mode rather than release mode. Code often compiles several times faster in debug mode, and for most procedural macros you won't even notice the difference in execution time.

The second reason is that procedural macros make it easy to generate a lot of code without realizing it. While the macro saves you from having to actually type the generated code, it does not save the compiler from having to parse, compile, and optimize it. As you use more procedural macros, that generated boilerplate adds up, and it can bloat your compile times.

It's worth pointing out that the actual execution time of procedural macros is rarely a factor in overall compile time. While the compiler has to wait for the procedural macro to do its thing before it can continue, in practice most procedural macros do not do any heavy computation. That said, if your procedural macro is particularly involved, you may end up with your compiler spending a significant chunk of execution time on your procedural macro code, which is worth keeping an eye out for!

## ***So You Think You Want a Macro***

Let's now look at some good use cases for each type of procedural macro. We'll start with the easy one: derive macros.

### **When to Use Derive Macros**

Derive macros are for used one thing, and one thing only: to automate the implementation of a trait where automation is possible. Not all traits have obvious automated implementations, but many do. In practice, you should consider adding a derive macro for a trait only if the trait is implemented often and if its implementation for any given type is fairly obvious. The first of these points may seem like common sense; if your trait is only going to be implemented once or twice, it's probably not worth writing and maintaining a convoluted derive macro for it.

The second may seem stranger, however: what does it mean for the implementation to be "obvious"? Consider a trait like `Debug`. If you were told what `Debug` does and shown a type, you would probably expect an implementation of `Debug` to output the name of each field alongside the debug representation of its value. And that's what `derive(Debug)` does. What about `Clone`? You'd probably expect it to just clone every field—and again, that's what `derive(Clone)` does. With `derive(serde::Serialize)`, we expect it to serialize every field and its value, and it does just that. In general, you want the derivation of a trait to match the developer's intuition for what it probably does. If there is no obvious derivation for a trait, or worse yet, if your derivation does not match the obvious implementation, then you're probably better off not giving it a derive macro.

## When to Use Function-Like Macros

Function-like procedural macros are harder to give a general rule of thumb for. You might say you should use function-like macros when you want a function-like macro but can't express it with `macro_rules!`, but that's a fairly subjective guideline. You can do a lot with declarative macros if you really put your mind to it, after all!

There are two particularly good reasons to reach for a function-like procedural macro:

- If you already have a declarative macro, and its definition is becoming so hairy that the macro is hard to maintain.
- If you have a pure function that you need to be able to execute at compile time, but cannot express with `const fn`. An example of this is the `phf` crate, which generates a hash map or set using a perfect hash function when given a set of keys provided at compile time. Another is `hex-literal`, which takes a string of hexadecimal characters and replaces it with the corresponding bytes. In general, anything that does not merely transform the input at compile time but actually computes over it is likely to be a good candidate.

I will also add that I do not recommend reaching for a function-like procedural macro just so that you can break hygiene within your macro. Hygiene for function-like macros is a feature that avoids many debugging headaches, and you should think very carefully before you intentionally break it.

## When to Use Attribute Macros

That leaves us with attribute macros. Though these are arguably the most general of procedural macros, it's also hardest to pin down when they are appropriate. Over the years, I have seen four use cases come up time and time again as examples of attribute procedural macros adding tremendous value:

### Test generation

It is very common to want to run the same test under multiple different configurations, or many similar tests with the same bootstrapping code. While a declarative macro may let you express this, your code is often easier to read and maintain if you have an attribute like `#[foo_test]` that introduces a setup prelude and postscript in each annotated test, or a repeatable attribute like `#[test_case(1)]` `#[test_case(2)]` to mark that a given test should be repeated multiple times, once with each input.

### Framework annotations

Libraries like `rocket` use attribute macros to augment functions and types with additional information that the framework then makes use of without the user having to do a lot of manual configuration. It's so much more convenient to be able to write `#[get("/<name>")] fn`

`hello(name: String)` than to have to set up a configuration struct with function pointers and the like. Essentially, the attributes make up a miniature domain-specific language (DSL) that hides a lot of boilerplate that'd otherwise be necessary. Similarly, the asynchronous I/O framework `tokio` lets you use `#[tokio::main] async fn main()` to automatically set up a runtime and run your asynchronous code, and thereby saves you from writing the same runtime setup in every asynchronous application's main function.

## Transparent middleware

Some libraries want to inject themselves into your application in unobtrusive ways to provide added value that does not change the application's functionality. For example, tracing and logging libraries like `tracing` and metric collection libraries like `metered` allow you to transparently instrument a function by adding an attribute to it, and then every call to that function will run some additional code dictated by the library.

## Type transformers

Sometimes you want to go beyond merely deriving traits for a type, and actually change the type's definition in some fundamental way. In these cases, attribute macros are the way to go. The `pin_project` crate is a great example of this: its primary purpose is not to implement a particular trait, but rather to ensure that all pinned access to fields of a given type happens according to the strict rules that are set forth by Rust's `Pin` type and the `Unpin` trait (we'll talk more about those types in [Chapter 9](#)). It does this by generating additional helper types, adding methods to the annotated type, and introducing static safety checks to ensure that users don't accidentally shoot themselves in the foot. While `pin_project` could have been implemented with a procedural derive macro, that would likely violate the expectation that a derived trait implementation is obvious.

## How Do They Work?

At the heart of all procedural macros is the `TokenStream` type, which can be iterated over to get the individual `TokenTree` items that make up that token stream. A `TokenTree` is either a single token—like an identifier, punctuation, or a literal—or another `TokenStream` enclosed in a delimiter like `()` or `{}`. By walking a `TokenStream`, you can parse out whatever syntax you wish as long as the individual tokens are valid Rust tokens. If you specifically want to parse your input as Rust code you likely want to use the `syn` crate, which implements a complete Rust parser and can turn a `TokenStream` into an easy-to-traverse Rust AST.

With most procedural macros you not only want to parse a `TokenStream`, but also to produce Rust code to be injected into the program that invokes the procedural macro. There are two main ways to do so. The first is to manually construct a `TokenStream` and extend it one `TokenTree` at a time. The second

is to use `TokenStream`'s implementation of `FromStr`, which lets you parse a string that contains Rust code into a `TokenStream` with `".parse::<TokenStream>()"`. You can also mix and match these; if you want to prepend some code to your macro's input, just construct a `TokenStream` for the prologue, and then use the `Extend` trait to append the original input.

**NOTE**

*`TokenStream` also implements `Display`, which pretty-prints the tokens in the stream. This comes in super handy for debugging!*

Tokens are very slightly more magical than I've described so far, in that every token, and indeed every `TokenTree`, also has a *span*. Spans are how the compiler ties generated code back to the source code that generated that code. Every token's span marks the original source location that token comes from. For example, consider a macro like the one in Listing 8-7, which generates a trivial `Debug` implementation for the provided type.

---

```
macro_rules! name_as_debug {
    ($t:ty) => {
        impl ::core::fmt::Debug for $t {
            fn fmt(&self, f: &mut ::core::fmt::Formatter<'_>) -> ::core::fmt::Result
            {
                ::core::write!(f, ::core::stringify!($t))
            }
        }
    }
}
```

---

*Listing 8-7: A very simple macro for implementing `Debug`*

Now let's imagine that someone invokes this macro with `name_as_debug!(u31)`. Technically, the compiler error occurs inside the macro, and specifically where we write `for $t` (the other use of `$t` can handle an invalid type). But we'd like the compiler to point the user at the `u31` in their code—and indeed, that's what spans let us do.

The span of the `$t` in the generated code is the code mapped to `$t` in the macro invocation. That information is then carried through the compiler and associated with the eventual compiler error. When that compiler error is eventually printed, the compiler will print the error from inside the macro saying that the type `u31` does not exist, but will highlight the `u31` argument in the macro invocation, since that's the error's associated span!

Spans are quite flexible, and they enable you to write procedural macros that can produce sophisticated error messages through the use of the `compile_error` macro. As its name implies, `compile_error!` causes the compiler to emit an error wherever it is placed with the provided string as the message. This may not seem very useful, until you pair it with a span. By setting the span of the `TokenTree` you generate for the `compile_error!` invocation to be equal to the span of some subset of the input, you are effectively telling the compiler “emit this compiler error, and point the user at this part of their source.” Together, these two mechanisms let a macro produce errors that seem to stem from the relevant part of the code, even though the actual compiler error is somewhere in the generated code that the user never even sees!

**NOTE**

*If you’ve ever been curious how `syn`’s error handling works, its `Error` type implements an `Error::to_compile_error` method which turns it into a `TokenStream` that holds only a `compile_error!` directive. What’s particularly neat with `syn`’s `Error` type is that it internally holds a collection of errors, each of which produces a distinct `compile_error!` directive with its own span so that you can easily produce multiple independent errors from your procedural macro.*

The power of spans doesn’t end there; spans are also how Rust’s macro hygiene is implemented. When you construct an `Ident` token, you also give the span for that identifier, and that span dictates the scope of that identifier. If you set the identifier’s span to be `Span::call_site()`, the identifier is resolved where the macro was called from, and will thus not be isolated from the surrounding scope. If, on the other hand, you set it to `Span::mixed_site()`, then (variable) identifiers are resolved at the macro definition site, and so will be completely hygienic with respect to similarly named variables at the call site. `Span::mixed_site` is so called because it matches the rules around identifier hygiene for `macro_rules!`, which as we discussed earlier is “mixed” between resolving identifiers at the call site and the macro definition site.

## Summary

In this chapter we covered both declarative and procedural macros and looked at when you might find each of them useful in your own code. We also took a deeper dive into the mechanisms that underpin each type of macro, and some of the features and gotchas to be aware of when you write your own macros. In the next chapter, we’ll start our journey into asynchronous programming and the `Future` trait. I promise—it’s just on the next page.





# 9

## ASYNCHRONOUS PROGRAMMING



Asynchronous programming is, as the name implies, programming that is not synchronous. At a high level, an asynchronous operation executes in the background—the program won't wait for the asynchronous operation to complete, but will instead continue on to the next line of code immediately. If you're not already familiar with asynchronous programming, that definition may feel insufficient as it doesn't actually explain what asynchronous programming *is*. To really understand the asynchronous programming model and how it works in Rust, we have to first dig into what the alternative is. That is, we need to understand the *synchronous* programming model before we can understand the *asynchronous* one. This is important in both clarifying the concepts and demonstrating the trade-offs of using asynchronous programming: an asynchronous solution is not always the right one! We'll

start this chapter by taking a quick journey through what motivates asynchronous programming as a concept in the first place; then we'll dig into how asynchrony in Rust actually works under the hood.

## What's the Deal with Asynchrony?

Before we get to the details of the synchronous and asynchronous programming models, we first need to take a quick look at what your computer is actually doing when it runs your programs.

Computers are fast. Really fast. So fast, in fact, that they spend most of their time waiting for things to happen. Unless you're decompressing files, encoding audio, or crunching numbers, chances are that your CPU spends most of its time sitting idle, waiting for operations to complete. It's waiting for a network packet to arrive, for the mouse to move, for the disk to finish writing some bytes, or maybe even just for a read from main memory to complete. From the CPU's perspective, eons go by between most such events. When one does occur, the CPU runs a few more instructions, then goes back to waiting again. Take a look at your CPU utilization—it's probably somewhere in the low single digits, and that's likely where it hovers the majority of the time.

### *Synchronous Interfaces*

Synchronous interfaces only allow your program (or rather, a single thread in your program) to execute a single operation at a time; each operation has to wait for the previous synchronous operation to finish before it gets to run. Most interfaces you see in the wild are synchronous: you call them, they go do some stuff, and eventually they return when the operation has completed and your program can continue from there. The reason for this, as we'll see later in this chapter, is that making an operation asynchronous takes a fair bit of extra machinery. Unless you need the benefits of asynchrony, sticking to the synchronous model requires much less pomp and circumstance.

Synchronous interfaces hide all this waiting; the application calls a function that says “write these bytes to this file,” and some time later, that function completes and the next line of code executes. Behind the scenes, what really happens is that the operating system queues up a write operation to the disk, and then puts the application to sleep until the disk reports that it has finished the write. The application experiences this as the function taking a long time to execute, but in reality it isn't really executing at all, just waiting.

An interface that performs operations sequentially in this way is also often referred to as *blocking*, since the operation in the interface that has to wait for some external event to happen in order for it to make progress blocks further execution until that event happens. Whether you refer to an interface as synchronous or blocking, the basic idea is the same: the application does not move on until the current operation finishes. While the operation is waiting, so is the application.

Synchronous interfaces are usually considered to be easy to work with and simple to reason about, since your code just executes one line at a time.

But they also only allow the application to do one thing at a time. That means if you want your program to wait for either user input or a network packet, you're out of luck unless your operating system provides an operation specifically for that. Similarly, even if your application could do some other useful work while the disk is writing out a file, it doesn't have that option as the file write operation blocks the execution!

## ***Enabling Concurrency with Multithreading***

By far the most common solution to allowing concurrent execution is to use *multithreading*. In a multithreaded program, each thread is responsible for executing a particular independent sequence of blocking operations, and the operating system multiplexes among the threads so that if any thread can make progress, progress is made. If one thread blocks, some other thread may still be runnable, and so the application can continue to do useful work.

Usually, these threads communicate with each other using a synchronization primitive like a lock or a channel so that the application can still coordinate their efforts. For example, you might have one thread that waits for user input, one thread that waits for network packets, and another thread that waits for either of those threads to send a message on a channel shared between all three threads.

Multithreading gives you *concurrency*—the ability to have multiple independent operations that can be executed at any one time. It's up to the system running the application (in this case, the operating system) to choose among the threads that aren't blocked and decide which to execute next. If one thread is blocked, it can choose to run another one that can make progress instead.

Multithreading combined with blocking interfaces gets you quite far, and large swaths of production-ready software are built in this way. But this approach is not without its shortcomings. First, keeping track of all these threads quickly gets cumbersome; if you have to spin up a thread for every concurrent task, including simple ones like waiting for keyboard input, the threads add up fast, and so does the additional complexity needed to keep track of how all those threads interact, communicate, and coordinate.

Second, switching between threads gets costly the more of them there are. Every time one thread stops running and another one starts back up in its place, you need to do a round-trip to the operating system scheduler, and that's not free. On some platforms, spawning new threads is also a fairly heavyweight process. Applications with high performance needs often mitigate this cost by reusing threads and using operating system calls that allow you to block on many related operations, but ultimately you are left with the same problem: blocking interfaces require that you have as many threads as the number of blocking calls you want to make.

Finally, threads introduce *parallelism* into your program. The distinction between concurrency and parallelism is subtle, but important: concurrency means that the execution of your tasks is interleaved, whereas parallelism means that multiple tasks are executing at the same time. If you have two

tasks, expressed in ASCII it might look like `_ _ _` (concurrency) versus `====` (parallelism). Multithreading does not necessarily imply parallelism—even though you have many threads, you might only have a single core, so only one thread is executing at a given time—but the two usually go hand-in-hand. You can make two threads mutually exclusive in their execution by using a `Mutex` or other synchronization primitive, but that introduces additional complexity—threads want to run in parallel. And while parallelism is often a good thing—who doesn’t want their program to run faster on more cores—it also means that your program must handle truly simultaneous access to shared data structures. This means moving from `Rc`, `Cell`, and `RefCell` to the more powerful, but also slower `Arc` and `Mutex`. While you *may* want to use the latter types in your concurrent program to enable parallelism, threading *forces* you to use them.

## Asynchronous Interfaces

Now that we’ve explored synchronous interfaces, we can look at the alternative: asynchronous or *nonblocking* interfaces. An asynchronous interface is one that may not yield a result straight away, and may instead indicate that the result will be available at some later time. This gives the caller the opportunity to do something else in the meantime, rather than having to go to sleep until that particular operation completes. In Rust parlance, an asynchronous interface is a method that returns a `Poll`, as defined in Listing 9-1.

---

```
enum Poll<T> {
    Ready(T),
    Pending
}
```

---

*Listing 9-1: The core of asynchrony: the “here you are or come back later” type*

`Poll` usually shows up in the return type of functions whose names start with `poll`—these are methods that signal that they can attempt an operation without blocking. We’ll get into how exactly they do that later in this chapter, but in general they attempt to perform as much as they can of the operation before they would normally block, and then return. Crucially, they remember where they left off so that they can resume execution later when additional progress can again be made.

These nonblocking functions allow us to easily perform multiple tasks concurrently. For example, if you want to read from either the network or the user’s keyboard, whichever has an event available first, all you have to do is poll both in a loop until one of them returns `Poll::Ready`. No need for any additional threads or synchronization!

The word “loop” here should make you a little nervous. You don’t want your program to burn through a loop three billion times a second when it may be minutes until the next input occurs. In the world of blocking interfaces this wasn’t a problem since the operating system simply put the thread to sleep and then took care of waking it up when a relevant event occurred, but how do we avoid burning cycles while waiting in this brave new nonblocking world? That’s what much of the remainder of this chapter will be about.

## Standardized Polling

To get to a world where every library can be used in a nonblocking fashion, we could have every library author cook up their own `poll` methods, all with slightly different names, signatures, and return types—but that would quickly get unwieldy. Instead, in Rust, this is standardized through the `Future` trait. A simplified version of `Future` is shown in Listing 9-2 (we’ll get back to the real one later in this chapter).

---

```
trait Future {
    type Output;
    fn poll(&mut self) -> Poll<Self::Output>;
}
```

---

*Listing 9-2: A simplified view of the `Future` trait*

Types that implement the `Future` trait are known as *futures* and represent values that may not be available yet. A future could represent the next time a network packet comes in, the next time the mouse cursor moves, or just after some amount of time has elapsed. You can read `Future<Output = Foo>` as “a type that will produce a `Foo` in the future.” Types like this are often referred to in other languages as *promises*—they promise that they will eventually yield the indicated type. When a future eventually returns `Poll::Ready(T)`, we say that the future *resolves* into a `T`.

With this trait in place, we can generalize the pattern of providing `poll` methods. Instead of having methods like `poll_recv` and `poll_keypress`, we can have methods like `recv` and `keypress` that both return `impl Future` with an appropriate `Output` type. This doesn’t change the fact that you have to poll them—we’ll deal with that later—but it does mean that at least there is a standardized interface to these kinds of pending values, and we don’t need to use the `poll_` prefix everywhere.

### NOTE

*In general, you should not poll a `Future` again after it has returned `Poll::Ready`. If you do, the `Future` is well within its rights to panic. A `Future` that is safe to poll after it has returned `Ready` is sometimes referred to as a fused `Future`.*

## Ergonomic Futures

Writing a type that implements `Future` in the way I’ve described so far is quite a pain. To see why, first take a look at the fairly straightforward asynchronous code block in Listing 9-3 that simply tries to forward messages from the input channel `rx` to the output channel `tx`.

---

```
async fn forward<T>(rx: Receiver<T>, tx: Sender<T>) {
    while let Some(t) = rx.next().await {
        tx.send(t).await;
    }
}
```

---

*Listing 9-3: Implementing a channel-forwarding future using `async` and `await`*

This code looks very similar to its equivalent synchronous code, and is easy to read. We simply send each message we receive in a loop until there are no more messages, and each `await` point corresponds to a place where a synchronous variant might block. Now think about if you instead had to express this code by manually implementing the `Future` trait. Since each call to `poll` starts at the top of the function, you'd need to package up the necessary state to continue from the last place the code yielded. The result is fairly grotesque, as Listing 9-4 demonstrates.

---

```
enum Forward<T> { ❶
    WaitingForReceive(ReceiveFuture<T>, Option<Sender<T>>),
    WaitingForSend(SendFuture<T>, Option<Receiver<T>>),
}

impl<T> Future for Forward<T> {
    type Output = (); ❷
    fn poll(&mut self) -> Poll<Self::Output> {
        match self { ❸
            Forward::WaitingForReceive(recv, tx) => {
                if let Poll::Ready((rx, v)) = recv.poll() {
                    if let Some(v) = v {
                        let tx = tx.take().unwrap(); ❹
                        *self = Forward::WaitingForSend(tx.send(v), Some(rx)); ❺
                        // Try to make progress on sending.
                        return self.poll(); ❻
                    } else {
                        // No more items.
                        Poll::Ready(())
                    }
                } else {
                    Poll::Pending
                }
            }
            Forward::WaitingForSend(send, rx) => {
                if let Poll::Ready(tx) = send.poll() {
                    let rx = rx.take().unwrap();
                    *self = Forward::WaitingForReceive(rx.receive(), Some(tx));
                    // Try to make progress on receiving.
                    return self.poll();
                } else {
                    Poll::Pending
                }
            }
        }
    }
}
```

---

*Listing 9-4: Manually implementing a channel-forwarding future*

You'll rarely have to write code like this in Rust any more, but it gives important insight into how things work under the hood, so let's walk through it. First, we define our future type as an enum ❶, which we'll use to keep track of what we're currently waiting on. This is a consequence of the

fact that when we return `Poll::Pending`, the next call to `poll` will start at the top of the function again. We need some way to know what we were in the middle of so that we know what operation to continue on. Furthermore, we need to keep track of different information depending on what we're doing: if we're waiting for a receive to finish we need to keep that `ReceiveFuture` (the definition of which is not shown in this example) around so that we can poll it the next time we are polled ourselves, and similar for `SendFuture`. The `Options` here might strike you as weird too; we'll get back to those shortly.

When we implement `Future` for `Forward`, we declare its output type as `()` ❷ because this future doesn't actually return anything. Instead, the future resolves (with no result) when it has finished forwarding everything from the input channel to the output channel. In a more complete example, the `Output` of our forwarding type might be a `Result` so that it could communicate errors from `receive()` and `send()` back up the stack to the function that's polling for the completion of the forwarding. But this code is complicated enough already, so we'll leave that for another day.

When `Forward` is polled, it needs to resume wherever it last left off, which we find out by matching on the enum variant currently held in `self` ❸. Whichever branch we go into, the first step is to poll the future that blocks progress for the current operation; if we're trying to receive we poll the `ReceiveFuture`, and if we're trying to send we poll the `SendFuture`. If that call to `poll` returns `Poll::Pending`, then we can make no progress, and we return `Poll::Pending` ourselves. But if the current future resolves, we have work to do!

When one of the inner futures resolves, we need to update what the current operation is by switching which enum variant is stored in `self`. In order to do so, we have to move out of `self` to call `Receiver::receive` or `Sender::send`—but we can't do that because all we have is `&mut self`. So, we store the state we have to move in an `Option`, which we move out of with `Option::take` ❹. This is silly since we're about to overwrite `self` anyway ❺, and hence the `Options` will always be `Some`, but sometimes tricks are needed to make the borrow checker happy.

Finally, if we do make progress, we then poll `self` again ❻ so that if we can immediately make progress on the pending send or receive, we do so. This is actually necessary for correctness when implementing the real `Future` trait, which we'll get back to later, but for now think of this as an optimization.

We just hand-wrote a *state machine*: a type that has a number of possible states, and moves between them in response to particular events. This was a fairly simple state machine, at that. Imagine having to write code like this for more complicated use cases where you have additional intermediate steps!

Beyond writing the unwieldy state machine, we have to know the types of the futures that `Sender::send` and `Receiver::receive` return so that we can store them in our type. If those methods instead returned `impl Future`, we'd have no way to write out the types for our variants. The `send` and `receive` methods also have to take ownership of the sender and the receiver; if they did not, the lifetimes of the futures they returned would be tied to the

borrow of `self`, which would end when we return from `poll`. But that would not work, since we’re trying to store those futures *in* `self`.

#### NOTE

*You may have noticed that `Receiver` looks a lot like an asynchronous version of `Iterator`. Others have noticed the same thing, and the standard library is on its way to adding a trait specifically for types that can meaningfully implement `poll_next`. Down the line, these asynchronous iterators (often referred to as streams) may end up with first-class language support, such as the ability to loop over them directly!*

Ultimately, this code is hard to write, hard to read, and hard to change. If we wanted to add error handling, for example, the code complexity would increase significantly. Luckily, there’s a better way!

## async/await

Rust 1.39 gave us the `async` keyword and the closely related `await` postfix operator, which we used in the original example in Listing 9-3. Together, they provide a much more convenient mechanism for writing asynchronous state machines like the one in Listing 9-5. Specifically, they let you write the code in such a way that it doesn’t even look like a state machine!

---

```
async fn forward<T>(rx: Receiver<T>, tx: Sender<T>) {
    while let Some(t) = rx.next().await {
        tx.send(t).await;
    }
}
```

---

*Listing 9-5: Implementing a channel-forwarding future using `async` and `await`, repeated from Listing 9-3*

If you don’t have much experience with `async` and `await`, the difference between Listing 9-3 and Listing 9-5 might give you an idea of why the Rust community was so excited to see them land. But since this is an intermediate book, let’s dive a little deeper to understand just how this short segment of code can replace the much longer manual implementation. To do that, we first need to talk about *generators*—the mechanism by which `async` and `await` are implemented.

## Generators

A generator is, briefly described, a chunk of code with some extra compiler-generated bits that enables it to stop, or *yield*, its execution midway through, and then resume from where it last yielded later on. Take the `forward` function in Listing 9-3, for example. Imagine that it gets to the call to `send`, but the channel is currently full. The function can’t make any more progress, but it also cannot block (this is nonblocking code, after all), so it needs to return. Now suppose the channel eventually clears up, and we want to proceed with the `send`. If we call `forward` again from the top, it’ll call `next` again and the item we previously tried to send will be lost, so that’s no good. Instead, we turn `forward` into a generator.



Whenever the forward generator cannot make progress anymore, it needs to store its current state somewhere so that when its execution eventually resumes, it resumes in the right place with the right state. It saves the state through an associated data structure that's generated by the compiler, which contains all the state of the generator at a given point in time. A method on that data structure (also generated) then allows the generator to resume from its current state, stored in `&mut self`, and updates the state again when the generator again cannot make progress.

This “return but allow me to resume later” operation is called *yielding*, which effectively means it returns while keeping some extra state on the side. When we later want to resume a call to `forward`, we invoke the known entry point into the generator (the *resume method*, which is `poll` for `async` generators), and the generator inspects the previously stored state in `self` to decide what to do next. This is exactly the same thing we did manually in Listing 9-4! In other words, the code in Listing 9-3 loosely desugars to the hypothetical code shown in Listing 9-6.

---

```
generator fn forward<T>(rx: Receiver<T>, tx: Sender<T>) {
    loop {
        let mut f = rx.next();
        let r = if let Poll::Ready(r) = f.poll() { r } else { yield };
        if let Some(t) = r {
            let mut f = tx.send(t);
            let _ = if let Poll::Ready(r) = f.poll() { r } else { yield };
        } else { break Poll::Ready(()); }
    }
}
```

---

*Listing 9-6: Desugaring `async/await` into a generator*

At the time of writing, generators are not actually usable in Rust—they are only used internally by the compiler to implement `async/await`—but that may change in the future. Generators come in handy in a number of cases, such as to implement iterators without having to carry around a struct, or an `impl Iterator` that figures out how to yield items one at a time.

If you look closely at Listings 9-3 and 9-5, they may seem a little magical once you know that every `await` or `yield` is really a return from the function. After all, there are several local variables in the function, and it's not clear how they're restored when we resume later on. This is where the compiler-generated part of generators comes into play. The compiler transparently injects code to persist those variables into and read them from the generator's associated data structure, rather than the stack, at the time of execution. So if you declare, write to, or read from some local variable `a`, you are really operating on something akin to `self.a`. Problem solved! It's all really quite marvelous.

One subtle but important difference between the manual forward implementation and the `async/await` version is that the latter can hold references across yield points. This enables functions like `Receiver::next` and `Sender::send` in Listing 9-5 to take `&mut self` rather than the `self` they took in Listing 9-3. If we tried to use a `&mut self` receiver for these methods in the manual state

machine implementation, the borrow checker would have no way to enforce that the Receiver stored inside `Forward` cannot be referenced between when `Receiver::next` is called and when the future it returns resolves, and so it would reject the code. Only by moving the Receiver into the future can we convince the compiler that the Receiver is not otherwise accessible. Meanwhile, with `async/await`, the borrow checker can inspect the code before the compiler turns it into a state machine and verify that `rx` is indeed not accessed again until after the future is dropped, when the `await` on it returns.

### THE SIZE OF GENERATORS

The data structure used to back a generator's state must be able to hold the combined state at any one yield point. If your `async fn` contains, say, a `[u8; 8192]`, those 8 KiB must be stored in the generator itself. Even if your `async fn` only contains smaller local variables, it must also contain any future that it awaits, since it needs to be able to poll such a future later, when `poll` is invoked.

This nesting means that generators, and thus futures based on `async` functions and blocks, can get quite large without any visible indicator of that increased size in your code. This can in turn impact your program's runtime performance, since those giant generators may have to be copied across function calls and in and out of data structures, which amounts to a fair amount of memory copying. In fact, you can usually identify when the size of your generator-based futures is affecting performance by looking for excessive amounts of time spent in the `memcpy` function in your application's performance profiles!

Finding these large futures isn't always easy, however, and often requires manually identifying long or complex chains of `async` functions. Clippy may be able to help with this in the future, but at the time of writing, you're on your own. When you do find a particularly large future, you have two options: you can try to reduce the amount of local state the `async` functions need, or you can move the future to the heap (with `Box::pin`), so that moving the future just requires moving the pointer to it. The latter is by far the easiest way to go, but also introduces an extra allocation and a pointer indirection. Your best bet is usually to put the problematic future on the heap, measure your performance, and then use your performance benchmarks to guide you from there.

### *Pin and Unpin*

We're not quite done. While generators are neat, a challenge arises from the technique as I've described it so far. In particular, it's not clear what happens if the code in the generator (or, equivalently, the `async` block) takes a reference to a local variable. In the code from Listing 9-5, the future that `rx.next()` returns must necessarily hold a reference to `rx` if a next message is not immediately available so that it knows where to try again when the generator next resumes. When the generator yields, the future and the reference the future contains get stashed away inside the generator. But

what now happens if the generator is moved? Specifically, look at the code in Listing 9-7 which calls forward.

---

```
async fn try_forward<T>(rx: Receiver<T>, tx: Sender<T>) -> Option<impl Future>
{
    let mut f = forward(rx, tx);
    if f.poll().is_pending() { Some(f) } else { None }
}
```

---

*Listing 9-8: Moving a future after polling it*

The `try_forward` function only polls forward once, to forward as many messages as possible without blocking. If the receiver may still produce more messages (that is, if it returned `Poll::Pending` instead of `Poll::Ready(None)`), those messages are deferred to be forwarded at some later time by returning the forwarding future to the caller, which may choose to poll again at a time when it sees fit.

Let's work through what happens here with what we know about `async` and `await` so far. When we poll the forward generator, it goes through the while loop some unknown number of times and eventually returns either `Poll::Ready()` if the receiver ended, or `Poll::Pending` otherwise. If it returns `Poll::Pending`, the generator contains a future returned from either `rx.next()` or `tx.send(t)`. Those futures both contain a reference to one of the arguments initially provided to `forward` (`rx` and `tx`, respectively), which must also be stored in the generator. But when `try_forward` returns the entire generator, the fields of the generator also move. Thus, `rx` and `tx` no longer reside at the same locations in memory, and the references stored in the stashed-away future are no longer pointing to the right data!

What we've run into here is a case of a *self-referential* data structure: one that holds both data and references into that data. With generators, these self-referential structures are very easy to construct, and being unable to support them would be a significant blow to ergonomics because it would mean you wouldn't be able to hold references across any yield point. The (ingenious) solution for supporting self-referential data structures in Rust comes in the form of the `Pin` type and the `Unpin` trait. Very briefly, `Pin` is a wrapper type that prevents the wrapped type from being (safely) moved, and `Unpin` is a marker trait that says that the implementing type *can* be removed safely from a `Pin`.

## Pin

There's a lot of nuance to cover here, so let's start with a concrete example of the wrapper `Pin`. In Listing 9-2 I gave you a simplified version of the `Future` trait, but we're now ready to peel back one part of the simplification. Listing 9-8 shows the `Future` trait somewhat closer to its final form.

---

```
trait Future {
    type Output;
    fn poll(self: Pin<&mut Self>) -> Poll<Self::Output>;
}
```

---

*Listing 9-8: A less simplified view of the Future trait with Pin*

In particular, this definition requires that you call `poll` on `Pin<&mut Self>`. Once you have a value behind a `Pin`, that constitutes a contract that that value will never move again. This means that you can construct self-references internally to your heart’s delight, exactly as you want for generators.

**NOTE**

While *Future* makes use of *Pin*, *Pin* is not tied to the *Future* trait—you can use *Pin* for any self-referential data structure.

But how do you get a `Pin` to call `poll`? And how can `Pin` ensure that the contained value won’t move? To see how this magic works, let’s look at the definition of `std::pin::Pin` and some of its key methods, shown in Listing 9-9.

---

```

struct Pin<P> { pointer: P }
impl<P> Pin<P> where P: Deref {
    pub unsafe fn new_unchecked(pointer: P) -> Self;
}
impl<'a, T> Pin<&'a mut T> {
    pub unsafe fn get_unchecked_mut(self) -> &'a mut T;
}
impl<P> Deref for Pin<P> where P: Deref {
    type Target = P::Target;
    fn deref(&self) -> &Self::Target;
}

```

---

Listing 9-9: `std::pin::Pin` and its key methods

There’s a lot to unpack here, and we’re going to have to go over the definition in Listing 9-9 a few times before all the bits make sense, so please bear with me.

First, you’ll notice that `Pin` holds a *pointer type*. That is, rather than hold some `T` directly, it holds a type `P` that dereferences through `Deref` into `T`. This means that rather than have a `Pin<MyType>`, you’ll have a `Pin<Box<MyType>>` or `Pin<Rc<MyType>>` or `Pin<&mut T>`. The reason for this design is simple—`Pin`’s primary goal is to make sure that once you place a `T` behind a `Pin`, that `T` won’t move, as doing so might invalidate self-references stored in the `T`. If the `Pin` just held a `T` directly, then simply moving the `Pin` would be enough to invalidate that invariant! In the remainder of this section, I’ll refer to `P` as the *pointer type* and `T` as the *target type*.

Next, notice that `Pin`’s constructor, `new_unchecked`, is `unsafe`. This is because the compiler has no way to actually check that the pointer type indeed promises that the pointed-to (target) type won’t move again. Consider, for example, a variable `foo` on the stack. If `Pin`’s constructor were safe, we could do `Pin::new(&mut foo)`, call a method that requires `Pin<&mut Self>` (and thus assumes that `Self` won’t move again), and then drop the `Pin`. At this point, we could modify `foo` as much as we liked, since it is no longer borrowed—including moving it! We could then pin it again and call the same method, which would be none the wiser that any self-referential pointers it may have constructed the first time around would now be invalid.

## PIN CONSTRUCTOR SAFETY

The other reason the constructor for `Pin` is unsafe is that its safety depends on the implementation of traits that are themselves safe. For example, the way that `Pin<P>` implements `get_unchecked_mut` is to use the implementation of `DerefMut::deref_mut` for `P`. While the call to `get_unchecked_mut` is unsafe, the `impl DerefMut` for `P` is not. Yet it receives a `&mut self`, and can thus freely (and without unsafe code) move the `T`. The same thing applies to `Drop`. The safety requirement for `Pin::new_unchecked` is therefore not only that the pointer type will not let the target type be moved again (like in the `Pin<&mut T>` example), but also that its `Deref`, `DerefMut`, and `Drop` implementations do not move the pointed-to value behind the `&mut self` they receive.

We then get to the `get_unchecked_mut` method, which gives you a mutable reference to the `T` behind the `Pin`'s pointer type. This method is also unsafe, because once we give out a `&mut T`, the caller has to promise it won't use that `&mut T` to move the `T` or otherwise invalidate its memory, lest any self-references be invalidated. If this method weren't unsafe, a caller could call a method that takes `Pin<&mut Self>` and then call the safe variant of `get_unchecked_mut` on two `Pin<&mut _>`s, then use `mem::swap` to swap the values behind the `Pin`. If we were to then call a method that takes `Pin<&mut Self>` again on either `Pin`, its assumption that the `Self` hasn't moved would be violated, and any internal references it stored would be invalid!

Perhaps surprisingly, `Pin<P>` always implements `Deref<Target = T>`, and that is entirely safe. The reason for this is that a `&T` does not let you move `T` without writing other unsafe code (`UnsafeCell`, for example, as we'll discuss in [Chapter 10](#)). This is a good example of why the scope of an unsafe block extends beyond just the code it contains. If you wrote some code in one part of the application that (unsafely) replaced a `T` behind an `&` using `UnsafeCell`, then it *could* be that that `&T` initially came from a `Pin<&mut T>`, and that you have now violated the invariant that the `T` behind the `Pin` may never move, even though the place where you unsafely replaced the `&T` did not even mention `Pin`!

### NOTE

*If you've browsed through the `Pin` documentation while reading this chapter, you may have noticed `Pin::set`, which takes a `&mut self` and a `<P as Deref::Target>` and safely changes the value behind the `Pin`. This is possible because `set` does not return the value that was previously pinned—it simply drops it in place and stores the new value there instead. Therefore, it does not violate the pinning invariants: the old value was never accessed outside of a `Pin` after it was placed there.*

## Unpin: The Key to Safe Pinning

At this point you might ask: given that getting a mutable reference is unsafe anyway, why not have `Pin` hold a `T` directly? That is, rather than require an

indirection through a pointer type, you could instead make the contract for `get_unchecked_mut` that it is only safe to call if you haven't moved the `Pin`. The answer to that question lies in a neat safe use of `Pin` that the pointer design enables. Recall that the whole reason we want `Pin` in the first place is so we can have target types that may contain references into themselves (like a generator), and give their methods a guarantee that the target type hasn't moved and thus that internal self-references remain valid. `Pin` lets us use the type system to enforce that guarantee, which is great. But unfortunately, with the design so far, `Pin` is very unwieldy to work with. This is because it always requires unsafe code, even if you are working with a target type that doesn't contain any self-references, and so doesn't care whether it's been moved or not.

This is where the marker trait `Unpin` comes into play. An implementation of `Unpin` for a type simply asserts that the type is safe to move out of a `Pin` when used as a target type. That is, the type promises that it will never use any of `Pin`'s guarantees about the referent not moving again when used as a target type, and thus that those guarantees may be broken. `Unpin` is an auto-trait, like `Send` and `Sync`, and so is auto-implemented by the compiler for any type that contains only `Unpin` members. Only types that explicitly opt out of `Unpin` (like generators) and types that contain those types are `!Unpin`.

For target types that are `Unpin`, we can provide a much simpler safe interface to `Pin`, as shown in Listing 9-10.

---

```
impl<P> Pin<P> where P: Deref, P::Target: Unpin {
    pub fn new(pointer: P) -> Self;
}
impl<P> DerefMut for Pin<P> where P: DerefMut, P::Target: Unpin {
    fn deref_mut(&mut self) -> &mut Self::Target;
}
```

---

*Listing 9-10: The safe API to `Pin` for `Unpin` target types*

To make sense of the safe API in Listing 9-10, think about the safety requirements of the unsafe methods from Listing 9-9: the function `Pin::new_unchecked` is unsafe because the caller must promise that the referent cannot be moved outside of the `Pin`, and that the implementations of `Deref`, `DerefMut`, and `Drop` for the pointer type do not move the referent through the reference they receive. Those requirements are there to ensure that once we give out a `Pin` to a `T`, we never move that `T` again. But if the `T` is `Unpin`, it has declared that it does not care if it is moved even if it was previously pinned, so it's fine if the caller does not satisfy any of those requirements!

Similarly, `get_unchecked_mut` is unsafe because the caller must guarantee that it doesn't move the `T` out of the `&mut T`—but with `T: Unpin`, `T` has declared that it's fine being moved even after being pinned, so that safety requirement is no longer important. This means that for `Pin<P> where P::Target: Unpin`, we can simply provide safe variants of both those methods (`DerefMut` being the safe version of `get_unchecked_mut`). In fact, we can even provide a `Pin::into_inner` that simply gives back the owned `P` if the target type is `Unpin`, since the `Pin` is essentially irrelevant!

## Obtaining a Pin

With our new understanding of `Pin` and `Unpin`, we can now make progress toward using the new `Future` definition from Listing 9-8 that requires `Pin<&mut Self>`. The first step is to construct the required type. If the future type is `Unpin`, that step is easy—we just use `Pin::new(&mut future)`. If it is not `Unpin`, we can pin the future in one of two main ways: by pinning to the heap or pinning to the stack.

Let's start with pinning to the heap. The primary contract of `Pin` is that once something has been pinned, it cannot move. The pinning API takes care of ensuring that for all methods and traits on `Pin`, so the main role of any function that constructs a `Pin` is to ensure that if the `Pin` *itself* moves, the referent value does not move too. The easiest way to ensure that is to place the referent on the heap, and then place just a pointer to the referent in the `Pin`. You can then move the `Pin` to your heart's delight, but the target will remain where it was. This is the rationale behind the (safe) method `Box::pin`, which takes a `T` and returns a `Pin<Box<T>>`. There's no magic to it; it simply asserts that `Box` follows the `Pin` constructor, `Deref`, and `Drop` contracts.

### UNPIN BOX

While we're on the topic of `Box`, take a look at the implementation of `Unpin` for `Box`. The `Box` type unconditionally implements `Unpin` for any `T`, even if that `T` is not `Unpin`. This might strike you as odd, given the earlier assertion that `Unpin` is an auto-trait that is only generally implemented for a type if all of the type's members are also `Unpin`. `Box` is an exception to this for the same reason that it can provide a safe `Pin` constructor: if you move a `Box<T>`, you do not move the `T`. In other words, the unconditional implementation asserts that you can move a `Box<T>` out of a `Pin` even if `T` cannot be moved out of a `Pin`. Note, however, that this does not enable you to move a `T` that is `!Unpin` out of a `Pin<Box<T>>`.

The other option, pinning to the stack, is a little more involved, and at the time of writing requires a smidgen of unsafe code. We have to ensure that the pinned value cannot be accessed after the `Pin` with a `&mut` to it has been dropped. We accomplish that by shadowing the value as shown in the macro in Listing 9-11, or using one of the crates that provide exactly this macro. One day it may even make it into the standard library!

---

```
macro_rules! pin_mut {
    ($var:ident) => {
        let mut $var = $var;
        let mut $var = unsafe { Pin::new_unchecked(&mut $var) };
    }
}
```

---

*Listing 9-11: Macro for pinning to the stack*

By taking the name of the variable to pin to the stack, the macro ensures that the caller has the value it wants to pin somewhere on the stack already. The shadowing of `$var` ensures that the caller cannot drop the `Pin` and continue to use the unpinned value (which would breach the `Pin` contract for any target type that's `!Unpin`). By moving the value stored in `$var`, the macro also ensures that the caller cannot drop the `$var` binding the macro declares without also dropping the original variable. Specifically, without that line, the caller could write (note the extra scope):

---

```
let foo = /* */; { pin_mut!(foo); foo.poll() }; foo.mut_self_method();
```

---

Here, we give a pinned instance of `foo` to `poll`, but then we later use a `&mut` to `foo` without a `Pin`, which violates the `Pin` contract. With the extra reassignment, on the other hand, that code would also move `foo` into the new scope, rendering it unusable after the scope ends.

Pinning on the stack therefore requires unsafe code, unlike `Box::pin`, but avoids the extra allocation that `Box` introduces, and also works in `no_std` environments.

## Back to the Future

We now have our pinned future, and we know what that means. But you may have noticed that none of this important pinning stuff shows up in most asynchronous code you write with `async` and `await`. And that's because the compiler hides it from you.

Remember back when we discussed Listing 9-5, when I told you that `<expr>.await` desugars into something like:

---

```
loop { if let Poll::Ready(r) = expr.poll() { break r } else { yield } }
```

---

That was an ever-so-slight simplification, because as we've seen you can only call `Future::poll` if you have a `Pin<&mut Self>` for the future. The desugaring is actually a bit more sophisticated, as shown in Listing 9-12.

---

```
❶ match expr {
    mut pinned => loop {
❷      match unsafe { Pin::new_unchecked(&mut pinned) }.poll() {
          Poll::Ready(r) => break r,
          Poll::Pending => yield,
        }
    }
}
```

---

*Listing 9-12: A more accurate de-sugaring of `<expr>.await`*

The match ❶ is a neat shorthand to ensure that the expansion remains a valid expression, while also moving the expression result into a variable that we can then pin on the stack. Beyond that, the main new addition is the call to `Pin::new_unchecked` ❷. That call is safe because for the containing `async` block to be polled, it must already be pinned due to the signature



of `Future::poll`. And the `async` block was polled for us to reach the call to `Pin::new_unchecked`, so the generator state is pinned. Since pinned is stored in the generator that corresponds to the `async` block (it must be so that `yield` will resume correctly), we know that pinned will not move again. Furthermore, pinned is not accessible except through a `Pin` once we're in the loop, so no code is able to move out of the value in pinned. Thus, we meet all the safety requirements of `Pin::new_unchecked`, and the code is safe.

## Going to Sleep

We went pretty deep into the weeds with `Pin`, but now that we're out the other side, there is another issue around futures that may have been making your brain itch. If a call to `Future::poll` returns `Poll::Pending`, you need something to call `poll` again at a later time to check whether you can make progress yet. That something is usually called the *executor*. Your executor could be a simple loop that polls all the futures you are waiting on until they've all returned `Poll::Ready`, but that would burn a lot of CPU cycles you could probably have used for other, more useful things, like running your web browser. Instead, we want the executor to do whatever useful work it can do, and then go to sleep. It should stay asleep until one of the futures can make progress, and only then wake up to do another pass, before going to sleep again.

### *Waking Up*

The condition that determines when to check back with a given future varies widely. It might be “when a network packet arrives on this port,” “when the mouse cursor moves,” “when someone sends on this channel,” “when the CPU receives a particular interrupt,” or even “after this much time has passed.” On top of that, developers can write their own futures that wrap multiple other futures, and thus may have several wake-up conditions. Some futures may even introduce their own entirely custom wake events.

To accommodate these many use cases, Rust introduces the notion of a *Waker*: a way to wake the executor to signal that progress can be made. The *Waker* is what makes the whole machinery around futures work. The executor constructs a *Waker* that integrates with the mechanism the executor uses to go to sleep, and passes the *Waker* in to any `Future` it polls. How? With the additional parameter to `Future::poll` that I've hidden from you so far. Sorry about that. Listing 9-13 gives the final and true definition for `Future`—no more lies!

---

```
trait Future {
    type Output;
    fn poll(self: Pin<&mut Self>, cx: &mut Context<'_>) -> Poll<Self::Output>;
}
```

---

*Listing 9-13: The actual `Future` trait with `Context`*

The `&mut Context` contains the `Waker`. The argument is a `Context`, not a `Waker` directly, so that we can augment the asynchronous ecosystem with additional context for futures should that be deemed necessary.

The primary method on `Waker` is `wake` (and the by-reference variant `wake_by_ref`). The `wake` method takes no arguments, and its effects are entirely defined by the executor that constructed the `Waker`. You see, `Waker` is secretly generic over the executor. Or, more precisely, whatever constructed the `Waker` gets to dictate what happens when `Waker::wake` is called, when a `Waker` is cloned, and when a `Waker` is dropped. This all happens through a manually implemented vtable, which functions similarly to the dynamic dispatch we discussed way back in [Chapter 3](#).

It's a somewhat involved process to construct a `Waker`, and the mechanics of it aren't all that important for using one, but you can see the building blocks in the `RawWakerVTable` type in the standard library. It has a constructor that takes the function pointers for `wake` and `wake_by_ref`, as well as `Clone` and `Drop`. The `RawWakerVTable`, which is usually shared among all of an executor's wakers, is bundled up with a raw pointer that is intended to hold data specific to each `Waker` instance (like which future it's for), and turned into a `RawWaker`. That is in turn passed to `Waker::from_raw` to produce a safe `Waker` that can be passed to `Future::poll`.

## The Poll Contract

So far we've skirted around what a future actually does with a `Waker`. The idea is fairly simple: if `Future::poll` returns `Poll::Pending`, it is the future's responsibility to ensure that *something* calls `wake` on the provided `Waker` when the future is next able to make progress. Most futures uphold this property by only returning `Poll::Pending` if some other future also returned `Poll::Pending`; in this way it trivially fulfills the contract of `poll` since the inner future must follow that same contract. But there can't be turtles all the way down. At some point, you reach a future that does not poll other futures, but instead does something like write to a network socket or attempt to receive on a channel. These are commonly referred to as *leaf futures* since they have no children. A leaf future has no inner future, but instead directly represents some resource that may not be ready to return a result yet.

Leaf futures typically come in one of two shapes: those that wait for events that originate within the same process (like a channel receiver), and those wait for events external to the process (like a TCP packet receive). Those that wait for internal events all tend to follow the same pattern: store the `Waker` somewhere where the code that will wake you up can find it, and have that code call `wake` on the `Waker` when it generates the relevant event. For example, consider a leaf future that has to wait for a message on an in-memory channel. It stores the `Waker` inside the part of the channel that is shared between the sender and the receiver, and then returns `Poll::Pending`. When a sender later comes along and injects a message into the channel, it notices the `Waker` left there by the waiting receiver and calls `wake` on the `Waker`

before returning from `send`. Now the receiver is awoken, and the poll contract is upheld.

Leaf futures that deal with external events are more involved, as the code that generates the event they're waiting for knows nothing of futures or wakers. Most often the generating code is the operating system kernel, which knows when a disk is ready or a timer expires, but it could also be a C library that invokes a callback into Rust when an operation completes or some other such external entity. A leaf future wrapping an external resource like this could spin up a thread that executes a blocking system call (or waits for the C callback) and then use the internal waking mechanism, but that would be wasteful; you would spin up a thread every time an operation had to wait and would be left with lots of single-use threads sitting around waiting for things.

Instead, executors tend to provide implementations of leaf futures that communicate behind the scenes with the executor to arrange for the appropriate interaction with the operating system. How exactly this is orchestrated depends on the executor and the operating system, but roughly speaking the executor keeps track of all the event sources that it should listen for the next time it goes to sleep. When a leaf future realizes it must wait for an external event, it updates that executor's state (which it knows about since it's provided by the executor crate) to include that external event source alongside its `Waker`. When the executor can no longer make progress, it gathers all of the event sources the various pending leaf futures are waiting for and does a big blocking call to the operating system telling it to return when *any* of the resources the leaf futures are waiting on have a new event. On Linux, this is usually achieved with the `epoll` system call; Windows, the BSDs, macOS, and pretty much every other operating system provide similar mechanisms. When that call returns, the executor calls `wake` on all the wakers associated with event sources that the operating system reported an event for, and thus the poll contract is fulfilled.

#### NOTE

*A reactor is the part of an executor that leaf futures register event sources with and that the executor waits on when it has no more useful work to do. It is possible to separate the executor and the reactor, though bundling them together often improves performance as the two can be co-optimized more readily.*

A knock-on effect of the tight integration between leaf futures and the executor is that leaf futures from one executor crate often cannot be used with a different executor. Or at least, they cannot be used unless the leaf future's executor is *also* running. When the leaf future goes to store its `Waker` and register the event source it's waiting for, the executor it was built against needs to have that state set up and needs to be running so that the event source will actually be monitored and `wake` eventually called. There are ways around this, such as having leaf futures spawn an executor if one is not already running, but this is not always advisable as it means that an application can transparently end up with multiple executors running at the same time, which can reduce performance and mean you must inspect the state of multiple executors when debugging.

Library crates that wish to support multiple executors have to be generic over their leaf resources. For example, instead of using a particular executor’s `TcpStream` or `File` future type, a library can store a generic `T: AsyncRead + AsyncWrite`. However, the ecosystem has yet to settle on exactly what these traits should look like and which traits are needed, so at the moment it’s fairly difficult to make code truly generic over the executor. For example, while `AsyncRead` and `AsyncWrite` are somewhat common across the ecosystem (or can be easily adapted if necessary), no traits currently exist for running a future in the background (*spawning*, which we’ll discuss later) or for representing a timer.

## ***Waking Is a Misnomer***

You may already have realized that `Waker::wake` doesn’t necessarily seem to *wake* anything. For example, for external events (as described in the previous section) the executor is already awake, and it might seem silly for it to then call `wake` on a `Waker` that belongs to that executor anyway! The reality is that `Waker::wake` is a bit of a misnomer—in reality, it signals that a particular future is *runnable*. That is, it tells the executor that it should make sure to poll this particular future when it gets around to it rather than go to sleep again, since this future can make progress. This might wake the executor if it is currently sleeping so it will go poll that future, but that’s more of a side effect than its primary purpose.

It is important for the executor to know which futures are runnable for two reasons. First, it needs to know when it can stop polling a future and go to sleep; it’s not sufficient to just poll each future until it returns `Poll::Pending`, since polling a later future might make it possible to progress an earlier future. Consider the case where two futures bounce messages back and forth on channels to one another. When you poll one, the other becomes ready, and vice versa. In this case, the executor should never go to sleep, as there is always more work to do.

Second, knowing which futures are runnable lets the executor avoid polling futures unnecessarily. If an executor manages thousands of pending futures, it shouldn’t poll all of them just because an event made one of them runnable. If it did, executing asynchronous code would get very slow indeed.

## ***Tasks***

The futures in an asynchronous program form a tree: a future may contain any number of other futures, which in turn may contain other futures, all the way down to the leaf futures that interact with wakers. The root of each tree is the future you give to whatever the executor’s main “run” function is. These root futures are called *tasks*, and they are the only point of contact between the executor and the futures tree. The executor calls `poll` on the task, and from that point forward the code of each contained future must figure out which inner future(s) to poll in response, all the way down to the relevant leaf.

Executors generally construct a separate `Waker` for each task they poll so that when `wake` is later called, they know which task was just made runnable and can mark it as such. That is what the raw pointer in `RawWaker` is for—to differentiate between tasks while sharing the code for the various `Waker` methods.

When the executor eventually polls a task, that task starts running from the top of its implementation of `Future::poll`, and must decide from there how to get to the future deeper down that can now make progress. Since each future only knows about its own fields, and nothing about the whole tree, this all happens through calls to `poll` that each traverse one edge in the tree.

The choice of which inner future to poll is often obvious, but not always. In the case of `async/await`, the future to poll is the one we’re blocked waiting for. But in a future that waits for the first of several futures to make progress (often called a *select*), or for all of a set of futures (often called a *join*), there are many options. A future that has to make such a choice is basically a subexecutor. It could poll all of its inner futures, but doing so could be quite wasteful. Instead, these subexecutors often wrap the `Waker` they receive in `poll`’s `Context` with their own `Waker` type before they invoke `poll` on any inner future. In the wrapping code, they mark the future they just polled as runnable in their own state before they call `wake` on the original `Waker`. That way, when the executor eventually polls the subexecutor future again, the subexecutor can consult its own internal state to figure out which of its inner futures caused the current call to `poll`, and then only poll those.

## Tying It All Together with `spawn`

When working with asynchronous executors, you may come across an operation that spawns a future. We’re now in a position to explore what that means! Let’s do so by way of example. First, consider the simple server implementation in Listing 9-14.

---

```

async fn handle_client(socket: TcpStream) -> Result<()> {
    // Interact with the client over the given socket.
}

async fn server(socket: TcpListener) -> Result<()> {
    while let Some(stream) = socket.accept().await? {
        handle_client(stream).await?;
    }
}

```

---

*Listing 9-14: Handling connections sequentially*

The top-level server function is essentially one big future that listens for new connections and does something when a new connection arrives. You hand that future to the executor and say “run this,” and since you don’t want your program to then exit immediately, you’ll probably have the

executor block on that future. That is, the call to the executor to run the server future will not return until the server future resolves, which may be never (another client could always arrive later).

Now, every time a new client connection comes in, the code in Listing 9-14 makes a new future (by calling `handle_client`) to handle that connection. Since the handling is itself a future, we `await` it and then move on to the next client connection.

The downside of this approach is that we only ever handle one connection at a time—there is no concurrency. Once the server accepts a connection, the `handle_client` function is called, and since we `await` it we don't go around the loop again until `handle_client`'s return future resolves (presumably when that client has left).

We could improve on this by keeping a set of all the client futures and having the loop in which the server accepts new connections also check all the client futures to see if any can make progress. Listing 9-15 shows what that might look like.

---

```

async fn server(socket: TcpListener) -> Result<> {
    let mut clients = Vec::new();
    loop {
        poll_client_futures(&mut clients)?;
        if let Some(stream) = socket.try_accept()? {
            clients.push(handle_client(stream));
        }
    }
}

```

---

*Listing 9-15: Handling connections with a manual executor*

This at least handles many connections concurrently, but it's quite messy. It's also not very efficient because the code now busy-loops, switching between handling the connections we already have and accepting new ones. And it has to check each connection each time, since it won't know which ones can make progress (if any). It also can't `await` at any point, since that would prevent the other futures from making progress. You could implement your own wakers to ensure that the code only polls the futures that can make progress, but ultimately this is going down the path of developing your own mini-executor.

Another downside of sticking with just the one task for the server that internally contains the futures for all of the client connections is that the server ends up being single-threaded. There is just the one task, and to poll it the code must hold an exclusive reference to the task's future (`poll` takes `Pin<&mut Self>`), which only one thread can hold at a time.

The solution is to make each client future its own task, and leave it to the executor to multiplex among all the tasks. Which, you guessed it, you do by spawning the future. The executor will continue to block on the server future, but if it cannot make progress on that future it will use its execution machinery to make progress on the other tasks in the meantime behind the scenes. And best of all, if the executor is multithreaded and

your client futures are `Send`, it can run them in parallel since it can hold `&mut`s to the separate tasks. Listing 9-16 gives an example of what this might look like.

---

```

async fn server(socket: TcpListener) -> Result<> {
    while let Some(stream) = socket.accept().await? {
        // Spawn a new task with the Future that represents this client.
        // The current task will continue to just poll for more connections,
        // and will run concurrently (and possibly in parallel) with handle_client.
        spawn(handle_client(stream));
    }
}

```

---

*Listing 9-16: Spawning futures to create more tasks that can be polled concurrently*

When you spawn a future, and thus make it a task, it's sort of like spawning a thread. The future continues running in the background and is multiplexed concurrently with any other tasks given to the executor. However, unlike a spawned thread, spawned tasks still depend on being polled by the executor. If the executor stops running, either because you drop it or because your code no longer runs the executor's code, those spawned tasks will stop making progress. In the server example, imagine what will happen if the main server future resolves for some reason. Since the executor has returned control back to your code, it cannot continue doing, well, anything. Multi-threaded executors often spawn background threads that continue to poll tasks even if the executor yields control back to the user's code, but not all executors do this, so check your executor before you rely on that behavior!

### BLOCKING IN ASYNC CODE

You must be careful about calling synchronous code from asynchronous code, since any time an executor thread spends executing the current task is time it's not spending running other tasks. If a task occupies the current thread for a prolonged period of time without yielding back to the executor, which might happen when executing a blocking system call (like `std::sync::sleep`) or running in a tight loop with no awaits, then other tasks the current executor thread is responsible for won't get to run during that time. Usually, this manifests as long delays between when certain tasks can make progress (such as when a client connects) and when they actually get to execute.

Some multithreaded executors implement *work-stealing* techniques, where idle executor threads steal tasks from busy executor threads, but this is more of a mitigation than a solution. Ultimately, you could end up in a situation where all the executor threads are blocked, and thus no tasks get run until one of the blocking operations completes.

In general, you should be very careful with executing compute-intensive operations or calling functions that could block in an asynchronous context.

*continued*

Such operations should either be converted to asynchronous operations where possible or executed on dedicated threads that then communicate using a primitive that does support asynchrony, like a channel. Some executors also provide mechanisms for indicating that a particular segment of asynchronous code might block, or for yielding voluntarily in the context of loops that might otherwise not yield, which can comprise part of the solution. A good rule of thumb is that no future should be able to run for more than 1 ms without returning `Poll::Pending`.

## Summary

In this chapter, we've taken a look behind the scenes of the asynchronous constructs available in Rust. We've seen how the compiler implements generators and self-referential types, and why that work was necessary to support what we now know as `async/await`. We've also explored how futures are executed, and how wakers allow executors to multiplex among tasks when only some of them can make progress at any given moment. In the next chapter, we'll tackle what is perhaps the deepest and most discussed area of Rust: unsafe code. Take a deep breath, and then turn the page.