

Equations for a growing and thickening cambial cell with a multilayered wall

Cyril Bozonnet

February 23, 2024

1 Overview

In this document I present the equations obtained when considering the growth and the wall thickening dynamic of a single cambial cell. For simplicity we consider a rectangular cell, elongating only along its anticlinal walls (= radial direction). All walls are viewed as multilayered, where fresh wall material is spreaded over already strained layers. Wall layers thicknesses dynamic is related to sugar availability (for newly deposited layers) and elongation rate (for all layers). The cell is connected to separated water and sugar sources.

2 Geometry and kinematics

2.1 At the cell scale




Figure 1: Geometry and notations. The reference frame at the top left corner shows the link between the present geometry and the one of an actual cambial cell whose growth would be mainly along r .

The geometry of the cambial cell is displayed in figure 1. Its total volume, V^T , is

$$V^T = L_a L_p L_z, \quad (1)$$

where L_a is the length in the anticlinal direction, L_p is the length in the periclinal direction, L_z is the length in the longitudinal direction. L_p and L_z will be considered constant throughout this work.

Neglecting the end walls along z , the volume of water within the cell, V_h , is

$$V_h = V^T - V_{wp}^T - V_{wa}^T, \quad (2)$$

where V_{wp}^T and V_{wa}^T are the anticlinal and periclinal total wall volume, respectively. Taking the derivative of the previous equation gives

$$\frac{dV_h}{dt} = L_p L_z \frac{dL_a}{dt} - \frac{dV_{wa}^T}{dt} - \frac{dV_{wp}^T}{dt}. \quad (3)$$

Normalising the previous relation by V_h leads to

$$\frac{1}{V_h} \frac{dV_h}{dt} = \frac{L_p L_z}{V_h} \frac{dL_a}{dt} - \frac{1}{V_h} \frac{dV_{wa}^T}{dt} - \frac{1}{V_h} \frac{dV_{wp}^T}{dt}. \quad (4)$$

Assuming $L_p L_z / V_h \approx 1 / L_a$, which is true as long as total cell wall volumes are small against the total cell volume, the previous expression becomes

$$\boxed{\frac{1}{V_h} \frac{dV_h}{dt} = \frac{1}{L_a} \frac{dL_a}{dt} - \frac{1}{V_h} \frac{dV_{wa}^T}{dt} - \frac{1}{V_h} \frac{dV_{wp}^T}{dt}}. \quad (5)$$

In the previous equation, we see that the volume of water in the cell increases with cell elongation and decreases with wall synthesis.

The total wall volumes can be computed as

$$V_{wp}^T = 2W_p^T L_p L_z, \quad (6)$$

and

$$V_{wa}^T = 2W_a^T L_z (L_a - 2W_p^T), \quad (7)$$

where W_p^T and W_a^T are the periclinal and anticlinal total wall thicknesses.

2.2 At the wall layer scale

Walls are actually composed of several layers. For each layer, the wall volume is

$$V_{wp}^j = 2W_p^j L_p L_z, \quad (8)$$

with j the layer number ($j \in [1; N_l^p]$, with N_l^p the number of periclinal layers), for periclinal wall layers, and

$$V_{wa}^i = 2W_a^i L_z (L_a - 2W_p^T), \quad (9)$$

with i the layer number ($i \in [1; N_l^a]$, with N_l^a the number of anticlinal layers), for anticlinal wall layers. In previous equations, V_{wp}^j , W_p^j , V_{wa}^i and W_a^i are the periclinal layer volume and thickness, and the anticlinal layer volume and thickness, respectively. Note that all periclinal layers have the same length (L_p) and all anticlinal layers have the same length ($L_a - 2W_p^T$).

Taking the derivative of Eq. (8) leads to

$$\frac{dV_{wp}^j}{dt} = 2L_z L_p \frac{dW_p^j}{dt}, \quad (10)$$

which gives an equation for each periclinal layer thickness,

$$\boxed{\frac{dW_p^j}{dt} = \frac{1}{2L_z L_p} \frac{dV_{wp}^j}{dt}}. \quad (11)$$

Thus, because we assumed a constant L_p , W_p only changes with periclinal wall synthesis.

Taking the derivative of Eq. (9) leads to

$$\frac{dV_{wa}^i}{dt} = 2L_z (L_a - 2W_p^T) \frac{dW_a^i}{dt} + 2W_a^i L_z \left(\frac{dL_a}{dt} - 2 \frac{dW_p^T}{dt} \right), \quad (12)$$

which can then be reorganised to give an equation for each anticlinal wall layer thickness,

$$\boxed{\frac{dW_a^i}{dt} = \frac{1}{2L_z (L_a - 2W_p^T)} \frac{dV_{wa}^i}{dt} - \frac{W_a^i}{L_a - 2W_p^T} \left(\frac{dL_a}{dt} - 2 \frac{dW_p^T}{dt} \right)}. \quad (13)$$

The previous equation shows that each anticlinal layer will grow with wall synthesis and with the growth of the periclinal wall (this latter property being the direct consequence of the geometry presented in figure 1). The layer thickness will decrease with anticlinal wall elongation.

2.3 Bridges between scales

The relations between the total and layer volumes are

$$V_{wp}^T = \sum_{j=1}^{j=N_l^p} V_{wp}^j, \quad \text{and} \quad V_{wa}^T = \sum_{i=1}^{i=N_l^a} V_{wa}^i. \quad (14)$$

In both walls, $i, j = 1$ corresponds to the outermost/oldest wall layer. Similarly, the relations for the thicknesses are

$$W_p^T = \sum_{j=1}^{j=N_l^p} W_p^j, \quad \text{and} \quad W_a^T = \sum_{i=1}^{i=N_l^a} W_a^i. \quad (15)$$

Taking the derivative of the previous expressions, we also have

$$\frac{dV_{wp}^T}{dt} = \sum_{j=1}^{j=N_l^p} \frac{dV_{wp}^j}{dt}, \quad \text{and} \quad \frac{dV_{wa}^T}{dt} = \sum_{i=1}^{i=N_l^a} \frac{dV_{wa}^i}{dt}, \quad (16)$$

for the wall volumes. Hence, the changes in total wall volumes are the sum of the volume changes of all the individual layers. Similarly, for wall thicknesses, we have

$$\frac{dW_p^T}{dt} = \sum_{j=1}^{j=N_l^p} \frac{dW_p^j}{dt}, \quad \text{and} \quad \frac{dW_a^T}{dt} = \sum_{i=1}^{i=N_l^a} \frac{dW_a^i}{dt}. \quad (17)$$

3 Water fluxes

The changes in the volume of water inside the cell depends on the water fluxes:

$$\frac{dV_h}{dt} = AK_h (P_{src} - \Pi_{src} - P + \Pi), \quad (18)$$

where $A = 2L_z(L_p + L_a)$ (neglecting water entry through end walls), K_h , P_{src} , Π_{src} , P and Π are the cylinder external area (m^2), the hydraulic conductivity (m/s/Pa), the pressure potential of the water source (Pa), the osmotic potential of water source (Pa), the cell turgor pressure (Pa) and the cell osmotic potential (Pa), respectively. Dividing by V_h further leads to

$$\boxed{\frac{1}{V_h} \frac{dV_h}{dt} = \frac{AK_h}{V_h} (P_{src} - \Pi_{src} - P + \Pi) \approx \frac{2(L_p + L_a)}{L_p L_a} K_h (\Psi_{src} - P + \Pi)}. \quad (19)$$

4 Wall rheology

The elongation rate of the anticlinal walls is

$$\dot{\epsilon}_a = \frac{1}{L_a} \frac{dL_a}{dt}. \quad (20)$$

One can identify its expression using Eq. (5):

$$\boxed{\dot{\epsilon}_a = \frac{1}{V_h} \frac{dV_h}{dt} + \frac{1}{V_h} \left(\frac{dV_{wa}^T}{dt} + \frac{dV_{wp}^T}{dt} \right)}, \quad (21)$$

where the first term on the right hand side will be computed from the water fluxes, and the second term will depend on the wall synthesis dynamic. Once the elongation rate is known, one can use it in different ways. First, one can use it to derive an equation for the cell length, i.e.,

$$\boxed{\frac{dL_a}{dt} = L_a \dot{\epsilon}_a}. \quad (22)$$

Secondly, it can be used to compute the evolution of the wall stresses in the anticlinal wall layers. Because of the geometry, all layers have the same elongation rate. If the rheology of the anticlinal wall layer material is described as a Bingham fluid, the elongation rate is related to the layer's stress, σ_a^i , as

$$\dot{\varepsilon}_a = \frac{(\sigma_a^i - \sigma_Y)^+}{\mu} + \frac{1}{E} \frac{d\sigma_a^i}{dt}, \quad (23)$$

where σ_Y is the wall layer yield stress (threshold for plastic deformation), μ is the wall layer viscosity, and E is the wall layer Young's modulus. These three material properties are considered homogeneous across all layers (but this hypothesis could be relaxed in futur work). The $(x)^+$ notation is equivalent to $\max(x, 0)$. This equation can further be rearranged to obtain the stress changes for each wall layer, i.e.,

$$\boxed{\frac{d\sigma_a^i}{dt} = E\dot{\varepsilon}_a - \frac{E(\sigma_a^i - \sigma_Y)^+}{\mu}}. \quad (24)$$

This equation is valid for $i \in [1; N_l^a]$. If for any numerical reasons there are layers with $i > N_l^a$, this expression must be equal to 0. The initial stress value (at the layer creation) can be equal to 0, or to σ_Y , or to another custom value.

The mean anticlinal wall stress is related to the layers' stresses and thicknesses through

$$\bar{\sigma}_a = \frac{\sum_i \sigma_a^i W_a^i}{\sum_i W_a^i}. \quad (25)$$

5 Mechanical equilibrium

Cell turgor pressure and mean wall stresses are related through the following equilibrium conditions

$$\bar{\sigma}_a = \frac{(P - P_{ext})L_p}{2W_a^T}, \quad (26)$$

$$\bar{\sigma}_p = \frac{(P - P_{ext})L_a}{2W_p^T}, \quad (27)$$

where P_{ext} is an external pressure applied on the walls. The first equation will be used to compute the turgor pressure, i.e.,

$$P = \frac{2\bar{\sigma}_a W_a^T}{L_p} + P_{ext}, \quad (28)$$

and the second equilibrium condition will be used to compute the stress in periclinal walls.

Remark: I think there are a couple of things missing in the model so far regarding the computation of periclinal wall stresses. What I would do so far is: 1) I can compute the mean value based of the equilibrium condition, 2) in case there is only one layer, the mean value is the layer value, 3) in case we start adding some layers, I can compute the mean value, then use the relation between mean and layer values to compute the new layer wall stress (whose thickness is known). All of this assume there is no stress relaxation due to plasticity in those layers...

6 Wall layer synthesis (inspired by Friend *et al.*, *Nature com.*, 2022)

Changes in wall layer volume are related to changes in mass, M_{wa}^i (kg/cell), through ρ_w , the cell wall density (kg/m³):

$$\boxed{\frac{dV_{wa}^i}{dt} = \frac{1}{\rho_w} \frac{dM_{wa}^i}{dt}}. \quad (29)$$

The same equation can be used for preclinal walls. With the modelling approach we used so far, the wall synthesis term is present in every cell wall layer. It could be used to represent a case where synthesis could still occur in old layers, in addition to the synthesis of new ones. As a first approximation, we will consider that wall synthesis occurs exclusively in the newest layer and is related to sugar availability through a Michaelis-Menten equation, i.e.,

$$\boxed{\frac{dM_{wa}^i}{dt} = \begin{cases} 0, & \text{if } i < N_l^a \\ \frac{\Delta M_{wa}^{max} n_s / V_h}{n_s / V_h + K_m}, & \text{if } i = N_l^a \end{cases}} \quad (30)$$

where ΔM_{wa}^{max} is the maximum speed of wall synthesis (kg/cell/s), n_s is the sugar content (in mol) of the cell and K_m is a kinetic constant (mol/m³). A similar equation can be used for the periclinal wall layers, but for now we will assume there is no synthesis in those layers, i.e.,

$$\boxed{\frac{dV_{wp}^j}{dt} = \frac{1}{\rho_w} \frac{dM_{wp}^j}{dt} = 0}, \quad (31)$$

for all periclinal layers. Note that the equations are implemented in their most general form so that in future development we can easily relax the different hypotheses made on wall synthesis.

The maximum speed of wall synthesis could further be related to water volume and temperature using a Boltzmann-Arrhenius equation,

$$\boxed{\Delta M_{wa}^{max} = \omega V_h e^{\frac{E_w^a}{k}(1/T_0 - 1/T)}}. \quad (32)$$

In the previous equation, ω is the normalised rate of cell-wall mass growth (kg/cell/s/m³) at temperature T_0 (273.15 K), E_w^a is an activation energy for wall building (eV), k is Boltzmann's constant (eV/K) and T is the actual temperature (K).

7 Osmotic potential and sugar content

If only one type of osmolytes is present, the cell osmotic potential is

$$\boxed{\Pi = \frac{n_s R_g T}{V_h}}, \quad (33)$$

where R_g is the ideal gas constant. The evolution of the sugar content can be related to wall synthesis and other sugar fluxes through

$$\boxed{\frac{dn_s}{dt} = -\frac{1}{M_s} \left(\sum_i \frac{dM_{wa}^i}{dt} + \sum_j \frac{dM_{wp}^j}{dt} \right) + f_s}, \quad (34)$$

where M_s is the sugar molar mass (kg/mol), and f_s is the sum of the sugar fluxes entering or leaving the cell. Note that with the hypotheses we made on wall synthesis, this equation reduces to

$$\frac{dn_s}{dt} = -\frac{1}{M_s} \frac{dM_{wa}^{i=N_t^a}}{dt} + f_s. \quad (35)$$

f_s can be a constant, i.e., a constant sugar flux forced into the cell, or can be computed through a diffusion equation, i.e.,

$$\boxed{f_s = \eta_s \left(C_s^{ext} - \frac{n_s}{V_h} \right)}, \quad (36)$$

with η_s the sugar diffusion constant (m³/s) and C_s^{ext} the external osmotic concentration. This external osmotic concentration can then be used to simulate periods of low or high sugar availability.

8 Wall layer deposition dynamic

Nothing has been said so far on the number of layers in each wall (N_l^a, N_l^p). There are several possibilities:

- creation of a new layer once the previous one has reached a threshold (predefined) size
- creation of a new layer at every iteration, which implies that some layers will have an extremely small thickness and can only be considered as “numerical” layers.

We chose the second possibility, i.e., a new layer at each iteration. N_l^a therefore increases with time. As we do not consider synthesis in the periclinal layers, we have $N_l^p = 1$.

In terms of numerical implementation with the function *odeint* in Python, this solver expects a constant number of unknowns through time. Therefore, one can either start the temporal integration with one initial layer and then stop the integration after each iteration to add a new layer, and start the integration again, or launch the integration with the correct amount of layers

(equal to the number of iterations) and move the wall source term from one layer to another at each new iteration. The second implementation seems much easier and will probably not induce a huge cost compared to the other where the solver must be restarted at each iteration.

NB: according to ChatGPT, the other built-in ODE solver (*solveivp*) would allow a non-constant number of unknowns throughout the integration.

9 Regulations

A couple of regulations can be tried, the most obvious one is probably to keep a constant total wall thickness with time despite the deposition of new layers at each iteration. One can derive the equivalent of Eq. (13) at the scale of the cell wall (it is the same equation with different superscripts),

$$\frac{dW_a^T}{dt} = \frac{1}{2L_z(L_a - 2W_p^T)} \frac{dV_{wa}^T}{dt} - \frac{W_a^T}{L_a - 2W_p^T} \left(\frac{dL_a}{dt} - 2 \frac{dW_p^T}{dt} \right). \quad (37)$$

For a constant wall thickness, the left hand side is zero, and we get an expression for the total wall synthesis,

$$\frac{dV_{wa}^T}{dt} = 2L_z W_a^T \left(\frac{dL_a}{dt} - 2 \frac{dW_p^T}{dt} \right). \quad (38)$$

Wall synthesis only occuring in the last layer (or current iteration), one obtains

$$\boxed{\frac{dV_{wa}^{i=N_l^a}}{dt} = 2L_z W_a^T \left(\frac{dL_a}{dt} - 2 \frac{dW_p^T}{dt} \right)}, \quad (39)$$

which will ensure a constant total wall thickness with a multilayered wall where new layers are deposited at each iteration. This will also stops wall synthesis when elongation stops.