

Building BOINC Client and Manager on Macintosh OSX

Written by Charlie Fenton
Last updated 6/24/2023

This document applies to BOINC version 7.24.0 and later. It has instructions for building the BOINC Client and Manager for Macintosh OSX. Information for building science project applications to run under BOINC on Macintosh OSX can be found [here](#) and [here](#).

Note: the information in this document changes from time to time for different versions of BOINC. For any version of BOINC source files, the corresponding version of this document can be found in the source tree at:

`boinc/mac_build/HowToBuildBOINC_XCode.rtf`

Contents of this document:

- Important requirements for building BOINC software for the Mac.
- Cross-Platform Development.
- Building BOINC Manager with embedded BOINC Client.
- Building BOINC Manager Installer.
- Code Signing the BOINC Manager Installer and Uninstaller.
- Debugging and BOINC security.
- Debugging into wxWidgets.
- Installing and setting up Xcode.

Note: `setupForBoinc.sh` (described later in this document) runs `buildWxMac.sh` to build the wxWidgets library used by BOINC Manager. If you built the wxWidgets library with an earlier version of `buildWxMac.sh`, then you must rebuild it with the `buildWxMac.sh` included in the newer source tree. Otherwise, the BOINC Manager build will fail with linker (ld) errors.

Important requirements for building BOINC software for the Mac

As of version 6.13.0, BOINC does not support Macintosh PowerPC processors. As of 7.15.0, BOINC is built entirely for 64-bit Intel, including the BOINC libraries. As of 7.16.14, BOINC is built as Universal2 Binaries which can run on both 64-bit Intel and Apple Silicon (arm64) hardware.

You need to take certain steps to ensure that you use only APIs that are available in all the OS versions BOINC supports for each architecture. The best way to accomplish this is to use a single development system running versions of MacOS and Xcode which are / were current at the time your target version of BOINC was released, and cross-compile for the various platforms. The remainder of this document describes that process.

The above requirements apply not only to BOINC itself, but also to the WxWidgets, c-ares, cURL, openssl, freetype and ftgl libraries, as well as all project applications.

Be sure to follow the directions in this document to ensure that these requirements are met.

Starting with version 7.16.14, the BOINC screensaver has supported only Mac OS 10.9.0 and later.

Cross-Platform Development

Apple provides the tools necessary to build BOINC on any Mac running OS 10.8.x or later.

You get these tools, including the GCC or Apple LLVM compiler and system library header files, by installing the Xcode Tools package.

You can download Xcode from Apple's App Store (it is large: over 4 GB). If you are a member of Apple's Mac Developer Program, you can also download it from Apple's web site: <http://developer.apple.com>.

Source files are now archived using git. For details, see:

<https://github.com/BOINC/boinc/wiki/SourceCodeGit>

Building BOINC Manager with embedded Core Client

BOINC depends on six third-party libraries: wxWidgets, c-ares, curl, openssl, freetype and ftgl. Different versions of BOINC require different versions of these libraries; any one version of BOINC will build with only one specific version of each library. For BOINC versions prior to 7.24.0, see `mac_build/HowToBuildBOINC.rtf` in the source tree for that version of BOINC for the library versions needed and how to download them.

Starting with BOINC 7.24.0, the `SetupForBOINC.sh` script (described below) in the source tree for any version of BOINC automatically downloads and builds the appropriate six third-party libraries for that version of BOINC.

You can obtain the source files from the following URLs. Clicking on the first URL of each pair will download the tar file. The second URL will open the third party's home web page. On Mac OS X the tar file will usually be downloaded into the Downloads folder. You will need to expand the tar files by double-clicking on them, which will create a folder and place the appropriate files into that folder. You will need to move these folders later.

More information about each third-party library can be found on its home page:

wxWidgets- (needed only if you are building the BOINC Manager): <https://wxwidgets.org>

curl: <https://curl.se>

c-ares (used by curl): <https://c-ares.org>

openssl: <http://www.openssl.org/>

freetype (needed only if you are building the BOINC default screensaver or a project screensaver): <http://www.freetype.org/>

ftgl (needed only if you are building the BOINC default screensaver or a project screensaver): <http://sourceforge.net/projects/ftgl>

IMPORTANT: The third-party libraries may not work properly with BOINC if you build them directly with either the Xcode projects which come with wxWidgets or the AutoMake scripts supplied with all six, so be sure to use our special scripts to build these packages.

[1] Make sure you are logged into the Mac using an account with administrator privileges. Create a parent directory within which to work. In this description; we will call it BOINC_dev, but you can name it anything you wish.

[2] If you have not yet done so, install Xcode and launch it once to accept the license agreement and complete the installation.

[3] Get the BOINC source tree from the repository, and put it in the BOINC_dev folder. To do this, type the following in Terminal (if you have problems, you may need to enter sudo and a space before the git command):

```
cd {path}/BOINC_dev/  
git clone https://github.com/BOINC/boinc.git boinc
```

(You may change the name of the boinc directory to anything you wish.)

The command above retrieves the source code from the HEAD / MASTER (TRUNK) or development branch of the git repository. You can also get or switch to the source code for any released version of BOINC. For more information on getting the BOINC source code, see:

<https://github.com/BOINC/boinc/wiki/SourceCodeGit>

[4] Run the script to download and build the c-ares, curl, openssl, wxWidgets, freetype and ftgl libraries as follows:

```
cd {path}/BOINC_dev/boinc/mac_build/  
source setupForBoinc.sh -clean
```

The above commands will download the libraries only if they haven't previously been downloaded. If you don't wish to force a full rebuild of everything, omit the -clean argument.

Note 1: Be sure to run the script using the source command. Do not double-click on the scripts or use the sh command to run them.

Note 2: This script tries to build all six third-party libraries: wxWidgets, c-ares, curl, openssl, freetype and ftgl. When the script finishes, it will display a warning about any libraries it was unable to build. To make it easier to find the error messages, clear the Terminal display and run the script again without -clean.

Note 3: setupForBoinc.sh runs buildWxMac.sh to build the wxWidgets library used by BOINC Manager. If you previously built the wxWidgets library with an earlier version of buildWxMac.sh, you may need to rebuild it with the buildWxMac.sh included in the newer source tree if the BOINC Manager build fails with linker (ld) errors for symbols starting with "wx".

Note 4: The {path} must not contain any space characters.

Hint: You don't need to type the path to a file or folder into Terminal; just drag the file or folder icon from a Finder window onto the Terminal window.

[5] Build BOINC as follows:

BOINC itself is built using the **boinc.xcodeproj** file. You can either build directly in Xcode (more information below) or run the **BuildMacBOINC.sh** script:

```
cd {path}/BOINC_dev/boinc/mac_build/  
source BuildMacBOINC.sh
```

The complete syntax for this script is

```
source BuildMacBOINC.sh [-dev] [-noclean] [-libstdc++] [-all] [-lib] [-client] [-zipapps] [-uc2] [-vboxwrapper] [-target targetName] [-setting name value] [-help]
```

The options for BuildMacBOINC.sh are:

-dev	Build the development (debug) build. Default is deployment (release) build.
-noclean	Don't do a "clean" of each target before building. Default is to clean all first.
-libstdc++	Build using libstdc++ instead of libc++

The following arguments determine which targets to build:

-all	Build all targets (i.e. target "Build_All" -- this is the default) except boinc_zip_test, testzlibconflict, UpperCase2 targets
------	--

(UC2-x86_64, UC2Gfx-x86_64 and slide_show-x86_64) and VBoxWrapper

- lib Build the six libraries: libboinc_api.a, libboinc_graphics_api.a, libboinc.a, libboinc_opengl.a, libboinc_zip.a, jpeglib.a
- client Build two targets: boinc client and command-line utility `boinccmd` (also builds libboinc.a, since boinc_cmd requires it.)
- zipapps Build two zip samples: boinc_zip_test and testzlibconflict
- uc2 Build the UpperCase2 targets: UC2-x86_64, UC2Gfx-x86_64 and slide_show-x86_64
- vboxwrapper Build the VBoxWrapper target
- libc Build using libc++ instead of libstdc++ (requires OS 10.7 or later)
- c++11 Build using c++11 language dialect instead of default

Both -lib and -client may be specified to build seven targets (no BOINC Manager or screensaver.)

The following arguments are used mainly for building the daily test builds and are not likely to be useful to you:

- target targetName Build *only* the one target specified by targetName
- setting name value Override setting 'name' to have the value 'value' (usually used along with -target.)
You can pass multiple -setting arguments.)

Note 1: `boinc.xcodeproj` in the `BOINC_dev/boinc/mac_build/` directory builds BOINC. It can be used either with the `BuildMacBOINC.sh` script or as a stand-alone project. The *Development* build configuration is used for debugging. The *Deployment* build configuration builds a universal binary and is suitable for release builds. If there are any other build configurations, they should not be used as they are obsolete.

Note 2: To perform a release build under Xcode 6 or later when not using the `BuildMacBOINC.sh` script, select "Build for Profiling" from Xcode's Product menu. To save disk space, do **not** select "Archive."

Note 3: Using the `BuildMacBOINC.sh` script is generally easier than building directly in Xcode. The script will place the built products in the directory `BOINC_dev/boinc/mac_build/build/Deployment/` or `BOINC_dev/boinc/mac_build/build/Development/` where they are easy to find.

Building directly in Xcode places the built products in a somewhat obscure location. To determine this location, control-click on *Products* in Xcode's Project Navigator and select "Show in Finder", or use the method in **Note 5** below. Building the `libboinc*.a` and `jpeglib.a` libraries will copy them to the directory `BOINC_dev/boinc/mac_build/build/Deployment/` or `BOINC_dev/boinc/mac_build/build/Development/`.

Note 4: As of version 7.15.0, BOINC is always built using libc++. Project applications built for libstdc++ with newer versions of Xcode will not link properly with BOINC libraries built for libc++.

Hint: You can install multiple versions of Xcode on the same Mac, either by putting them in different directories or by renaming Xcode.app of different versions. You can then specify which version the `BuildMacBOINC.sh` script should use by setting the `DEVELOPER_DIR` environment variable using the `env` command. For example, if you have installed Xcode 6.2 in the Applications directory and renamed Xcode.app to Xcode_6_2.app, you can invoke the script with:

```
env DEVELOPER_DIR=/Applications/Xcode_6_2.app/Contents/Developer sh BuildMacBOINC.sh
```

Note 5: When building the client or BOINC Manager, the BOINC Xcode project has built-in scripts which create a text file with the path to the built products at either `BOINC_dev/boinc/mac_build/Build_Deployment_Dir` or `BOINC_dev/boinc/mac_build/Build_Development_Dir`. These files are used by the `release_boinc.sh` script, but you can also use them to access the built products directly as follows; open the file with TextEdit and copy the path, then enter command-shift-G in the Finder and paste the path into the Finder's dialog.

Building BOINC Manager Installer

In order to execute BOINC Manager, you must install it using BOINC Manager Installer. Otherwise, you will encounter an error prompting for proper installation.

To build the Installer for the BOINC Manager, you must be logged in as an administrator. If you are building BOINC version number x.y.z, type the following in Terminal, then enter your administrator password when prompted by the script:

```
cd {path}/BOINC_dev/boinc/  
source ./mac_installer/release_boinc.sh x y z
```

Substitute the 3 parts of the BOINC version number for x y and z in the above. For example, to build the installer for BOINC version 7.24.0, the command would be

```
source {path}/BOINC_dev/boinc/mac_installer/release_boinc.sh 7 24 0
```

This will create a directory "BOINC_Installer/New_Release_7_24_0" in the BOINC_dev directory, and the installer will be located in '{path}/BOINC_dev/BOINC_Installer/New_Release_7_24_0/boinc_7.24.0_macOSX_universal'.

The installer script uses the deployment (release) build of BOINC; it won't work with a development (debug) build. You can find the current version number in the file {path}/BOINC_dev/boinc/version.h

Code Signing the BOINC Manager Installer and Uninstaller

Mac OS 10.8 introduces a security feature called Gatekeeper, whose default settings won't allow a user to run applications or installers downloaded from the Internet unless they are signed by a registered Apple Developer. The `release_boinc.sh` script looks for a file `~/BOINCCodeSignIdentities.txt` containing the name of a valid code signing identity stored in the user's Keychain. If this is found, the script will automatically sign the BOINC installer and BOINC uninstaller using that identity. For example, if your user name is John Smith, the first line of `~/BOINCCodeSignIdentities.txt` would be something like the following:

Developer ID Application: John Smith

If you wish to also code sign the installer package, add a second line to `~/BOINCCodeSignIdentities.txt` with the installer code signing identity. This would be something like the following:

Developer ID Installer: John Smith

If there is no `~/BOINCCodeSignIdentities.txt` file, then the script will not sign the installer or uninstaller. Code signing is not necessary if you won't be transferring the built software over the Internet. For more information on code signing identities see the documentation for the `codesign` utility, Apple's [Code Signing Guide](#) and [Tech Note 2206](#).

Important: Code signed under MacOS 11.0 or later is not compatible with MacOS 10.11.6 or earlier and will be rejected with "Signature invalid." If backward compatibility is desired to allow installing and running on systems prior to MacOS 10.12.0, run the `release_boinc.sh` script under MacOS 10.15.7 or earlier. You can do this even if you performed the previous steps under MacOS 11.0 or later.

As of MacOS 10.15 Catalina, the OS does not allow the user to run downloaded software unless it has been "notarized" by Apple. You can notarize BOINC only if you have code signed everything. If you are building BOINC version number x.y.z, type the following in Terminal to notarize the installer and uninstaller:

```
cd {path}/BOINC_dev/boinc/  
source ./mac_installer/notarize_boinc.sh x y z
```

Substitute the 3 parts of the BOINC version number for x y and z in the above using the same values you used when building the installer.

You must have done the following before running this script:

- Created an app-specific password by following the instructions on "Using app-specific passwords" here.
- **NOTE:** You cannot use your normal Apple ID password.
- Created a profile named "notarycredentials" in your keychain using the "notarytool store-credentials" command (enter "man notarytool" in Terminal for details.)
- Run the `release_boinc.sh` script as described above.

For more information, type the following in Terminal:

```
xcrun notarytool --help  
man stapler
```

Debugging and BOINC security

Version 5.5.4 of BOINC Manager for the Macintosh introduced new, stricter security measures. For details, please see the file `BOINC_dev/boinc/mac_installer/Readme.rtf` and https://boinc.berkeley.edu/sandbox_design.php and <https://github.com/BOINC/boinc/wiki/SandboxUser>

The LLDB debugger can't attach to applications which are running as a different user or group so it ignores the `S_ISUID` and `S_ISGID` permission bits when launching an application. To work around this, the BOINC *Development* build does not use the special `boinc_master` or `boinc_project` users or groups, and so can be run under the debugger from Xcode. This also streamlines the development cycle by avoiding the need to run the installer for every change. (To generate the development build under Xcode, choose "Build" from the product menu, or enter command-B on the keyboard.)

To restore the standard ownerships and permissions, run the installer or run the `BOINC_dev/boinc/mac_build/Mac_SA_Secure.sh` shell script in Terminal (the comments in this script have instructions for running it.)

For information on interpreting crash dumps and backtraces, see [Mac Backtrace](#).

Debugging into wxWidgets

The BOINC Xcode project links the BOINC Manager with the non-debugging (Deployment) build of wxWidgets for the Deployment build configuration of the Manager, and with the debugging (Development) build of wxWidgets for the Development build configuration of the Manager. You should use the Development build of the Manager and wxWidgets for debugging; this allows you to step into internal

wxWidgets code. With the Development build, you can even put breakpoints in wxWidgets; this is most easily done after stepping into a function in wxWidgets source file containing the code where you wish to put the breakpoint.

Installing and setting up Xcode

If Xcode is obtained from the Apple Store then it will be installed automatically into the Applications folder. Double-click on the installed Xcode icon to run Xcode. Xcode will display a dialog allowing you to finish the installation; you must do this before running BOINC's build scripts. (Some versions of Xcode may not display this dialog until you open a file with Xcode.)