

Manipulating tonals

Please read the ReadMeFirst file before attempting to use this software.

Saving and loading sets of tonals

The dtTonalsLoad and dtTonalsSave functions can be used to load and save lists of tonal time x frequency contours.

tonal_set = dtTonalsLoad(filename) will load a set of tonals from the specified filename. An optional true/false flag controls whether or not a user interface dialog is presented. When true, filename may be the empty matrix [], or contain a name that will be used as the default value.

dtTonalsSave(filename, tonal_set) saves a set of tonals to the specified file. Like dtTonalsLoad, an optional true/false flag can be used to request a user interface dialog.

Using detected tonals

Sets of tonals are instances of Java collections. As such, one can use methods associated with the collection interface. Suppose we had a set of tonals called tonal_set. The following are examples of methods that could be used:

- tonal_set.size() – Returns the number of tonals in the set.
- tonal_set.get(n) – Return the n^{th} tonal. Java enumerates arrays and collections starting at 0, so n must be in the range $0 \leq n < \text{tonal_set.size}()$.
- tonal_set.add(t) – Add a tonal t to the set.
- tonal_set.iterator() – Returns a Java iterator, an object that can be used to loop over the tonal set:

```
% Assume that tonals contains a tonal set
% We will loop to find the minimum and maximum
% frequency
minfreq = Inf;
maxfreq = -Inf;
it = tonals.iterator(); % Create an iterator
while it.hasNext() % any more?
    ton = it.next(); % get next tonal
    f = ton.get_freq(); % get frequency list
    % update min/max frequencies
    minfreq = min(minfreq, min(f));
    maxfreq = max(maxfreq, max(f));

% We could plot the tonal with:
%     plot(ton.get_time(), ton.get_freq());
end
```

Each tonal has a number of methods associated with it. A complete list can be seen in the source code for Java class `tonal` in the `tonals` package. Some of the more useful ones are:

- `get_time()` – Returns array of time offsets from the start of the detection file in s.
- `get_freq()` – Returns the frequencies associated with each time.
- `get_duration()` – Returns length of detection in s.
- `overlapping_tonals(tonal_set)` – Returns a new set containing tonals in `tonal_set` that overlap in time with this one.
- `toString(firstN, lastN)` - When tonals are displayed in Matlab, by default the first two time x frequency nodes and the last one are displayed. To see more of the tonal, the `toString` method can be used specifying how many nodes should be displayed at the head and tail of the list. Specifying -1 for the `firstN` argument will display all nodes.

Constructing tonals and tonal sets

When creating tonal objects, it is important to first tell Matlab that the `tonals` package will be used via the `import` command:

```
import tonals.*; % Import Java's tonals package
```

Once this has been done, tonals can be created by using the `tonal` constructor, providing a pair of vectors specifying times and frequencies:

```
new_tonal = tonal(time, frequency);
```

Be sure to avoid using the variable name `tonal`, or you will not be able to create new tonal objects until it is cleared.

Tonal sets can be created as follows, this example creates a set whose order is dependent upon the insertion order:

```
tonals = java.util.LinkedList(); % Empty linked list created
tonals.add(new_tonal); % Adds tonal to the list
another_tonal = tonal(time, frequency);
tonals.add(another_tonal); % Adds another tonal to the list
```