

Hibernate Validator

JSR 349 Reference Implementation

使用指南

5.0.1.Final

由 Hardy Ferentschik和Gunnar Morling

and thanks to Shaozhuang Liu


序言	vii
1. Getting started	1
1.1. Project set up	1
1.1.1. Unified EL	1
1.1.2. CDI	2
1.2. Applying constraints	2
1.3. Validating constraints	3
1.4. Where to go next?	5
2. Declaring and validating bean constraints	7
2.1. Declaring bean constraints	7
2.1.1. Field-level constraints	7
2.1.2. Property-level constraints	8
2.1.3. Class-level constraints	9
2.1.4. Constraint inheritance	10
2.1.5. Object graphs	11
2.2. Validating bean constraints	12
2.2.1. Obtaining a Validator instance	12
2.2.2. Validator methods	13
2.2.3. ConstraintViolation methods	14
2.3. Built-in constraints	15
2.3.1. Bean Validation constraints	15
2.3.2. Additional constraints	19
3. Declaring and validating method constraints	25
3.1. Declaring method constraints	26
3.1.1. Parameter constraints	26
3.1.2. Return value constraints	28
3.1.3. Cascaded validation	29
3.1.4. Method constraints in inheritance hierarchies	31
3.2. Validating method constraints	33
3.2.1. Obtaining an ExecutableValidator instance	34
3.2.2. ExecutableValidator methods	34
3.2.3. ConstraintViolation methods for method validation	37
4. Interpolating constraint error messages	39
4.1. Default message interpolation	39
4.1.1. Special characters	40
4.1.2. Interpolation with message expressions	40
4.1.3. Examples	41
4.2. Custom message interpolation	43
4.2.1. ResourceBundleLocator	43
5. Grouping constraints	45
5.1. Requesting groups	45
5.2. Defining group sequences	49
5.3. Redefining the default group sequence	50
5.3.1. @GroupSequence	50

5.3.2. @GroupSequenceProvider	51
5.4. Group conversion	52
6. Creating custom constraints	57
6.1. Creating a simple constraint	57
6.1.1. The constraint annotation	57
6.1.2. The constraint validator	59
6.1.3. The error message	62
6.1.4. Using the constraint	62
6.2. Class-level constraints	63
6.2.1. Custom property paths	64
6.3. Cross-parameter constraints	65
6.4. Constraint composition	68
7. Configuring via XML	71
7.1. Configuring the validator factory in validation.xml	71
7.2. Mapping constraints via constraint-mappings	74
8. Bootstrapping	81
8.1. Retrieving ValidatorFactory and Validator	81
8.1.1. ValidationProviderResolver	82
8.2. Configuring a ValidatorFactory	83
8.2.1. MessageInterpolator	83
8.2.2. TraversableResolver	84
8.2.3. ConstraintValidatorFactory	85
8.2.4. ParameterNameProvider	86
8.2.5. Adding mapping streams	87
8.2.6. Provider-specific settings	87
8.3. Configuring a Validator	88
9. Using constraint metadata	89
9.1. BeanDescriptor	90
9.2. PropertyDescriptor	93
9.3. MethodDescriptor and ConstructorDescriptor	93
9.4. ElementDescriptor	95
9.5. GroupConversionDescriptor	98
9.6. ConstraintDescriptor	98
10. Integrating with other frameworks	101
10.1. ORM集成	101
10.1.1. 与数据库集成校验	101
10.1.2. 基于Hibernate事件模型的校验	101
10.1.3. JPA	103
10.2. JSF & Seam	103
10.3. CDI	104
10.3.1. Dependency injection	104
10.3.2. Method validation	106
10.4. Java EE	110
11. Hibernate Validator Specifics	111


11.1. Public API	111
11.2. Fail fast mode	112
11.3. Programmatic constraint declaration	113
11.4. Boolean composition of constraints	116
11.5. ResourceBundleLocator	117
12. Annotation Processor	119
12.1. Prerequisites	119
12.2. Features	119
12.3. Options	120
12.4. Using the Annotation Processor	120
12.4.1. Command line builds	120
12.4.2. IDE builds	122
12.5. Known issues	125
13. Further reading	127

序言

Validating data is a common task that occurs throughout all application layers, from the presentation to the persistence layer. Often the same validation logic is implemented in each layer which is time consuming and error-prone. To avoid duplication of these validations, developers often bundle validation logic directly into the domain model, cluttering domain classes with validation code which is really metadata about the class itself.



JSR 349 - Bean Validation 1.1 - defines a metadata model and API for entity and method validation. The default metadata source are annotations, with the ability to override and extend the meta-data through the use of XML. The API is not tied to a specific application tier nor programming model. It is specifically not tied to either web or persistence tier, and is available for both server-side application programming, as well as rich client Swing application developers.



Hibernate Validator is the reference implementation of this JSR 349. The implementation itself as well as the Bean Validation API and TCK are all provided and distributed under the [Apache Software License 2.0](http://www.apache.org/licenses/LICENSE-2.0) [<http://www.apache.org/licenses/LICENSE-2.0>].

Getting started

This chapter will show you how to get started with Hibernate Validator, the reference implementation (RI) of Bean Validation. For the following quickstart you need:

- A JDK ≥ 6
- [Apache Maven](http://maven.apache.org/) [<http://maven.apache.org/>]
- An Internet connection (Maven has to download all required libraries)

1.1. Project set up

In order to use Hibernate Validator within a Maven project, simply add the following dependency to your `pom.xml`:

例 1.1. Hibernate Validator Maven dependency

```
<dependency>
  <groupId>org.hibernate</groupId>
  <artifactId>hibernate-validator</artifactId>
  <version>5.0.1.Final</version>
</dependency>
```

This transitively pulls in the dependency to the Bean Validation API (`javax.validation:validation-api:1.1.0.Final`).

1.1.1. Unified EL

Hibernate Validator requires an implementation of the Unified Expression Language ([JSR 341](http://jcp.org/en/jsr/detail?id=341) [jcp.org/en/jsr/detail?id=341]) for evaluating dynamic expressions in constraint violation messages (see [第 4.1 节 “Default message interpolation”](#)). When your application runs in a Java EE container such as JBoss AS, an EL implementation is already provided by the container. In a Java SE environment, however, you have to add an implementation as dependency to your POM file. For instance you can add the following two dependencies to use the JSR 341 [reference implementation](http://ue1.java.net/) [<http://ue1.java.net/>]:

例 1.2. Maven dependencies for Unified EL reference implementation

```
<dependency>
  <groupId>javax.el</groupId>
  <artifactId>javax.el-api</artifactId>
  <version>2.2.4</version>
</dependency>
<dependency>
  <groupId>org.glassfish.web</groupId>
  <artifactId>javax.el</artifactId>
```

```
<version>2.2.4</version>
</dependency>
```

1.1.2. CDI

Bean Validation defines integration points with CDI (Contexts and Dependency Injection for Java™ EE, [JSR 346](http://jcp.org/en/jsr/detail?id=346) [http://jcp.org/en/jsr/detail?id=346]). If your application runs in an environment which does not provide this integration out of the box, you may use the Hibernate Validator CDI portable extension by adding the following Maven dependency to your POM:

例 1.3. Hibernate Validator CDI portable extension Maven dependency

```
<dependency>
  <groupId>org.hibernate</groupId>
  <artifactId>hibernate-validator-cdi</artifactId>
  <version>5.0.1.Final</version>
</dependency>
```

Note that adding this dependency is usually not required for applications running on a Java EE application server. You can learn more about the integration of Bean Validation and CDI in [第 10.3 节 “CDI”](#).

1.2. Applying constraints

Lets dive directly into an example to see how to apply constraints.

例 1.4. Class Car annotated with constraints

```
package org.hibernate.validator.referenceguide.chapter01;

import javax.validation.constraints.Min;
import javax.validation.constraints.NotNull;
import javax.validation.constraints.Size;

public class Car {

    @NotNull
    private String manufacturer;

    @NotNull
    @Size(min = 2, max = 14)
    private String licensePlate;

    @Min(2)
    private int seatCount;

    public Car(String manufacturer, String licencePlate, int seatCount) {
        this.manufacturer = manufacturer;
    }
}
```

```

        this.licensePlate = licencePlate;
        this.seatCount = seatCount;
    }

    //getters and setters ...
}

```

The `@NotNull`, `@Size` and `@Min` annotations are used to declare the constraints which should be applied to the fields of a `Car` instance:

- `manufacturer` must never be `null`
- `licensePlate` must never be `null` and must be between 2 and 14 characters long
- `seatCount` must be at least 2



提示

You can find the complete source code of all examples used in this reference guide in the `Hibernate Validator source repository` [<https://github.com/hibernate/hibernate-validator/tree/master/documentation/src/test>] on GitHub.

1.3. Validating constraints

To perform a validation of these constraints, you use a `Validator` instance. Let's have a look at a unit test for `Car`:

例 1.5. Class `CarTest` showing validation examples

```

package org.hibernate.validator.referenceguide.chapter01;

import java.util.Set;
import javax.validation.ConstraintViolation;
import javax.validation.Validation;
import javax.validation.Validator;
import javax.validation.ValidatorFactory;

import org.junit.BeforeClass;
import org.junit.Test;

import static org.junit.Assert.assertEquals;

public class CarTest {

    private static Validator validator;

    @BeforeClass
    public static void setUp() {
        ValidatorFactory factory = Validation.buildDefaultValidatorFactory();
    }
}

```

```
        validator = factory.getValidator();
    }

    @Test
    public void manufacturerIsNull() {
        Car car = new Car( null, "DD-AB-123", 4 );

        Set<ConstraintViolation<Car>> constraintViolations =
            validator.validate( car );

        assertEquals( 1, constraintViolations.size() );
        assertEquals( "may not be null", constraintViolations.iterator().next().getMessage() );
    }

    @Test
    public void licensePlateTooShort() {
        Car car = new Car( "Morris", "D", 4 );

        Set<ConstraintViolation<Car>> constraintViolations =
            validator.validate( car );

        assertEquals( 1, constraintViolations.size() );
        assertEquals(
            "size must be between 2 and 14",
            constraintViolations.iterator().next().getMessage()
        );
    }

    @Test
    public void seatCountTooLow() {
        Car car = new Car( "Morris", "DD-AB-123", 1 );

        Set<ConstraintViolation<Car>> constraintViolations =
            validator.validate( car );

        assertEquals( 1, constraintViolations.size() );
        assertEquals(
            "must be greater than or equal to 2",
            constraintViolations.iterator().next().getMessage()
        );
    }

    @Test
    public void carIsValid() {
        Car car = new Car( "Morris", "DD-AB-123", 2 );

        Set<ConstraintViolation<Car>> constraintViolations =
            validator.validate( car );

        assertEquals( 0, constraintViolations.size() );
    }
}
```

In the `setUp()` method a `Validator` object is retrieved from the `ValidatorFactory`. A `Validator` instance is thread-safe and may be reused multiple times. It thus can safely be stored in a static field and be used in the test methods to validate the different `Car` instances.

The `validate()` method returns a set of `ConstraintViolation` instances, which you can iterate over in order to see which validation errors occurred. The first three test methods show some expected constraint violations:

- The `@NotNull` constraint on `manufacturer` is violated in `manufacturerIsNull()`
- The `@Size` constraint on `licensePlate` is violated in `licensePlateTooShort()`
- The `@Min` constraint on `seatCount` is violated in `seatCountTooLow()`

If the object validates successfully, `validate()` returns an empty set as you can see in `carIsValid()`.

Note that only classes from the package `javax.validation` are used. These are provided from the Bean Validation API. No classes from Hibernate Validator are directly referenced, resulting in portable code.

1.4. Where to go next?

That concludes the 5 minute tour through the world of Hibernate Validator and Bean Validation. Continue exploring the code examples or look at further examples referenced in [第 13 章 Further reading](#).

To learn more about the validation of beans and properties, just continue reading [第 2 章 Declaring and validating bean constraints](#). If you are interested in using Bean Validation for the validation of method pre- and postcondition refer to [第 3 章 Declaring and validating method constraints](#). In case your application has specific validation requirements have a look at [第 6 章 Creating custom constraints](#).

Declaring and validating bean constraints

In this chapter you will learn how to declare (see [第 2.1 节 “Declaring bean constraints”](#)) and validate (see [第 2.2 节 “Validating bean constraints”](#)) bean constraints. [第 2.3 节 “Built-in constraints”](#) provides an overview of all built-in constraints coming with Hibernate Validator.

If you are interested in applying constraints to method parameters and return values, refer to [第 3 章 Declaring and validating method constraints](#).

2.1. Declaring bean constraints

Constraints in Bean Validation are expressed via Java annotations. In this section you will learn how to enhance an object model with these annotations. There are the following three types of bean constraints:

- field constraints
- property constraints
- class constraints



注意

Not all constraints can be placed on all of these levels. In fact, none of the default constraints defined by Bean Validation can be placed at class level. The `java.lang.annotation.Target` annotation in the constraint annotation itself determines on which elements a constraint can be placed. See [第 6 章 Creating custom constraints](#) for more information.

2.1.1. Field-level constraints

Constraints can be expressed by annotating a field of a class. [例 2.1 “Field-level constraints”](#) shows a field level configuration example:

例 2.1. Field-level constraints

```
package org.hibernate.validator.referenceguide.chapter02.fieldlevel;

public class Car {
```

```
@NotNull
private String manufacturer;

@AssertTrue
private boolean isRegistered;

public Car(String manufacturer, boolean isRegistered) {
    this.manufacturer = manufacturer;
    this.isRegistered = isRegistered;
}

//getters and setters...
}
```

When using field-level constraints field access strategy is used to access the value to be validated. This means the validation engine directly accesses the instance variable and does not invoke the property accessor method even if such an accessor exists.

Constraints can be applied to fields of any access type (public, private etc.). Constraints on static fields are not supported, though.



提示

When validating byte code enhanced objects property level constraints should be used, because the byte code enhancing library won't be able to determine a field access via reflection.

2.1.2. Property-level constraints

If your model class adheres to the [JavaBeans](http://java.sun.com/javase/technologies/desktop/javabeans/index.jsp) [http://java.sun.com/javase/technologies/desktop/javabeans/index.jsp] standard, it is also possible to annotate the properties of a bean class instead of its fields. 例 2.2 “Property-level constraints” uses the same entity as in 例 2.1 “Field-level constraints”, however, property level constraints are used.

例 2.2. Property-level constraints

```
package org.hibernate.validator.referenceguide.chapter02.propertylevel;

public class Car {

    private String manufacturer;

    private boolean isRegistered;

    public Car(String manufacturer, boolean isRegistered) {
        this.manufacturer = manufacturer;
        this.isRegistered = isRegistered;
    }
}
```



```

@NotNull
public String getManufacturer() {
    return manufacturer;
}

public void setManufacturer(String manufacturer) {
    this.manufacturer = manufacturer;
}

@AssertTrue
public boolean isRegistered() {
    return isRegistered;
}

public void setRegistered(boolean isRegistered) {
    this.isRegistered = isRegistered;
}
}

```



注意

The property's getter method has to be annotated, not its setter. That way also read-only properties can be constrained which have no setter method.

When using property level constraints property access strategy is used to access the value to be validated, i.e. the validation engine accesses the state via the property accessor method.



提示

It is recommended to stick either to field or property annotations within one class. It is not recommended to annotate a field and the accompanying getter method as this would cause the field to be validated twice.

2.1.3. Class-level constraints

Last but not least, a constraint can also be placed on the class level. In this case not a single property is subject of the validation but the complete object. Class-level constraints are useful if the validation depends on a correlation between several properties of an object.

The Car class in [例 2.3 “Class-level constraint”](#) has the two attributes seatCount and passengers and it should be ensured that the list of passengers has not more entries than seats are available. For that purpose the `@ValidPassengerCount` constraint is added on the class level. The validator of that constraint has access to the complete Car object, allowing to compare the numbers of seats and passengers.

Refer to [第 6.2 节 “Class-level constraints”](#) to learn in detail how to implement this custom constraint.

例 2.3. Class-level constraint

```
package org.hibernate.validator.referenceguide.chapter02.classlevel;

@ValidPassengerCount
public class Car {

    private int seatCount;

    private List<Person> passengers;

    //...
}
```

2.1.4. Constraint inheritance

When a class implements an interface or extends another class, all constraint annotations declared on the supertype apply in the same manner as the constraints specified on the class itself. To make things clearer let's have a look at the following example:

例 2.4. Constraint inheritance

```
package org.hibernate.validator.referenceguide.chapter02.inheritance;

public class Car {

    private String manufacturer;

    @NotNull
    public String getManufacturer() {
        return manufacturer;
    }

    //...
}
```

```
package org.hibernate.validator.referenceguide.chapter02.inheritance;

public class RentalCar extends Car {

    private String rentalStation;

    @NotNull
    public String getRentalStation() {
        return rentalStation;
    }
}
```

```
    //...  
}
```

Here the class `RentalCar` is a subclass of `Car` and adds the property `rentalStation`. If an instance of `RentalCar` is validated, not only the `@NotNull` constraint on `rentalStation` is evaluated, but also the constraint on `manufacturer` from the parent class.

The same would be true, if `Car` was not a superclass but an interface implemented by `RentalCar`.

Constraint annotations are aggregated if methods are overridden. So if `RentalCar` overrode the `getManufacturer()` method from `Car`, any constraints annotated at the overriding method would be evaluated in addition to the `@NotNull` constraint from the superclass.

2.1.5. Object graphs

The Bean Validation API does not only allow to validate single class instances but also complete object graphs (cascaded validation). To do so, just annotate a field or property representing a reference to another object with `@Valid` as demonstrated in [例 2.5 “Cascaded validation”](#).

例 2.5. Cascaded validation

```
package org.hibernate.validator.referenceguide.chapter02.objectgraph;  
  
public class Car {  
  
    @NotNull  
    @Valid  
    private Person driver;  
  
    //...  
}
```

```
package org.hibernate.validator.referenceguide.chapter02.objectgraph;  
  
public class Person {  
  
    @NotNull  
    private String name;  
  
    //...  
}
```

If an instance of `Car` is validated, the referenced `Person` object will be validated as well, as the `driver` field is annotated with `@Valid`. Therefore the validation of a `Car` will fail if the `name` field of the referenced `Person` instance is null.

The validation of object graphs is recursive, i.e. if a reference marked for cascaded validation points to an object which itself has properties annotated with `@Valid`, these references will be followed up by the validation engine as well. The validation engine will ensure that no infinite loops occur during cascaded validation, for example if two objects hold references to each other.

Note that null values are getting ignored during cascaded validation.

Object graph validation also works for collection-typed fields. That means any attributes that

- are arrays
- implement `java.lang.Iterable` (especially `Collection`, `List` and `Set`)
- implement `java.util.Map`

can be annotated with `@Valid`, which will cause each contained element to be validated, when the parent object is validated.

例 2.6. Cascaded validation of a collection

```
package org.hibernate.validator.referenceguide.chapter02.objectgraph.list;

public class Car {

    @NotNull
    @Valid
    private List<Person> passengers = new ArrayList<Person>();

    //...
}
```

So when validating an instance of the `Car` class shown in [例 2.6 “Cascaded validation of a collection”](#), a `ConstraintViolation` will be created, if any of the `Person` objects contained in the `passengers` list has a null name.

2.2. Validating bean constraints

The `Validator` interface is the most important object in Bean Validation. The next section shows how to obtain a `Validator` instance. Afterwards you'll learn how to use the different methods of the `Validator` interface.

2.2.1. Obtaining a `Validator` instance

The first step towards validating an entity instance is to get hold of a `Validator` instance. The road to this instance leads via the `Validation` class and a `ValidatorFactory`. The easiest way is to use the static method `Validation#buildDefaultValidatorFactory()`:

例 2.7. Validation#buildDefaultValidatorFactory()

```
ValidatorFactory factory = Validation.buildDefaultValidatorFactory();
Validator validator = factory.getValidator();
```

This bootstraps a validator in the default configuration. Refer to [第 8 章 Bootstrapping](#) to learn more about the different bootstrapping methods and how to obtain a specifically configured Validator instance.

2.2.2. Validator methods

The Validator interface contains three methods that can be used to either validate entire entities or just single properties of the entity.

All three methods return a `Set<ConstraintViolation>`. The set is empty, if the validation succeeds. Otherwise a `ConstraintViolation` instance is added for each violated constraint.

All the validation methods have a var-args parameter which can be used to specify, which validation groups shall be considered when performing the validation. If the parameter is not specified the default validation group (`javax.validation.groups.Default`) is used. The topic of validation groups is discussed in detail in [第 5 章 Grouping constraints](#).

2.2.2.1. Validator#validate()

Use the `validate()` method to perform validation of all constraints of a given bean. [例 2.8 “Using Validator#validate\(\)”](#) shows the validation of an instance of the `Car` class from [例 2.2 “Property-level constraints”](#) which fails to satisfy the `@NotNull` constraint on the `manufacturer` property. The validation call therefore returns one `ConstraintViolation` object.

例 2.8. Using Validator#validate()

```
Car car = new Car( null, true );

Set<ConstraintViolation<Car>> constraintViolations = validator.validate( car );

assertEquals( 1, constraintViolations.size() );
assertEquals( "may not be null", constraintViolations.iterator().next().getMessage() );
```

2.2.2.2. Validator#validateProperty()

With help of the `validateProperty()` you can validate a single named property of a given object. The property name is the JavaBeans property name.

例 2.9. Using `Validator#validateProperty()`

```
Car car = new Car( null, true );

Set<ConstraintViolation<Car>> constraintViolations = validator.validateProperty(
    car,
    "manufacturer"
);

assertEquals( 1, constraintViolations.size() );
assertEquals( "may not be null", constraintViolations.iterator().next().getMessage() );
```

2.2.2.3. `Validator#validateValue()`

By using the `validateValue()` method you can check whether a single property of a given class can be validated successfully, if the property had the specified value:

例 2.10. Using `Validator#validateValue()`

```
Set<ConstraintViolation<Car>> constraintViolations = validator.validateValue(
    Car.class,
    "manufacturer",
    null
);

assertEquals( 1, constraintViolations.size() );
assertEquals( "may not be null", constraintViolations.iterator().next().getMessage() );
```



注意

`@Valid` is not honored by `validateProperty()` or `validateValue()`.

`Validator#validateProperty()` is for example used in the integration of Bean Validation into JSF 2 (see [第 10.2 节 “JSF & Seam”](#)) to perform a validation of the values entered into a form before they are propagated to the model.

2.2.3. `ConstraintViolation` methods

Now it is time to have a closer look at what a `ConstraintViolation` is. Using the different methods of `ConstraintViolation` a lot of useful information about the cause of the validation failure can be determined. [表 2.1 “The various `ConstraintViolation` methods”](#) gives an overview of these methods. The values in the "Example" column refer to [例 2.8 “Using `Validator#validate\(\)`”](#).

表 2.1. The various ConstraintViolation methods

Method	Usage	Example
<code>getMessage()</code>	The interpolated error message	"may not be null"
<code>getMessageTemplate()</code>	The non-interpolated error message	"{... NotNull.message}"
<code>getRootBean()</code>	The root bean being validated	car
<code>getRootBeanClass()</code>	The class of the root bean being validated	Car.class
<code>getLeafBean()</code>	If a bean constraint, the bean instance the constraint is applied on; If a property constraint, the bean instance hosting the property the constraint is applied on	car
<code>getPropertyPath()</code>	The property path to the validated value from root bean	contains one node with kind PROPERTY and name "manufacturer"
<code>getInvalidValue()</code>	The value failing to pass the constraint	null
<code>getConstraintDescriptor()</code>	Constraint metadata reported to fail	descriptor for @NotNull

2.3. Built-in constraints

Hibernate Validator comprises a basic set of commonly used constraints. These are foremost the constraints defined by the Bean Validation specification (see [表 2.2 “Bean Validation constraints”](#)). Additionally, Hibernate Validator provides useful custom constraints (see [表 2.3 “Custom constraints”](#) and [表 2.4 “Custom country specific constraints”](#)).

2.3.1. Bean Validation constraints

[表 2.2 “Bean Validation constraints”](#) shows purpose and supported data types of all constraints specified in the Bean Validation API. All these constraints apply to the field/property level, there are no class-level constraints defined in the Bean Validation specification. If you are using the Hibernate object-relational mapper, some of the constraints are taken into account when creating the DDL for your model (see column "Hibernate metadata impact").



注意

Hibernate Validator allows some constraints to be applied to more data types than required by the Bean Validation specification (e.g. `@Max` can be applied to Strings). Relying on this feature can impact portability of your application between Bean Validation providers.

表 2.2. Bean Validation constraints

Annotation	Supported data types	Use	Hibernate metadata impact
<code>@AssertFalse</code>	Boolean, boolean	Checks that the annotated element is false	None
<code>@AssertTrue</code>	Boolean, boolean	Checks that the annotated element is true	None
<code>@DecimalMax(value, inclusive=)</code>	BigDecimal, BigInteger, CharSequence, byte, short, int, long and the respective wrappers of the primitive types; Additionally supported by HV: any sub-type of Number	Checks whether the annotated value is less than the specified maximum, when <code>inclusive=false</code> . Otherwise whether the value is less than or equal to the specified maximum. The parameter value is the string representation of the max value according to the BigDecimal string representation.	None
<code>@DecimalMin(value, inclusive=)</code>	BigDecimal, BigInteger, CharSequence, byte, short, int, long and the respective wrappers of the primitive types; Additionally supported by HV: any sub-type of Number	Checks whether the annotated value is larger than the specified minimum, when <code>inclusive=false</code> . Otherwise whether the value is larger than or equal to the specified minimum. The parameter value is the string representation of the min value according to the BigDecimal string representation.	None

Annotation	Supported data types	Use	Hibernate metadata impact
<code>@Digits(integer=fraction=)</code>	BigDecimal, BigInteger, CharSequence, byte, short, int, long and the respective wrappers of the primitive types; Additionally supported by HV: any sub-type of Number	Checks whether the annotated value is a number having up to integer digits and fraction fractional digits	Defines column precision and scale
<code>@Future</code>	java.util.Date, java.util.Calendar; Additionally supported by HV, if the Joda Time [http://joda-time.sourceforge.net/] date/time API is on the class path: any implementations of ReadablePartial and ReadableInstant	Checks whether the annotated date is in the future	None
<code>@Max(value=)</code>	BigDecimal, BigInteger, byte, short, int, long and the respective wrappers of the primitive types; Additionally supported by HV: any sub-type of CharSequence (the numeric value represented by the character sequence is evaluated), any sub-type of Number	Checks whether the annotated value is less than or equal to the specified maximum	Adds a check constraint on the column
<code>@Min(value=)</code>	BigDecimal, BigInteger, byte, short, int, long and the respective wrappers of the primitive types; Additionally supported by HV: any sub-type of CharSequence (the numeric value represented by the char sequence is evaluated), any sub-type of Number	Checks whether the annotated value is higher than or equal to the specified minimum	Adds a check constraint on the column

Annotation	Supported data types	Use	Hibernate metadata impact
@NotNull	Any type	Checks that the annotated value is not null.	Column(s) are not nullable
@Null	Any type	Checks that the annotated value is null	None
@Past	java.util.Date, java.util.Calendar; Additionally supported by HV, if the Joda Time [http://joda-time.sourceforge.net/] date/time API is on the class path: any implementations of ReadablePartial and ReadableInstant	Checks whether the annotated date is in the past	None
@Pattern(regex=,flag=)	CharSequence	Checks if the annotated string matches the regular expression regex considering the given flag match	None
@Size(min=, max=)	CharSequence, Collection, Map and arrays	Checks if the annotated element's size is between min and max (inclusive)	Column length will be set to max
@Valid	Any non-primitive type	Performs validation recursively on the associated object. If the object is a collection or an array, the elements are validated recursively. If the object is a map, the value elements are validated recursively.	None



注意

On top of the parameters indicated in 表 2.2 “Bean Validation constraints” each constraint has the parameters message, groups and payload. This is a requirement of the Bean Validation specification.

2.3.2. Additional constraints

In addition to the constraints defined by the Bean Validation API Hibernate Validator provides several useful custom constraints which are listed in 表 2.3 “Custom constraints”. With one exception also these constraints apply to the field/property level, only `@ScriptAssert` is a class-level constraint.

表 2.3. Custom constraints

Annotation	Supported data types	Use	Hibernate metadata impact
<code>@CreditCardNumber</code>	CharSequence	Checks that the annotated character sequence passes the Luhn checksum test. Note, this validation aims to check for user mistakes, not credit card validity! See also Anatomy of Credit Card Numbers [http://www.merriampark.com/anatomycc.htm].	None
<code>@Email</code>	CharSequence	Checks whether the specified character sequence is a valid email address. The optional parameters regexp and flags allow to specify an additional regular expression (including regular expression flags)	None

Annotation	Supported data types	Use	Hibernate metadata impact
		which the email must match.	
@Length(min=, max=)	CharSequence	Validates that the annotated character sequence is between min and max included	Column length will be set to max
@ModCheck(modType=, multiplier=, startIndex=, endIndex=, checkDigitPosition=, ignoreNonDigitCharacters=)	CharSequence	Checks that the digits within the annotated character sequence pass the mod 10 or mod 11 checksum algorithm. modType is used to select the modulo type and the multiplier determines the algorithm specific multiplier (see also Luhn algorithm [http://en.wikipedia.org/wiki/Luhn_algorithm]). startIndex and endIndex allow to only run the modulo algorithm on the specified sub-string. checkDigitPosition allows to use an arbitrary digit within the character sequence to be the check digit. If not specified it is assumed that the check digit is part of the	None

Annotation	Supported data types	Use	Hibernate metadata impact
		specified range. Last but not least, <code>ignoreNonDigitCharacters</code> allows to ignore non digit characters.	
<code>@NotBlank</code>	<code>CharSequence</code>	Checks that the annotated character sequence is not null and the trimmed length is greater than 0. The difference to <code>@NotEmpty</code> is that this constraint can only be applied on strings and that trailing whitespaces are ignored.	None
<code>@NotEmpty</code>	<code>CharSequence</code> , <code>Collection</code> , <code>Map</code> and arrays	Checks whether the annotated element is not null nor empty	None
<code>@Range(min=, max=)</code>	<code>BigDecimal</code> , <code>BigInteger</code> , <code>CharSequence</code> , <code>byte</code> , <code>short</code> , <code>int</code> , <code>long</code> and the respective wrappers of the primitive types	Checks whether the annotated value lies between (inclusive) the specified minimum and maximum	None
<code>@SafeHtml(whitelistType=, additionalTags=)</code>	<code>CharSequence</code>	Checks whether the annotated value contains potentially malicious fragments such as <code><script/></code> . In order to use this constraint, the jsoup [http://jsoup.org/] library	None

Annotation	Supported data types	Use	Hibernate metadata impact
		must be part of the class path. With the whitelistType attribute predefined whitelist types can be chosen. You can also specify additional html tags for the whitelist with the additionalTags attribute.	
<code>@ScriptAssert(lang=, script=, alias=)</code>	Any type	Checks whether the given script can successfully be evaluated against the annotated element. In order to use this constraint, an implementation of the Java Scripting API as defined by JSR 223 ("Scripting for the Java™ Platform") must part of the class path. The expressions to be evaluated can be written in any scripting or expression language, for which a JSR 223 compatible engine can be found in the class path.	None

Annotation	Supported data types	Use	Hibernate metadata impact
<code>@URL(protocol=, host=, port= regexp=, flags=)</code>	<code>CharSequence</code>	Checks if the annotated character sequence is a valid URL according to RFC2396. If any of the optional parameters <code>protocol</code> , <code>host</code> or <code>port</code> are specified, the corresponding URL fragments must match the specified values. The optional parameters <code>regexp</code> and <code>flags</code> allow to specify an additional regular expression (including regular expression flags) which the URL must match.	None

2.3.2.1. Country specific constraints

Hibernate Validator offers also some country specific constraints, e.g. for the validation of social security numbers.



注意

If you have to implement a country specific constraint, consider making it a contribution to Hibernate Validator!

表 2.4. Custom country specific constraints

Annotation	Supported data types	Use	Country	Hibernate metadata impact
<code>@CNPJ</code>	<code>CharSequence</code>	Checks that the annotated character sequence	Brazil	None

Annotation	Supported data types	Use	Country	Hibernate metadata impact
		represents a Brazilian corporate tax payer registry number (Cadastro de Pessoa Jurídica)		
@CPF	CharSequence	Checks that the annotated character sequence represents a Brazilian individual taxpayer registry number (Cadastro de Pessoa Física)	Brazil	None
@TituloEleitoral	CharSequence	Checks that the annotated character sequence represents a Brazilian voter ID card number (Titulo Eleitoral [http://ghiorzi.org/cgcancpf.htm])	Brazil	None



提示

In some cases neither the Bean Validation constraints nor the custom constraints provided by Hibernate Validator will fulfill your requirements. In this case you can easily write your own constraint. You can find more information in [第 6 章 Creating custom constraints](#).

Declaring and validating method constraints

As of Bean Validation 1.1, constraints can not only be applied to JavaBeans and their properties, but also to the parameters and return values of the methods and constructors of any Java type. That way Bean Validation constraints can be used to specify

- the preconditions that must be satisfied by the caller before a method or constructor may be invoked (by applying constraints to the parameters of an executable)
- the postconditions that are guaranteed to the caller after a method or constructor invocation returns (by applying constraints to the return value of an executable)



注意

For the purpose of this reference guide, the term method constraint refers to both, method and constructor constraints, if not stated otherwise. Occasionally, the term executable is used when referereng to methods and constructors.

This approach has several advantages over traditional ways of checking the correctness of parameters and return values:

- the checks don't have to be performed manually (e.g. by throwing `IllegalArgumentException`s or similar), resulting in less code to write and maintain
- an executable's pre- and postconditions don't have to be expressed again in its documentation, since the constraint annotations will automatically be included in the generated JavaDoc. This avoids redundancies and reduces the chance of inconsistencies between implementation and documentation



提示

In order to make annotations show up in the JavaDoc of annotated elements, the annotation types themselves must be annotated with the meta annotation `@Documented`. This is the case for all built-in constraints and is considered a best practice for any custom constraints.

In the remainder of this chapter you will learn how to declare parameter and return value constraints and how to validate them using the `ExecutableValidator` API.

3.1. Declaring method constraints

3.1.1. Parameter constraints

You specify the preconditions of a method or constructor by adding constraint annotations to its parameters as demonstrated in [例 3.1 “Declaring method and constructor parameter constraints”](#).

例 3.1. Declaring method and constructor parameter constraints

```
package org.hibernate.validator.referenceguide.chapter03.parameter;

public class RentalStation {

    public RentalStation(@NotNull String name) {
        //...
    }

    public void rentCar(
        @NotNull Customer customer,
        @NotNull @Future Date startDate,
        @Min(1) int durationInDays) {
        //...
    }
}
```

The following preconditions are declared here:

- The name passed to the RentalCar constructor must not be null
- When invoking the rentCar() method, the given customer must not be null, the rental's start date must not be null and must be in the future and the rental duration must be at least one day

Note that declaring method or constructor constraints itself does not automatically cause their validation upon invocation of the executable. Instead, the ExecutableValidator API (see [第 3.2 节 “Validating method constraints”](#)) must be used to perform the validation, which is often done using a method interception facility such as AOP, proxy objects etc.

Constraints may only be applied to instance methods, i.e. declaring constraints on static methods is not supported. Depending on the interception facility you use for triggering method validation, additional restrictions may apply, e.g. with respect to the visibility of methods supported as target of interception. Refer to the documentation of the interception technology to find out whether any such limitations exist.

3.1.1.1. Cross-parameter constraints

Sometimes validation does not only depend on a single parameter but on several or even all parameters of a method or constructor. This kind of requirement can be fulfilled with help of a cross-parameter constraint.

Cross-parameter constraints can be considered as the method validation equivalent to class-level constraints. Both can be used to implement validation requirements which are based on several elements. While class-level constraints apply to several properties of a bean, cross-parameter constraints apply to several parameters of an executable.

In contrast to single-parameter constraints, cross-parameter constraints are declared on the method or constructor as you can see in [例 3.2 “Declaring a cross-parameter constraint”](#). Here the cross-parameter constraint `@LuggageCountMatchesPassengerCount` declared on the `load()` method is used to ensure that no passenger has more than two pieces of luggage.

例 3.2. Declaring a cross-parameter constraint

```
package org.hibernate.validator.referenceguide.chapter03.crossparameter;

public class Car {

    @LuggageCountMatchesPassengerCount(piecesOfLuggagePerPassenger = 2)
    public void load(List<Person> passengers, List<PieceOfLuggage> luggage) {
        //...
    }
}
```

As you will learn in the next section, return value constraints are also declared on the method level. In order to distinguish cross-parameter constraints from return value constraints, the constraint target is configured in the `ConstraintValidator` implementation using the `@SupportedValidationTarget` annotation. You can find out about the details in [第 6.3 节 “Cross-parameter constraints”](#) which shows how to implement your own cross-parameter constraint.

In some cases a constraint can be applied to an executable's parameters (i.e. it is a cross-parameter constraint), but also to the return value. One example for this are custom constraints which allow to specify validation rules using expression or script languages.

Such constraints must define a member `validationAppliesTo()` which can be used at declaration time to specify the constraint target. As shown in [例 3.3 “Specifying a constraint's target”](#) you apply the constraint to an executable's parameters by specifying `validationAppliesTo = ConstraintTarget.PARAMETERS`, while `ConstraintTarget.RETURN_VALUE` is used to apply the constraint to the executable return value.

例 3.3. Specifying a constraint's target

```
package org.hibernate.validator.referenceguide.chapter03.crossparameter.constrainttarget;

public class Garage {

    @ELAssert(expression = "...", validationAppliesTo = ConstraintTarget.PARAMETERS)
    public Car buildCar(List<Part> parts) {
        //...
    }

    @ELAssert(expression = "...", validationAppliesTo = ConstraintTarget.RETURN_VALUE)
    public Car paintCar(int color) {
        //...
    }
}
```

Although such a constraint is applicable to the parameters and return value of an executable, the target can often be inferred automatically. This is the case, if the constraint is declared on

- a void method with parameters (the constraint applies to the parameters)
- an executable with return value but no parameters (the constraint applies to the return value)
- neither a method nor a constructor, but a field, parameter etc. (the constraint applies to the annotated element)

In these situations you don't have to specify the constraint target. It is still recommended to do so if it increases readability of the source code. If the constraint target is not specified in situations where it can't be determined automatically, a `ConstraintDeclarationException` is raised.

3.1.2. Return value constraints

The postconditions of a method or constructor are declared by adding constraint annotations to the executable as shown in [例 3.4 “Declaring method and constructor return value constraints”](#).

例 3.4. Declaring method and constructor return value constraints

```
package org.hibernate.validator.referenceguide.chapter03.returnvalue;

public class RentalStation {

    @ValidRentalStation
    public RentalStation() {
        //...
    }
}
```

```

        @NotNull
        @Size(min = 1)
        public List<Customer> getCustomers() {
            //...
        }
    }
}

```

The following constraints apply to the executables of RentalStation:

- Any newly created RentalStation object must satisfy the @ValidRentalStation constraint
- The customer list returned by getCustomers() must not be null and must contain at least one element

3.1.3. Cascaded validation

Similar to the cascaded validation of JavaBeans properties (see [第 2.1.5 节 “Object graphs”](#)), the @Valid annotation can be used to mark executable parameters and return values for cascaded validation. When validating a parameter or return value annotated with @Valid, the constraints declared on the parameter or return value object are validated as well.

In [例 3.5 “Marking executable parameters and return values for cascaded validation”](#), the car parameter of the method Garage#checkCar() as well as the return value of the Garage constructor are marked for cascaded validation.

例 3.5. Marking executable parameters and return values for cascaded validation

```

package org.hibernate.validator.referenceguide.chapter03.cascaded;

public class Garage {

    @NotNull
    private String name;

    @Valid
    public Garage(String name) {
        this.name = name;
    }

    public boolean checkCar(@Valid @NotNull Car car) {
        //...
    }
}

```

```

package org.hibernate.validator.referenceguide.chapter03.cascaded;

public class Car {

```

```
@NotNull
private String manufacturer;

@NotNull
@Size(min = 2, max = 14)
private String licensePlate;

public Car(String manufacturer, String licencePlate) {
    this.manufacturer = manufacturer;
    this.licensePlate = licencePlate;
}

//getters and setters ...
}
```

When validating the arguments of the `checkCar()` method, the constraints on the properties of the passed `Car` object are evaluated as well. Similarly, the `@NotNull` constraint on the `name` field of `Garage` is checked when validating the return value of the `Garage` constructor.

Generally, the cascaded validation works for executables in exactly the same way as it does for JavaBeans properties.

In particular, null values are ignored during cascaded validation (naturally this can't happen during constructor return value validation) and cascaded validation is performed recursively, i.e. if a parameter or return value object which is marked for cascaded validation itself has properties marked with `@Valid`, the constraints declared on the referenced elements will be validated as well.

Cascaded validation can not only be applied to simple object references but also to collection-typed parameters and return values. This means when putting the `@Valid` annotation to a parameter or return value which

- is an array
- implements `java.lang.Iterable`
- or implements `java.util.Map`

each contained element gets validated. So when validating the arguments of the `checkCars()` method in [例 3.6 “List-typed method parameter marked for cascaded validation”](#), each element instance of the passed list will be validated and a `ConstraintViolation` created when any of the contained `Car` objects is invalid.

例 3.6. List-typed method parameter marked for cascaded validation

```
package org.hibernate.validator.referenceguide.chapter03.cascaded.collection;

public class Garage {
```

```
public boolean checkCars(@Valid @NotNull List<Car> cars) {  
    //...  
}  
}
```

3.1.4. Method constraints in inheritance hierarchies

When declaring method constraints in inheritance hierarchies, it is important to be aware of the following rules:

- The preconditions to be satisfied by the caller of a method may not be strengthened in subtypes
- The postconditions guaranteed to the caller of a method may not be weakened in subtypes

These rules are motivated by the concept of behavioral subtyping which requires that wherever a type *T* is used, also a subtype *S* of *T* may be used without altering the program's behavior.

As an example, consider a class invoking a method on an object with the static type *T*. If the runtime type of that object was *S* and *S* imposed additional preconditions, the client class might fail to satisfy these preconditions as is not aware of them. The rules of behavioral subtyping are also known as the [Liskov substitution principle](http://en.wikipedia.org/wiki/Liskov_substitution_principle) [http://en.wikipedia.org/wiki/Liskov_substitution_principle].

The Bean Validation specification implements the first rule by disallowing parameter constraints on methods which override or implement a method declared in a supertype (superclass or interface). 例 3.7 “Illegal method parameter constraint in subtype” shows a violation of this rule.

例 3.7. Illegal method parameter constraint in subtype

```
package org.hibernate.validator.referenceguide.chapter03.inheritance.parameter;  
  
public interface Vehicle {  
  
    void drive(@Max(75) int speedInMph);  
}
```

```
package org.hibernate.validator.referenceguide.chapter03.inheritance.parameter;  
  
public class Car implements Vehicle {  
  
    @Override  
    public void drive(@Max(55) int speedInMph) {  
        //...  
    }  
}
```

The `@Max` constraint on `Car#drive()` is illegal since this method implements the interface method `Vehicle#drive()`. Note that parameter constraints on overriding methods are also disallowed, if the supertype method itself doesn't declare any parameter constraints.

Furthermore, if a method overrides or implements a method declared in several parallel supertypes (e.g. two interfaces not extending each other or a class and an interface not implemented by that class), no parameter constraints may be specified for the method in any of the involved types. The types in [例 3.8 “Illegal method parameter constraint in parallel types of a hierarchy”](#) demonstrate a violation of that rule. The method `RacingCar#drive()` overrides `Vehicle#drive()` as well as `Car#drive()`. Therefore the constraint on `Vehicle#drive()` is illegal.

例 3.8. Illegal method parameter constraint in parallel types of a hierarchy

```
package org.hibernate.validator.referenceguide.chapter03.inheritance.parallel;

public interface Vehicle {

    void drive(@Max(75) int speedInMph);
}
```

```
package org.hibernate.validator.referenceguide.chapter03.inheritance.parallel;

public interface Car {

    public void drive(int speedInMph);
}
```

```
package org.hibernate.validator.referenceguide.chapter03.inheritance.parallel;

public class RacingCar implements Car, Vehicle {

    @Override
    public void drive(int speedInMph) {
        //...
    }
}
```

The previously described restrictions only apply to parameter constraints. In contrast, return value constraints may be added in methods overriding or implementing any supertype methods.

In this case, all the method's return value constraints apply for the subtype method, i.e. the constraints declared on the subtype method itself as well as any return value constraints on overridden/implemented supertype methods. This is legal as putting

additional return value constraints in place may never represent a weakening of the postconditions guaranteed to the caller of a method.

So when validating the return value of the method `Car#getPassengers()` shown in [例 3.9](#) “Return value constraints on supertype and subtype method”, the `@Size` constraint on the method itself as well as the `@NotNull` constraint on the implemented interface method `Vehicle#getPassengers()` apply.

例 3.9. Return value constraints on supertype and subtype method

```
package org.hibernate.validator.referenceguide.chapter03.inheritance.returnvalue;

public interface Vehicle {

    @NotNull
    List<Person> getPassengers();

}
```

```
package org.hibernate.validator.referenceguide.chapter03.inheritance.returnvalue;

public class Car implements Vehicle {

    @Override
    @Size(min = 1)
    public List<Person> getPassengers() {
        //...
    }

}
```

If the validation engine detects a violation of any of the aforementioned rules, a `ConstraintDeclarationException` will be raised.



注意

The rules described in this section only apply to methods but not constructors. By definition, constructors never override supertype constructors. Therefore, when validating the parameters or the return value of a constructor invocation only the constraints declared on the constructor itself apply, but never any constraints declared on supertype constructors.

3.2. Validating method constraints

The validation of method constraints is done using the `ExecutableValidator` interface.

In [第 3.2.1 节 “Obtaining an ExecutableValidator instance”](#) you will learn how to obtain an ExecutableValidator instance while [第 3.2.2 节 “ExecutableValidator methods”](#) shows how to use the different methods offered by this interface.

Instead of calling the ExecutableValidator methods directly from within application code, they are usually invoked via a method interception technology such as AOP, proxy objects, etc. This causes executable constraints to be validated automatically and transparently upon method or constructor invocation. Typically a ConstraintViolationException is raised by the integration layer in case any of the constraints is violated.

3.2.1. Obtaining an ExecutableValidator instance

You can retrieve an ExecutableValidator instance via Validator#forExecutables() as shown in [例 3.10 “Obtaining an ExecutableValidator”](#).

例 3.10. Obtaining an ExecutableValidator

```
ValidatorFactory factory = Validation.buildDefaultValidatorFactory();
executableValidator = factory.getValidator().forExecutables();
```

In the example the executable validator is retrieved from the default validator factory, but if required you could also bootstrap a specifically configured factory as described in [第 8 章 Bootstrapping](#), for instance in order to use a specific parameter name provider (see [第 8.2.4 节 “ParameterNameProvider”](#)).

3.2.2. ExecutableValidator methods

The ExecutableValidator interface offers altogether four methods:

- validateParameters() and validateReturnValue() for method validation
- validateConstructorParameters() and validateConstructorReturnValue() for constructor validation

Just as the methods on Validator, all these methods return a Set<ConstraintViolation> which contains a ConstraintViolation instance for each violated constraint and which is empty if the validation succeeds. Also all the methods have a var-args groups parameter by which you can pass the validation groups to be considered for validation.

The examples in the following sections are based on the methods on constructors of the Car class shown in [例 3.11 “Class Car with constrained methods and constructors”](#).

例 3.11. Class Car with constrained methods and constructors

```
package org.hibernate.validator.referenceguide.chapter03.validation;
```

```

public class Car {

    public Car(@NotNull String manufacturer) {
        //...
    }

    @ValidRacingCar
    public Car(String manufacturer, String team) {
        //...
    }

    public void drive(@Max(75) int speedInMph) {
        //...
    }

    @Size(min = 1)
    public List<Passenger> getPassengers() {
        //...
    }
}

```

3.2.2.1. ExecutableValidator#validateParameters()

The method `validateParameters()` is used to validate the arguments of a method invocation.

例 3.12 “Using `ExecutableValidator#validateParameters()`” shows an example. The validation results in a violation of the `@Max` constraint on the parameter of the `drive()` method.

例 3.12. Using `ExecutableValidator#validateParameters()`

```

Car object = new Car( "Morris" );
Method method = Car.class.getMethod( "drive", int.class );
Object[] parameterValues = { 80 };
Set<ConstraintViolation<Car>> violations = executableValidator.validateParameters(
    object,
    method,
    parameterValues
);

assertEquals( 1, violations.size() );
Class<? extends Annotation> constraintType = violations.iterator()
    .next()
    .getConstraintDescriptor()
    .getAnnotation()
    .annotationType();
assertEquals( Max.class, constraintType );

```

Note that `validateParameters()` validates all the parameter constraints of a method, i.e. constraints on individual parameters as well as cross-parameter constraints.

3.2.2.2. ExecutableValidator#validateReturnValue()

Using `validateReturnValue()` the return value of a method can be validated. The validation in [例 3.13 “Using ExecutableValidator#validateReturnValue\(\)”](#) yields one constraint violation since the `getPassengers()` method is expected to return at least one `Passenger` object.

例 3.13. Using ExecutableValidator#validateReturnValue()

```
Car object = new Car( "Morris" );
Method method = Car.class.getMethod( "getPassengers" );
Object returnValue = Collections.<Passenger>emptyList();
Set<ConstraintViolation<Car>> violations = executableValidator.validateReturnValue(
    object,
    method,
    returnValue
);

assertEquals( 1, violations.size() );
Class<? extends Annotation> constraintType = violations.iterator()
    .next()
    .getConstraintDescriptor()
    .getAnnotation()
    .annotationType();
assertEquals( Size.class, constraintType );
```

3.2.2.3. ExecutableValidator#validateConstructorParameters()

The arguments of constructor invocations can be validated with `validateConstructorParameters()` as shown in method [例 3.14 “Using ExecutableValidator#validateConstructorParameters\(\)”](#). Due to the `@NotNull` constraint on the manufacturer parameter, the validation call returns one constraint violation.

例 3.14. Using ExecutableValidator#validateConstructorParameters()

```
Constructor<Car> constructor = Car.class.getConstructor( String.class );
Object[] parameterValues = { null };
Set<ConstraintViolation<Car>> violations = executableValidator.validateConstructorParameters(
    constructor,
    parameterValues
);

assertEquals( 1, violations.size() );
Class<? extends Annotation> constraintType = violations.iterator()
    .next()
    .getConstraintDescriptor()
    .getAnnotation()
    .annotationType();
assertEquals( NotNull.class, constraintType );
```

3.2.2.4. ExecutableValidator#validateConstructorReturnValue()

Finally, by using `validateConstructorReturnValue()` you can validate a constructor's return value. In [例 3.15 “Using ExecutableValidator#validateConstructorReturnValue\(\)”](#), `validateConstructorReturnValue()` returns one constraint violation, since the `Car` object returned by the constructor doesn't satisfy the `@ValidRacingCar` constraint (not shown).

例 3.15. Using ExecutableValidator#validateConstructorReturnValue()

```
//constructor for creating racing cars
Constructor<Car> constructor = Car.class.getConstructor( String.class, String.class );
Car createdObject = new Car( "Morris", null );
Set<ConstraintViolation<Car>> violations = executableValidator.validateConstructorReturnValue(
    constructor,
    createdObject
);

assertEquals( 1, violations.size() );
Class<? extends Annotation> constraintType = violations.iterator()
    .next()
    .getConstraintDescriptor()
    .getAnnotation()
    .annotationType();
assertEquals( ValidRacingCar.class, constraintType );
```

3.2.3. ConstraintViolation methods for method validation

In addition to the methods introduced in [第 2.2.3 节 “ConstraintViolation methods”](#), `ConstraintViolation` provides two more methods specific to the validation of executable parameters and return values.

`ConstraintViolation#getExecutableParameters()` returns the validated parameter array in case of method or constructor parameter validation, while `ConstraintViolation#getExecutableReturnValue()` provides access to the validated object in case of return value validation.

All the other `ConstraintViolation` methods generally work for method validation in the same way as for validation of beans. Refer to the [JavaDoc](http://docs.jboss.org/hibernate/beanvalidation/spec/1.1/api/index.html?javax/validation/metadata/BeanDescriptor.html) [<http://docs.jboss.org/hibernate/beanvalidation/spec/1.1/api/index.html?javax/validation/metadata/BeanDescriptor.html>] to learn more about the behavior of the individual methods and their return values during bean and method validation.

Note that `getPropertyPath()` can be very useful in order to obtain detailed information about the validated parameter or return value, e.g. for logging purposes. In particular, you can retrieve name and argument types of the concerned method as well as the index of the concerned parameter from the path nodes. How this can be done is shown in [例 3.16 “Retrieving method and parameter information”](#).

例 3.16. Retrieving method and parameter information

```
Car object = new Car( "Morris" );
Method method = Car.class.getMethod( "drive", int.class );
Object[] parameterValues = { 80 };
Set<ConstraintViolation<Car>> violations = executableValidator.validateParameters(
    object,
    method,
    parameterValues
);

assertEquals( 1, violations.size() );
Iterator<Node> propertyPath = violations.iterator()
    .next()
    .getPropertyPath()
    .iterator();

MethodNode methodNode = propertyPath.next().as( MethodNode.class );
assertEquals( "drive", methodNode.getName() );
assertEquals( Arrays.<Class<?>>asList( int.class ), methodNode.getParameterTypes() );

ParameterNode parameterNode = propertyPath.next().as( ParameterNode.class );
assertEquals( "arg0", parameterNode.getName() );
assertEquals( 0, parameterNode.getParameterIndex() );
```

The parameter name is determined using the current `ParameterNameProvider` (see [第 8.2.4 节 “ParameterNameProvider”](#)) and defaults to `arg0`, `arg1` etc.

Interpolating constraint error messages

Message interpolation is the process of creating error messages for violated Bean Validation constraints. In this chapter you will learn how such messages are defined and resolved and how you can plug in custom message interpolators in case the default algorithm is not sufficient for your requirements.

4.1. Default message interpolation

Constraint violation messages are retrieved from so called message descriptors. Each constraint defines its default message descriptor using the message attribute. At declaration time, the default descriptor can be overridden with a specific value as shown in [例 4.1 “Specifying a message descriptor using the message attribute”](#).

例 4.1. Specifying a message descriptor using the `message` attribute

```
package org.hibernate.validator.referenceguide.chapter04;

public class Car {

    @NotNull(message = "The manufacturer name must not be null")
    private String manufacturer;

    //constructor, getters and setters ...
}
```

If a constraint is violated, its descriptor will be interpolated by the validation engine using the currently configured `MessageInterpolator`. The interpolated error message can then be retrieved from the resulting constraint violation by calling `ConstraintViolation#getMessage()`.

Message descriptors can contain message parameters as well as message expressions which will be resolved during interpolation. Message parameters are string literals enclosed in `{}`, while message expressions are string literals enclosed in `${}`. The following algorithm is applied during method interpolation:

1. Resolve any message parameters by using them as key for the resource bundle `ValidationMessages`. If this bundle contains an entry for a given message parameter, that parameter will be replaced in the message with the corresponding value from the bundle. This step will be executed recursively in case the replaced value again contains message parameters. The resource bundle is expected to be provided by the application developer, e.g. by adding a file named `ValidationMessages.properties` to the

classpath. You can also create localized error messages by providing locale specific variations of this bundle, such as `ValidationMessages_en_US.properties`. By default, the JVM's default locale (`Locale#getDefault()`) will be used when looking up messages in the bundle.

2. Resolve any message parameters by using them as key for a resource bundle containing the standard error messages for the built-in constraints as defined in Appendix B of the Bean Validation specification. In the case of Hibernate Validator, this bundle is named `org.hibernate.validator.ValidationMessages`. If this step triggers a replacement, step 1 is executed again, otherwise step 3 is applied.
3. Resolve any message parameters by replacing them with the value of the constraint annotation member of the same name. This allows to refer to attribute values of the constraint (e.g. `Size#min()`) in the error message (e.g. "must be at least `{min}`").
4. Resolve any message expressions by evaluating them as expressions of the Unified Expression Language. See [第 4.1.2 节 “Interpolation with message expressions”](#) to learn more about the usage of Unified EL in error messages.



提示

You can find the formal definition of the interpolation algorithm in section 5.3.1.1 [<http://beanvalidation.org/1.1/spec/#default-resolution-algorithm>] of the Bean Validation specification.

4.1.1. Special characters

Since the characters `{`, `}` and `$` have a special meaning in message descriptors they need to be escaped if you want to use them literally. The following rules apply:

- `\{` is considered as the literal `{`
- `\}` is considered as the literal `}`
- `\$` is considered as the literal `$`
- `\\` is considered as the literal `\`

4.1.2. Interpolation with message expressions

As of Hibernate Validator 5 (Bean Validation 1.1) it is possible to use the Unified Expression Language (as defined by [JSR 341](#) [<http://jcp.org/en/jsr/detail?id=341>]) in constraint violation messages. This allows to define error messages based on conditional logic and also enables advanced formatting options. The validation engine makes the following objects available in the EL context:

- the attribute values of the constraint mapped to the attribute names
- the currently validated value (property, bean, method parameter etc.) under the name `validatedValue`
- a bean mapped to the name formatter exposing the var-arg method `format(String format, Object... args)` which behaves like `java.util.Formatter.format(String format, Object... args)`.

The following section provides several examples for using EL expressions in error messages.

4.1.3. Examples

例 4.2 “Specifying message descriptors” shows how to make use of the different options for specifying message descriptors.

例 4.2. Specifying message descriptors

```
package org.hibernate.validator.referenceguide.chapter04.complete;

public class Car {

    @NotNull
    private String manufacturer;

    @Size(
        min = 2,
        max = 14,
        message = "The license plate must be between {min} and {max} characters long"
    )
    private String licensePlate;

    @Min(
        value = 2,
        message = "There must be at least {value} seat${value > 1 ? 's' : ''}"
    )
    private int seatCount;

    @DecimalMax(
        value = "350",
        message = "The top speed ${formatter.format('%1$.2f', validatedValue)}
is higher " +
                                "than {value}"
    )
    private double topSpeed;

    @DecimalMax(value = "100000", message = "Price must not be higher than ${value}")
    private BigDecimal price;

    public Car(
        String manufacturer,
        String licensePlate,
        int seatCount,
```

```
        double topSpeed,  
        BigDecimal price) {  
            this.manufacturer = manufacturer;  
            this.licensePlate = licensePlate;  
            this.seatCount = seatCount;  
            this.topSpeed = topSpeed;  
            this.price = price;  
        }  
  
        //getters and setters ...  
    }  
}
```

Validating an invalid Car instance yields constraint violations with the messages shown by the assertions in [例 4.3 “Expected error messages”](#) :

- the `@NotNull` constraint on the `manufacturer` field causes the error message "may not be null", as this is the default message defined by the Bean Validation specification and no specific descriptor is given in the message attribute
- the `@Size` constraint on the `licensePlate` field shows the interpolation of message parameters (`{min}`, `{max}`)
- the `@Min` constraint on `seatCount` demonstrates how use an EL expression with a ternery expression to dynamically chose singular or plural form, depending on an attribute of the constraint ("There must be at least 1 seat" vs. "There must be at least 2 seats")
- the message for the `@DecimalMax` constraint on `topSpeed` shows how to refer to the validated object in the error message and format it using the formatter object
- finally, the `@DecimalMax` constraint on `price` shows that parameter interpolation has precedence over expression evaluation, causing the \$ sign to show up in front of the maximum price

例 4.3. Expected error messages

```
Car car = new Car( null, "A", 1, 400.123456, BigDecimal.valueOf( 200000 ) );  
  
String message = validator.validateProperty( car, "manufacturer" )  
    .iterator()  
    .next()  
    .getMessage();  
assertEquals( "may not be null", message );  
  
message = validator.validateProperty( car, "licensePlate" )  
    .iterator()  
    .next()  
    .getMessage();  
assertEquals(  
    "The license plate must be between 2 and 14 characters long",  
    message  
);
```

```

message = validator.validateProperty( car, "seatCount" ).iterator().next().getMessage();
assertEquals( "There must be at least 2 seats", message );

message = validator.validateProperty( car, "topSpeed" ).iterator().next().getMessage();
assertEquals( "The top speed 400.12 is higher than 350", message );

message = validator.validateProperty( car, "price" ).iterator().next().getMessage();
assertEquals( "Price must not be higher than $100000", message );

```

4.2. Custom message interpolation

If the default message interpolation algorithm does not fit your requirements it is also possible to plug in a custom `MessageInterpolator` implementation.

Custom interpolators must implement the interface `javax.validation.MessageInterpolator`. Note that implementations must be thread-safe. It is recommended that custom message interpolators delegate final implementation to the default interpolator, which can be obtained via `Configuration#getDefaultMessageInterpolator()`.

In order to use a custom message interpolator it must be registered either by configuring it in the Bean Validation XML descriptor `META-INF/validation.xml` (see [第 7.1 节 “Configuring the validator factory in validation.xml”](#)) or by passing it when bootstrapping a `ValidatorFactory` or `Validator` (see [第 8.2.1 节 “MessageInterpolator”](#) and [第 8.3 节 “Configuring a Validator”](#), respectively).

4.2.1. `ResourceBundleLocator`

In some use cases you want to use the message interpolation algorithm as defined by the Bean Validation specification, but retrieve error messages from other resource bundles than `ValidationMessages`. In this situation Hibernate Validator's `ResourceBundleLocator` SPI can help.

The default message interpolator in Hibernate Validator, `ResourceBundleMessageInterpolator`, delegates retrieval of resource bundles to that SPI. Using an alternative bundle only requires passing an instance of `PlatformResourceBundleLocator` with the bundle name when bootstrapping the `ValidatorFactory` as shown in [例 4.4 “Using a specific resource bundle”](#).

例 4.4. Using a specific resource bundle

```

Validator validator = Validation.byDefaultProvider()
    .configure()
    .messageInterpolator(
        new ResourceBundleMessageInterpolator(
            new PlatformResourceBundleLocator( "MyMessages" )
        )
    )
    .buildValidatorFactory()

```

```
.getValidator();
```

Of course you also could implement a completely different `ResourceBundleLocator`, which for instance returns bundles backed by records in a database. In this case you can obtain the default locator via `HibernateValidatorConfiguration#getDefaultResourceBundleLocator()`, which you e.g. could use as fallback for your custom locator.

Besides `PlatformResourceBundleLocator`, Hibernate Validator provides another resource bundle locator implementation out of the box, namely `AggregateResourceBundleLocator`, which allows to retrieve error messages from more than one resource bundle. You could for instance use this implementation in a multi-module application where you want to have one message bundle per module. 例 4.5 “Using `AggregateResourceBundleLocator`” shows how to use `AggregateResourceBundleLocator`.

例 4.5. Using `AggregateResourceBundleLocator`

```
Validator validator = Validation.byDefaultProvider()
    .configure()
    .messageInterpolator(
        new ResourceBundleMessageInterpolator(
            new AggregateResourceBundleLocator(
                Arrays.asList(
                    "MyMessages",
                    "MyOtherMessages"
                )
            )
        )
    )
    .buildValidatorFactory()
    .getValidator();
```

Note that the bundles are processed in the order as passed to the constructor. That means if several bundles contain an entry for a given message key, the value will be taken from the first bundle in the list containing the key.

Grouping constraints

All validation methods on `Validator` and `ExecutableValidator` discussed in earlier chapters also take a var-arg argument `groups`. So far we have been ignoring this parameter, but it is time to have a closer look.

5.1. Requesting groups

Groups allow you to restrict the set of constraints applied during validation. One use case for validation groups are UI wizards where in each step only a specified subset of constraints should get validated. The groups targeted are passed as var-arg parameters to the appropriate `validate` method.

Let's have a look at an example. The class `Person` in 例 5.1 “`Person`” has a `@NotNull` constraint on `name`. Since no group is specified for this annotation the default group `javax.validation.groups.Default` is assumed.



注意

When more than one group is requested, the order in which the groups are evaluated is not deterministic. If no group is specified the default group `javax.validation.groups.Default` is assumed.

例 5.1. `Person`

```
package org.hibernate.validator.referenceguide.chapter05;

public class Person {

    @NotNull
    private String name;

    public Person(String name) {
        this.name = name;
    }

    // getters and setters ...
}
```

The class `Driver` in 例 5.2 “`Driver`” extends `Person` and adds the properties `age` and `hasDrivingLicense`. Drivers must be at least 18 years old (`@Min(18)`) and have a driving license (`@AssertTrue`). Both constraints defined on these properties belong to the group `DriverChecks` which is just a simple tagging interface.



提示

Using interfaces makes the usage of groups type-safe and allows for easy refactoring. It also means that groups can inherit from each other via class inheritance.

例 5.2. Driver

```
package org.hibernate.validator.referenceguide.chapter05;

public class Driver extends Person {

    @Min(
        value = 18,
        message = "You have to be 18 to drive a car",
        groups = DriverChecks.class
    )
    public int age;

    @AssertTrue(
        message = "You first have to pass the driving test",
        groups = DriverChecks.class
    )
    public boolean hasDrivingLicense;

    public Driver(String name) {
        super( name );
    }

    public void passedDrivingTest(boolean b) {
        hasDrivingLicense = b;
    }

    public int getAge() {
        return age;
    }

    public void setAge(int age) {
        this.age = age;
    }
}
```

```
package org.hibernate.validator.referenceguide.chapter05;

public interface DriverChecks {
}
```

Finally the class `Car` (例 5.3 “Car”) has some constraints which are part of the default group as well as `@AssertTrue` in the group `CarChecks` on the property `passedVehicleInspection` which indicates whether a car passed the road worthy tests.

例 5.3. Car

```
package org.hibernate.validator.referenceguide.chapter05;

public class Car {
    @NotNull
    private String manufacturer;

    @NotNull
    @Size(min = 2, max = 14)
    private String licensePlate;

    @Min(2)
    private int seatCount;

    @AssertTrue(
        message = "The car has to pass the vehicle inspection first",
        groups = CarChecks.class
    )
    private boolean passedVehicleInspection;

    @Valid
    private Driver driver;

    public Car(String manufacturer, String licencePlate, int seatCount) {
        this.manufacturer = manufacturer;
        this.licensePlate = licencePlate;
        this.seatCount = seatCount;
    }

    // getters and setters ...
}
```

```
package org.hibernate.validator.referenceguide.chapter05;

public interface CarChecks {
}
```

Overall three different groups are used in the example:

- The constraints on `Person.name`, `Car.manufacturer`, `Car.licensePlate` and `Car.seatCount` all belong to the `Default` group
- The constraints on `Driver.age` and `Driver.hasDrivingLicense` belong to `DriverChecks`
- The constraint on `Car.passedVehicleInspection` belongs to the group `CarChecks`

例 5.4 “Using validation groups” shows how passing different group combinations to the `Validator#validate()` method results in different validation results.

例 5.4. Using validation groups

```
// create a car and check that everything is ok with it.
Car car = new Car( "Morris", "DD-AB-123", 2 );
Set<ConstraintViolation<Car>> constraintViolations = validator.validate( car );
assertEquals( 0, constraintViolations.size() );

// but has it passed the vehicle inspection?
constraintViolations = validator.validate( car, CarChecks.class );
assertEquals( 1, constraintViolations.size() );
assertEquals(
    "The car has to pass the vehicle inspection first",
    constraintViolations.iterator().next().getMessage()
);

// let's go to the vehicle inspection
car.setPassedVehicleInspection( true );
assertEquals( 0, validator.validate( car ).size() );

// now let's add a driver. He is 18, but has not passed the driving test yet
Driver john = new Driver( "John Doe" );
john.setAge( 18 );
car.setDriver( john );
constraintViolations = validator.validate( car, DriverChecks.class );
assertEquals( 1, constraintViolations.size() );
assertEquals(
    "You first have to pass the driving test",
    constraintViolations.iterator().next().getMessage()
);

// ok, John passes the test
john.passedDrivingTest( true );
assertEquals( 0, validator.validate( car, DriverChecks.class ).size() );

// just checking that everything is in order now
assertEquals(
    0, validator.validate(
        car,
        Default.class,
        CarChecks.class,
        DriverChecks.class
    ).size()
);
```

The first `validate()` call in 例 5.4 “Using validation groups” is done using no explicit group. There are no validation errors, even though the property `passedVehicleInspection` is per default false. However, the constraint defined on this property does not belong to the default group.

The next validation using the `CarChecks` group fails until the car passes the vehicle inspection. Adding a driver to the car and validating against `DriverChecks` again yields

one constraint violation due to the fact that the driver has not yet passed the driving test. Only after setting `passedDrivingTest` to `true` the validation against `DriverChecks` passes.

The last `validate()` call finally shows that all constraints are passing by validating against all defined groups.

5.2. Defining group sequences

By default, constraints are evaluated in no particular order, regardless of which groups they belong to. In some situations, however, it is useful to control the order constraints are evaluated.

In the example from [例 5.4 “Using validation groups”](#) it could for instance be required that first all default car constraints are passing before checking the road worthiness of the car. Finally, before driving away, the actual driver constraints should be checked.

In order to implement such a validation order you just need to define an interface and annotate it with `@GroupSequence`, defining the order in which the groups have to be validated (see [例 5.5 “Defining a group sequence”](#)). If at least one constraint fails in a sequenced group none of the constraints of the following groups in the sequence get validated.

例 5.5. Defining a group sequence

```
package org.hibernate.validator.referenceguide.chapter05;

@GroupSequence({ Default.class, CarChecks.class, DriverChecks.class })
public interface OrderedChecks {
}
```



警告

Groups defining a sequence and groups composing a sequence must not be involved in a cyclic dependency either directly or indirectly, either through cascaded sequence definition or group inheritance. If a group containing such a circularity is evaluated, a `GroupDefinitionException` is raised.

You then can use the new sequence as shown in in [例 5.6 “Using a group sequence”](#).

例 5.6. Using a group sequence

```
Car car = new Car( "Morris", "DD-AB-123", 2 );
```

```
car.setPassedVehicleInspection( true );

Driver john = new Driver( "John Doe" );
john.setAge( 18 );
john.passedDrivingTest( true );
car.setDriver( john );

assertEquals( 0, validator.validate( car, OrderedChecks.class ).size() );
```

5.3. Redefining the default group sequence

5.3.1. @GroupSequence

Besides defining group sequences, the `@GroupSequence` annotation also allows to redefine the default group for a given class. To do so, just add the `@GroupSequence` annotation to the class and specify the sequence of groups which substitute Default for this class within the annotation.

例 5.7 “Class RentalCar with redefined default group” introduces a new class RentalCar with a redefined default group.

例 5.7. Class RentalCar with redefined default group

```
package org.hibernate.validator.referenceguide.chapter05;

@GroupSequence({ RentalChecks.class, CarChecks.class, RentalCar.class })
public class RentalCar extends Car {
    @AssertFalse(message = "The car is currently rented out", groups = RentalChecks.class)
    private boolean rented;

    public RentalCar(String manufacturer, String licencePlate, int seatCount) {
        super( manufacturer, licencePlate, seatCount );
    }

    public boolean isRented() {
        return rented;
    }

    public void setRented(boolean rented) {
        this.rented = rented;
    }
}
```

```
package org.hibernate.validator.referenceguide.chapter05;

public interface RentalChecks {
}
```

With this definition you can evaluate the constraints belonging to RentalChecks, CarChecks and RentalCar by just requesting the Default group as seen in [例 5.8 “Validating an object with redefined default group”](#).

例 5.8. Validating an object with redefined default group

```
RentalCar rentalCar = new RentalCar( "Morris", "DD-AB-123", 2 );
rentalCar.setPassedVehicleInspection( true );
rentalCar.setRented( true );

Set<ConstraintViolation<RentalCar>> constraintViolations = validator.validate( rentalCar );

assertEquals( 1, constraintViolations.size() );
assertEquals(
    "Wrong message",
    "The car is currently rented out",
    constraintViolations.iterator().next().getMessage()
);

rentalCar.setRented( false );
constraintViolations = validator.validate( rentalCar );

assertEquals( 0, constraintViolations.size() );
```



注意

Since there must no cyclic dependency in the group and group sequence definitions one cannot just add Default to the sequence redefining Default for a class. Instead the class itself has to be added!

The Default group sequence overriding is local to the class it is defined on and is not propagated to associated objects. For the example this means that adding DriverChecks to the default group sequence of RentalCar would not have any effects. Only the group Default will be propagated to the driver association.

Note that you can control the propagated group(s) by declaring a group conversion rule (see [第 5.4 节 “Group conversion”](#)).

5.3.2. @GroupSequenceProvider

In addition to statically redefining default group sequences via @GroupSequence, Hibernate Validator also provides an SPI for the dynamic redefinition of default group sequences depending on the object state.

For that purpose you need to implement the interface DefaultGroupSequenceProvider and register this implementation with the target class via the @GroupSequenceProvider annotation. In the rental car scenario you could for instance dynamically add the CarChecks as seen in [例 5.9 “Implementing and using a default group sequence provider”](#).

例 5.9. Implementing and using a default group sequence provider

```
package org.hibernate.validator.referenceguide.chapter05.groupsequenceprovider;

public class RentalCarGroupSequenceProvider
    implements DefaultGroupSequenceProvider<RentalCar> {

    @Override
    public List<Class<?>> getValidationGroups(RentalCar car) {
        List<Class<?>> defaultGroupSequence = new ArrayList<Class<?>>();
        defaultGroupSequence.add( RentalCar.class );

        if ( car != null && !car.isRented() ) {
            defaultGroupSequence.add( CarChecks.class );
        }

        return defaultGroupSequence;
    }
}
```

```
package org.hibernate.validator.referenceguide.chapter05.groupsequenceprovider;

@GroupSequenceProvider(RentalCarGroupSequenceProvider.class)
public class RentalCar extends Car {

    @AssertFalse(message = "The car is currently rented out", groups = RentalChecks.class)
    private boolean rented;

    public RentalCar(String manufacturer, String licencePlate, int seatCount) {
        super( manufacturer, licencePlate, seatCount );
    }

    public boolean isRented() {
        return rented;
    }

    public void setRented(boolean rented) {
        this.rented = rented;
    }
}
```

5.4. Group conversion

What if you wanted to validate the car related checks together with the driver checks? Of course you could pass the required groups to the validate call explicitly, but what if you wanted to make these validations occur as part of the Default group validation? Here `@ConvertGroup` comes into play which allows you during cascaded validation to use a different group than the originally requested one.

Let's have a look at 例 5.10 “`@ConvertGroup` usage”. Here `@GroupSequence({ CarChecks.class, Car.class })` is used to combine the car related constraints

under the Default group (see [第 5.3 节 “Redefining the default group sequence”](#)). There is also a `@ConvertGroup(from = Default.class, to = DriverChecks.class)` which ensures the Default group gets converted to the DriverChecks group during cascaded validation of the driver association.

例 5.10. `@ConvertGroup` usage

```
package org.hibernate.validator.referenceguide.chapter05.groupconversion;

public class Driver {

    @NotNull
    private String name;

    @Min(
        value = 18,
        message = "You have to be 18 to drive a car",
        groups = DriverChecks.class
    )
    public int age;

    @AssertTrue(
        message = "You first have to pass the driving test",
        groups = DriverChecks.class
    )
    public boolean hasDrivingLicense;

    public Driver(String name) {
        this.name = name;
    }

    public void passedDrivingTest(boolean b) {
        hasDrivingLicense = b;
    }

    // getters and setters ...
}
```

```
package org.hibernate.validator.referenceguide.chapter05.groupconversion;

@GroupSequence({ CarChecks.class, Car.class })
public class Car {

    @NotNull
    private String manufacturer;

    @NotNull
    @Size(min = 2, max = 14)
    private String licensePlate;

    @Min(2)
    private int seatCount;

    @AssertTrue(
```

```
        message = "The car has to pass the vehicle inspection first",
        groups = CarChecks.class
    )
    private boolean passedVehicleInspection;

    @Valid
    @ConvertGroup(from = Default.class, to = DriverChecks.class)
    private Driver driver;

    public Car(String manufacturer, String licencePlate, int seatCount) {
        this.manufacturer = manufacturer;
        this.licensePlate = licencePlate;
        this.seatCount = seatCount;
    }

    // getters and setters ...
}
```

As a result the validation in 例 5.11 “Test case for @ConvertGroup” succeeds, even though the constraint on `hasDrivingLicense` belongs to the `DriverChecks` group and only the `Default` group is requested in the `validate()` call.

例 5.11. Test case for @ConvertGroup

```
// create a car and validate. The Driver is still null and does not get validated
Car car = new Car( "VW", "USD-123", 4 );
car.setPassedVehicleInspection( true );
Set<ConstraintViolation<Car>> constraintViolations = validator.validate( car );
assertEquals( 0, constraintViolations.size() );

// create a driver who has not passed the driving test
Driver john = new Driver( "John Doe" );
john.setAge( 18 );

// now let's add a driver to the car
car.setDriver( john );
constraintViolations = validator.validate( car );
assertEquals( 1, constraintViolations.size() );
assertEquals(
    "The driver constraint should also be validated as part of the default group",
    constraintViolations.iterator().next().getMessage(),
    "You first have to pass the driving test"
);
```

You can define group conversions wherever `@Valid` can be used, namely associations as well as method and constructor parameters and return values. Multiple conversions can be specified using `@ConvertGroup.List`.

However, the following restrictions apply:

- `@ConvertGroup` must only be used in combination with `@Valid`. If used without, a `ConstraintDeclarationException` is thrown.

- It is not legal to have multiple conversion rules on the same element with the same from value. In this case, a `ConstraintDeclarationException` is raised.
- The from attribute must not refer to a group sequence. A `ConstraintDeclarationException` is raised in this situation.



注意

Rules are not executed recursively. The first matching conversion rule is used and subsequent rules are ignored. For example if a set of `@ConvertGroup` declarations chains group A to B and B to C, the group A will be converted to B and not to C.

Creating custom constraints

The Bean Validation API defines a whole set of standard constraint annotations such as `@NotNull`, `@Size` etc. In cases where these built-in constraints are not sufficient, you can easily create custom constraints tailored to your specific validation requirements.

6.1. Creating a simple constraint

To create a custom constraint, the following three steps are required:

- Create a constraint annotation
- Implement a validator
- Define a default error message

6.1.1. The constraint annotation

This section shows how to write a constraint annotation which can be used to ensure that a given string is either completely upper case or lower case. Later on this constraint will be applied to the `licensePlate` field of the `Car` class from [第 1 章 Getting started](#) to ensure, that the field is always an upper-case string.

The first thing needed is a way to express the two case modes. While you could use String constants, a better approach is using a Java 5 enum for that purpose:

例 6.1. Enum `CaseMode` to express upper vs. lower case

```
package org.hibernate.validator.referenceguide.chapter06;

public enum CaseMode {
    UPPER,
    LOWER;
}
```

The next step is to define the actual constraint annotation. If you've never designed an annotation before, this may look a bit scary, but actually it's not that hard:

例 6.2. Defining the `@CheckCase` constraint annotation

```
package org.hibernate.validator.referenceguide.chapter06;

@Target({ FIELD, METHOD, PARAMETER, ANNOTATION_TYPE })
@Retention(RUNTIME)
@Constraint(validatedBy = CheckCaseValidator.class)
@Documented
```

```
public @interface CheckCase {

    String message() default "{org.hibernate.validator.referenceguide.chapter06.CheckCase." +
        "message}";

    Class<?>[] groups() default { };

    Class<? extends Payload>[] payload() default { };

    CaseMode value();

    @Target({ FIELD, METHOD, PARAMETER, ANNOTATION_TYPE })
    @Retention(RUNTIME)
    @Documented
    @interface List {
        CheckCase[] value();
    }
}
```

An annotation type is defined using the `@interface` keyword. All attributes of an annotation type are declared in a method-like manner. The specification of the Bean Validation API demands, that any constraint annotation defines

- an attribute `message` that returns the default key for creating error messages in case the constraint is violated
- an attribute `groups` that allows the specification of validation groups, to which this constraint belongs (see [第 5 章 Grouping constraints](#)). This must default to an empty array of type `Class<?>`.
- an attribute `payload` that can be used by clients of the Bean Validation API to assign custom payload objects to a constraint. This attribute is not used by the API itself. An example for a custom payload could be the definition of a severity:

```
public class Severity {
    public interface Info extends Payload {
    }

    public interface Error extends Payload {
    }
}

public class ContactDetails {
    @NotNull(message = "Name is mandatory", payload = Severity.Error.class)
    private String name;

    @NotNull(message = "Phone number not specified, but not mandatory",
        payload = Severity.Info.class)
    private String phoneNumber;

    // ...
}
```

Now a client can after the validation of a `ContactDetails` instance access the severity of a constraint using `ConstraintViolation.getConstraintDescriptor().getPayload()` and adjust its behaviour depending on the severity.

Besides these three mandatory attributes there is another one, `value`, allowing for the required case mode to be specified. The name `value` is a special one, which can be omitted when using the annotation, if it is the only attribute specified, as e.g. in `@CheckCase(CaseMode.UPPER)`.

In addition, the constraint annotation is decorated with a couple of meta annotations:

- `@Target({ FIELD, METHOD, PARAMETER, ANNOTATION_TYPE })`: Defines the supported target element types for the constraint. `@CheckCase` may be used on fields (element type `FIELD`), JavaBeans properties as well as method return values (`METHOD`) and method/constructor parameters (`PARAMETER`). The element type `ANNOTATION_TYPE` allows for the creation of composed constraints (see [第 6.4 节 “Constraint composition”](#)) based on `@CheckCase`.

When creating a class-level constraint (see [第 2.1.3 节 “Class-level constraints”](#)), the element type `TYPE` would have to be used. Constraints targetting the return value of a constructor need to support the element type `CONSTRUCTOR`. Cross-parameter constraints (see [第 6.3 节 “Cross-parameter constraints”](#)) which are used to validate all the parameters of a method or constructor together, must support `METHOD` or `CONSTRUCTOR`, respectively.

- `@Retention(RUNTIME)`: Specifies, that annotations of this type will be available at runtime by the means of reflection
- `@Constraint(validatedBy = CheckCaseValidator.class)`: Marks the annotation type as constraint annotation and specifies the validator to be used to validate elements annotated with `@CheckCase`. If a constraint may be used on several data types, several validators may be specified, one for each data type.
- `@Documented`: Says, that the use of `@CheckCase` will be contained in the JavaDoc of elements annotated with it

Finally, there is an inner annotation type named `List`. This annotation allows to specify several `@CheckCase` annotations on the same element, e.g. with different validation groups and messages. While also another name could be used, the Bean Validation specification recommends to use the name `List` and make the annotation an inner annotation of the corresponding constraint type.

6.1.2. The constraint validator

Having defined the annotation, you need to create a constraint validator, which is able to validate elements with a `@CheckCase` annotation. To do so, implement the interface `ConstraintValidator` as shown below:

例 6.3. Implementing a constraint validator for the constraint `@CheckCase`

```
package org.hibernate.validator.referenceguide.chapter06;

public class CheckCaseValidator implements ConstraintValidator<CheckCase, String> {

    private CaseMode caseMode;

    @Override
    public void initialize(CheckCase constraintAnnotation) {
        this.caseMode = constraintAnnotation.value();
    }

    @Override
    public boolean isValid(String object, ConstraintValidatorContext constraintContext) {
        if ( object == null ) {
            return true;
        }

        if ( caseMode == CaseMode.UPPER ) {
            return object.equals( object.toUpperCase() );
        }
        else {
            return object.equals( object.toLowerCase() );
        }
    }
}
```

The `ConstraintValidator` interface defines two type parameters which are set in the implementation. The first one specifies the annotation type to be validated (`CheckCase`), the second one the type of elements, which the validator can handle (`String`). In case a constraint supports several data types, a `ConstraintValidator` for each allowed type has to be implemented and registered at the constraint annotation as shown above.

The implementation of the validator is straightforward. The `initialize()` method gives you access to the attribute values of the validated constraint and allows you to store them in a field of the validator as shown in the example.

The `isValid()` method contains the actual validation logic. For `@CheckCase` this is the check whether a given string is either completely lower case or upper case, depending on the case mode retrieved in `initialize()`. Note that the Bean Validation specification recommends to consider null values as being valid. If null is not a valid value for an element, it should be annotated with `@NotNull` explicitly.

6.1.2.1. The `ConstraintValidatorContext`

例 6.3 “Implementing a constraint validator for the constraint `@CheckCase`” relies on the default error message generation by just returning true or false from the `isValid()` method. Using the passed `ConstraintValidatorContext` object it is possible to either add additional error messages or completely disable the default error message generation

and solely define custom error messages. The `ConstraintValidatorContext` API is modeled as fluent interface and is best demonstrated with an example:

例 6.4. Using `ConstraintValidatorContext` to define custom error messages

```
package org.hibernate.validator.referenceguide.chapter06.constraintvalidatorcontext;

public class CheckCaseValidator implements ConstraintValidator<CheckCase, String> {

    private CaseMode caseMode;

    @Override
    public void initialize(CheckCase constraintAnnotation) {
        this.caseMode = constraintAnnotation.value();
    }

    @Override
    public boolean isValid(String object, ConstraintValidatorContext constraintContext) {
        if ( object == null ) {
            return true;
        }

        boolean isValid;
        if ( caseMode == CaseMode.UPPER ) {
            isValid = object.equals( object.toUpperCase() );
        }
        else {
            isValid = object.equals( object.toLowerCase() );
        }

        if ( !isValid ) {
            constraintContext.disableDefaultConstraintViolation();
            constraintContext.buildConstraintViolationWithTemplate(
                "{org.hibernate.validator.referenceguide.chapter03." +
                "constraintvalidatorcontext.CheckCase.message}"
            )
                .addConstraintViolation();
        }

        return isValid;
    }
}
```

例 6.4 “Using `ConstraintValidatorContext` to define custom error messages” shows how you can disable the default error message generation and add a custom error message using a specified message template. In this example the use of the `ConstraintValidatorContext` results in the same error message as the default error message generation.



提示

It is important to add each configured constraint violation by calling `addConstraintViolation()`. Only after that the new constraint violation will be created.

Refer to [第 6.2.1 节 “Custom property paths”](#) to learn how to use the `ConstraintValidatorContext` API to control the property path of constraint violations for class-level constraints.

6.1.3. The error message

The last missing building block is an error message which should be used in case a `@CheckCase` constraint is violated. To define this, create a file `ValidationMessages.properties` with the following contents (see also [第 4.1 节 “Default message interpolation”](#)):

例 6.5. Defining a custom error message for the `CheckCase` constraint

```
org.hibernate.validator.referenceguide.chapter06.CheckCase.message=Case mode must be {value}.
```

If a validation error occurs, the validation runtime will use the default value, that you specified for the message attribute of the `@CheckCase` annotation to look up the error message in this resource bundle.

6.1.4. Using the constraint

You can now use the constraint in the `Car` class from the [第 1 章 Getting started](#) chapter to specify that the `licensePlate` field should only contain upper-case strings:

例 6.6. Applying the `@CheckCase` constraint

```
package org.hibernate.validator.referenceguide.chapter06;

public class Car {

    @NotNull
    private String manufacturer;

    @NotNull
    @Size(min = 2, max = 14)
    @CheckCase(CaseMode.UPPER)
    private String licensePlate;

    @Min(2)
    private int seatCount;
```

```

    public Car ( String manufacturer, String licencePlate, int seatCount ) {
        this.manufacturer = manufacturer;
        this.licensePlate = licencePlate;
        this.seatCount = seatCount;
    }

    //getters and setters ...
}

```

Finally, 例 6.7 “Validating objects with the @CheckCase constraint” demonstrates how validating a Car object with an invalid license plate causes the @CheckCase constraint to be violated.

例 6.7. Validating objects with the @CheckCase constraint

```

//invalid license plate
Car car = new Car( "Morris", "dd-ab-123", 4 );
Set<ConstraintViolation<Car>> constraintViolations =
    validator.validate( car );
assertEquals( 1, constraintViolations.size() );
assertEquals(
    "Case mode must be UPPER.",
    constraintViolations.iterator().next().getMessage()
);

//valid license plate
car = new Car( "Morris", "DD-AB-123", 4 );

constraintViolations = validator.validate( car );

assertEquals( 0, constraintViolations.size() );

```

6.2. Class-level constraints

As discussed earlier, constraints can also be applied on the class level to validate the state of an entire object. Class-level constraints are defined in the same way as are property constraints. 例 6.8 “Implementing a class-level constraint” shows constraint annotation and validator of the @ValidPassengerCount constraint you already saw in use in 例 2.3 “Class-level constraint”.

例 6.8. Implementing a class-level constraint

```

package org.hibernate.validator.referenceguide.chapter06.classlevel;

@Target({ TYPE, ANNOTATION_TYPE })
@Retention(RUNTIME)
@Constraint(validatedBy = { ValidPassengerCountValidator.class })
@Documented
public @interface ValidPassengerCount {

```

```
String message() default "{org.hibernate.validator.referenceguide.chapter06.classlevel." +
    "ValidPassengerCount.message}";

Class<?>[] groups() default { };

Class<? extends Payload>[] payload() default { };
}
```

```
package org.hibernate.validator.referenceguide.chapter06.classlevel;

public class ValidPassengerCountValidator
    implements ConstraintValidator<ValidPassengerCount, Car> {

    @Override
    public void initialize(ValidPassengerCount constraintAnnotation) {
    }

    @Override
    public boolean isValid(Car car, ConstraintValidatorContext context) {
        if ( car == null ) {
            return true;
        }

        return car.getPassengers().size() <= car.getSeatCount();
    }
}
```

As the example demonstrates, you need to use the element type `TYPE` in the `@Target` annotation. This allows the constraint to be put on type definitions. The validator of the constraint in the example receives a `Car` in the `isValid()` method and can access the complete object state to decide whether the given instance is valid or not.

6.2.1. Custom property paths

By default the constraint violation for a class-level constraint is reported on the level of the annotated type, e.g. `Car`.

In some cases it is preferable though that the violation's property path refers to one of the involved properties. For instance you might want to report the `@ValidPassengerCount` constraint against the `passengers` property instead of the `Car` bean.

例 6.9 “Adding a new `ConstraintViolation` with custom property path” shows how this can be done by using the constraint validator context passed to `isValid()` to build a custom constraint violation with a property node for the property `passengers`. Note that you also could add several property nodes, pointing to a sub-entity of the validated bean.

例 6.9. Adding a new `ConstraintViolation` with custom property path

```
package org.hibernate.validator.referenceguide.chapter06.custompath;
```



```

public class ValidPassengerCountValidator
    implements ConstraintValidator<ValidPassengerCount, Car> {

    @Override
    public void initialize(ValidPassengerCount constraintAnnotation) {
    }

    @Override
    public boolean isValid(Car car, ConstraintValidatorContext constraintValidatorContext) {
        if ( car == null ) {
            return true;
        }

        boolean isValid = car.getPassengers().size() <= car.getSeatCount();

        if ( !isValid ) {
            constraintValidatorContext.disableDefaultConstraintViolation();
            constraintValidatorContext
                .buildConstraintViolationWithTemplate( "{my.custom.template}" )
                .addPropertyNode( "passengers" ).addConstraintViolation();
        }

        return isValid;
    }
}

```

6.3. Cross-parameter constraints

Bean Validation distinguishes between two different kinds of constraints.

Generic constraints (which have been discussed so far) apply to the annotated element, e.g. a type, field, method parameter or return value etc. Cross-parameter constraints, in contrast, apply to the array of parameters of a method or constructor and can be used to express validation logic which depends on several parameter values.

In order to define a cross-parameter constraint, its validator class must be annotated with `@SupportedValidationTarget(ValidationTarget.PARAMETERS)`. The type parameter `T` from the `ConstraintValidator` interface must resolve to either `Object` or `Object[]` in order to receive the array of method/constructor arguments in the `isValid()` method.

The following example shows the definition of a cross-parameter constraint which can be used to check that two `Date` parameters of a method are in the correct order:

例 6.10. Cross-parameter constraint

```

package org.hibernate.validator.referenceguide.chapter06.crossparameter;

@Constraint(validatedBy = ConsistentDateParameterValidator.class)
@Target({ METHOD, CONSTRUCTOR, ANNOTATION_TYPE })
@Retention(RUNTIME)
@Documented

```

```

public @interface ConsistentDateParameters {

    String message() default "{org.hibernate.validator.referenceguide.chapter06." +
        "crossparameter.ConsistentDateParameters.message}";

    Class<?>[] groups() default { };

    Class<? extends Payload>[] payload() default { };

}

```

The definition of a cross-parameter constraint isn't any different from defining a generic constraint, i.e. it must specify the members `message()`, `groups()` and `payload()` and be annotated with `@Constraint`. This meta annotation also specifies the corresponding validator, which is shown in [例 6.11 “Generic and cross-parameter constraint”](#). Note that besides the element types `METHOD` and `CONSTRUCTOR` also `ANNOTATION_TYPE` is specified as target of the annotation, in order to enable the creation of composed constraints based on `@ConsistentDateParameters` (see [第 6.4 节 “Constraint composition”](#)).



注意

Cross-parameter constraints are specified directly on the declaration of a method or constructor, which is also the case for return value constraints. In order to improve code readability, it is therefore recommended to chose constraint names – such as `@ConsistentDateParameters` – which make the constraint target apparent.

例 6.11. Generic and cross-parameter constraint

```

package org.hibernate.validator.referenceguide.chapter06.crossparameter;

@SupportedValidationTarget(ValidationTarget.PARAMETERS)
public class ConsistentDateParameterValidator implements
    ConstraintValidator<ConsistentDateParameters, Object[]> {

    @Override
    public void initialize(ConsistentDateParameters constraintAnnotation) {
    }

    @Override
    public boolean isValid(Object[] value, ConstraintValidatorContext context) {
        if ( value.length != 2 ) {
            throw new IllegalArgumentException( "Illegal method signature" );
        }

        //leave null-checking to @NotNull on individual parameters
        if ( value[0] == null || value[1] == null ) {
            return true;
        }

        if ( !( value[0] instanceof Date ) || !( value[1] instanceof Date ) ) {

```

```

        throw new IllegalArgumentException(
            "Illegal method signature, expected two " +
            "parameters of type Date."
        );
    }

    return ( (Date) value[0] ).before( (Date) value[1] );
}
}

```

As discussed above, the validation target `PARAMETERS` must be configured for a cross-parameter validator by using the `@SupportedValidationTarget` annotation. Since a cross-parameter constraint could be applied to any method or constructor, it is considered a best practice to check for the expected number and types of parameters in the validator implementation.

As with generic constraints, null parameters should be considered valid and `@NotNull` on the individual parameters should be used to make sure that parameters are not null.



提示

Similar to class-level constraints, you can create custom constraint violations on single parameters instead of all parameters when validating a cross-parameter constraint. Just obtain a node builder from the `ConstraintValidatorContext` passed to `isValid()` and add a parameter node by calling `addParameterNode()`. In the example you could use this to create a constraint violation on the end date parameter of the validated method.

In rare situations a constraint is both, generic and cross-parameter. This is the case if a constraint has a validator class which is annotated with `@SupportedValidationTarget({ValidationTarget.PARAMETERS, ValidationTarget.ANNOTATED_ELEMENT})` or if it has a generic and a cross-parameter validator class.

When declaring such a constraint on a method which has parameters and also a return value, the intended constraint target can't be determined. Constraints which are generic and cross-parameter at the same time, must therefore define a member `validationAppliesTo()` which allows the constraint user to specify the constraint's target as shown in [例 6.12 “Generic and cross-parameter constraint”](#).

例 6.12. Generic and cross-parameter constraint

```

package org.hibernate.validator.referenceguide.chapter06.crossparameter;

@Constraint(validatedBy = {
    ScriptAssertObjectValidator.class,
    ScriptAssertParametersValidator.class
})

```

```
@Target({ TYPE, FIELD, PARAMETER, METHOD, CONSTRUCTOR, ANNOTATION_TYPE })
@Retention(RUNTIME)
@Documented
public @interface ScriptAssert {

    String message() default "{org.hibernate.validator.referenceguide.chapter06." +
        "crossparameter.ScriptAssert.message}";

    Class<?>[] groups() default { };

    Class<? extends Payload>[] payload() default { };

    String script();

    ConstraintTarget validationAppliesTo() default ConstraintTarget.IMPLICIT;
}
```

The `@ScriptAssert` constraint has two validators (not shown), a generic and a cross-parameter one and thus defines the member `validationAppliesTo()`. The default value `IMPLICIT` allows to derive the target automatically in situations where this is possible (e.g. if the constraint is declared on a field or on a method which has parameters but no return value).

If the target can not be determined implicitly, it must be set by the user to either `PARAMETERS` or `RETURN_VALUE` as shown in [例 6.13 “Specifying the target for a generic and cross-parameter constraint”](#).

例 6.13. Specifying the target for a generic and cross-parameter constraint

```
@ScriptAssert(script = "arg1.size() <= arg0", validationAppliesTo = ConstraintTarget.PARAMETERS)
public Car buildCar(int seatCount, List<Passenger> passengers) {
    //...
}
```

6.4. Constraint composition

Looking at the `licensePlate` field of the `Car` class in [例 6.6 “Applying the `@CheckCase` constraint”](#), you see three constraint annotations already. In complexer scenarios, where even more constraints could be applied to one element, this might become a bit confusing easily. Furthermore, if there was a `licensePlate` field in another class, you would have to copy all constraint declarations to the other class as well, violating the DRY principle.

You can address this kind of problem by creating higher level constraints, composed from several basic constraints. [例 6.14 “Creating a composing constraint `@ValidLicensePlate`”](#) shows a composed constraint annotation which comprises the constraints `@NotNull`, `@Size` and `@CheckCase`:

例 6.14. Creating a composing constraint `@ValidLicensePlate`

```

package org.hibernate.validator.referenceguide.chapter06.constraintcomposition;

@NotNull
@Size(min = 2, max = 14)
@CheckCase(CaseMode.UPPER)
@Target({ METHOD, FIELD, ANNOTATION_TYPE })
@Retention(RUNTIME)
@Constraint(validatedBy = { })
@Documented
public @interface ValidLicensePlate {

    String message() default "{org.hibernate.validator.referenceguide.chapter06." +
        "constraintcomposition.ValidLicensePlate.message}";

    Class<?>[] groups() default { };

    Class<? extends Payload>[] payload() default { };
}

```

To create a composed constraint, simply annotate the constraint declaration with its comprising constraints. If the composed constraint itself requires a validator, this validator is to be specified within the `@Constraint` annotation. For composed constraints which don't need an additional validator such as `@ValidLicensePlate`, just set `validatedBy()` to an empty array.

Using the new composed constraint at the `licensePlate` field is fully equivalent to the previous version, where the three constraints were declared directly at the field itself:

例 6.15. Application of composing constraint `ValidLicensePlate`

```

package org.hibernate.validator.referenceguide.chapter06.constraintcomposition;

public class Car {

    @ValidLicensePlate
    private String licensePlate;

    //...
}

```

The set of `ConstraintViolations` retrieved when validating a `Car` instance will contain an entry for each violated composing constraint of the `@ValidLicensePlate` constraint. If you rather prefer a single `ConstraintViolation` in case any of the composing constraints is violated, the `@ReportAsSingleViolation` meta constraint can be used as follows:

例 6.16. Using `@ReportAsSingleViolation`

```
//...
@ReportAsSingleViolation
public @interface ValidLicensePlate {

    String message() default "{org.hibernate.validator.referenceguide.chapter06." +
        "constraintcomposition.ValidLicensePlate.message}";

    Class<?>[] groups() default { };

    Class<? extends Payload>[] payload() default { };
}
```

Configuring via XML

So far we have used the default configuration source for Bean Validation, namely annotations. However, there also exist two kinds of XML descriptors allowing configuration via XML. The first descriptor describes general Bean Validation behaviour and is provided as META-INF/validation.xml. The second one describes constraint declarations and closely matches the constraint declaration approach via annotations. Let's have a look at these two document types.




注意

The XSD files are available via <http://www.jboss.org/xml/ns/java/validation/configuration> [http://www.jboss.org/xml/ns/java/validation/configuration/] and <http://www.jboss.org/xml/ns/java/validation/mapping>.

7.1. Configuring the validator factory in `validation.xml`

The key to enable XML configuration for Hibernate Validator is the file META-INF/validation.xml. If this file exists on the classpath its configuration will be applied when the ValidatorFactory gets created. 例 7.1 “[validation-configuration-1.1.xsd](#)” shows a model view of the XML schema to which validation.xml has to adhere.

例 7.1. validation-configuration-1.1.xsd



例 7.2 “validation.xml” shows the several configuration options of validation.xml. All settings are optional and the same configuration options are also available programmatically through javax.validation.Configuration. In fact the XML configuration will be overridden by values explicitly specified via the programmatic API. It is even possible to ignore the XML configuration completely via Configuration#ignoreXmlConfiguration(). See also 第 8.2 节 “Configuring a ValidatorFactory” .

例 7.2. validation.xml

```
<validation-config
```



```

xmlns="http://jboss.org/xml/ns/javax/validation/configuration"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
xsi:schemaLocation="http://jboss.org/xml/ns/javax/validation/configuration">

<default-provider>com.acme.ValidationProvider</default-provider>

<message-interpolator>com.acme.MessageInterpolator</message-interpolator>
<traversable-resolver>com.acme.TraversableResolver</traversable-resolver>
<constraint-validator-factory>
    com.acme.ConstraintValidatorFactory
</constraint-validator-factory>
<parameter-name-provider>com.acme.ParameterNameProvider</parameter-name-provider>

<executable-validation enabled="true">
    <default-validated-executable-types>
        <executable-type>CONSTRUCTORS</executable-type>
        <executable-type>NON_GETTER_METHODS</executable-type>
        <executable-type>GETTER_METHODS</executable-type>
    </default-validated-executable-types>
</executable-validation>

<constraint-mapping>META-INF/validation/constraints-car.xml</constraint-mapping>

<property name="hibernate.validator.fail_fast">false</property>
</validation-config>

```



警告

There must only be one file named META-INF/validation.xml on the classpath. If more than one is found an exception is thrown.

The node `default-provider` allows to choose the Bean Validation provider. This is useful if there is more than one provider on the classpath. `message-interpolator`, `traversable-resolver`, `constraint-validator-factory` and `parameter-name-provider` allow to customize the used implementations for the interfaces `MessageInterpolator`, `TraversableResolver`, `ConstraintValidatorFactory` and `ParameterNameProvider` defined in the `javax.validation` package. See the sub-sections of [第 8.2 节 “Configuring a ValidatorFactory”](#) for more information about these interfaces.

`executable-validation` and its subnodes define defaults for method validation. The Bean Validation specification defines constructor and non getter methods as defaults. The `enabled` attribute acts as global switch to turn method validation on and off (see also [第 3 章 Declaring and validating method constraints](#)).


Via the `constraint-mapping` element you can list an arbitrary number of additional XML files containing the actual constraint configuration. Mapping file names must be specified using their fully-qualified name on the classpath. Details on writing mapping files can be found in the next section.

Last but not least, you can specify provider specific properties via the property nodes. In the example we are using the Hibernate Validator specific `hibernate.validator.fail_fast` property (see [第 11.2 节 “Fail fast mode”](#)).

7.2. Mapping constraints via constraint-mappings

Expressing constraints in XML is possible via files adhering to the schema seen in [例 7.3 “validation-mapping-1.1.xsd”](#). Note that these mapping files are only processed if listed via `constraint-mapping` in `validation.xml`.

例 7.3. validation-mapping-1.1.xsd



例 7.4 “Bean constraints configured via XML” shows how the classes `Car` and `RentalCar` from 例 5.3 “Car” resp. 例 5.7 “Class `RentalCar` with redefined default group” could be mapped in XML.

例 7.4. Bean constraints configured via XML

```
<constraint-mappings
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="http://jboss.org/xml/ns/javax/validation/mapping validation-
mapping-1.1.xsd"
  xmlns="http://jboss.org/xml/ns/javax/validation/mapping" version="1.1">

  <default-package>org.hibernate.validator.referenceguide.chapter05</default-package>
  <bean class="Car" ignore-annotations="true">
    <field name="manufacturer">
      <constraint annotation="javax.validation.constraints.NotNull"/>
    </field>
    <field name="licensePlate">
      <constraint annotation="javax.validation.constraints.NotNull"/>
    </field>
    <field name="seatCount">
      <constraint annotation="javax.validation.constraints.Min">
        <element name="value">2</element>
      </constraint>
    </field>
    <field name="driver">
      <valid/>
    </field>
    <getter name="passedVehicleInspection" ignore-annotations="true">
      <constraint annotation="javax.validation.constraints.AssertTrue">
        <message>The car has to pass the vehicle inspection first</message>
        <groups>
          <value>CarChecks</value>
        </groups>
        <element name="max">10</element>
      </constraint>
    </getter>
  </bean>
  <bean class="RentalCar" ignore-annotations="true">
    <class ignore-annotations="true">
      <group-sequence>
        <value>RentalCar</value>
        <value>CarChecks</value>
      </group-sequence>
    </class>
  </bean>
  <constraint-definition annotation="org.mycompany.CheckCase">
    <validated-by include-existing-validators="false">
      <value>org.mycompany.CheckCaseValidator</value>
    </validated-by>
  </constraint-definition>
</constraint-mappings>
```

例 7.5 “Method constraints configured via XML” shows how the constraints from 例 3.1 “Declaring method and constructor parameter constraints”, 例 3.4 “Declaring method and constructor return value constraints” and 例 3.3 “Specifying a constraint's target” can be expressed in XML.

例 7.5. Method constraints configured via XML

```

<constraint-mappings
    xmlns="http://jboss.org/xml/ns/javax/validation/mapping"
    xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
    xsi:schemaLocation=
        "http://jboss.org/xml/ns/javax/validation/mapping validation-
mapping-1.1.xsd" version="1.1">

    <default-package>org.hibernate.validator.referenceguide.chapter07</default-package>

    <bean class="RentalStation" ignore-annotations="true">
        <constructor>
            <return-value>
                <constraint annotation="ValidRentalStation"/>
            </return-value>
        </constructor>

        <constructor>
            <parameter type="java.lang.String">
                <constraint annotation="javax.validation.constraints.NotNull"/>
            </parameter>
        </constructor>

        <method name="getCustomers">
            <return-value>
                <constraint annotation="javax.validation.constraints.NotNull"/>
                <constraint annotation="javax.validation.constraints.Size">
                    <element name="min">1</element>
                </constraint>
            </return-value>
        </method>

        <method name="rentCar">
            <parameter type="Customer">
                <constraint annotation="javax.validation.constraints.NotNull"/>
            </parameter>
            <parameter type="java.util.Date">
                <constraint annotation="javax.validation.constraints.NotNull"/>
                <constraint annotation="javax.validation.constraints.Future"/>
            </parameter>
            <parameter type="int">
                <constraint annotation="javax.validation.constraints.Min">
                    <element name="value">1</element>
                </constraint>
            </parameter>
        </method>
    </bean>

    <bean class="Garage" ignore-annotations="true">
        <method name="buildCar">
            <parameter type="java.util.List"/>
            <cross-parameter>
                <constraint annotation="ELAssert">
                    <element name="expression">...</element>
                    <element name="validationAppliesTo">PARAMETERS</element>
                </constraint>
            </cross-parameter>
        </method>
    </bean>

```

```
        </cross-parameter>
    </method>
    <method name="paintCar">
        <parameter type="int"/>
        <return-value>
            <constraint annotation="ELAssert">
                <element name="expression">...</element>
                <element name="validationAppliesTo">RETURN_VALUE</element>
            </constraint>
        </return-value>
    </method>
</bean>

</constraint-mappings>
```

The XML configuration is closely mirroring the programmatic API. For this reason it should suffice to just add some comments. `default-package` is used for all fields where a class name is expected. If the specified class is not fully qualified the configured default package will be used. Every mapping file can then have several bean nodes, each describing the constraints on the entity with the specified class name.



警告

A given entity can only be configured once across all configuration files. The same applies for constraint definitions for a given constraint annotation. It can only occur in one mapping file. If these rules are violated a `ValidationException` is thrown.

Setting `ignore-annotations` to `true` means that constraint annotations placed on the configured bean are ignored. The default for this value is `true`. `ignore-annotations` is also available for the nodes `class`, `fields`, `getter`, `constructor`, `method`, `parameter`, `cross-parameter` and `return-value`. If not explicitly specified on these levels the configured bean value applies.

The nodes `class`, `field`, `getter`, `constructor` and `method` (and its sub node `parameter`) determine on which level the constraint gets placed. The constraint node is then used to add a constraint on the corresponding level. Each constraint definition must define the class via the `annotation` attribute. The constraint attributes required by the Bean Validation specification (`message`, `groups` and `payload`) have dedicated nodes. All other constraint specific attributes are configured using the `element` node.

The `class` node also allows to reconfigure the default group sequence (see [第 5.3 节 “Redefining the default group sequence”](#)) via the `group-sequence` node. Not shown in the example is the use of `convert-group` to specify group conversions (see [第 5.4 节 “Group conversion”](#)). This node is available on `field`, `getter`, `parameter` and `return-value` and specifies a `from` and `to` attribute to specify the groups.

Last but not least, the list of `ConstraintValidators` associated to a given constraint can be altered via the `constraint-definition` node. The `annotation` attribute represents the constraint annotation being altered. The `validated-by` elements represent the (ordered) list of `ConstraintValidator` implementations associated to the constraint. If `include-existing-validator` is set to `false`, validators defined on the constraint annotation are ignored. If set to `true`, the list of constraint validators described in XML is concatenated to the list of validators specified on the annotation.

Bootstrapping

In [第 2.2.1 节 “Obtaining a Validator instance”](#) you already saw one way for creating a Validator instance - via `Validation#buildDefaultValidatorFactory()`. In this chapter you will learn how to use the other methods in `javax.validation.Validation` in order to bootstrap specifically configured validators.

8.1. Retrieving `ValidatorFactory` and `Validator`

You obtain a `Validator` by retrieving a `ValidatorFactory` via one of the static methods on `javax.validation.Validation` and calling `getValidator()` on the factory instance.

[例 8.1 “Bootstrapping default `ValidatorFactory` and `Validator`”](#) shows how to obtain a validator from the default validator factory:

例 8.1. Bootstrapping default `ValidatorFactory` and `Validator`

```
ValidatorFactory factory = Validation.buildDefaultValidatorFactory();
Validator validator = factory.getValidator();
```



提示

The generated `ValidatorFactory` and `Validator` instances are thread-safe and can be cached. As Hibernate Validator uses the factory as context for caching constraint metadata it is recommended to work with one factory instance within an application.

Bean Validation supports working with several providers such as Hibernate Validator within one application. If more than one provider is present on the classpath, it is not guaranteed which one is chosen when creating a factory via `buildDefaultValidatorFactory()`.

In this case you can explicitly specify the provider to use via `Validation#byProvider()`, passing the provider's `ValidationProvider` class as shown in [例 8.2 “Bootstrapping `ValidatorFactory` and `Validator` using a specific provider”](#).

例 8.2. Bootstrapping `ValidatorFactory` and `Validator` using a specific provider

```
ValidatorFactory validatorFactory = Validation.byProvider( HibernateValidator.class )
    .configure()
    .buildValidatorFactory();
Validator validator = validatorFactory.getValidator();
```

Note that the configuration object returned by `configure()` allows to specifically customize the factory before calling `buildValidatorFactory()`. The available options are discussed later in this chapter.

Similarly you can retrieve the default validator factory for configuration which is demonstrated in [例 8.3 “Retrieving the default ValidatorFactory for configuration”](#).

例 8.3. Retrieving the default ValidatorFactory for configuration

```
ValidatorFactory validatorFactory = Validation.byDefaultProvider()
    .configure()
    .buildValidatorFactory();
Validator validator = validatorFactory.getValidator();
```



注意

If a `ValidatorFactory` instance is no longer in use, it should be disposed by calling `ValidatorFactory#close()`. This will free any resources possibly allocated by the factory.

8.1.1.1. ValidationProviderResolver

By default, available Bean Validation providers are discovered using the [Java Service Provider](#) [<http://docs.oracle.com/javase/6/docs/technotes/guides/jar/jar.html#Service%20Provider>] mechanism.

For that purpose, each provider includes the file `META-INF/services/javax.validation.spi.ValidationProvider`, containing the fully qualified classname of its `ValidationProvider` implementation. In the case of Hibernate Validator this is `org.hibernate.validator.HibernateValidator`.

Depending on your environment and its classloading specifics, provider discovery via the Java's service loader mechanism might not work. In this case you can plug in a custom `ValidationProviderResolver` implementation which performs the provider retrieval. An example is OSGi, where you could implement a provider resolver which uses OSGi services for provider discovery.

To use a custom provider resolver pass it via `providerResolver()` as shown shown in [例 8.4 “Using a custom ValidationProviderResolver”](#).

例 8.4. Using a custom ValidationProviderResolver

```
package org.hibernate.validator.referenceguide.chapter08;

public class OsgiServiceDiscoverer implements ValidationProviderResolver {
```

```

@Override
public List<ValidationProvider<?>> getValidationProviders() {
    //...
}
}

```

```

ValidatorFactory validatorFactory = Validation.byDefaultProvider()
    .providerResolver( new OsgiServiceDiscoverer() )
    .configure()
    .buildValidatorFactory();
Validator validator = validatorFactory.getValidator();

```

8.2. Configuring a ValidatorFactory

By default validator factories retrieved from `Validation` and any validators they create are configured as per the XML descriptor `META-INF/validation.xml` (see [第 7 章 Configuring via XML](#)), if present.

If you want to disable the XML based configuration, you can do so by invoking `Configuration#ignoreXmlConfiguration()`.

The different values of the XML configuration can be accessed via `Configuration#getBootstrapConfiguration()`. This can for instance be helpful if you want to integrate Bean Validation into a managed environment and want to create managed instances of the objects configured via XML.

Using the fluent configuration API, you can override one or more of the settings when bootstrapping the factory. The following sections show how to make use of the different options. Note that the `Configuration` class exposes the default implementations of the different extension points which can be useful if you want to use these as delegates for your custom implementations.

8.2.1. MessageInterpolator

Message interpolators are used by the validation engine to create user readable error messages from constraint message descriptors.

In case the default message interpolation algorithm described in [第 4 章 Interpolating constraint error messages](#) is not sufficient for your needs, you can pass in your own implementation of the `MessageInterpolator` interface via `Configuration#messageInterpolator()` as shown in [例 8.5 “Using a custom MessageInterpolator”](#).

例 8.5. Using a custom MessageInterpolator

```

package org.hibernate.validator.referenceguide.chapter08;

```

```
public class MyMessageInterpolator implements MessageInterpolator {

    @Override
    public String interpolate(String messageTemplate, Context context) {
        //...
    }

    @Override
    public String interpolate(String messageTemplate, Context context, Locale locale) {
        //...
    }
}
```

```
ValidatorFactory validatorFactory = Validation.byDefaultProvider()
    .configure()
    .messageInterpolator( new MyMessageInterpolator() )
    .buildValidatorFactory();
Validator validator = validatorFactory.getValidator();
```

8.2.2. TraversableResolver

In some cases the validation engine should not access the state of a bean property. The most obvious example for that is a lazily loaded property or association of a JPA entity. Validating this lazy property or association would mean that its state would have to be accessed, triggering a load from the database.

Which properties can be accessed and which ones not is controlled by querying the TraversableResolver interface. [例 8.6 “Using a custom TraversableResolver”](#) shows how to use a custom traversable resolver implementation.

例 8.6. Using a custom TraversableResolver

```
package org.hibernate.validator.referenceguide.chapter08;

public class MyTraversableResolver implements TraversableResolver {

    @Override
    public boolean isReachable(
        Object traversableObject,
        Node traversableProperty,
        Class<?> rootBeanType,
        Path pathToTraversableObject,
        ElementType elementType) {
        //...
    }

    @Override
    public boolean isCascadable(
        Object traversableObject,
        Node traversableProperty,
        Class<?> rootBeanType,
```

```

        Path pathToTraversableObject,
        ElementType elementType) {
        //...
    }
}

```

```

ValidatorFactory validatorFactory = Validation.byDefaultProvider()
    .configure()
    .traversableResolver( new MyTraversableResolver() )
    .buildValidatorFactory();
Validator validator = validatorFactory.getValidator();

```

Hibernate Validator provides two TraversableResolvers out of the box which will be enabled automatically depending on your environment. The first is DefaultTraversableResolver which will always return true for `isReachable()` and `isTraversable()`. The second is JPATraversableResolver which gets enabled when Hibernate Validator is used in combination with JPA 2.

8.2.3. ConstraintValidatorFactory

ConstraintValidatorFactory is the extension point for customizing how constraint validators are instantiated and released.

The default ConstraintValidatorFactory provided by Hibernate Validator requires a public no-arg constructor to instantiate ConstraintValidator instances (see [第 6.1.2 节 “The constraint validator”](#)). Using a custom ConstraintValidatorFactory offers for example the possibility to use dependency injection in constraint validator implementations.

To configure a custom constraint validator factory call `Configuration#constraintValidatorFactory()` (see [例 8.7 “Using a custom ConstraintValidatorFactory”](#)).

例 8.7. Using a custom ConstraintValidatorFactory

```

package org.hibernate.validator.referenceguide.chapter08;

public class MyConstraintValidatorFactory implements ConstraintValidatorFactory {

    @Override
    public <T extends ConstraintValidator<?, ?>> T getInstance(Class<T> key) {
        //...
    }

    @Override
    public void releaseInstance(ConstraintValidator<?, ?> instance) {
        //...
    }
}

```

```
ValidatorFactory validatorFactory = Validation.byDefaultProvider()
    .configure()
    .constraintValidatorFactory( new MyConstraintValidatorFactory() )
    .buildValidatorFactory();
Validator validator = validatorFactory.getValidator();
```



警告

Any constraint implementations relying on `ConstraintValidatorFactory` behaviors specific to an implementation (dependency injection, no no-arg constructor and so on) are not considered portable.



注意

`ConstraintValidatorFactory` implementations should not cache validator instances as the state of each instance can be altered in the `initialize()` method.

8.2.4. `ParameterNameProvider`

In case a method or constructor parameter constraint is violated, the `ParameterNameProvider` interface is used to retrieve the parameter's name and make it available to the user via the constraint violation's property path.

The default implementation returns parameter names in the form `arg0`, `arg1` etc., while custom implementations could e.g. be based on parameter annotations, debug symbols or a feature for retrieving parameter names at runtime possibly provided by future Java versions.

Custom `ParameterNameProvider` implementations are used as demonstrated in [例 8.8 “Using a custom `ParameterNameProvider`”](#).

例 8.8. Using a custom `ParameterNameProvider`

```
package org.hibernate.validator.referenceguide.chapter08;

public class MyParameterNameProvider implements ParameterNameProvider {

    @Override
    public List<String> getParameterNames(Constructor<?> constructor) {
        //...
    }

    @Override
    public List<String> getParameterNames(Method method) {
```

```

        //...
    }
}

```

```

ValidatorFactory validatorFactory = Validation.byDefaultProvider()
    .configure()
    .parameterNameProvider( new MyParameterNameProvider() )
    .buildValidatorFactory();
Validator validator = validatorFactory.getValidator();

```

8.2.5. Adding mapping streams

As discussed earlier you can configure the constraints applying for your Java beans using XML based constraint mappings.

Besides the mapping files specified in META-INF/validation.xml you can add further mappings via `Configuration#addMapping()` (see [例 8.9 “Adding constraint mapping streams”](#)). Note that the passed input stream(s) must adhere to the XML schema for constraint mappings presented in [第 7.2 节 “Mapping constraints via constraint-mappings”](#).

例 8.9. Adding constraint mapping streams

```

InputStream constraintMapping1 = ...;
InputStream constraintMapping2 = ...;
ValidatorFactory validatorFactory = Validation.byDefaultProvider()
    .configure()
    .addMapping( constraintMapping1 )
    .addMapping( constraintMapping2 )
    .buildValidatorFactory();
Validator validator = validatorFactory.getValidator();

```

You should close any passed input stream after the validator factory has been created.

8.2.6. Provider-specific settings

Via the configuration object returned by `Validation#byProvider()` provider specific options can be configured.

In case of Hibernate Validator this allows you to enable the fail fast mode and pass one or more programmatic constraint mappings as demonstrated in [例 8.10 “Setting Hibernate Validator specific options”](#).

例 8.10. Setting Hibernate Validator specific options

```

ValidatorFactory validatorFactory = Validation.byProvider( HibernateValidator.class )
    .configure()

```

```
.failFast( true )
.addMapping( (ConstraintMapping) null )
.buildValidatorFactory();
Validator validator = validatorFactory.getValidator();
```

Alternatively, provider-specific options can be passed via `Configuration#addProperty()`. Hibernate Validator supports enabling the fail fast mode that way, too:

例 8.11. Enabling a Hibernate Validator specific option via `addProperty()`

```
ValidatorFactory validatorFactory = Validation.byProvider( HibernateValidator.class )
    .configure()
    .addProperty( "hibernate.validator.fail_fast", "true" )
    .buildValidatorFactory();
Validator validator = validatorFactory.getValidator();
```

Refer to [第 11.2 节 “Fail fast mode”](#) and [第 11.3 节 “Programmatic constraint declaration”](#) to learn more about the fail fast mode and the constraint declaration API.

8.3. Configuring a Validator

When working with a configured validator factory it can occasionally be required to apply a different configuration to a single Validator instance. [例 8.12 “Configuring a Validator via usingContext\(\)”](#) shows how this can be achieved by calling `ValidatorFactory#usingContext()`.

例 8.12. Configuring a Validator via `usingContext()`

```
ValidatorFactory validatorFactory = Validation.buildDefaultValidatorFactory();

Validator validator = validatorFactory.usingContext()
    .messageInterpolator( new MyMessageInterpolator() )
    .traversableResolver( new MyTraversableResolver() )
    .getValidator();
```


Using constraint metadata

The Bean Validation specification provides not only a validation engine, but also an API for retrieving constraint metadata in a uniform way, no matter whether the constraints are declared using annotations or via XML mappings. Read this chapter to learn more about this API and its possibilities. You can find all the metadata API types in the package `javax.validation.metadata`.

The examples presented in this chapter are based on the classes and constraint declarations shown in [例 9.1 “Example classes”](#).

例 9.1. Example classes

```
package org.hibernate.validator.referenceguide.chapter07;

public class Person {

    public interface Basic {
    }

    @NotNull
    private String name;

    //getters and setters ...
}
```

```
public interface Vehicle {

    public interface Basic {
    }

    @NotNull(groups = Vehicle.Basic.class)
    String getManufacturer();
}
```

```
@ValidCar
public class Car implements Vehicle {

    public interface SeverityInfo extends Payload {
    }

    private String manufacturer;

    @NotNull
    @Size(min = 2, max = 14)
    private String licensePlate;

    private Person driver;
```

```
private String modelName;

public Car() {
}

public Car(
    @NotNull String manufacturer,
    String licencePlate,
    Person driver,
    String modelName) {

    this.manufacturer = manufacturer;
    this.licensePlate = licencePlate;
    this.driver = driver;
    this.modelName = modelName;
}

public void driveAway(@Max(75) int speed) {
    //...
}

@LuggageCountMatchesPassengerCount(
    piecesOfLuggagePerPassenger = 2,
    validationAppliesTo = ConstraintTarget.PARAMETERS,
    payload = SeverityInfo.class,
    message = "There must not be more than {piecesOfLuggagePerPassenger}
pieces of " +
                                "luggage per passenger."
)
public void load(List<Person> passengers, List<PieceOfLuggage> luggage) {
    //...
}

@Override
@Size(min = 3)
public String getManufacturer() {
    return manufacturer;
}

public void setManufacturer(String manufacturer) {
    this.manufacturer = manufacturer;
}

@Valid
@ConvertGroup(from = Default.class, to = Person.Basic.class)
public Person getDriver() {
    return driver;
}

//further getters and setters...
}
```

9.1. BeanDescriptor

The entry point into the metadata API is the method `Validator#getConstraintsForClass()`, which returns an instance of

the `BeanDescriptor` [<http://docs.jboss.org/hibernate/beanvalidation/spec/1.1/api/index.html?javax/validation/metadata/BeanDescriptor.html>] interface. Using this descriptor, you can obtain metadata for constraints declared directly on the bean itself (class- or property-level), but also retrieve metadata descriptors representing single properties, methods and constructors.

例 9.2 “Using `BeanDescriptor`” demonstrates how to retrieve a `BeanDescriptor` for the `Car` class and how to use this descriptor in form of assertions.



提示

If a constraint declaration hosted by the requested class is invalid, a `ValidationException` is thrown.

例 9.2. Using `BeanDescriptor`

```
Validator validator = Validation.buildDefaultValidatorFactory().getValidator();

BeanDescriptor carDescriptor = validator.getConstraintsForClass( Car.class );

assertTrue( carDescriptor.isBeanConstrained() );

//one class-level constraint
assertEquals( 1, carDescriptor.getConstraintDescriptors().size() );

//manufacturer, licensePlate, driver
assertEquals( 3, carDescriptor.getConstrainedProperties().size() );

//property has constraint
assertNotNull( carDescriptor.getConstraintsForProperty( "licensePlate" ) );

//property is marked with @Valid
assertNotNull( carDescriptor.getConstraintsForProperty( "driver" ) );

//constraints from getter method in interface and implementation class are returned
assertEquals(
    2,
    carDescriptor.getConstraintsForProperty( "manufacturer" )
                  .getConstraintDescriptors()
                  .size()
);

//property is not constrained
assertNull( carDescriptor.getConstraintsForProperty( "modelName" ) );

//driveAway(int), load(List<Person>, List<PieceOfLuggage>)
assertEquals( 2, carDescriptor.getConstrainedMethods( MethodType.NON_GETTER ).size() );

//driveAway(int), getManufacturer(), getDriver(), load(List<Person>, List<PieceOfLuggage>)
assertEquals(
    4,
    carDescriptor.getConstrainedMethods( MethodType.NON_GETTER, MethodType.GETTER )
```

```
        .size()
    );

    //driveAway(int)
    assertNotNull( carDescriptor.getConstraintsForMethod( "driveAway", int.class ) );

    //getManufacturer()
    assertNotNull( carDescriptor.getConstraintsForMethod( "getManufacturer" ) );

    //setManufacturer() is not constrained
    assertNull( carDescriptor.getConstraintsForMethod( "setManufacturer", String.class ) );

    //Car(String, String, Person, String)
    assertEquals( 1, carDescriptor.getConstrainedConstructors().size() );

    //Car(String, String, Person, String)
    assertNotNull(
        carDescriptor.getConstraintsForConstructor(
            String.class,
            String.class,
            Person.class,
            String.class
        )
    );
};
```

You can determine whether the specified class hosts any class- or property-level constraints via `isBeanConstrained()`. Method or constructor constraints are not considered by `isBeanConstrained()`.

The method `getConstraintDescriptors()` is common to all descriptors derived from `ElementDescriptor` (see [第 9.4 节 “ElementDescriptor”](#)) and returns a set of descriptors representing the constraints directly declared on the given element. In case of `BeanDescriptor`, the bean's class-level constraints are returned. More details on `ConstraintDescriptor` can be found in [第 9.6 节 “ConstraintDescriptor”](#).

Via `getConstraintsForProperty()`, `getConstraintsForMethod()` and `getConstraintsForConstructor()` you can obtain a descriptor representing one given property or executable element, identified by its name and, in case of methods and constructors, parameter types. The different descriptor types returned by these methods are described in the following sections.

Note that these methods consider constraints declared at super-types according to the rules for constraint inheritance as described in [第 2.1.4 节 “Constraint inheritance”](#). An example is the descriptor for the manufacturer property, which provides access to all constraints defined on `Vehicle#getManufacturer()` and the implementing method `Car#getManufacturer()`. `null` is returned in case the specified element does not exist or is not constrained.

The methods `getConstrainedProperties()`, `getConstrainedMethods()` and `getConstrainedConstructors()` return (potentially empty) sets with all constrained properties, methods and constructors, respectively. An element is considered

constrained, if it has at least one constraint or is marked for cascaded validation. When invoking `getConstrainedMethods()`, you can specify the type of the methods to be returned (getters, non-getters or both).

9.2. PropertyDescriptor

The interface `PropertyDescriptor` [<http://docs.jboss.org/hibernate/beanvalidation/spec/1.1/api/index.html?javax/validation/metadata/PropertyDescriptor.html>] represents one given property of a class. It is transparent whether constraints are declared on a field or a property getter, provided the JavaBeans naming conventions are respected. 例 9.3 “Using PropertyDescriptor” shows how to use the `PropertyDescriptor` interface.

例 9.3. Using PropertyDescriptor

```
PropertyDescriptor licensePlateDescriptor = carDescriptor.getConstraintsForProperty(
    "licensePlate"
);

// "licensePlate" has two constraints, is not marked with @Valid and defines no group conversions
assertEquals( "licensePlate", licensePlateDescriptor.getPropertyName() );
assertEquals( 2, licensePlateDescriptor.getConstraintDescriptors().size() );
assertTrue( licensePlateDescriptor.hasConstraints() );
assertFalse( licensePlateDescriptor.isCascaded() );
assertTrue( licensePlateDescriptor.getGroupConversions().isEmpty() );

PropertyDescriptor driverDescriptor = carDescriptor.getConstraintsForProperty( "driver" );

// "driver" has no constraints, is marked with @Valid and defines one group conversion
assertEquals( "driver", driverDescriptor.getPropertyName() );
assertTrue( driverDescriptor.getConstraintDescriptors().isEmpty() );
assertFalse( driverDescriptor.hasConstraints() );
assertTrue( driverDescriptor.isCascaded() );
assertEquals( 1, driverDescriptor.getGroupConversions().size() );
```

Using `getConstrainedDescriptors()`, you can retrieve a set of `ConstraintDescriptors` providing more information on the individual constraints of a given property. The method `isCascaded()` returns true, if the property is marked for cascaded validation (either using the `@Valid` annotation or via XML), false otherwise. Any configured group conversions are returned by `getGroupConversions()`. See 第 9.5 节 “GroupConversionDescriptor” for more details on `GroupConversionDescriptor`.

9.3. MethodDescriptor and ConstructorDescriptor

Constrained methods and constructors are represented by the interfaces `MethodDescriptor` [<http://docs.jboss.org/hibernate/beanvalidation/spec/1.1/api/index.html?javax/validation/metadata/MethodDescriptor.html>] and `ConstructorDescriptor` [<http://docs.jboss.org/hibernate/beanvalidation/spec/1.1/api/index.html?javax/validation/metadata/ConstructorDescriptor.html>], respectively. 例 9.4

“Using MethodDescriptor and ConstructorDescriptor” demonstrates how to work with these descriptors.

例 9.4. Using MethodDescriptor and ConstructorDescriptor

```
//driveAway(int) has a constrained parameter and an unconstrained return value
MethodDescriptor driveAwayDescriptor = carDescriptor.getConstraintsForMethod(
    "driveAway",
    int.class
);
assertEquals( "driveAway", driveAwayDescriptor.getName() );
assertTrue( driveAwayDescriptor.hasConstrainedParameters() );
assertFalse( driveAwayDescriptor.hasConstrainedReturnValue() );

//always returns an empty set; constraints are retrievable by navigating to
//one of the sub-descriptors, e.g. for the return value
assertTrue( driveAwayDescriptor.getConstraintDescriptors().isEmpty() );

ParameterDescriptor speedDescriptor = driveAwayDescriptor.getParameterDescriptors()
    .get( 0 );

//The "speed" parameter is located at index 0, has one constraint and is not cascaded
//nor does it define group conversions
assertEquals( "arg0", speedDescriptor.getName() );
assertEquals( 0, speedDescriptor.getIndex() );
assertEquals( 1, speedDescriptor.getConstraintDescriptors().size() );
assertFalse( speedDescriptor.isCascaded() );
assert speedDescriptor.getGroupConversions().isEmpty();

//getDriver() has no constrained parameters but its return value is marked for cascaded
//validation and declares one group conversion
MethodDescriptor getDriverDescriptor = carDescriptor.getConstraintsForMethod(
    "getDriver"
);
assertFalse( getDriverDescriptor.hasConstrainedParameters() );
assertTrue( getDriverDescriptor.hasConstrainedReturnValue() );

ReturnValueDescriptor returnValueDescriptor = getDriverDescriptor.getReturnValueDescriptor();
assertTrue( returnValueDescriptor.getConstraintDescriptors().isEmpty() );
assertTrue( returnValueDescriptor.isCascaded() );
assertEquals( 1, returnValueDescriptor.getGroupConversions().size() );

//load(List<Person>, List<PieceOfLuggage>) has one cross-parameter constraint
MethodDescriptor loadDescriptor = carDescriptor.getConstraintsForMethod(
    "load",
    List.class,
    List.class
);
assertTrue( loadDescriptor.hasConstrainedParameters() );
assertFalse( loadDescriptor.hasConstrainedReturnValue() );
assertEquals(
    1,
    loadDescriptor.getCrossParameterDescriptor().getConstraintDescriptors().size()
);

//Car(String, String, Person, String) has one constrained parameter
ConstructorDescriptor constructorDescriptor = carDescriptor.getConstraintsForConstructor(
```

```

        String.class,
        String.class,
        Person.class,
        String.class
    );

    assertEquals( "Car", constructorDescriptor.getName() );
    assertFalse( constructorDescriptor.hasConstrainedReturnValue() );
    assertTrue( constructorDescriptor.hasConstrainedParameters() );
    assertEquals(
        1,
        constructorDescriptor.getParameterDescriptors()
            .get( 0 )
            .getConstraintDescriptors()
            .size()
    );

```

`getName()` returns the name of the given method or constructor. The methods `hasConstrainedParameters()` and `hasConstrainedReturnValue()` can be used to perform a quick check whether an executable element has any parameter constraints (either constraints on single parameters or cross-parameter constraints) or return value constraints.

Note that any constraints are not directly exposed on `MethodDescriptor` and `ConstructorDescriptor`, but rather on dedicated descriptors representing an executable's parameters, its return value and its cross-parameter constraints. To get hold of one of these descriptors, invoke `getParameterDescriptors()`, `getReturnValueDescriptor()` or `getCrossParameterDescriptor()`, respectively.

These descriptors provide access to the element's constraints (`getConstraintDescriptors()`) and, in case of parameters and return value, to its configuration for cascaded validation (`isValid()` and `getGroupConversions()`). For parameters, you also can retrieve the index and the name, as returned by the currently used parameter name provider (see [第 8.2.4 节 “ParameterNameProvider”](#)) via `getName()` and `getIndex()`.



提示

Getter methods following the JavaBeans naming conventions are considered as bean properties but also as constrained methods.

That means you can retrieve the related metadata either by obtaining a `PropertyDescriptor` (e.g. `BeanDescriptor.getConstraintsForProperty("foo")`) or by examining the return value descriptor of the getter's `MethodDescriptor` (e.g. `BeanDescriptor.getConstraintsForMethod("getFoo").getReturnValueDescriptor()`).

9.4. ElementDescriptor

The [ElementDiscriptor](#) [<http://docs.jboss.org/hibernate/beanvalidation/spec/1.1/api/index.html?javax/validation/metadata/ElementDescriptor.html>] interface is the common

base class for the individual descriptor types such as `BeanDescriptor`, `PropertyDescriptor` etc. Besides `getConstraintDescriptors()` it provides some more methods common to all descriptors.

`hasConstraints()` allows for a quick check whether an element has any direct constraints (e.g. class-level constraints in case of `BeanDescriptor`). `getElementClass()` returns the Java type of the element represented by a given descriptor. More specifically, the method returns

- the object type when invoked on `BeanDescriptor`,
- the type of a property or parameter when invoked on `PropertyDescriptor` or `ParameterDescriptor` respectively,
- `Object[].class` when invoked on `CrossParameterDescriptor`,
- the return type when invoked on `ConstructorDescriptor`, `MethodDescriptor` or `ReturnValueDescriptor`. `void.class` will be returned for methods which don't have a return value.

例 9.5 “Using `ElementDescriptor` methods” shows how these methods are used.

例 9.5. Using `ElementDescriptor` methods

```
PropertyDescriptor manufacturerDescriptor = carDescriptor.getConstraintsForProperty(
    "manufacturer"
);

assertTrue( manufacturerDescriptor.hasConstraints() );
assertEquals( String.class, manufacturerDescriptor.getElementClass() );

CrossParameterDescriptor loadCrossParameterDescriptor = carDescriptor.getConstraintsForMethod(
    "load",
    List.class,
    List.class
).getCrossParameterDescriptor();

assertTrue( loadCrossParameterDescriptor.hasConstraints() );
assertEquals( Object[].class, loadCrossParameterDescriptor.getElementClass() );
```

Finally, `ElementDescriptor` offers access to the `ConstraintFinder` API which allows you to query for constraint metadata in a fine grained way. 例 9.6 “Usage of `ConstraintFinder`” shows how to retrieve a `ConstraintFinder` instance via `findConstraints()` and use the API to query for constraint metadata.

例 9.6. Usage of `ConstraintFinder`

```
PropertyDescriptor manufacturerDescriptor = carDescriptor.getConstraintsForProperty(
```



```

        "manufacturer"
    );

    // "manufacturer" constraints are declared on the getter, not the field
    assertTrue(
        manufacturerDescriptor.findConstraints()
            .declaredOn( ElementType.FIELD )
            .getConstraintDescriptors()
            .isEmpty()
    );

    // @NotNull on Vehicle#getManufacturer() is part of another group
    assertEquals(
        1,
        manufacturerDescriptor.findConstraints()
            .unorderedAndMatchingGroups( Default.class )
            .getConstraintDescriptors()
            .size()
    );

    // @Size on Car#getManufacturer()
    assertEquals(
        1,
        manufacturerDescriptor.findConstraints()
            .lookingAt( Scope.LOCAL_ELEMENT )
            .getConstraintDescriptors()
            .size()
    );

    // @Size on Car#getManufacturer() and @NotNull on Vehicle#getManufacturer()
    assertEquals(
        2,
        manufacturerDescriptor.findConstraints()
            .lookingAt( Scope.HIERARCHY )
            .getConstraintDescriptors()
            .size()
    );

    // Combining several filter options
    assertEquals(
        1,
        manufacturerDescriptor.findConstraints()
            .declaredOn( ElementType.METHOD )
            .lookingAt( Scope.HIERARCHY )
            .unorderedAndMatchingGroups( Vehicle.Basic.class )
            .getConstraintDescriptors()
            .size()
    );

```

Via `declaredOn()` you can search for `ConstraintDescriptors` declared on certain element types. This is useful to find property constraints declared on either fields or getter methods.

`unorderedAndMatchingGroups()` restricts the resulting constraints to those matching the given validation group(s).

lookingAt() allows to distinguish between constraints directly specified on the element (Scope.LOCAL_ELEMENT) or constraints belonging to the element but hosted anywhere in the class hierarchy (Scope.HIERARCHY).

You can also combine the different options as shown in the last example.



警告

Order is not respected by `unorderedAndMatchingGroups()`, but group inheritance and inheritance via sequence are.

9.5. GroupConversionDescriptor

All those descriptor types that represent elements which can be subject of cascaded validation (i.e., `PropertyDescriptor`, `ParameterDescriptor` and `ReturnValueDescriptor`) provide access to the element's group conversions via `getGroupConversions()`. The returned set contains a [GroupConversionDescriptor](http://docs.jboss.org/hibernate/beanvalidation/spec/1.1/api/index.html?javax/validation/metadata/GroupConversionDescriptor.html) [http://docs.jboss.org/hibernate/beanvalidation/spec/1.1/api/index.html?javax/validation/metadata/GroupConversionDescriptor.html] for each configured conversion, allowing to retrieve source and target groups of the conversion. 例 9.7 “Using GroupConversionDescriptor” shows an example.

例 9.7. Using GroupConversionDescriptor

```
PropertyDescriptor driverDescriptor = carDescriptor.getConstraintsForProperty( "driver" );

Set<GroupConversionDescriptor> groupConversions = driverDescriptor.getGroupConversions();
assertEquals( 1, groupConversions.size() );

GroupConversionDescriptor groupConversionDescriptor = groupConversions.iterator()
    .next();
assertEquals( Default.class, groupConversionDescriptor.getFrom() );
assertEquals( Person.Basic.class, groupConversionDescriptor.getTo() );
```

9.6. ConstraintDescriptor

Last but not least, the [ConstraintDescriptor](http://docs.jboss.org/hibernate/beanvalidation/spec/1.1/api/index.html?javax/validation/metadata/ConstraintDescriptor.html) [http://docs.jboss.org/hibernate/beanvalidation/spec/1.1/api/index.html?javax/validation/metadata/ConstraintDescriptor.html] interface describes a single constraint together with its composing constraints. Via an instance of this interface you get access to the constraint annotation and its parameters.

例 9.8 “Using ConstraintDescriptor” shows how to retrieve default constraint attributes (such as message template, groups etc.) as well as custom constraint attributes (piecesOfLuggagePerPassenger) and other metadata such as the constraint's annotation type and its validators from a `ConstraintDescriptor`.

例 9.8. Using ConstraintDescriptor

```

//descriptor for the @LuggageCountMatchesPassengerCount constraint on the
//load(List<Person>, List<PieceOfLuggage>) method
ConstraintDescriptor<?> constraintDescriptor = carDescriptor.getConstraintsForMethod(
    "load",
    List.class,
    List.class
).getCrossParameterDescriptor().getConstraintDescriptors().iterator().next();

//constraint type
assertEquals(
    LuggageCountMatchesPassengerCount.class,
    constraintDescriptor.getAnnotation().annotationType()
);

//standard constraint attributes
assertEquals( SeverityInfo.class, constraintDescriptor.getPayload().iterator().next() );
assertEquals(
    ConstraintTarget.PARAMETERS,
    constraintDescriptor.getValidationAppliesTo()
);
assertEquals( Default.class, constraintDescriptor.getGroups().iterator().next() );
assertEquals(
    "There must not be more than {piecesOfLuggagePerPassenger} pieces of luggage per " +
    "passenger.",
    constraintDescriptor.getMessageTemplate()
);

//custom constraint attribute
assertEquals(
    2,
    constraintDescriptor.getAttributes().get( "piecesOfLuggagePerPassenger" )
);

//no composing constraints
assertTrue( constraintDescriptor.getComposingConstraints().isEmpty() );

//validator class
assertEquals(
    Arrays.<Class<?>>asList( LuggageCountMatchesPassengerCount.Validator.class ),
    constraintDescriptor.getConstraintValidatorClasses()
);

```


Integrating with other frameworks

Hibernate Validator is intended to be used to implement multi-layered data validation, where constraints are expressed in a single place (the annotated domain model) and checked in various different layers of the application. For this reason there are multiple integration points with other technologies.

10.1. ORM集成

Hibernate Validator不仅能够和Hibernate集成工作，还能够和任何JPA的实现很好的一起工作。



提示

When lazy loaded associations are supposed to be validated it is recommended to place the constraint on the getter of the association. Hibernate replaces lazy loaded associations with proxy instances which get initialized/loaded when requested via the getter. If, in such a case, the constraint is placed on field level the actual proxy instance is used which will lead to validation errors.

10.1.1. 与数据库集成校验

Out of the box, Hibernate (as of version 3.5.x) will translate the constraints you have defined for your entities into mapping metadata. For example, if a property of your entity is annotated `@NotNull`, its columns will be declared as not null in the DDL schema generated by Hibernate.

If, for some reason, the feature needs to be disabled, set `hibernate.validator.apply_to_ddl` to false. See also 表 2.2 “Bean Validation constraints” and 表 2.3 “Custom constraints”.

你也可以限制这个DDL约束自动生成的特性只应用到一部分实体类。只需要设置 `org.hibernate.validator.group.ddl` 属性，这个属性的值是你想要应用此特性的实体类的全路径名称，每个以逗号分隔。

10.1.2. 基于Hibernate事件模型的校验

Hibernate Annotations (即 Hibernate 3.5.x) 中包含了一个的 Hibernate 事件监听器(译注: 请阅读Hibernate Core文档了解Hibernate的事件模型) - `org.hibernate.cfg.beanvalidation.BeanValidationEventListener` [<http://fisheye.jboss.org/browse/Hibernate/core/trunk/annotations/src/main/java/org/hibernate/cfg/beanvalidation/BeanValidationEventListener.java>] - 来为Hibernate Validator服务。 当一个 `PreInsertEvent`, `PreUpdateEvent` 或 `PreDeleteEvent` 事件发生的时候, 这

个监听器就可以对该事件所涉及到的实体对象进行校验，如果校验不通过的话，则抛出异常。默认情况下，Hibernate在对每个对象进行保存或者修改操作的时候，都会对其进行校验，而删除操作则不会。你可以通过`javax.persistence.validation.group.pre-persist`，`javax.persistence.validation.group.pre-update`和`javax.persistence.validation.group.pre-remove`属性来定义对应事件发生的时候，具体要校验哪(些)个校验组，这个属性的值是要应用的校验组类的全路径，使用逗号分隔。例 10.1 “自定义BeanValidationEventListener”显示了这几个属性在Hibernate内部定义的默认值，所以，你不需要在你的应用中再重复定义了。

如果发生了违反约束条件的情况，该监听器会抛出一个运行时的`ConstraintViolationException`异常，此异常包含了一系列的`ConstraintViolation`对象用于描述每个违反了约束条件的情况。

如果类路径上有Hibernate Validator，则Hibernate Annotations（或 Hibernate EntityManager）会自动调用它，如果你想避免这种情况，可以设置`javax.persistence.validation.mode`属性为none。



注意

如果实体模型上没有定义约束条件，则不会有任何性能损耗。

如果你想在Hibernate Core中使用上面提到的事件监听器，则可以在`hibernate.cfg.xml`中定义如下配置信息：

例 10.1. 自定义BeanValidationEventListener

```
<hibernate-configuration>
  <session-factory>
    ...
    <property name="javax.persistence.validation.group.pre-persist">
      javax.validation.groups.Default
    </property>
    <property name="javax.persistence.validation.group.pre-update">
      javax.validation.groups.Default
    </property>
    <property name="javax.persistence.validation.group.pre-remove"></property>
    ...
    <event type="pre-update">
      <listener class="org.hibernate.cfg.beanvalidation.BeanValidationEventListener"/>
    </event>
    <event type="pre-insert">
      <listener class="org.hibernate.cfg.beanvalidation.BeanValidationEventListener"/>
    </event>
    <event type="pre-delete">
      <listener class="org.hibernate.cfg.beanvalidation.BeanValidationEventListener"/>
    </event>
  </session-factory>
</hibernate-configuration>
```

10.1.3. JPA

If you are using JPA 2 and Hibernate Validator is in the classpath the JPA2 specification requires that Bean Validation gets enabled. The properties `javax.persistence.validation.group.pre-persist`, `javax.persistence.validation.group.pre-update` and `javax.persistence.validation.group.pre-remove` as described in 第 10.1.2 节 “基于Hibernate事件模型的校验” can in this case be configured in `persistence.xml`. `persistence.xml` also defines a node `validation-mode` which can be set to `AUTO`, `CALLBACK`, `NONE`. The default is `AUTO`.

对于JPA1来讲，你需要自己创建和注册Hibernate Validator。如果你是使用Hibernate EntityManager，那么你可以把第 10.1.2 节 “基于Hibernate事件模型的校验” 中列出来的`BeanValidationEventListener`类添加到你的项目中，然后再手工注册它。

10.2. JSF & Seam

When working with JSF2 or JBoss Seam™ and Hibernate Validator (Bean Validation) is present in the runtime environment, validation is triggered for every field in the application. 例 10.2 “在JSF2中使用Bean Validation” shows an example of the `f:validateBean` tag in a JSF page. The `validationGroups` attribute is optional and can be used to specify a comma separated list of validation groups. The default is `javax.validation.groups.Default`. For more information refer to the Seam documentation or the JSF 2 specification.

例 10.2. 在JSF2中使用Bean Validation

```
<h:form>
  <f:validateBean validationGroups="javax.validation.groups.Default">
    <h:inputText value=#{model.property}# />
    <h:selectOneRadio value=#{model.radioProperty}# > ... </h:selectOneRadio>
    <!-- other input components here -->
  </f:validateBean>
</h:form>
```



提示

The integration between JSF 2 and Bean Validation is described in the "Bean Validation Integration" chapter of JSR-314 [<http://jcp.org/en/jsr/detail?id=314>]. It is interesting to know that JSF 2 implements a custom `MessageInterpolator` to ensure ensure proper localization. To encourage the use of the Bean Validation message facility, JSF 2 will per default only display the generated Bean Validation message. This can, however, be configured via the application resource bundle by providing the following

```
configuration ({0} is replaced with the Bean Validation message and {1}
is replaced with the JSF component label):
```

```
javax.faces.validator.BeanValidator.MESSAGE={1}< {0}
```

The default is:

```
javax.faces.validator.BeanValidator.MESSAGE={0}
```

10.3. CDI

As of version 1.1, Bean Validation is integrated with CDI (Contexts and Dependency Injection for Java™ EE).

This integration provides CDI managed beans for Validator and ValidatorFactory and enables dependency injection in constraint validators as well as custom message interpolators, traversable resolvers, constraint validator factories and parameter name providers.

Furthermore, parameter and return value constraints on the methods and constructors of CDI managed beans will automatically be validated upon invocation.

When your application runs on a Java EE container, this integration is enabled by default. When working with CDI in a Servlet container or in a pure Java SE environment, you can use the CDI portable extension provided by Hibernate Validator. To do so, add the portable extension to your class path as described in [第 1.1.2 节 “CDI”](#).

10.3.1. Dependency injection

CDI's dependency injection mechanism makes it very easy to retrieve ValidatorFactory and Validator instances and use them in your managed beans. Just annotate instance fields of your bean with `@javax.inject.Inject` as shown in [例 10.3 “Retrieving validator factory and validator via @Inject”](#).

例 10.3. Retrieving validator factory and validator via @Inject

```
package org.hibernate.validator.referenceguide.chapter10.cdi.validator;

@ApplicationScoped
public class RentalStation {

    @Inject
    private ValidatorFactory validatorFactory;

    @Inject
    private Validator validator;
```



```
//...
}
```

The injected beans are the default validator factory and validator instances. In order to configure them - e.g. to use a custom message interpolator - you can use the Bean Validation XML descriptors as discussed in [第 7 章 Configuring via XML](#).

If you are working with several Bean Validation providers you can make sure that factory and validator from Hibernate Validator are injected by annotating the injection points with the `@HibernateValidator` qualifier which is demonstrated in [例 10.4 “Using the @HibernateValidator qualifier annotation”](#).

例 10.4. Using the `@HibernateValidator` qualifier annotation

```
package org.hibernate.validator.referenceguide.chapter10.cdi.validator.qualifier;

import javax.annotation.processing.Generated;
import javax.enterprise.context.ApplicationScoped;
import javax.inject.Inject;
import javax.validation.ValidatorFactory;
import javax.validation.Validator;
import org.hibernate.validator.HibernateValidator;

@ApplicationScoped
public class RentalStation {

    @Inject
    @HibernateValidator
    private ValidatorFactory validatorFactory;

    @Inject
    @HibernateValidator
    private Validator validator;

    //...
}
```



提示

The fully-qualified name of the qualifier annotation is `org.hibernate.validator.cdi.HibernateValidator`. Be sure to not import `org.hibernate.validator.HibernateValidator` instead which is the `ValidationProvider` implementation used for selecting Hibernate Validator when working with the bootstrapping API (see [第 8.1 节 “Retrieving ValidatorFactory and Validator”](#)).

Via `@Inject` you also can inject dependencies into constraint validators and other Bean Validation objects such as `MessageInterpolator` implementations etc.

[例 10.5 “Constraint validator with injected bean”](#) demonstrates how an injected CDI bean is used in a `ConstraintValidator` implementation to determine whether the given constraint is valid or not. As the example shows, you also can work with the `@PostConstruct` and `@PreDestroy` callbacks to implement any required construction and destruction logic.

例 10.5. Constraint validator with injected bean

```
package org.hibernate.validator.referenceguide.chapter10.cdi.injection;

public class ValidLicensePlateValidator
    implements ConstraintValidator<ValidLicensePlate, String> {

    @Inject
    private VehicleRegistry vehicleRegistry;

    @PostConstruct
    public void postConstruct() {
        //do initialization logic...
    }

    @PreDestroy
    public void preDestroy() {
        //do destruction logic...
    }

    @Override
    public void initialize(ValidLicensePlate constraintAnnotation) {
    }

    @Override
    public boolean isValid(String licensePlate, ConstraintValidatorContext constraintContext) {
        return vehicleRegistry.isValidLicensePlate( licensePlate );
    }
}
```

10.3.2. Method validation

The method interception facilities of CDI allow for a very tight integration with Bean Validation's method validation functionality. Just put constraint annotations to the parameters and return values of the executables of your CDI beans and they will be validated automatically before (parameter constraints) and after (return value constraints) a method or constructor is invoked.

Note that no explicit interceptor binding is required, instead the required method validation interceptor will automatically be registered for all managed beans with constrained methods and constructors.

You can see an example in [例 10.6 “CDI managed beans with method-level constraints”](#).

例 10.6. CDI managed beans with method-level constraints

```
package org.hibernate.validator.referenceguide.chapter10.cdi.methodvalidation;

@ApplicationScoped
public class RentalStation {

    @Valid
```

```

    public RentalStation() {
        //...
    }

    @NotNull
    @Valid
    public Car rentCar(
        @NotNull Customer customer,
        @NotNull @Future Date startDate,
        @Min(1) int durationInDays) {
        //...
    }

    @NotNull
    List<Car> getAvailableCars() {
        //...
    }
}

```

```

package org.hibernate.validator.referenceguide.chapter10.cdi.methodvalidation;

@RequestScoped
public class RentCarRequest {

    @Inject
    private RentalStation rentalStation;

    public void rentCar(String customerId, Date startDate, int duration) {
        //causes ConstraintViolationException
        rentalStation.rentCar( null, null, -1 );
    }
}

```

Here the `RentalStation` bean hosts several method constraints. When invoking one of the `RentalStation` methods from another bean such as `RentCarRequest`, the constraints of the invoked method are automatically validated. If any illegal parameter values are passed as in the example, a `ConstraintViolationException` will be thrown by the method interceptor, providing detailed information on the violated constraints. The same is the case if the method's return value violates any return value constraints.

Similarly, constructor constraints are validated automatically upon invocation. In the example the `RentalStation` object returned by the constructor will be validated since the constructor return value is marked with `@Valid`.

10.3.2.1. Validated executable types

Bean Validation allows for a fine-grained control of the executable types which are automatically validated. By default, constraints on constructors and non-getter methods are validated. Therefore the `@NotNull` constraint on the method `RentalStation#getAvailableCars()` in [例 10.6 “CDI managed beans with method-level constraints”](#) gets not validated when the method is invoked.

You have the following options to configure which types of executables are validated upon invocation:

- Configure the executable types globally via the XML descriptor META-INF/validation.xml; see 第 7.1 节 “Configuring the validator factory in validation.xml” for an example
- Use the `@ValidateOnExecution` annotation on the executable or type level

If several sources of configuration are specified for a given executable, `@ValidateOnExecution` on the executable level takes precedence over `@ValidateOnExecution` on the type level and `@ValidateOnExecution` generally takes precedence over the globally configured types in META-INF/validation.xml.

例 10.7 “Using `@ValidateOnExecution`” shows how to use the `@ValidateOnExecution` annotation:

例 10.7. Using `@ValidateOnExecution`

```
package org.hibernate.validator.referenceguide.chapter10.cdi.methodvalidation.configuration;

@ApplicationScoped
@ValidateOnExecution(type = ExecutableType.ALL)
public class RentalStation {

    @Valid
    public RentalStation() {
        //...
    }

    @NotNull
    @Valid
    @ValidateOnExecution(type = ExecutableType.NONE)
    public Car rentCar(
        @NotNull Customer customer,
        @NotNull @Future Date startDate,
        @Min(1) int durationInDays) {
        //...
    }

    @NotNull
    public List<Car> getAvailableCars() {
        //...
    }
}
```

Here the method `rentCar()` won't be validated upon invocation because it is annotated with `@ValidateOnExecution(type = ExecutableType.NONE)`. In contrast, the constructor and the method `getAvailableCars()` will be validated due to `@ValidateOnExecution(type = ExecutableType.ALL)` being given on the type level. `ExecutableType.ALL` is a more compact form for explicitly specifying all the types `CONSTRUCTORS`, `GETTER_METHODS` and `NON_GETTER_METHODS`.



提示

Executable validation can be turned off globally by specifying `<executable-validation enabled="false"/>` in `META-INF/validation.xml`. In this case, any `@ValidateOnExecution` annotations are ignored.

Note that when a method overrides or implements a super-type method the configuration will be taken from that overridden or implemented method (as given via `@ValidateOnExecution` on the method itself or on the super-type). This protects a client of the super-type method from an unexpected alteration of the configuration, e.g. disabling validation of an overridden executable in a sub-type.

In case a CDI managed bean overrides or implements a super-type method and this super-type method hosts any constraints, it can happen that the validation interceptor is not properly registered with the bean, resulting in the bean's methods not being validated upon invocation. In this case you can specify the executable type `IMPLICIT` on the subclass as shown in [例 10.8 “Using ExecutableType.IMPLICIT”](#), which makes sure that all required metadata is discovered and the validation interceptor kicks in when the methods on `ExpressRentalStation` are invoked.

例 10.8. Using `ExecutableType.IMPLICIT`

```
package org.hibernate.validator.referenceguide.chapter10.cdi.methodvalidation.implicit;

@ValidateOnExecution(type = ExecutableType.ALL)
public interface RentalStation {

    @NotNull
    @Valid
    Car rentCar(
        @NotNull Customer customer,
        @NotNull @Future Date startDate,
        @Min(1) int durationInDays);
}
```

```
package org.hibernate.validator.referenceguide.chapter10.cdi.methodvalidation.implicit;

@ApplicationScoped
@ValidateOnExecution(type = ExecutableType.IMPLICIT)
public class ExpressRentalStation implements RentalStation {

    @Override
    public Car rentCar(Customer customer, Date startDate, @Min(1) int durationInDays) {
        //...
    }
}
```

10.4. Java EE

When your application runs on a Java EE application server such as WildFly, you also can obtain `Validator` and `ValidatorFactory` instances via `@Resource` injection in managed objects such as EJBs etc., as shown in [例 10.9 “Retrieving Validator and ValidatorFactory via @Resource injection”](#).

例 10.9. Retrieving Validator and ValidatorFactory via @Resource injection

```
package org.hibernate.validator.referenceguide.chapter10.javaee;

@Stateless
public class RentalStationBean {

    @Resource
    private ValidatorFactory validatorFactory;

    @Resource
    private Validator validator;

    //...
}
```

Alternatively you can obtain a validator and a validator factory from JNDI under the names `"java:comp/Validator"` and `"java:comp/ValidatorFactory"`, respectively.

Similar to CDI-based injection via `@Inject`, these objects represent default validator and validator factory and thus can be configured using the XML descriptor `META-INF/validation.xml` (see [第 7 章 Configuring via XML](#)).

When your application is CDI-enabled, the injected objects are CDI-aware as well and e.g. support dependency injection in constraint validators.

Hibernate Validator Specifics

In this chapter you will learn how to make use of several features provided by Hibernate Validator in addition to the functionality defined by the Bean Validation specification. This includes the fail fast mode, the API for programmatic constraint configuration and the boolean composition of constraints.



注意

Using the features described in the following sections may result in application code which is not portable between Bean Validation providers.

11.1. Public API

Let's start, however, with a look at the public API of Hibernate Validator. [表 11.1 “Hibernate Validator public API”](#) lists all packages belonging to this API and describes their purpose. Note that when a package is part of the public this is not necessarily true for its sub-packages.

表 11.1. Hibernate Validator public API

Packages	Description
org.hibernate.validator	Classes used by the Bean Validation bootstrap mechanism (eg. validation provider, configuration class); For more details see 第 8 章 Bootstrapping .
org.hibernate.validator.cfg, org.hibernate.validator.cfg.context, org.hibernate.validator.cfg.defs	Hibernate Validator's fluent API for constraint declaration; In org.hibernate.validator.cfg you will find the ConstraintMapping interface and in org.hibernate.validator.cfg.defs all constraint definitions. Refer to 第 11.3 节 “Programmatic constraint declaration” for the details.
org.hibernate.validator.constraints, org.hibernate.validator.constraints.br	Some useful custom constraints provided by Hibernate Validator in addition to the built-in constraints defined by the Bean Validation specification; The constraints are described in detail in 第 2.3.2 节 “Additional constraints” .
org.hibernate.validator.group, org.hibernate.validator.spi.group	The group sequence provider feature which allows you to define dynamic default group

Packages	Description
	sequences in function of the validated object state; The specifics can be found in 第 5.3 节 “Redefining the default group sequence” .
org.hibernate.validator.messageinterpolation, org.hibernate.validator.resourceloading, org.hibernate.validator.spi.resourceloading	Classes related to constraint message interpolation; The first package contains Hibernate Validator's default message interpolator, ResourceBundleMessageInterpolator. The latter two packages provide the ResourceBundleLocator SPI for the loading of resource bundles (see 第 4.2.1 节 “ResourceBundleLocator”) and its default implementation.



注意

The public packages of Hibernate Validator fall into two categories: while the actual API parts are intended to be invoked or used by clients (e.g. the API for programmatic constraint declaration or the custom constraints), the SPI (service provider interface) packages contain interfaces which are intended to be implemented by clients (e.g. ResourceBundleLocator).

Any packages not listed in that table are internal packages of Hibernate Validator and are not intended to be accessed by clients. The contents of these internal packages can change from release to release without notice, thus possibly breaking any client code relying on it.

11.2. Fail fast mode

Using the fail fast mode, Hibernate Validator allows to return from the current validation as soon as the first constraint violation occurs. This can be useful for the validation of large object graphs where you are only interested in a quick check whether there is any constraint violation at all.

[例 11.1 “Using the fail fast validation mode”](#) shows how to bootstrap and use a fail fast enabled validator.

例 11.1. Using the fail fast validation mode

```
package org.hibernate.validator.referenceguide.chapter11.failfast;

public class Car {
```



```

@NotNull
private String manufacturer;

@AssertTrue
private boolean isRegistered;

public Car(String manufacturer, boolean isRegistered) {
    this.manufacturer = manufacturer;
    this.isRegistered = isRegistered;
}

//getters and setters...
}

```

```

Validator validator = Validation.byProvider( HibernateValidator.class )
    .configure()
    .failFast( true )
    .buildValidatorFactory()
    .getValidator();

Car car = new Car( null, false );

Set<ConstraintViolation<Car>> constraintViolations = validator.validate( car );

assertEquals( 1, constraintViolations.size() );

```

Here the validated object actually fails to satisfy both the constraints declared on the Car class, yet the validation call yields only one ConstraintViolation since the fail fast mode is enabled.



注意

There is no guarantee in which order the constraints are evaluated, i.e. it is not deterministic whether the returned violation originates from the @NotNull or the @AssertTrue constraint. If required, a deterministic evaluation order can be enforced using group sequences as described in [第 5.2 节 “Defining group sequences”](#).

Refer to [第 8.2.6 节 “Provider-specific settings”](#) to learn about the different ways of enabling the fail fast mode when bootstrapping a validator.

11.3. Programmatic constraint declaration

As per the Bean Validation specification, you can declare constraints using Java annotations and XML based constraint mappings.

In addition, Hibernate Validator provides a fluent API which allows for the programmatic configuration of constraints. Use cases include the dynamic addition of constraints

at runtime depending on some application state or tests where you need entities with different constraints in different scenarios but don't want to implement actual Java classes for each test case.

By default, constraints added via the fluent API are additive to constraints configured via the standard configuration capabilities. But it is also possible to ignore annotation and XML configured constraints where required.

The API is centered around the `ConstraintMapping` interface. You obtain a new mapping via `HibernateValidatorConfiguration#createConstraintMapping()` which you then can configure in a fluent manner as shown in [例 11.2 “Programmatic constraint declaration”](#).

例 11.2. Programmatic constraint declaration

```
HibernateValidatorConfiguration configuration = Validation
    .byProvider( HibernateValidator.class )
    .configure();

ConstraintMapping constraintMapping = configuration.createConstraintMapping();

constraintMapping
    .type( Car.class )
    .property( "manufacturer", FIELD )
    .constraint( new NotNullDef() )
    .property( "licensePlate", FIELD )
    .ignoreAnnotations()
    .constraint( new NotNullDef() )
    .constraint( new SizeDef().min( 2 ).max( 14 ) )
    .type( RentalCar.class )
    .property( "rentalStation", METHOD )
    .constraint( new NotNullDef() );

Validator validator = configuration.addMapping( constraintMapping )
    .buildValidatorFactory()
    .getValidator();
```

Constraints can be configured on multiple classes and properties using method chaining. The constraint definition classes `NotNullDef` and `SizeDef` are helper classes which allow to configure constraint parameters in a type-safe fashion. Definition classes exist for all built-in constraints in the `org.hibernate.validator.cfg.defs` package. By calling `ignoreAnnotations()` any constraints configured via annotations or XML are ignored for the given element.

Having configured the mapping, you must add it back to the configuration object from which you then can obtain a validator factory.

For custom constraints you can either create your own definition classes extending `ConstraintDef` or you can use `GenericConstraintDef` as seen in [例 11.3 “Programmatic declaration of a custom constraint”](#).

例 11.3. Programmatic declaration of a custom constraint

```

ConstraintMapping constraintMapping = configuration.createConstraintMapping();

constraintMapping
    .type( Car.class )
    .property( "licensePlate", FIELD )
        .constraint( new GenericConstraintDef<CheckCase>( CheckCase.class )
            .param( "value", CaseMode.UPPER )
        );

```

By invoking `valid()` a member is marked for cascaded validation which is equivalent to annotating it with `@Valid`. An example can be seen in 例 11.4 “Marking a property for cascaded validation”.

例 11.4. Marking a property for cascaded validation

```

ConstraintMapping constraintMapping = configuration.createConstraintMapping();

constraintMapping
    .type( Car.class )
    .property( "driver", FIELD )
        .constraint( new NotNullDef() )
        .valid()
    .type( Person.class )
    .property( "name", FIELD )
        .constraint( new NotNullDef() );

```

Not only bean constraints but also method constraints can be configured using the fluent API. As shown in 例 11.5 “Programmatic declaration of method constraints” methods are identified by their name and parameter types. Having selected a method, you can mark its parameters and/or return value for cascaded validation and add constraints.

例 11.5. Programmatic declaration of method constraints

```

ConstraintMapping constraintMapping = configuration.createConstraintMapping();

constraintMapping
    .type( Car.class )
    .method( "drive", int.class )
        .parameter( 0 )
        .constraint( new MaxDef().value ( 75 ) )
    .method( "getDriver" )
        .returnValue()
        .constraint( new NotNullDef() )
        .valid();

```

Last but not least you can configure the default group sequence or the default group sequence provider of a type as shown in the following example.

例 11.6. Configuration of default group sequence and default group sequence provider

```
ConstraintMapping constraintMapping = configuration.createConstraintMapping();

constraintMapping
    .type( Car.class )
        .defaultGroupSequence( Car.class, CarChecks.class )
    .type( RentalCar.class )
        .defaultGroupSequenceProviderClass( RentalCarGroupSequenceProvider.class );
```

11.4. Boolean composition of constraints

Bean Validation specifies that the constraints of a composed constraint (see [第 6.4 节 “Constraint composition”](#)) are all combined via a logical AND. This means all of the composing constraints need to return true in order for an overall successful validation.

Hibernate Validator offers an extension to this and allows you to compose constraints via a logical OR or NOT. To do so you have to use the `ConstraintComposition` annotation and the enum `CompositionType` with its values `AND`, `OR` and `ALL_FALSE`.

例 11.7 “OR composition of constraints” shows how to build a composed constraint `@PatternOrSize` where only one of the composing constraints needs to be valid in order to pass the validation. Either the validated string is all lower-cased or it is between two and three characters long.

例 11.7. OR composition of constraints

```
package org.hibernate.validator.referenceguide.chapter11.booleancomposition;

@ConstraintComposition(OR)
@Pattern(regexp = "[a-z]")
@Size(min = 2, max = 3)
@ReportAsSingleViolation
@Target({ METHOD, FIELD })
@Retention(RUNTIME)
@Constraint(validatedBy = { })
public @interface PatternOrSize {
    String message() default "{org.hibernate.validator.referenceguide.chapter11." +
        "booleancomposition.PatternOrSize.message}";

    Class<?>[] groups() default { };

    Class<? extends Payload>[] payload() default { };
}
```



提示

Using `ALL_FALSE` as composition type implicitly enforces that only a single violation will get reported in case validation of the constraint composition fails.

11.5. ResourceBundleLocator

As described in [第 4.2 节 “Custom message interpolation”](#), Bean Validation allows to plug in custom message interpolator implementations.

With `ResourceBundleLocator`, Hibernate Validator provides an additional SPI which allows to retrieve error messages from other resource bundles than `ValidationMessages` while still using the actual interpolation algorithm as defined by the specification. Refer to [第 4.2.1 节 “ResourceBundleLocator”](#) to learn how to make use of that SPI.

Annotation Processor

Have you ever caught yourself by unintentionally doing things like

- specifying constraint annotations at unsupported data types (e.g. by annotating a `String` with `@Past`)
- annotating the setter of a JavaBeans property (instead of the getter method)
- annotating static fields/methods with constraint annotations (which is not supported)?

Then the Hibernate Validator Annotation Processor is the right thing for you. It helps preventing such mistakes by plugging into the build process and raising compilation errors whenever constraint annotations are incorrectly used.



提示

You can find the Hibernate Validator Annotation Processor as part of the distribution bundle on [Sourceforge](http://sourceforge.net/projects/hibernate/files/hibernate-validator) [<http://sourceforge.net/projects/hibernate/files/hibernate-validator>] or in the usual Maven repositories such as Maven Central under the GAV `org.hibernate:hibernate-validator-annotation-processor:5.0.1.Final`.

12.1. Prerequisites

The Hibernate Validator Annotation Processor is based on the "Pluggable Annotation Processing API" as defined by [JSR 269](http://jcp.org/en/jsr/detail?id=269) [<http://jcp.org/en/jsr/detail?id=269>] which is part of the Java Platform since Java 6.

12.2. Features

As of Hibernate Validator 5.0.1.Final the Hibernate Validator Annotation Processor checks that:

- constraint annotations are allowed for the type of the annotated element
- only non-static fields or methods are annotated with constraint annotations
- only non-primitive fields or methods are annotated with `@Valid`
- only such methods are annotated with constraint annotations which are valid JavaBeans getter methods (optionally, see below)
- only such annotation types are annotated with constraint annotations which are constraint annotations themselves
- definition of dynamic default group sequence with `@GroupSequenceProvider` is valid

12.3. Options

The behavior of the Hibernate Validator Annotation Processor can be controlled using the [processor options](http://java.sun.com/javase/6/docs/technotes/tools/windows/javac.html#options) [http://java.sun.com/javase/6/docs/technotes/tools/windows/javac.html#options] listed in table 表 12.1 “[Hibernate Validator Annotation Processor options](#)” :

表 12.1. Hibernate Validator Annotation Processor options

Option	Explanation
diagnosticKind	Controls how constraint problems are reported. Must be the string representation of one of the values from the enum <code>javax.tools.Diagnostic.Kind</code> , e.g. <code>WARNING</code> . A value of <code>ERROR</code> will cause compilation to halt whenever the AP detects a constraint problem. Defaults to <code>ERROR</code> .
methodConstraintsSupported	Controls whether constraints are allowed at methods of any kind. Must be set to <code>true</code> when working with method level constraints as supported by Hibernate Validator. Can be set to <code>false</code> to allow constraints only at JavaBeans getter methods as defined by the Bean Validation API. Defaults to <code>true</code> .
verbose	Controls whether detailed processing information shall be displayed or not, useful for debugging purposes. Must be either <code>true</code> or <code>false</code> . Defaults to <code>false</code> .

12.4. Using the Annotation Processor

This section shows in detail how to integrate the Hibernate Validator Annotation Processor into command line builds (javac, Ant, Maven) as well as IDE-based builds (Eclipse, IntelliJ IDEA, NetBeans).

12.4.1. Command line builds

12.4.1.1. javac

When compiling on the command line using [javac](http://java.sun.com/javase/6/docs/technotes/guides/javac/index.html) [http://java.sun.com/javase/6/docs/technotes/guides/javac/index.html], specify the JAR `hibernate-validator-annotation-processor-5.0.1.Final.jar` using the `"processorpath"` option as shown in the following listing. The processor will be detected automatically by the compiler and invoked during compilation.

例 12.1. Using the annotation processor with javac

```
javac src/main/java/org/hibernate/validator/ap/demo/Car.java \
  -cp /path/to/validation-api-1.1.0.Final.jar \
  -processorpath /path/to/hibernate-validator-annotation-processor-5.0.1.Final.jar
```

12.4.1.2. Apache Ant

Similar to directly working with javac, the annotation processor can be added as a compiler argument when invoking the `javac` task [http://ant.apache.org/manual/CoreTasks/javac.html] for `Apache Ant` [http://ant.apache.org/]:

例 12.2. Using the annotation processor with Ant

```
<javac srcdir="src/main"
      destdir="build/classes"
      classpath="/path/to/validation-api-1.1.0.Final.jar">
  <compilerarg value="-processorpath" />
  <compilerarg value="/path/to/hibernate-validator-annotation-processor-5.0.1.Final.jar"/>
</javac>
```

12.4.1.3. Maven

There are several options for integrating the annotation processor with `Apache Maven` [http://maven.apache.org/]. Generally it is sufficient to add the Hibernate Validator Annotation Processor as dependency to your project:

例 12.3. Adding the HV Annotation Processor as dependency

```
...
<dependency>
  <groupId>org.hibernate</groupId>
  <artifactId>hibernate-validator-annotation-processor</artifactId>
  <version>5.0.1.Final</version>
</dependency>
...
```

The processor will then be executed automatically by the compiler. This basically works, but comes with the disadvantage that in some cases messages from the annotation processor are not displayed (see `MCOMPILER-66` [http://jira.codehaus.org/browse/MCOMPILER-66]).

Another option is using the `Maven Annotation Plugin` [http://code.google.com/p/maven-annotation-plugin/]. To work with this plugin, disable the standard annotation processing performed by the compiler plugin and configure the annotation plugin by

specifying an execution and adding the Hibernate Validator Annotation Processor as plugin dependency (that way the processor is not visible on the project's actual classpath):

例 12.4. Configuring the Maven Annotation Plugin

```
...
<plugin>
  <artifactId>maven-compiler-plugin</artifactId>
  <configuration>
    <source>1.6</source>
    <target>1.6</target>
    <compilerArgument>-proc:none</compilerArgument>
  </configuration>
</plugin>
<plugin>
  <groupId>org.bsc.maven</groupId>
  <artifactId>maven-processor-plugin</artifactId>
  <version>2.2.1</version>
  <executions>
    <execution>
      <id>process</id>
      <goals>
        <goal>process</goal>
      </goals>
      <phase>process-sources</phase>
    </execution>
  </executions>
  <dependencies>
    <dependency>
      <groupId>org.hibernate</groupId>
      <artifactId>hibernate-validator-annotation-processor</artifactId>
      <version>5.0.1.Final</version>
    </dependency>
  </dependencies>
</plugin>
...
```

12.4.2. IDE builds


12.4.2.1. Eclipse

Do the following to use the annotation processor within the [Eclipse](http://www.eclipse.org/) [http://www.eclipse.org/] IDE:

- Right-click your project, choose "Properties"
- Go to "Java Compiler" and make sure, that "Compiler compliance level" is set to "1.6". Otherwise the processor won't be activated
- Go to "Java Compiler - Annotation Processing" and choose "Enable annotation processing"

- Go to "Java Compiler - Annotation Processing - Factory Path" and add the JAR hibernate-validator-annotation-processor-5.0.1.Final.jar
- Confirm the workspace rebuild

You now should see any annotation problems as regular error markers within the editor and in the "Problem" view:




12.4.2.2. IntelliJ IDEA

The following steps must be followed to use the annotation processor within [IntelliJ IDEA](http://www.jetbrains.com/idea/) [http://www.jetbrains.com/idea/] (version 9 and above):

- Go to "File", then "Settings",
- Expand the node "Compiler", then "Annotation Processors"
- Choose "Enable annotation processing" and enter the following as "Processor path": /path/to/hibernate-validator-annotation-processor-5.0.1.Final.jar
- Add the processor's fully qualified name org.hibernate.validator.ap.ConstraintValidationProcessor to the "Annotation Processors" list

- If applicable add you module to the "Processed Modules" list

Rebuilding your project then should show any erroneous constraint annotations:




12.4.2.3. NetBeans

Starting with version 6.9, also the [NetBeans](http://www.netbeans.org/) IDE supports using annotation processors within the IDE build. To do so, do the following:

- Right-click your project, choose "Properties"
- Go to "Libraries", tab "Processor", and add the JAR hibernate-validator-annotation-processor-5.0.1.Final.jar
- Go to "Build - Compiling", select "Enable Annotation Processing" and "Enable Annotation Processing in Editor". Add the annotation processor by specifying its fully qualified name org.hibernate.validator.ap.ConstraintValidationProcessor

Any constraint annotation problems will then be marked directly within the editor:



12.5. Known issues

The following known issues exist as of May 2010:

- [HV-308](http://opensource.atlassian.com/projects/hibernate/browse/HV-308) [<http://opensource.atlassian.com/projects/hibernate/browse/HV-308>]: Additional validators registered for a constraint using XML [http://docs.jboss.org/hibernate/stable/validator/reference/en/html_single/#d0e1957] are not evaluated by the annotation processor.
- Sometimes custom constraints can't be properly evaluated [<http://opensource.atlassian.com/projects/hibernate/browse/HV-293>] when using the processor within Eclipse. Cleaning the project can help in these situations. This seems to be an issue with the Eclipse JSR 269 API implementation, but further investigation is required here.
- When using the processor within Eclipse, the check of dynamic default group sequence definitions doesn't work. After further investigation, it seems to be an issue with the Eclipse JSR 269 API implementation.

Further reading

Last but not least, a few pointers to further information.

A great source for examples is the Bean Validation TCK which is available for anonymous access on [GitHub](https://github.com/beanvalidation/beanvalidation-tck) [https://github.com/beanvalidation/beanvalidation-tck]. In particular the TCK's [tests](https://github.com/beanvalidation/beanvalidation-tck/tree/1.1.0.Final/tests) [https://github.com/beanvalidation/beanvalidation-tck/tree/1.1.0.Final/tests] might be of interest. [The JSR 349](http://beanvalidation.org/1.1/spec/1.1.0.cr3) [http://beanvalidation.org/1.1/spec/1.1.0.cr3] specification itself is also a great way to deepen your understanding of Bean Validation resp. Hibernate Validator.

If you have any further questions to Hibernate Validator or want to share some of your use cases have a look at the [Hibernate Validator Wiki](http://community.jboss.org/en/hibernate/validator) [http://community.jboss.org/en/hibernate/validator] and the [Hibernate Validator Forum](https://forum.hibernate.org/viewforum.php?f=9) [https://forum.hibernate.org/viewforum.php?f=9].

In case you would like to report a bug use [Hibernate's Jira](http://opensource.atlassian.com/projects/hibernate/browse/HV) [http://opensource.atlassian.com/projects/hibernate/browse/HV] instance. Feedback is always welcome!
