

Mark Craig

ForgeRock AS 201 Mission St., Suite 2900 San Francisco, CA 94105, USA +1 415-599-1100 (US) www.forgerock.com

Copyright © 2011-2014 ForgeRock AS

Abstract

This guide shows you how to install OpenDJ directory services. The OpenDJ project offers open source LDAP directory services in Java.



This work is licensed under the Creative Commons Attribution-NonCommercial-NoDerivs 3.0 Unported License.

To view a copy of this license, visit http://creativecommons.org/licenses/by-nc-nd/3.0/ or send a letter to Creative Commons, 444 Castro Street, Suite 900, Mountain View, California, 94041, USA.

ForgeRock[™] is the trademark of ForgeRock Inc. or its subsidiaries in the U.S. and in other countries. Trademarks are the property of their respective owners.

UNLESS OTHERWISE MUTUALLY AGREED BY THE PARTIES IN WRITING, LICENSOR OFFERS THE WORK AS-IS AND MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND CONCERNING THE WORK, EXPRESS, IMPLIED, STATUTORY OR OTHERWISE, INCLUDING, WITHOUT LIMITATION, WARRANTIES OF TITLE, MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, NOINFRINGEMENT, OR THE ABSENCE OF LATENT OR OTHER DEFECTS, ACCURACY, OR THE PRESENCE OF ABSENCE OF ERRORS, WHETHER OR NOT DISCOVERABLE. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OF IMPLIED WARRANTIES, SO SUCH EXCLUSION MAY NOT APPLY TO YOU.

EXCEPT TO THE EXTENT REQUIRED BY APPLICABLE LAW, IN NO EVENT WILL LICENSOR BE LIABLE TO YOU ON ANY LEGAL THEORY FOR ANY SPECIAL, INCIDENTAL, CONSEQUENTIAL, PUNITIVE OR EXEMPLARY DAMAGES ARISING OUT OF THIS LICENSE OR THE USE OF THE WORK, EVEN IF LICENSOR HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

DejaVu Fonts

Bitstream Vera Fonts Copyright

Copyright (c) 2003 by Bitstream, Inc. All Rights Reserved. Bitstream Vera is a trademark of Bitstream, Inc.

Permission is hereby granted, free of charge, to any person obtaining a copy of the fonts accompanying this license ("Fonts") and associated documentation files (the "Font Software"), to reproduce and distribute the Font Software, including without limitation the rights to use, copy, merge, publish, distribute, and/or sell copies of the Font Software, and to permit persons to whom the Font Software is furnished to do so, subject to the following conditions:

The above copyright and trademark notices and this permission notice shall be included in all copies of one or more of the Font Software typefaces.

The Font Software may be modified, altered, or added to, and in particular the designs of glyphs or characters in the Fonts may be modified and additional glyphs or characters may be added to the Fonts, only if the fonts are renamed to names not containing either the words "Bitstream" or the word "Vera".

This License becomes null and void to the extent applicable to Fonts or Font Software that has been modified and is distributed under the "Bitstream Vera" names.

The Font Software may be sold as part of a larger software package but no copy of one or more of the Font Software typefaces may be sold by itself.

THE FONT SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF COPYRIGHT, PATENT, TRADEMARK, OR OTHER RIGHT, IN NO EVENT SHALL BITSTREAM OR THE GNOME FOUNDATION BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, INCLUDING ANY GENERAL, SPECIAL, INDIRECT, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF THE USE OR INABILITY TO USE THE FONT SOFTWARE OR FROM OTHER DEALINGS IN THE FONT SOFTWARE.

Except as contained in this notice, the names of Gnome, the Gnome Foundation, and Bitstream Inc., shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Font Software without prior written authorization from the Gnome Foundation or Bitstream Inc., respectively. For further information, contact: fonts at gnome dot org.

Arev Fonts Copyright

Copyright (c) 2006 by Tavmjong Bah. All Rights Reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of the fonts accompanying this license ("Fonts") and associated documentation files (the "Font Software"), to reproduce and distribute the modifications to the Bitstream Vera Font Software, including without limitation the rights to use, copy, merge, publish, distribute, and/or sell copies of the Font Software, and to permit persons to whom the Font Software is furnished to do so, subject to the following conditions:

The above copyright and trademark notices and this permission notice shall be included in all copies of one or more of the Font Software typefaces.

The Font Software may be modified, altered, or added to, and in particular the designs of glyphs or characters in the Fonts may be modified and additional glyphs or characters may be added to the Fonts, only if the fonts are renamed to names not containing either the words "Tavmjong Bah" or the word "Arev".

This License becomes null and void to the extent applicable to Fonts or Font Software that has been modified and is distributed under the "Tavmjong Bah Arev" names.

The Font Software may be sold as part of a larger software package but no copy of one or more of the Font Software typefaces may be sold by itself.

THE FONT SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF COPYRICHT, PATENT, TRADEMARK, OR OTHER RIGHT, IN NO EVENT SHALL TAVMJONG BAH BE LLABLE FOR ANY CLAIM, DAMAGES OR OTHER LLABILITY, INCLUDING ANY GENERAL, SPECIAL, INDIRECT, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF THE USE OR INABILITY TO USE THE FONT SOFTWARE OR FROM OTHER DEALINGS IN THE FONT SOFTWARE.

Except as contained in this notice, the name of Tavmjong Bah shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Font Software without prior written authorization from Tavmjong Bah. For further information, contact: tavmjong @ free . fr.

Admonition graphics by Yannick Lung. Free for commerical use. Available at Freecns Cumulus.

Table of Contents

Prefacev
1. Who Should Read this Guide v
2. Formatting Conventions vi
3. Accessing Documentation Online vi
4. Joining the ForgeRock Community vii
1. Installing OpenDJ With the QuickSetup Wizard 1
2. Installing OpenDJ From the Command Line
3. Tuning JVM Options 25
4. Upgrading to OpenDJ 27
5. Removing OpenDJ Servers
Index

Preface

This guide shows you how to install, upgrade, and remove OpenDJ software. Unless you are planning a throwaway evaluation or test installation, read the *Release Notes* before you get started.

If you want only to try OpenDJ server software, and you do not plan to store any real or important data that you want to keep, then you need not read this entire guide. Instead, try *Installing OpenDJ With the QuickSetup Wizard*.

1 Who Should Read this Guide

This guide is written for anyone installing OpenDJ who plans to maintain directory services for client applications. Basic OpenDJ installation, especially using Java WebStart, can be simple and straightforward, particularly if you are already acquainted with directory services. Upgrading a running directory service without a single point of failure that can cause downtime requires at least a little thought and planning. Also, even in the case of basic installation, you may find yourself wanting more background about what you are doing.

This guide covers the install, upgrade, and removal (a.k.a. uninstall) procedures that you theoretically perform only once per version. This guide aims to provide you with at least some idea of what happens behind the scenes when you perform the steps.

You do not need to be an LDAP wizard to learn something from this guide, though a background in directory services and maintaining server software can help. You do need some background in managing servers and services on your operating system of choice. You can nevertheless get started with this guide, and then learn more as you go along.

2 Formatting Conventions

Most examples in the documentation are created in GNU/Linux or Mac OS X operating environments. If distinctions are necessary between operating environments, examples are labeled with the operating environment name in parentheses. To avoid repetition file system directory names are often given only in UNIX format as in /path/to/server, even if the text applies to C:\path\to \server as well.

Absolute path names usually begin with the placeholder /path/to/. This path might translate to /opt/, C:\Program Files\, or somewhere else on your system.

Command line, terminal sessions are formatted as follows:

\$ echo \$JAVA_HOME
/path/to/jdk

Command output is sometimes formatted for narrower, more readable output even though formatting parameters are not shown in the command. In the following example, the query string parameter _prettyPrint=true is omitted and some of the output is replaced with an ellipsis (...):

```
$ curl https://bjensen:hifalutin@opendj.example.com:8443/users/newuser
{
    "_rev" : "000000005b337348",
    "_id" : "newuser",
    ...
}
```

Program listings are formatted as follows:

```
class Test {
   public static void main(String [] args) {
      System.out.println("This is a program listing.");
   }
}
```

3 Accessing Documentation Online

ForgeRock core documentation, such as this document, aims to be technically accurate and complete with respect to the software documented.

Core documentation therefore follows a three-phase review process designed to eliminate errors:

- Product managers and software architects review project documentation design with respect to the readers' software lifecycle needs.
- Subject matter experts review proposed documentation changes for technical accuracy and completeness with respect to the corresponding software.
- Quality experts validate implemented documentation changes for technical accuracy, completeness in scope, and usability for the readership.

The review process helps to ensure that documentation published for a ForgeRock release is technically accurate and complete.

Fully reviewed, published core documentation is available at http:// backstage.forgerock.com/. Use this documentation when working with a ForgeRock Enterprise release.

You can find pre-release draft documentation at the online community resource center. Use this documentation when trying a nightly build.

4 Joining the ForgeRock Community

Visit the community resource center where you can find information about each project, download nightly builds, browse the resource catalog, ask and answer questions on the forums, find community events near you, and of course get the source code as well.

Chapter 1 Installing OpenDJ With the QuickSetup Wizard

If you want only to try OpenDJ server software, and you do not plan to store any real or important data that you want to keep, then read only this chapter, or just try out installation without reading any further.

Download OpenDJ software from one of the following locations.

- The ForgeRock Enterprise Downloads page has the latest stable, supported release of OpenDJ and the other products in the ForgeRock identity stack.
- The Nightly Builds page posts links to the latest nightly builds of OpenDJ software. Note that these builds are the working version from the trunk and are not for use in a production environment.
- The Community Archives page includes stable community builds for previous releases of OpenDJ software.

QuickSetup uses Java WebStart to let you perform an installation of OpenDJ directory server starting with a click in your web browser, which can be a great way to try OpenDJ directory server for the first time, or to do a quick test installation.



Note

OpenDJ directory server relies on Java 6 or later, so if your browser picks up an old installation of Java 5 for example, installation can fail. You might see an application error message such as this:



If the WebStart installation does not work in your browser, copy the WebStart URL, ending in QuickSetup.jnlp, from the OpenDJ download page. Next, pass the link as an argument to the **javaws** command in a terminal window to start the installer.

```
$ export PATH=/path/to/java/bin:$PATH
$ javaws URL-to-QuickSetup-Installer
```

The WebStart installer corresponds to what you start if you download OpenDJ-.zip, unzip the file, and then run **opendj/setup** (UNIX), **opendj/setup.bat** (Windows), or **opendj/QuickSetup.app** (Mac OS X).

Java WebStart launches the the QuickSetup wizard, and soon the Welcome screen appears.

000	OpenDJ QuickSetup				
 Welcome	Welcome				
License	The OpenDJ QuickSetup tool will ask you for some basic server and data configuration settings and will get your server up and running quickly.				
Server Settings	OpenDJ requires a Java SE 6.0 or higher runtime.				
Topology Options	Additional information on QuickSetup is available on the OpenDJ documentation site.				
Runtime Options					
Review					
Progr <mark>es</mark> s					
Finished					
	Next > Quit	:			
000	OpenDJ QuickSetup				
000 Welcome	OpenDJ QuickSetup				
○ ○ ○ Welcome ⇒ License	OpenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation.				
♥elcome ➡ License Server Settings	OpenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE EOPCERPORT SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE EOPCERPORT SOFTWARE UP ON UN ON PENALE OF SOURCE COMPANY. ACCEPTE TO				
 ○ ○ ○ Welcome ◆ License Server Settings Topology Options 	OpenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE.				
Welcome License Server Settings Topology Options Runtime Options	OpenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Software License.				
 ✓ ✓	OpenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Software License. 1.1. Development Right to Use, If Company intends to or does use the ForgeRock				
 Welcome ➡ License Server Settings Topology Options Runtime Options Review Progress 	OpenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Software License. 1.1. Development Right to Use. If Company intends to or does use the ForgeRock Software only for the purpose(s) of developing, testing, prototyping and demonstrating its application software, then ForgeRock hereby grants Company a				
 ✓ ✓	DpenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Software License. 1.1. Development Right to Use. If Company intends to or does use the ForgeRock Software only for the purpose(s) of developing, testing, prototyping and demonstrating its application software, then ForgeRock hereby grants Company a nonexclusive, nontransferable, limited license to use the ForgeRock Software only for those purposes, solely at Company's facilities and only in a				
Welcome Welcome Server Settings Topology Options Runtime Options Review Progress Finished	DeenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Software License. 1.1. Development Right to Use. If Company intends to or does use the ForgeRock Software only for the purpose(s) of developing, testing, prototyping and demonstrating its application software, then ForgeRock hereby grants Company a nonexclusive, nontransferable, limited license to use the ForgeRock Software only for those purposes, solely at Company's facilities and only in a non-production environment. ForgeRock may audit Company's use of the ForgeRock Software to confirm that a production license is not required upon reasonable				
Welcome Welcome Cicense Server Settings Topology Options Runtime Options Review Progress Finished	DpenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Software License. 1.1. Development Right to Use. If Company intends to or does use the ForgeRock Software only for the purpose(s) of developing, testing, prototyping and demonstrating its application software, then ForgeRock hereby grants Company a nonexclusive, nontransferable, limited license to use the ForgeRock Software only for those purposes, solely at Company's facilities and only in a non-production environment. ForgeRock may audit Company's use of the ForgeRock Software to confirm that a production license is not required upon reasonable written notice to Company. If Company intends to use the ForgeRock Software in a live environment. ForgeRock may a production license and may only use				
Welcome Welcome Cicense Server Settings Topology Options Runtime Options Review Progress Finished	DpenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Software License. 1.1. Development Right to Use. If Company intends to or does use the ForgeRock Software only for the purpose(s) of developing, testing, prototyping and demonstrating its application software, then ForgeRock hereby grants Company a nonexclusive, nontransferable, limited license to use the ForgeRock Software only for those purposes, solely at Company's facilities and only in a non-production environment. ForgeRock may audit Company's use of the ForgeRock Software to confirm that a production license is not required upon reasonable written notice to Company. Inf Company intends to use the ForgeRock Software in a live environment, Company must purchase a production license and may only use the ForgeRock Software licensed thereunder in accordance with the terms and conditions of that subscription argeement.				
Welcome Welcome Cicense Server Settings Topology Options Runtime Options Review Progress Finished	DpenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORCEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Software License. 1.1. Development Right to Use. If Company intends to or does use the ForgeRock Software only for the purpose(s) of developing, testing, prototyping and demonstrating its application software, then ForgeRock hereby grants Company a non-production environment. ForgeRock may audit Company's use of the ForgeRock Software to confirm that a production license is not required upon reasonable written notice to Company use purchase a production license and may only use the ForgeRock Software licensed thereunder in accordance with the terms and conditions of that subscription agreement. 1.2. Restrictions. Excent as expressly set forth in this ForgeRock Software				
 Welcome ➢ License Server Settings Topology Options Runtime Options Review Progress Finished 	DeenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Software License. 1.1. Development Right to Use. If Company intends to or does use the ForgeRock Software only for the purpose(s) of developing, testing, prototyping and demonstrating its application software, then ForgeRock hereby grants Company a non-production environment. ForgeRock may audit Company's use of the ForgeRock Software to confirm that a production license is not required upon reasonable written notice to Company. If Company intends to use the ForgeRock Software in a live environment. Company must purchase a production license and may only use the ForgeRock Software licensed thereunder in accordance with the terms and conditions of that subscription agreement. 1.2. Restrictions. Except as expressly set forth in this ForgeRock Software License Agreement (the "Agreement"), Company shall not, directly or indirectly: (a) sublicense a read listicity or order to remoter transfer area (lister or order).				
Welcome Welcome Server Settings Topology Options Runtime Options Review Progress Finished	DeenDJ QuickSetup License Please read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Software License. 1.1. Development Right to Use. If Company intends to or does use the ForgeRock Software only for the purpose(s) of developing, testing, prototyping and demonstrating its application software, then ForgeRock hereby grants Company a none-production environment. ForgeRock may audit Company's use of the ForgeRock Software to confirm that a production license is not required upon reasonable written notice to Company. If Company intends to use the ForgeRock Software in a live environment, Company nuchades a production license and may only use the ForgeRock Software licensed thereunder in accordance with the terms and conditions of that subscription agreement. 1.2. Restrictions. Except as expressly set forth in this ForgeRock Software (is usblicense, resell, ernt, lease, distribute or otherwise transfer rights or usage in the ForgeRock Software, including without limitation to Company				
 Welcome ➢ License Server Settings Topology Options Runtime Options Review Progress Finished 	 DpenDJ QuickSetup License Masse read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. If YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Development Right to Use. If Company intends to or does use the ForgeRock Software low for the purpose(s) of developing, testing, prototyping and demonstrating its application software, then ForgeRock hereby grants Company a nonexclusive, nontransferable, limited license to use the ForgeRock Software only for those purposes, solely at Company's facilities and only in a non-production environment. ForgeRock may audit Company's use of the ForgeRock Software to confirm that a production license is not required upon reasonable written notice to Company. Inf Company intends to use the ForgeRock Software in a live environment, Company must purchase a production license and may only use the ForgeRock Software licensed thereunder in accordance with the terms and conditions of that subscription agreement. 1. Restrictions. Except as expressly set forth in this ForgeRock Software license Agreement (the "Agreement"). Company shall not, directly or indirectly: (a) sublicense, resell, rent, lease, distribute or otherwise transfer rights or usace in the ForgeRock Software, including without limitation to Company. 				
 Welcome ➡ License Server Settings Topology Options Runtime Options Review Progress Finished 	 OpenDJ QuickSetup License Mease read the following License Agreement. You must accept the terms of the agreement before continuing with the installation. READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. 1. Obvelopment Right to Use. If Company intends to or does use the ForgeRock Software only for the purpose(s) of developing, testing, prototyping and demonstrating its application software, then ForgeRock hereby grants Company a nonexclusive, nontransferable, limited license to use the ForgeRock Software only for those purposes, solely at Company's facilities and only in a non-production environment. ForgeRock may audit Company's use of the ForgeRock Software to confirm that a production license is not required upon reasonable written notice to Company. If Company intends to use the ForgeRock Software in a live environment, Company must purchase a production license and may only use the ForgeRock Software licensed there under in accordance with the terms and conditions of that subscription agreement. 1.9. Restrictions. Except as expressly set forth in this ForgeRock Software license Agreement (the "Agreement"), Company shall not, directly or indirectly: (a) sublicense, resell, rent, lease, distribute or otherwise transfer rights or usage in the ForgeRock Software, including without limitation to Company f Click to accept Arevious 				

000	OpenDJ Qu	uickSetup				
Welcome	Server Settings					
License	Choose a location for the server files and enter a password for the server administrative user.					
🔿 Server Settings	Installation Path:	/path/to	/ opendj			
Topology Options		Browse.				
Runtime Options	Fully Qualified Host Name:	opendj.example.com				
Review	LDAR Lictorer Ports	1280 Could not use 280. Port i	in use or user not authorized			
Progress	EDAF Listener Fort.	Could not use 589. Port	in use of user not authorized.			
Finished	Administration Connector Port: 4444					
- Instea	LDAP Secure Access:	Enable StartTLS Enable SSL on LDAP Port 1636 Create a new Self-Signed Certificate	Configure			
	Root User DN:	cn=Directory Manager				
	Password:	•••••				
	Password (confirm):	•••••				
000	<pre></pre>	uickSetup	Quit			
Welcome	Topology Options					
License	Choose the Data Replication Optio	ns.				
Server Settings	 This will be a stand alone service This server will be part of a result of a	eplication topology				
Topology Options	Replication Port: 8989	Configure as Secure				
Runtime Options	There is already a serve	er in the topology				
Review	Fully Qualified Host Na	ime:				
Progress	Administration Connec	tor Port: 4444				
Finished	Admin User:	cn=Directory Manager				
	Admin Password:					
	< Previous Next >		Quit			

000		OpenDJ QuickSetup		
Welcome	Directory Data			
License	Choose options for th	e LDAP data to be hosted by the	server.	
Server Settings Topology Options Directory Data	Directory Base DN:	dc=example,dc=com		
		Leave empty if you do not want to crea	ite a base DN.	
	Directory Data:	Only Create Base Entry (dc=	example,dc=com)	
		Leave Database Empty		
Runtime Options		Path: /path/to/Example.	ldif	Browse
Review		Import Automatically-Gener	ated Sample Data	
Progress		Number of User Entries:	2000	
Finished				
		Naut 5		(Ouit)
	< Previous	Next >		Quit
000	< Previous	Next > OpenDJ QuickSetup		Quit
Welcome	< Previous	Next > OpenDJ QuickSetup		Quit
Welcome License	< Previous Runtime Options Specify the runtime o	Next > OpenDJ QuickSetup ; ptions that the Java virtual maching	ne will use to run the serv	Quit er and the import tool.
Welcome License Server Settings	< Previous	Next > OpenDJ QuickSetup ; ptions that the Java virtual machin ings: Use Default	ne will use to run the serv Change	Quit er and the import tool.
Welcome License Server Settings Topology Options	< Previous Runtime Options Specify the runtime o Server Runtime Sett Import Runtime Set	Next > OpenDJ QuickSetup ; ptions that the Java virtual machin ings: Use Default tings: Use Default	ne will use to run the serv Change Change	Quit er and the import tool.
Welcome License Server Settings Topology Options Directory Data	< Previous Runtime Options Specify the runtime o Server Runtime Sett Import Runtime Set	Next > OpenDJ QuickSetup ptions that the Java virtual machin ings: Use Default tings: Use Default	ne will use to run the serv Change Change	Quit er and the import tool.
Welcome License Server Settings Topology Options Directory Data	< Previous	Next > OpenDJ QuickSetup ptions that the Java virtual machin ings: Use Default tings: Use Default	ne will use to run the serv Change Change	Quit er and the import tool.
Welcome License Server Settings Topology Options Directory Data	< Previous	Next > OpenDJ QuickSetup ing tions that the Java virtual machin ings: Use Default tings: Use Default	ne will use to run the serv Change Change	Quit er and the import tool.
Welcome License Server Settings Topology Options Directory Data	< Previous	Next > OpenDJ QuickSetup ptions that the Java virtual machin ings: Use Default tings: Use Default	ne will use to run the serv Change Change	Quit er and the import tool.
Welcome License Server Settings Topology Options Directory Data Progress	< Previous	Next > OpenDJ QuickSetup ptions that the Java virtual machin ings: Use Default tings: Use Default	ne will use to run the serv Change Change	Quit er and the import tool.
Welcome License Server Settings Topology Options Directory Data Runtime Options Review Progress Finished	< Previous	Next > OpenDJ QuickSetup ptions that the Java virtual machin ings: Use Default tings: Use Default	ne will use to run the serv Change Change	Quit er and the import tool.
Welcome License Server Settings Topology Options Directory Data Runtime Options Review Progress Finished	< Previous	Next > OpenDJ QuickSetup ptions that the Java virtual machin ings: Use Default tings: Use Default	he will use to run the serv Change Change	Quit er and the import tool.
Welcome License Server Settings Topology Options Directory Data Review Progress Finished	< Previous	Next > OpenDJ QuickSetup ptions that the Java virtual machin ings: Use Default tings: Use Default	ne will use to run the serv Change Change	Quit er and the import tool.
Welcome License Server Settings Topology Options Directory Data Review Progress Finished	< Previous	Next > OpenDJ QuickSetup ings: Use Default tings: Use Default	ne will use to run the serv Change Change	Quit
Welcome License Server Settings Topology Options Directory Data Progress Finished	< Previous	Next > OpenDJ QuickSetup ptions that the Java virtual machin ings: Use Default tings: Use Default	ne will use to run the serv Change Change	Quit
Welcome License Server Settings Topology Options Directory Data Runtime Options Review Progress Finished	< Previous	Next > OpenDJ QuickSetup ptions that the Java virtual machin ings: Use Default tings: Use Default	he will use to run the serv Change Change	Quit er and the import tool.
Welcome License Server Settings Topology Options Directory Data Progress Finished	< Previous	Next > OpenDJ QuickSetup ing: Use Default tings: Use Default	he will use to run the serv Change Change	Quit er and the import tool.



	0	1					
▼ Dir	rectory Data		Server Status -				
Ma	nage Entries		Server Status:	Started	S	top	Restart
Ne	w Base DN		Open Connection	ns: 1			
Im	port LDIF	11	open connection				
Exp	port LDIF	l r	Server Details				
Bao	ckup		Host Name:		opene	dj.examp	le.com
Re	store		Administrative U	sers:	cn=D	irectory	Manager
► Scl	hema	-	Installation Path:		/path	n/to/oper	ndj
▶ Inc	leves	-	Version:		Open	DJ 2.6.0	
			Java Version:		1.7.0	_25	
b Ma	mitoring	Administration Connector: Port 4444 (LDAPS)					
► Mo	onitoring		Administration C	onnector	Port 4	4444 (LD)	APS)
▶ Mo ▶ Ru	ntime Options		Administration C	ionnector:	Port 4	4444 (LD)	APS)
► Mo ► Ru	ntime Options		Administration C Connection Hand Address:Port	onnector: llers Protocol	Port 4	4444 (LD)	APS) State
► Mo	ntioring ntime Options		Administration C Connection Hand Address:Port	Connector: llers Protocol LDIF	Port 4	1444 (LD)	APS) State Disabled
► Mo	nitoring ntime Options		Administration C Connection Hand Address:Port 0.0.0.0:161	Connector: Ilers Protocol LDIF SNMP	Port 4	4444 (LD)	APS) State Disabled Disabled
► Mo	nitoring ntime Options		Administration C Connection Hand Address:Port 0.0.0.0:161 0.0.0.0:1389	Connector: Ilers Protocol LDIF SNMP LDAP (allow	Port 4	1444 (LD)	APS) State Disabled Disabled Enabled
► Mo	nitoring ntime Options		Administration C Connection Hand Address:Port 0.0.0.0:161 0.0.0.0:1389 0.0.0.0:1636	Connector: Ilers Protocol LDIF SNMP LDAP (allow LDAPS	: Port 4	1444 (LD) tTLS)	APS) State Disabled Disabled Enabled Enabled
► Mo	nitoring ntime Options		Administration C Connection Hand Address:Port 0.0.0.0:161 0.0.0.0:1389 0.0.0.0:1636 0.0.0.0:1689	Connector: Ilers Protocol LDIF SNMP LDAP (allow LDAPS JMX	vs Star	4444 (LD) tTLS)	APS) State Disabled Disabled Enabled Enabled Disabled
► Mo	ntime Options		Administration C Connection Hand Address:Port 0.0.0.0:161 0.0.0.0:1389 0.0.0.0:1636 0.0.0.0:1689 0.0.0.0:8080	Ilers Protocol LDIF SNMP LDAP (allow LDAPS JMX HTTP	: Port 4	4444 (LD) tTLS)	APS) State Disabled Disabled Enabled Disabled Disabled Disabled
► Ru	ntime Options		Administration C Connection Hand Address:Port 0.0.0.0:161 0.0.0.0:1389 0.0.0.0:1636 0.0.0.0:1689 0.0.0.0:8080 Data Sources	Ilers Protocol LDIF SNMP LDAP (allow LDAPS JMX HTTP	vs Star	4444 (LD) tTLS)	APS) State Disabled Enabled Disabled Disabled Disabled Disabled
► Ru	ntime Options		Administration C Connection Hand Address:Port 0.0.0.0:161 0.0.0.0:1389 0.0.0.0:1689 0.0.0.0:8080 Data Sources Base DN	Ilers Protocol LDIF SNMP LDAP (allow LDAPS JMX HTTP Backer	ws Star	tTLS)	APS) State Disabled Disabled Enabled Disabled Disabled Disabled Note: Replication

To launch OpenDJ Control Panel again later, you can run one of the following, depending on your host system.

- (Mac OS X) opendj/bin/ControlPanel.app
- (UNIX) opendj/bin/control-panel
- (Windows) opendj\bat\control-panel.bat

Chapter 2 Installing OpenDJ From the Command Line

This chapter covers command-line installation with additional information on setup options.

- Procedure 2.1, "To Prepare For Installation"
- Procedure 2.2, "To Install OpenDJ Directory Server"
- Procedure 2.3, "To Install From the Debian Package"
- Procedure 2.4, "To Install From the RPM Package"
- Procedure 2.5, "To Install OpenDJ Directory Server With a Properties File"
- Procedure 2.6, "To Install OpenDJ REST LDAP Gateway"
- Procedure 2.7, "To Install OpenDJ DSML gateway"

Procedure 2.1. To Prepare For Installation

1. Make sure you have the correct Java environment installed, as described in the *Release Notes* section on *Java Environment* requirements.

If your default Java environment is not appropriate, set <code>OPENDJ_JAVA_HOME</code> to the path to the correct Java environment, or set <code>OPENDJ_JAVA_BIN</code> to the absolute path of the **java** command. The latter environment variable is

useful for example if you have both 32-bit and 64-bit versions of the Java environment installed, and want to make sure you use the 64-bit version.

2.

Download OpenDJ software from one of the following locations.

- The ForgeRock Enterprise Downloads page has the latest stable, supported release of OpenDJ and the other products in the ForgeRock identity stack.
- The Nightly Builds page posts links to the latest nightly builds of OpenDJ software. Note that these builds are the working version from the trunk and are not for use in a production environment.
- The Community Archives page includes stable community builds for previous releases of OpenDJ software.

The following server software is available.

OpenDJ-.zip

Cross-platform OpenDJ directory server installation files

opendj_-1_all.deb

OpenDJ directory server native package for Debian and related Linux distributions.

```
opendj--1.noarch.rpm
```

OpenDJ directory server native package for Red Hat and related Linux distributions.

OpenDJ--DSML.war

Cross-platform OpenDJ DSML gateway web archive

opendj-rest2ldap-servlet--servlet.war

Cross-platform OpenDJ REST LDAP gateway web archive

3.

If you plan to install OpenDJ DSML gateway or OpenDJ REST LDAP gateway, make sure you have an appropriate application server installed.

4. If you plan to configure SSL or TLS to secure network communications between the server and client applications, get a properly signed digital certificate that your client applications recognize, such as one that fits with your organization's PKI or one provided by a recognized certificate authority.

To use the certificate during installation, the certificate must be located in a key store provided with Java (JKS, JCEKS, PKCS#12), or on a PKCS#11 token. To import a signed certificate into a key store, you can use the Java **keytool** command.

See *Preparing For Secure Communications* in the *Administration Guide* for examples.

Procedure 2.2. To Install OpenDJ Directory Server

1. Unzip OpenDJ-.zip in the file system directory where you want to install the server.

Unlike the web-based Quick Setup install, the **setup** command uses the directory where you unzipped the files as the installation directory, and does not ask you where to install OpenDJ. Therefore, if you want to install elsewhere on the file system, unzip the files in that location.

2. Run the setup --cli command found in the opendj directory.

This command starts the setup program in interactive mode on the command line, prompting you for each option. Alternatively, use additional **setup** options to specify values for the options you choose during interactive mode, thus scripting the installation process. See **setup --help** and the notes below.

To perform a non-interactive, silent installation, provide all the options to configure OpenDJ, and then also use the -n or --no-prompt option.

The **setup** command without the --cli option runs the Quick Start GUI installer with your local version of software, as does Java WebStart with a remote version of the software.

\$ /path/to/opendj/setup --cli READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE. ... Please read the License Agreement above. You must accept the terms of the agreement before continuing with the installation. Accept the license (Yes/No) [No]:Yes What would you like to use as the initial root user DN for the Directory Server? [cn=Directory Manager]: Please provide the password to use for the initial root user: Please re-enter the password for confirmation: Provide the fully-gualified directory server host name that will be used when generating self-signed certificates for LDAP SSL/StartTLS, the administration connector, and replication [opendj.example.com]: On which port would you like the Directory Server to accept connections from LDAP clients? [1389]: On which port would you like the Administration Connector to accept connections? [4444]: Do you want to create base DNs in the server? (yes / no) [yes]: Provide the base DN for the directory data: dc=example,dc=com Options for populating the database: 1) Only create the base entry 2) Leave the database empty 3) Import data from an LDIF file 4) Load automatically-generated sample data Enter choice [1]: 3 Please specify the path to the LDIF file containing the data to import: \setminus /path/to/Example.ldif Do you want to enable SSL? (yes / no) [no]: Do you want to enable Start TLS? (yes / no) [no]: Do you want to start the server when the configuration is completed? (yes / no) [yes]: Setup Summary _____ 1389 LDAP Listener Port: Administration Connector Port: 4444 LDAP Secure Access: disabled Root User DN: cn=Directory Manager Directory Data: Create New Base DN dc=example,dc=com. Base DN Data: Import Data from LDIF File (/path/to/Example.ldif) Start Server when the configuration is completed What would you like to do? 1) Set up the server with the parameters above 2) Provide the setup parameters again 3) Print equivalent non-interactive command-line 4) Cancel and exit Enter choice [1]: See /var/.../opendj-setup...log for a detailed log of this operation. Configuring Directory Server Done. Importing LDIF file /path/to/Example.ldif Done. Starting Directory Server Done. To see basic server configuration status and configuration you can launch \setminus /path/to/opendj/bin/status

Some notes on the options follow.

Initial root user DN

The root user Distinguished Name identifies a user who can perform all administrative and other operations allowed for the server, called root user due to the similarity to the UNIX root. The default, cn=Directory Manager, is a well-known name. If you have reason to be paranoid, you might opt for a different name.

Initial root user password

The root user will use simple, password-based authentication. Later you can limit clear text access to avoid snooping, but for now use a strong password here unless this is a throwaway server.

Fully-qualified directory server host name

OpenDJ uses fully-qualified host name in self-signed certificates and for identification when you use replication. If you are installing a single server temporarily for evaluation, and are not concerned about replication and whether self-signed certificates can be trusted, then you can use an FQDN such as localhost.localdomain. Otherwise, use an FQDN that other hosts can resolve to reach your server.

LDAP port

The default for LDAP is 389. If you are working as a user who cannot open port 389, setup suggests 1389 by default.

Administration port

This is the service entrance used to configure the server, run tasks, and so forth. The default is 4444.

Create base DNs

You need a base Distinguished Name, such as dc=example,dc=com, to add directory data. If you already have LDIF, the base DN you want is the distinguished name suffix common to all entries in your LDIF. You can provide more than one base DN if your data belongs in more than one suffix.

Import LDIF

LDAP data interchange format is the standard text format for expressing LDAP data. If you have LDIF already, one reason you might not want to import the data at the same time you install is because your data uses attributes not defined in the default schema, and so you will wait to add schema definitions before you import.

If you have a huge data set to import, you no doubt should also increase the import cache size, which you can do by passing a Java properties file. You might also prefer to perform data import offline.

Enable SSL and TLS

Enabling Secure Sockets Layer or Transport Layer Security lets you protect the network traffic between directory clients and your server.

SSL

SSL requires its own, separate port for LDAPS traffic. The default port for LDAPS is 636. If you are working as a user who cannot open port 636, setup suggests 1636 by default.

TLS

TLS lets you use StartTLS to negotiate a secure connection between a client and server, starting from the same server port you configured for LDAP.

X.509 certificates

The digital certificate you need for SSL and TLS can be self-signed and created on the fly. Trouble is, client applications view selfsigned certificates like fake IDs, and so do not trust them. Self-signed certificates facilitate testing, but are not intended for production use.

Start the server

If you do not start the server during installation, you can use the **/path/to/opendj/bin/start-ds** command later.

3. Run the **status** command to make sure your OpenDJ server is working as expected.

```
$ /path/to/opendj/bin/status
>>>> Specify OpenDJ LDAP connection parameters
Administrator user bind DN [cn=Directory Manager]:
Password for user 'cn=Directory Manager':
         --- Server Status ---
Server Run Status: Started
Open Connections:
                       1
         --- Server Details ---
Host Name:
                      opendj.example.com
                      cn=Directory Manager
Administrative Users:
Installation Path:
                      /path/to/opendj
Version:
                       OpenDJ
Java Version:
                       version
Administration Connector: Port 4444 (LDAPS)
         --- Connection Handlers ---
Address:Port : Protocol : State
-- : LDIF : Disabled
0.0.0.0:161 : SNMP
                    : Disabled
0.0.0.0:636 : LDAPS
                   : Disabled
                   : Enabled
0.0.0.0:1389 : LDAP
0.0.0.0:1689 : JMX
                     : Disabled
         --- Data Sources ---
Base DN: dc=example,dc=com
Backend ID: userRoot
Entries:
         160
Replication: Disabled
```



Note

You can install OpenDJ in unattended and silent fashion, too. See the procedure, Procedure 2.5, "To Install OpenDJ Directory Server With a Properties File".

Procedure 2.3. To Install From the Debian Package

On Debian and related Linux distributions such as Ubuntu, you can install OpenDJ directory server from the Debian package.

1. (Optional) Before you install OpenDJ, install a Java runtime environment if none is installed yet.

```
$ sudo apt-get install default-jre
```

2. Install the OpenDJ directory server package.

```
$ sudo dpkg -i opendj_-1_all.deb
Selecting previously unselected package opendj.
(Reading database ... 185569 files and directories currently installed.)
Unpacking opendj (from opendj_-1_all.deb) ...
Setting up opendj () ...
$
```

The .deb installs OpenDJ directory server in the directory /opt/opendj.

The files are owned by root by default, making it easier to have OpenDJ listen on ports 389 and 636.

3. Configure OpenDJ directory server by using the command **sudo /opt/opendj/ setup**.

```
$ sudo /opt/opendj/setup --cli
...
To see basic server configuration status and configuration you can launch
/opt/opendj/bin/status
```

4. (Optional) Check OpenDJ directory server status.

```
$ sudo /opt/opendj/bin/status
>>>> Specify OpenDJ LDAP connection parameters
Administrator user bind DN [cn=Directory Manager]:
Password for user 'cn=Directory Manager':
           --- Server Status ---
Server Run Status: Started
Open Connections:
                             1
           --- Server Details ---
               ubuntu.example.com
Host Name:
Administrative Users: cn=Directory Manager
Installation Path: /opt/opendj
Version: 0penDJ
Java Version: version
Administration Connector: Port 4444 (LDAPS)
           --- Connection Handlers ---
Address:Port : Protocol
                                         : State
. . . . . ; . . . .
             : LDIF
                       : Disabled
0.0.0.0:161 : SNMP : Disabled
0.0.0.0:389 : LDAP (allows StartTLS) : Enabled
0.0.0.0:636 : LDAPS : Enabled
0.0.0.0:636 : MX : Disabled
- -
0.0.0.0:8080 : HTTP
                                        : Disabled
           --- Data Sources ---
Base DN: dc=example,dc=com
Backend ID: userRoot
Entries:
              2002
Replication:
```

5. (Optional) If you want to run OpenDJ when the system starts, see create-rc-script.

Procedure 2.4. To Install From the RPM Package

On Red Hat and related Linux distributions such as Fedora and CentOS, you can install OpenDJ directory server from the RPM package.

1. Log in as superuser to install the software.

```
$ su
Password:
#
```

2. (Optional) Before you install OpenDJ, install a Java runtime environment if none is installed yet.

You might need to download an .rpm to install the Java runtime environment, and then install it using the **rpm** command.

```
# rpm -ivh jre-*.rpm
```

3. Install the OpenDJ directory server package.

```
# rpm -i opendj--1.noarch.rpm
Pre Install - initial install
Post Install - initial install
#
```

The .rpm installs OpenDJ directory server in the directory /opt/opendj.

The files are owned by root by default, making it easier to have OpenDJ listen on ports 389 and 636.

4. Configure OpenDJ directory server by using the command /opt/opendj/setup.

```
# /opt/opendj/setup --cli
...
To see basic server configuration status and configuration you can launch
/opt/opendj/bin/status
```

5. (Optional) Check OpenDJ directory server status.

```
# /opt/opendj/bin/status
>>>> Specify OpenDJ LDAP connection parameters
Administrator user bind DN [cn=Directory Manager]:
Password for user 'cn=Directory Manager':
           --- Server Status ---
Server Run Status: Started
Open Connections:
                             1
           --- Server Details ---
Host Name:
                fedora.example.com
Administrative Users: cn=Directory Manager
Installation Path: /opt/opendj
Version: 0penDJ
Java Version: version
Administration Connector: Port 4444 (LDAPS)
           --- Connection Handlers ---
Address:Port : Protocol
                                         : State
- - - - - : - -
             : LDIF : Disabled
0.0.0.0:161 : SNMP : Disabled
0.0.0.0:389 : LDAP (allows StartTLS) : Enabled
0.0.0.0:636 : LDAPS : Enabled
0.0.0.0:636 : MX : Disabled
0.0.0.0:8080 : HTTP
                                         : Disabled
           --- Data Sources ---
Base DN: dc=example,dc=com
Backend ID: userRoot
Entries:
              2002
Replication:
```

6. (Optional) If you want to run OpenDJ when the system starts, see create-rc-script.

Procedure 2.5. To Install OpenDJ Directory Server With a Properties File

You can install OpenDJ directory server by using the **setup** command with a properties file.

Property names correspond to the option names, but without leading dashes. Options that take no arguments become boolean properties as in the following example.

enableStartTLS=true

If you use a properties file with multiple tools, prefix the property name with the tool name followed by a dot (.), as in the following example.

```
setup.rootUserPasswordFile=/tmp/pwd.txt
```

The following steps demonstrate use of a properties file as part of a scripted installation process.

1. Prepare your properties file.

This procedure uses the following example properties file.

```
# Sample properties file to set up OpenDJ directory server
#
                                =opendj.example.com
hostname
ldapPort
                                =1389
generateSelfSignedCertificate
                                =true
enableStartTLS
                                =true
ldapsPort
                                =1636
jmxPort
                                =1689
adminConnectorPort
                                =4444
rootUserDN
                                =cn=Directory Manager
rootUserPassword
                                =password
baseDN
                                =dc=example,dc=com
ldifFile
                                =/net/install/dj/Example.ldif
#sampleData
                                =2000
```

If you have multiple servers to install, consider scripting creation of the properties files.

2. Prepare an installation script.

```
$ cat /net/install/dj/1/setup.sh
#!/bin/sh
unzip -d /path/to /net/install/dj/0penDJ-.zip && cd /path/to/opendj
./setup --cli --propertiesFilePath /net/install/dj/1/setup.props \
        --acceptLicense --no-prompt
```

3. Run your installation script.

```
$ /net/install/dj/1/setup.sh
Archive: /net/install/dj/OpenDJ-.zip
   creating: /path/to/opendj
  inflating: /path/to/opendj/setup
  inflating: /path/to/opendj/uninstall
  inflating: /path/to/opendj/upgrade
READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING
THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO
BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE
TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE.
. . .
Do you accept the License Agreement?yes
See /var/folders/.../opendj-setup-...log for a detailed log of this operation.
Configuring Directory Server ..... Done.
Configuring Certificates ..... Done.
Importing LDIF file /net/install/dj/Example.ldif ..... Done.
Starting Directory Server ..... Done.
To see basic server configuration status and configuration you can launch
/path/to/opendj/bin/status
```

At this point you can use OpenDJ directory server, or you can perform additional configuration.

Procedure 2.6. To Install OpenDJ REST LDAP Gateway

The OpenDJ REST LDAP gateway functions as a web application in a web application container, running independently of OpenDJ. Alternatively, you can use the HTTP connection handler in OpenDJ directory server. See the procedure, *To Set Up REST Access to OpenDJ Directory Server*, for instructions.

You configure the gateway to access your directory service by editing opendj-rest2ldap-servlet.json where you deploy the gateway web application.

- 1. Deploy opendj-rest2ldap-servlet--servlet.war according to the instructions for your application server.
- 2. Edit opendj-rest2ldap-servlet.json where you deployed the gateway web application.

The default JSON resource for the configuration includes both connection and authentication information, and also mappings. The mappings describe how the gateway translates between JSON and LDAP representations of your data. The default mappings are built to work with generated example data and also the sample content in Example.ldif. At minimum, make sure that the host name and port numbers for primaryLDAPServers are properly configured, that authentication reflects the correct simple bind credentials, and that the mappings for the endpoints correctly match your directory data.

For details on the configuration, see REST LDAP Configuration.

When connecting to directory servers over LDAPS or LDAP and StartTLS, you can configure the trust manager to use a file-based trust store for server certificates that the gateway should trust. This allows the gateway to validate server certificates signed for example by a Certificate Authority not recognized by the Java environment when setting up LDAPS or StartTLS connections. See *Preparing For Secure Communications* for an example showing how to use the **keytool** command to support a server certificate into a trust store file.

- 3. Restart the REST LDAP gateway or the application server to make sure the changes are taken into account.
- 4. Make sure that your directory server is running, and then check that the gateway is connecting correctly.

The following command reads Babs Jensen's entry through the gateway to the backend holding data from Example.ldif.

```
$ curl http://biensen:hifalutin@opendj.example.com:8080/rest2ldap/users/bjensen
 ?_prettyPrint=true
{
  " rev" : "000000002ee3b764",
  "schemas" : [ "urn:scim:schemas:core:1.0" ],
  "contactInformation" : {
    "telephoneNumber" : "+1 408 555 1862",
    "emailAddress" : "bjensen@example.com"
  },
  "id" : "bjensen",
  "name" : {
    "familyName" : "Jensen",
    "givenName" : "Barbara"
  },
  "userName" : "bjensen@example.com",
  "displayName" : "Barbara Jensen",
  "manager" : [ {
    "_id" : "trigden"
    "displayName" : "Torrey Rigden"
  }]
}
```

If you generated example data, Babs Jensen's entry is not included. Try a URL such as http://user.0:password@opendj.example.com:8080/rest2ldap/users/user.0 instead.

Procedure 2.7. To Install OpenDJ DSML gateway

The OpenDJ DSML gateway functions as a web application located in a web application container. The DSML gateway runs independently of OpenDJ directory server. You configure the gateway to access your directory service by editing the ldap.host and ldap.port parameters in the WEB-INF/web.xml configuration file.

- 1. Deploy OpenDJ--DSML.war according to the instructions for your application server.
- 2. Edit WEB-INF/web.xml to ensure the values for ldap.host and ldap.port are correct.
- 3. Restart the web application container according to the instructions for your application server.

^{Chapter 3} Tuning JVM Options

By default, OpenDJ installs with options appropriate for evaluation, not for production.

You can change JVM options for the server in the QuickStart installer, and alternatively using the Control Panel (Runtime Options > Java Settings), or with the **dsjavaproperties** command after editing the config/java.properties file.

Heap size

The JVM heap size by default is either 256 MB or 1 GB.

In production, use at least a 2 GB heap (-Xms2G -Xmx2G).

Server optimizations

Use -server to select the HotSpot Server VM.

32-bit vs. 64-bit

For heap sizes over 4 GB on 64-bit systems use -d64.

Garbage collection

Use -XX:+UseConcMarkSweepGC to select the CMS garbage collector for low GC pause times.

New generation size

If your directory handles high throughput, set the new generation size large enough for the JVM to avoid promoting short-lived objects into the old gen space (-XX:NewSize=512M).

^{Chapter 4} Upgrading to OpenDJ

This chapter covers upgrade from OpenDJ 2.4.5 and later versions.

For upgrades from earlier versions, upgrade first to at least OpenDJ 2.4.5, and then follow the procedures in this chapter. See Upgrading OpenDJ Directory Server in the OpenDJ Wiki for details on upgrading to OpenDJ 2.4.5 from earlier versions.

Procedure 4.1. Before You Upgrade

1. Prepare to perform the upgrade procedure as the user who owns the OpenDJ server files.

Make sure you have the credentials to run commands as the user who owns the server.

- 2. Download OpenDJ software from one of the following locations.
 - The ForgeRock Enterprise Downloads page has the latest stable, supported release of OpenDJ and the other products in the ForgeRock identity stack.
 - The Nightly Builds page posts links to the latest nightly builds of OpenDJ software. Note that these builds are the working version from the trunk and are not for use in a production environment.
 - The Community Archives page includes stable community builds for previous releases of OpenDJ software.

3. In order to revert if the upgrade fails, make sure you perform a full backup of your current OpenDJ installation.

It might be most expedient to back up the file system directory where the current OpenDJ server is installed as part of the upgrade process.

Alternatively, see *Backing Up & Restoring Data* for instructions.

Procedure 4.2. To Upgrade an OpenDJ Directory Server

To upgrade OpenDJ directory server installed from native packages (.deb, .rpm), use the command-line package management tools provided by the system.

The following steps describe how to upgrade OpenDJ directory server installed from the cross-platform (.zip) delivery.

- 1. Login as the user who owns the current OpenDJ server.
- 2. Stop the current OpenDJ server.
- 3. (Optional) If you have not already backed up the current OpenDJ server, make a back up copy of the directory where OpenDJ is installed.
- 4. (Optional) If OpenDJ is currently installed in a directory such as OpenDJ-2.4.5, you can change the directory name to opendj to make it easier to unpack subsequent .zip deliveries for future upgrades.
- 5. Unpack the new files from the .zip delivery over the current server files.

If your directory is not named opendj, then you can first unpack the files, then copy everything in the opendj over the current server files.

6. Run the **upgrade** command to bring OpenDJ configuration and application data up to date with the new binary and script files that you copied over the current server files.

By default, the **upgrade** command requests confirmation before making important configuration changes. You can use the --no-prompt option to run the command non-interactively, with the --acceptLicense option to accept the license terms non-interactively.

When using the --no-prompt option, if the **upgrade** command cannot complete because it requires confirmation for a potentially very long or critical task, then it exits with an error and a message about how to finish making the changes. You can add the --force option to force a non-interactive upgrade to continue in this case, also performing long running and critical tasks.

7. When you upgrade from OpenDJ 2.5.0-Xpress1, you must rebuild the ds-synchist ordering index before you restart the server, as indicated in the message from the upgrade tool.

OpenDJ 2.5.0-Xpress1 introduced a regression in the ds-sync-hist ordering index. This index must be rebuilt after the upgrade has completed and before restarting OpenDJ. Do you wish to continue? (yes/no) [no]: yes

To rebuild the index, use the **rebuild-index** command after upgrade but before starting the server as in the following example.

\$./opendj/bin/rebuild-index --baseDN dc=example,dc=com --index ds-sync-hist ... msg=Rebuild of index(es) ds-sync-hist started msg=Rebuild complete. Processed XXX entries in YYY seconds...

8. Start the upgraded OpenDJ server.

At this point the upgrade process is complete. See the resulting upgrade.log file for a full list of operations performed.

Example 4.1. Upgrading From OpenDJ 2.4.5

The following example upgrades an OpenDJ 2.4.5 directory server installed in /path/to/OpenDJ-2.4.5, backing up the current server directory in case the upgrade process fails, and changing the directory name to /path/to/opendj to simplify future upgrades.

```
$ cd /path/to
$ls
OpenDJ-2.4.5
$ ./OpenDJ-2.4.5/bin/stop-ds --quiet
... msg=The backend userRoot is now taken offline
... msg=The Directory Server is now stopped
$ zip -rq OpenDJ-backup.zip OpenDJ-2.4.5
$ unzip -g ~/Downloads/OpenDJ-2.6.0.zip
$ cp -r opendj/* OpenDJ-2.4.5/
$ rm -rf opendi
$ mv OpenDJ-2.4.5 opendj
$ ./opendj/upgrade --no-prompt --acceptLicense
>>>> OpenDJ Upgrade Utility
 * OpenDJ will be upgraded from version 2.4.5.7743 to 2.6.0.9086
 * See '/path/to/opendj/upgrade.log' for a detailed log of this operation
READ THIS SOFTWARE LICENSE AGREEMENT CAREFULLY. BY DOWNLOADING OR INSTALLING
THE FORGEROCK SOFTWARE, YOU, ON BEHALF OF YOURSELF AND YOUR COMPANY, AGREE TO
BE BOUND BY THIS SOFTWARE LICENSE AGREEMENT. IF YOU DO NOT AGREE TO THESE
TERMS, DO NOT DOWNLOAD OR INSTALL THE FORGEROCK SOFTWARE.
 . . .
Please read the License Agreement above.
You must accept the terms of the agreement before continuing with the
installation
Do you accept the License Agreement? yes
>>>> Preparing to upgrade
```

OpenDJ 2.5.0 modified the default configuration of the 'isMemberOf' virtual attribute so that it is included with group entries. This was done in order to make it easier for users to determine which groups a 'nested' group belonas to. Do you want to make this configuration change? (yes/no) yes The upgrade is ready to proceed. Do you wish to continue? (yes/no) yes >>>> Performing upgrade Fixing de-DE collation matching rule OID..... 100% Updating password policy configurations..... 100% Updating audit log publisher configuration..... 100% Rename SNMP security config file..... 100% Adding 'etag' virtual attribute schema..... 100% Configuring 'etag' virtual attribute..... 100% Configuring 'ds-pwp-password-expiration-time' virtual attribute..... 100%Updating certificate syntax configuration..... 100% Updating JPEG syntax configuration..... 100% Updating country string syntax configuration..... 100% Modifying filter in 'isMemberOf' virtual attribute configuration.... 100% Updating dictionary password validator configuration..... 100% Updating attribute value password validator configuration..... 100% Adding PBKDF2 password storage scheme configuration..... 100% Adding 'http-config.json' configuration file..... 100% Adding HTTP connection handler configuration..... 100% Adding file-based HTTP access logger..... 100% Adding 'emailAddress' attribute.... 100% Updating subject attribute to user attribute configuration..... 100% Replacing schema file '02-config.ldif'..... 100% Archiving concatenated schema..... 100% >>>> OpenDJ was successfully upgraded from version 2.4.5.7743 to 2.6.0.9086 * See '/path/to/opendj/upgrade.log' for a detailed log of this operation \$./opendj/bin/start-ds --quiet

Procedure 4.3. To Upgrade Replicated Servers

• Upgrade each server sequentially, as described above.

Procedure 4.4. To Upgrade OpenDJ DSML Gateway

• Replace the gateway web application with the newer version, as for a fresh installation.

Chapter 5 Removing OpenDJ Servers

Remove OpenDJ directory server software with the **uninstall** command.

Procedure 5.1. To Uninstall OpenDJ From the Graphical Uninstaller

1. (UNIX) Run opendj/uninstall.

(Windows) Double-click opendj\uninstall.bat.

000	OpenDJ Uninstall
🕏 Uninstall Options	Uninstall Options
Progress	The Uninstall tool will remove all parts of the server you have selected below from your system. If all are selected, the server will be removed entirely.
Finished	Server Path: /path/to/opendj Server Libraries and Administrative Tools Database Contents Log Files Configuration and Schema Files Sackup Files Contained in bak Directory LDIF Export Files Contained in Idif Directory
	Uninstall Quit

2. When the process is finished, you might still have some files to remove manually.



Procedure 5.2. To Uninstall OpenDJ On the Command Line

- 1. Login as the user who installed and runs the server.
- 2. Run the **opendj/uninstall --cli** command.

This command starts the removal program in interactive mode on the command line, prompting you for each option. Alternatively, use additional **uninstall** options to specify choices for the options. See **uninstall --help** for more information.

```
$ cd /path/to/opendj
$ ./uninstall --cli
Do you want to remove all components of the server or select the components to
remove?
        Remove all components
    1)
    2) Select the components to be removed
    q) quit
Enter choice [1]:
The server is currently running and must be stopped before uninstallation can
continue.
Stop the Server and permanently delete the files? (yes / no) [yes]:
Stopping Directory Server ..... Done.
Deleting Files under the Installation Path ..... Done.
The Uninstall Completed Successfully.
To complete the uninstallation, you must delete manually the following files
and directories:
/path/to/opendj/lib
See /var/....log for a detailed log of this operation.
```

3. If the command output tells you to delete files manually, then remove those remaining files to complete the process.

\$ rm -rf /path/to/opendj

Procedure 5.3. To Uninstall the Debian Package

When you uninstall the Debian package from the command line, OpenDJ directory server is stopped if it is running.

• Remove the package from your system.

```
$ sudo dpkg -r opendj
(Reading database ... 185725 files and directories currently installed.)
Removing opendj ...
*Stopping OpenDJ server...
[03/Jun/2013:10:00:49 +0200] category=BACKEND severity=NOTICE
msgID=9896306 msg=The backend userRoot is now taken offline
[03/Jun/2013:10:00:49 +0200] category=CORE severity=NOTICE
msgID=458955 msg=The Directory Server is now stopped
*OpenDJ successfully removed
$
```

Removing the package does not remove your data or configuration. You must remove /opt/opendj manually to get rid of all files.

Procedure 5.4. To Uninstall the RPM Package

When you uninstall the RPM package from the command line, OpenDJ directory server is stopped if it is running.

• Remove the package from your system.

```
# rpm -e opendj
Pre Uninstall - uninstall
Stopping Server...
[03/Jun/2013:10:42:46 +0200] category=BACKEND severity=NOTICE
msgID=9896306 msg=The backend userRoot is now taken offline
[03/Jun/2013:10:42:46 +0200] category=CORE severity=NOTICE
msgID=458955 msg=The Directory Server is now stopped
Post Uninstall - uninstall
OpenDJ successfully removed.
#
```

Removing the package does not remove your data or configuration. You must remove /opt/opendj manually to get rid of all files.

Index

С

Command-line installation, 11

D

Debian (.deb) package, 15, 33 Downloading OpenDJ, 1, 10 DSML gateway, 10, 23

J

Java Settings, 25

Q

Quick install, 1

R

Red Hat (.rpm) package, 17, 34 REST LDAP gateway, 21

S

Silent installation, 11

U

Uninstalling, 31 Upgrading, 27