

# Assignment 3, Part 1, Specification

SFWR ENG 2AA4

April 9, 2018

The purpose of this software design exercise is to design and implement a portion of the specification for a Geographic Information System (GIS). This document shows the complete specification, which will be the basis for your implementation and testing. In this specification natural numbers ( $\mathbb{N}$ ) include zero (0).

[The parts that you need to fill in are marked by comments, like this one. In several of the modules local functions are specified. You can use these local functions to complete the missing specifications. —SS]

# Map Types Module

## Module

MapTypes

## Uses

N/A

## Syntax

### Exported Constants

None

### Exported Types

CompassT = {N, S, E, W}

LanduseT = {Recreational, Transport, Agricultural, Residential, Commercial}

RotateT = {CW, CCW}

### Exported Access Programs

None

## Semantics

### State Variables

None

### State Invariant

None

# Point ADT Module

## Template Module

PointT

## Uses

N/A

## Syntax

### Exported Types

[PointT = ? —SS]

### Exported Access Programs

Routine name	In	Out	Exceptions
PointT	$\mathbb{Z}, \mathbb{Z}$	PointT	
x		$\mathbb{Z}$	
y		$\mathbb{Z}$	
translate	$\mathbb{Z}, \mathbb{Z}$	PointT	

## Semantics

### State Variables

*xc*: [ $\mathbb{Z}$  —SS]

*yc*: [ $\mathbb{Z}$  —SS]

### State Invariant

None

### Assumptions

The constructor PointT is called for each object instance before any other access routine is called for that object. The constructor cannot be called on an existing object.

## Access Routine Semantics

PointT( $x, y$ ):

- transition:  $[\text{xc}, \text{yc} := x, y \text{ ---SS}]$
- output:  $\text{out} := \text{self}$
- exception: None

x():

- output:  $\text{out} := xc$
- exception: None

y():

- output:  $\text{out} := yc$
- exception: None

translate( $\Delta x, \Delta y$ ):

- $[\text{output: out: PointT}(\text{xc} + \Delta x, \text{yc} + \Delta y) \text{ ---SS}]$
- exception: None

# Line ADT Module

## Template Module

LineT

## Uses

[\[PointT, MapTypes for CompassT and RotateT —SS\]](#)

## Syntax

### Exported Types

LineT = ?

### Exported Access Programs

Routine name	In	Out	Exceptions
LineT	PointT, CompassT, $\mathbb{N}$	LineT	invalid_argument
strt		PointT	
end		PointT	
orient		CompassT	
len		$\mathbb{Z}$	
flip		LineT	
rotate	RotateT	LineT	
translate	$\mathbb{Z}, \mathbb{Z}$	LineT	

## Semantics

### State Variables

$s$ : PointT

$o$ : CompassT

$L$ :  $\mathbb{N}$

### State Invariant

None

## Assumptions

The constructor `LineT` is called for each object instance before any other access routine is called for that object. The constructor cannot be called on an existing object.

## Access Routine Semantics

`LineT(st, ornt, l)`:

- transition:  $s, o, L := st, ornt, l$
- output:  $out := self$
- exception:  $[l \leq 0 \implies invalid\_argument \text{ ---SS}]$

`strt()`:

- output:  $out := \text{PointT}(st.x, st.y)$
- exception: None

`end()`:

- output:  $[PointT(x, y) \text{ where, } ((o = N \implies y = strt().y() + l) \parallel (o = S \implies y = strt().y() - l) \parallel (o = E \implies y = strt().x() + l) \parallel (o = W \implies y = strt().x() - l)) \text{ ---SS}]$
- exception: None

`orient()`:

- output:  $out := o$
- exception: None

`len()`:

- output:  $out := L$
- exception: None

`flip()`:

- output:  $[LineT(strt(), o, l) \text{ where, } (o = rotate(CW), o = rotate(CW)) \text{ ---SS}]$
- exception: None

rotate(r):

• output:			<i>out</i> :=
	<i>r</i> = CW	<i>o</i> = N	[E —SS]
		<i>o</i> = S	[W —SS]
		<i>o</i> = W	[N —SS]
		<i>o</i> = E	[S —SS]
	<i>r</i> = CCW	<i>o</i> = N	[W —SS]
		<i>o</i> = S	[E —SS]
		<i>o</i> = W	[S —SS]
		<i>o</i> = E	[N —SS]

- exception: None

translate( $\Delta x$ ,  $\Delta y$ ):

- output: [LineT(newPoint, o, *l*) where, (newPoint = st.translate( $\Delta x$ ,  $\Delta y$ ) —SS]
- exception: None

# Path ADT Module

## Template Module

PathT

## Uses

PointT, LineT, MapTypes

## Syntax

### Exported Types

PathT = ?

### Exported Access Programs

Routine name	In	Out	Exceptions
PathT	PointT, CompassT, N	PathT	
append	CompassT, N		invalid_argument
strt		PointT	
end		PointT	
line	N	LineT	outside_bounds
size		N	
len		N	
translate	$\mathbb{Z}$ , $\mathbb{Z}$	LineT	

## Semantics

### State Variables

$s$ : sequence of LineT

### State Invariant

None



## Assumptions

- The constructor `PathT` is called for each object instance before any other access routine is called for that object. The constructor cannot be called on an existing object.

## Access Routine Semantics

`PathT(st, ornt, l):`

- transition:  $[s_0 := \text{LineT}(st, ornt, l) \text{---SS}]$
- output:  $out := self$
- exception: `None`

`append(ornt, l):`

- transition:  $[s := s + \text{LineT}(z, ornt, l) \text{ where, } (z = adjPt(ornt)). \text{---SS}]$
- exception:  $[s_{|s|-1}.rotate(CW).rotate(CW).orient = ornt \implies invalid\_argument \text{---SS}]$

`strt():`

- output:  $[out := s_0.st \text{---SS}]$
- exception: `None`

`end():`

- output:  $[out := s_{|s|-1}.end \text{---SS}]$
- exception: `None`

`line(i):`

- output:  $[out := s_i \text{---SS}]$
- exception:  $[i < 0 || i \geq s.len \implies outside\_bounds \text{---SS}]$

`size:`

- output:  $[out := s.len \text{---SS}]$
- exception: `None`

len:

- output:  $[out := +\forall(i : \mathbb{N} | i \in [0..s.len - 1] : pointsInLine(i)) - SS]$
- exception: None

translate( $\Delta x, \Delta y$ ):

- output: Create a new PathT object with state variable  $s'$  such that:

$$\forall(i : \mathbb{N} | i \in [0..|s| - 1] : s'[i] = s[i].translate(\Delta x, \Delta y))$$

- exception: None

## Local Functions

pointsInLine: LineT  $\rightarrow$  (set of PointT)

pointsInLine ( $l$ )

$$\equiv \{i : \mathbb{N} | i \in [0..(l.len - 1)] : l.strt.translate.($$

$$(\begin{array}{|l|l|} \hline l.orient = N & (0, 1) \\ \hline l.orient = S & (0, -1) \\ \hline l.orient = W & (-1, 0) \\ \hline l.orient = E & (1, 0) \\ \hline \end{array}) - SS]$$

adjPt: CompassT  $\rightarrow$  PointT

adjPt( $ornt$ )  $\equiv$

$ornt = N$	$s[ s  - 1].end.translate[(0, 1) - - - SS]$
$ornt = S$	$s[ s  - 1].end.translate[(0, -1) - - - SS]$
$ornt = W$	$s[ s  - 1].end.translate[(-1, 0) - - - SS]$
$ornt = E$	$s[ s  - 1].end.translate[(1, 0) - - - SS]$

# Generic Seq2D Module

## Generic Template Module

Seq2D(T)

### Uses

N/A

### Syntax

#### Exported Types

Seq2D(T) = ?

#### Exported Constants

None

#### Exported Access Programs

Routine name	In	Out	Exceptions
Seq2D	seq of (seq of T), $\mathbb{R}$	Seq2D	invalid_argument
set	PointT, T		outside_bounds
get	PointT	T	outside_bounds
getNumRow		$\mathbb{N}$	
getNumCol		$\mathbb{N}$	
getScale		$\mathbb{R}$	
count	T	$\mathbb{N}$	
count	LineT, T	$\mathbb{N}$	invalid_argument
count	PathT, T	$\mathbb{N}$	invalid_argument
length	PathT	$\mathbb{R}$	invalid_argument
connected	PointT, PointT	$\mathbb{B}$	invalid_argument

### Semantics

#### State Variables

$s$ : seq of (seq of T)

scale:  $\mathbb{R}$

nRow:  $\mathbb{N}$

nCol:  $\mathbb{N}$

## State Invariant

None

## Assumptions

- The Seq2D(T) constructor is called for each object instance before any other access routine is called for that object. The constructor can only be called once.
- Assume that the input to the constructor is a sequence of rows, where each row is a sequence of elements of type T. The number of columns (number of elements) in each row is assumed to be equal. That is each row of the grid has the same number of entries.  $s[i][j]$  means the  $i$ th row and the  $j$ th column. The 0th row is at the bottom of the map and the 0th column is at the leftmost side of the map.

## Access Routine Semantics

Seq2D( $S$ , scl):

- transition:  $[s, scale, nRow, nCol := S, scl, S.len, S[0].len \text{ ---SS}]$
- output:  $out := self$
- exception:  $[scl < 0 \parallel \neg(validRow) \parallel \neg(validCol) \parallel S.len \neq S[0].len \implies invalid\_argument \text{ ---SS}]$

set( $p, v$ ):

- transition:  $[s[p.y][p.x] := v \text{ ---SS}]$
- exception:  $[p.y < 0 \parallel p.x < 0 \parallel p.y \geq nRow \parallel p.x \geq nCol \implies outside\_bounds \text{ ---SS}]$

get( $p$ ):

- output:  $[out := s[p.y][p.x] \text{ ---SS}]$
- exception:  $[p.y < 0 \parallel p.x < 0 \parallel p.y \geq nRow \parallel p.x \geq nCol \implies outside\_bounds \text{ ---SS}]$

getNumRow():

- output:  $out := nRow$

- exception: None

getNumCol():

- output:  $out := nCol$
- exception: None

getScale():

- output:  $out := scale$
- exception: None

count( $t$ : T):

- output:  $[out := +(\forall i : \mathbb{N} | i \in [0 \dots nRow] \bullet \forall j : \mathbb{N} | j \in [0 \dots nCol] \bullet s[i][j] = t : 1) \text{---SS}]$
- exception: None

count( $l$ : LineT,  $t$ : T):

- output:  $[out := +(\forall i : \mathbb{N} | i \in [l.strt.y \dots l.end.y] \bullet \forall j : \mathbb{N} | j \in [l.strt.x \dots l.end.x] \bullet s[i][j] = t : 1) \text{---SS}]$
- exception:  $[\neg(validLine(l)) \implies invalid\_argument \text{---SS}]$

count( $pth$ : PathT,  $t$ : T):

- output:  $[out := +(\forall k : \mathbb{N} | k \in [0 \dots pth.size-1] \bullet \forall i : \mathbb{N} | i \in [pth[k].strt.y \dots pth[k].end.y] \bullet \forall j : \mathbb{N} | j \in [pth[k].strt.x \dots pth[k].end.x] \bullet s[i][j] = t : 1) \text{---SS}]$
- exception:  $[\neg(validPath(pth)) \implies invalid\_argument \text{---SS}]$

length( $pth$ : PathT):

- output:  $[out := scl \times pth.len \text{---SS}]$
- exception:  $[\neg(validPath(pth)) \implies invalid\_argument \text{---SS}]$

connected( $p_1$ : PointT,  $p_2$ : PointT):

- output:  $[out := ((\forall k : \mathbb{N} | k \in [0 \dots pth.size-1] \bullet \exists p_1 : PointT | \bullet pointsInPath(pth)[k] = p_1) \wedge (\forall k : \mathbb{N} | k \in [0 \dots pth.size-1] \bullet \exists p_2 : PointT | \bullet pointsInPath(pth)[k] = p_2)) \implies true \text{---SS}]$
- exception:  $[\neg(validPoints(p_1) \wedge validPoints(p_2)) \implies invalid\_argument \text{---SS}]$

## Local Functions

validRow:  $\mathbb{N} \rightarrow \mathbb{B}$

[validRow( $i$ )  $\equiv 0 < i < nRow = true$ , where  $i \rightarrow \mathbb{N} \text{---SS}$ ]

validCol:  $\mathbb{N} \rightarrow \mathbb{B}$

[validCol( $i$ )  $\equiv 0 < i < nCol = true$ , where  $i \rightarrow \mathbb{N} \text{---SS}$ ]

validPoint:  $\text{PointT} \rightarrow \mathbb{B}$

[validPoint( $point$ )  $\equiv (point.x \wedge point.y) \geq 0 \wedge (point.x \wedge point.y) < (nRow \wedge nCol) \implies true$ , where  $point \rightarrow \text{PointT} \text{---SS}$ ]

validLine:  $\text{LineT} \rightarrow \mathbb{B}$

[validLine( $i$ )  $\equiv (validPoint(l.start) \wedge validPoint(l.end)) \implies true$ , where  $l \rightarrow \text{LineT} \text{---SS}$ ]

validPath:  $\text{PathT} \rightarrow \mathbb{B}$

[validPath( $i$ )  $\equiv \forall : \mathbb{N} | k \in [0..pth.size - 1] \bullet (validLine(pth[k])) \implies true$ , where  $pth \rightarrow \text{PathT} \text{---SS}$ ]

pointsInLine:  $\text{LineT} \rightarrow (\text{set of PointT})$

pointsInLine ( $l$ ) [pointsInLine( $l$ )  $\equiv i : \mathbb{N} | i \in [0..(l.len-1)] : l.start.translate($

$l.orient = N$	$(0, 1)$
$l.orient = S$	$(0, -1)$
$l.orient = W$	$(-1, 0)$
$l.orient = E$	$(1, 0)$

$\text{---SS}$ ]

pointsInPath:  $\text{PathT} \rightarrow (\text{set of PointT})$

[pointsInPath( $p$ )  $\equiv \cup(k : \mathbb{N} | k \in [0..(p.size - 1)] : (pointsInLine(p[k])))$ , where  $p \rightarrow \text{PathT} \text{---SS}$ ]

## LanduseMap Module

### Template Module

LanduseMapT is Seq2D(LanduseT)

## DEM Module

### Template Module

DEMT is Seq2D( $\mathbb{Z}$ )

## Critique of Design

In general, the specifications were easy to follow. However, one thing that could be added are hints to use the local functions for certain exceptions earlier on in each module because some time was wasted to create exceptions beforehand, only to realize that one could use the local functions as exceptions.